

NEXTSTOP

Owner Manual

Fuel Station Management System

User Manual

Generated 2026-06-05

Who this is for: the station **Owner** - the top role with full control. You do everything a manager does (review handovers, close off the day, manage stock, settings, users, audit) and you also have owner-only powers: the **first-time setup**, **Stations** (run more than one station), **Infrastructure** (tanks, islands and nozzles), and **approving stock takes**.

Your menu (top bar): seven groups - **Dashboard**, **My Shift**, **Operations**, **Inventory & Sales**, **Reconciliation**, **Reports**, **Administration** - plus a **station selector** (if you have more than one station), a **bell** (alerts), a **light/dark** toggle, and **Logout**.

Money is shown in ZMW (K). Tip: the **date** you pick on the dashboard is remembered as you move between pages.

1. First-time setup (first login only)

The very first time you log in, the system runs a short **setup wizard**. You cannot use the rest of the app until it is finished. It has eight steps; click **Next** to move forward and **Back** to revise.

1. **Welcome** - a short overview. Click **Next**.
2. **Your Profile** - enter your **Full Name**; optionally set a **new password** (leave blank to keep the current one). Click **Next**. *What to expect:* your account name/password is saved.
3. **Business Info** - enter the **Business/Station Name** (required), and optional **Location**, **Contact Email**, **Contact Phone**. *What to expect:* the station record and system settings are saved.
4. **Tanks** - set up your fuel storage. Two tanks are pre-filled (one Diesel, one Petrol, 20,000 L each). For each tank set **Tank ID**, **Fuel Type** (Diesel/Petrol), and **Capacity (L)**. Use **Add tank / Remove** to change the list (at least one tank; IDs must be unique).
5. **Pricing & Tax** - enter the **Diesel price/L**, **Petrol price/L**, ****VAT rate (%)**, and **Fuel levy (ZMW/L)****.
6. **Operational Settings** - thresholds and tolerances:
 - **Allowable losses:** diesel %, petrol %, nozzle loss (L).
 - **Validation thresholds:** pass %, warning %.
 - **Stock alerts:** low-stock %, critical %.
 - **Reconciliation tolerances:** choose a mode (percentage, fixed litres, hybrid, or tiered) and set the cash minor / investigation amounts. *What to expect:* values are validated (e.g. pass must be below warning) and saved.
7. **Staff** - optionally create your first users (attendant, supervisor, or manager): **Full Name**, **Username**, **Password** (min 6 characters). You can add more later under Admin > Users.
8. **All Set** - a success screen. Click **Go to Dashboard**. *What to expect:* setup is marked complete; from now on you log straight in to the dashboard.

2. Logging in (after setup)

1. Open the station web address.
2. Enter your **email** and **password**.
3. Click **Sign in**.

What to expect: you land on the **Dashboard**, which includes the **Today's Flow** card (your daily checklist). If you manage more than one station, a **station selector** appears in the top bar.

3. Switching stations (if you run more than one)

1. In the top bar, open the **station selector** dropdown.
2. Choose a station.

What to expect: the app reloads showing that station's data. Everything you do (shifts, stock, reports, settings) applies to the **currently selected** station. You can also manage stations in detail under **Admin > Stations** (Section 9).

4. Your home: "Today's Flow"

The dashboard's **Today's Flow** card is your daily hub. It shows the day's chain as four steps, each with a status dot and a button:

- **Shift set up** - an active shift with attendants assigned.
- **Tank dips recorded** - opening/closing dips entered.
- **Handovers reviewed** - how many attendant handovers are pending vs approved.
- **Day closed** - whether the day has been closed off.

What each part does: the **button on each row** opens the page for that step; the **date picker** sets the working day. Click the **NextStop logo** anytime to return here.

5. Running the day - Operations

Open the **Operations** menu.

Shifts

1. Click **Operations > Shifts**.

What you can do: create a shift (pick date and Day/Night), assign attendants to islands/nozzles, and set who the shift supervisor is. **What to expect:** the shift validates (every attendant needs at least one nozzle; no nozzle assigned twice) and becomes the active shift attendants work against.

Handover Review

1. Click **Operations > Handover Review** (this is also "Handovers" on Today's Flow).

What you can do: review each attendant's end-of-shift handover.

- **Click a row** to expand full detail (nozzle readings, sales, credit, deposits).
- **Approve** a clean handover - it is approved and stock applied.
- **Approve** a flagged handover - a box opens that **requires a written note** (reason chips help); click **Confirm Approve**.

- **Return** a handover - a box opens **requiring a reason**; the attendant is notified to fix and resubmit.
- Tick several clean handovers and use **Approve Selected (N)**.

What to expect: when all are reviewed, a **Next: Daily Close-Off** button appears.

Daily Tank Reading / Fuel Operations / LPG Daily / Lubricants Daily

- **Daily Tank Reading** - record per-tank dips, nozzle readings and deliveries.
- **Fuel Operations** - record fuel deliveries and tank movements.
- **LPG Daily Operations** - LPG cylinder sales, trades and damages.
- **Lubricants Daily** - lubricant and accessory sales.

These are normally done by supervisors/attendants; as owner you can view or enter them. Each saves the day's figures used in reconciliation.

6. Closing off the day - Administration > Daily Close-Off

1. Click **Admin > Daily Close-Off** (or **Next: Daily Close-Off** after review).

What you see: the date and status (Open / Pending Reviews / Closed), the **Approved Shifts** table, and the **Daily P&L Snapshot**.

2. If any handover is unapproved, a warning links you back to Handover Review; the close button stays disabled until all are approved.
3. Enter the **bank deposit**: amount (required), reference (optional), notes (optional). A live line shows deposit vs actual cash (over / short / exact).
4. Click **Close Day & Lock Handovers**, then confirm.

What to expect: the day is **locked** and cannot be undone; it shows who closed it and the deposit variance. **Close-Off History** lets you review past days.

7. Managing stock - Inventory & Sales

Open the **Inventory & Sales** menu.

Stores / Stock

1. Click **Inventory & Sales > Stores / Stock**.

What you see: summary cards, a re-order alert for low items, and a table of items with Stores and Forecourt quantities.

2. Click **Manage stock** on an item. A window opens with an action selector:

Receive (into Stores), **Issue** (to Forecourt), **Damage** (write off, needs a reason), **Adjust** (set the counted quantity, needs a reason). Enter the quantity, add a reason where required, then **Confirm**.

3. **+ Add / Edit Item** adds or edits a product. **Show recent movements** shows the stock ledger.

Stock Takes (you approve these)

1. Click **Inventory & Sales > Stock Takes**.

The flow: a manager starts a count, enters quantities, and **Submits** it - it then shows a **Submitted** badge.

2. Open a **Submitted** stock take. **What to expect:** the counts are read-only and a **Variance** column shows the net difference. As owner you see an **Approve** button.
3. Click **Approve**. **What to expect:** the status changes to **Approved**, the record is locked, and the approval is recorded in the Audit Log.

Tank Levels / Sales / Credit Accounts

- **Tank Levels** - current fuel volumes (view).
 - **Sales** - sales figures and trends (view).
 - **Credit Accounts** - manage credit customers and their limits.
-

8. Reviewing the numbers - Reconciliation and Reports

Reconciliation menu (read-only):

- **Three-Way Reconciliation** - physical vs meter vs accounting.
- **Tank Analysis** - tank movement and possible loss/variance.
- **Shift Reconciliation** - per-shift detail.

Reports menu (read-only; most export):

- **Sales Reports, Tank Readings & Monitor, Advanced Reports** (staff / nozzle / island / product / custom), **Anomaly Alerts, Notifications**.

What to expect: choose a date range or filter where offered, then view or export. These never change data.

9. Administration

Open the **Admin** menu. As owner you have the full set, including two owner-only pages: **Stations** and **Infrastructure**.

Settings

1. Click **Admin > Settings**.

What you can do: fuel prices (immediate or **scheduled** for a future time), tax/levy rates, validation thresholds (e.g. cash-shortage tolerance, meter-deviation percentage), and reconciliation tolerances. Changes are recorded in the Audit Log.

Users

1. Click **Admin > Users**.

What you can do: create, edit, or deactivate users and set their role (attendant, supervisor, manager).

Audit Log

1. Click **Admin > Audit Log**.

What to expect: a searchable record of every change (prices, approvals, returns, settings, users, stock-take approvals), filterable by action, type, user and date.

Stations (owner only)

1. Click **Admin > Stations**.

What you can do:

- **+ New Station** - enter **Name** (required) and **Location**; leave **Quick Setup** ticked to auto-create default islands, tanks, nozzles and accounts.
- **Edit** - change a station's name/location, then **Save**.
- **Switch to Station** - make a station the active one (the app reloads).
- **Disable / Enable** - turn a station off/on (you cannot disable the last active station).
- **Delete** - only for a disabled, non-current station; you must type the station name to confirm. This permanently removes its shifts, readings, sales and settings. You cannot delete the last station.

Infrastructure (owner only)

1. Click **Admin > Infrastructure**.

It has two tabs.

Tanks tab:

- **+ Create New Tank** - set **Tank ID**, **Fuel Type**, **Capacity (L)**, and an optional **Initial level**. Click **create**.
- **Edit Capacity** - change a tank's capacity (must be at least the current level), then **Save**.
- **Set Level** - enter the current level (0 to capacity) and click **Set Level**.
- **Delete Tank** - removes the tank (with confirmation).

Each tank card shows level, capacity, a colour-coded fill bar, and a low-fuel warning under 30%.

Islands & Pumps tab:

- **Rename** - rename an island, then **Save** (or press **Enter**).
- **Configure nozzles** - use a preset: **All Diesel**, **All Petrol**, or **Mixed** (one of each). If you have more than one tank of a fuel, pick the tank. For full control click **Advanced** and choose **Custom** to assign each nozzle to a specific tank. Click **Apply configuration**.
- **Activate / Deactivate** - only active islands appear in operations.
- **Delete Island** - removes the island and its nozzles (with confirmation).

10. Logging out

Click **Logout** (top-right). You return to the login screen.

Quick reference - the owner's tasks

- **First login:** complete the **setup wizard** (profile, business, tanks, pricing/tax, settings, staff), then **Go to Dashboard**.

- **Daily: Operations > Handover Review** (approve/return), then ****Admin > Daily Close-Off (enter bank deposit, Close Day & Lock**)**.
- **Stock: Inventory & Sales > Stores / Stock**; **approve Stock Takes** that managers submit.
- **Setup/config: Admin > Stations** (add/switch/disable/delete stations) and **Admin > Infrastructure** (tanks, islands, nozzles).
- **Oversight: Reconciliation, Reports, Admin > Audit Log.**
- **People & rules: Admin > Users** and **Admin > Settings.**

Rules to remember

- You **cannot close the day** until **all handovers are approved**; closing is **final**.
- **Flagged approvals** and **returns** require a **written note** (kept in the audit trail).
- A **stock take** is submitted by a manager and **approved by you**.
- **Disabling/deleting a station** is guarded: you cannot remove the last station, and deletion requires typing the station name.
- Everything you do applies to the **currently selected station**.