docker-swarm 集群搭建和使用

Name: 曲中岭

Email: zlingqu@126.com

Q Q :441869115

第一章 部署准备

1.1 目的

使用官方提供的 Swarm 工具搭建 Docker 集群,实现小规模 docker 集群的管理。

1.2 规划

OS : CentOS_7.5 x64

Host1 : 172.16.6.31 (docker01), manager 节点, 监听 TCP2377 Host1 : 172.16.6.31 (docker01), worker 节点, 监听 TCP2375

(manager 节点,默认也是 worker 节点,也会监听 2375)

Host2 : 172.16.6.32(docker02), worker 节点, 监听 TCP2375 Host3 : 172.16.6.33(docker03), worker 节点, 监听 TCP2375

Docker-ce : 18.09.0 Docker-ce : 18.09.0

Swarm : leatest (>1.2.8)

第二章 docker 安装

操作对象:

172.16.6.31

172.16.6.32

172.16.6.33

安装方法有很多,这里选择其中一种,rpm方式。

2.1 安装

添加 docker 源:

yum-config-manager --add-repo https://download.docker.com/linux/centos/docker-ce.repo

或者使用国内阿里云或者清华的源:

yum-config-manager --add-repo https://mirrors.aliyun.com/docker-ce/linux/centos/docker-ce.repo

yum-config-manager --add-repo

https://mirrors.tuna.tsinghua.edu.cn/docker-ce/linux/centos/docker-ce.repo

从指定源安装 docker-ce:

yum install docker-ce --enablerepo=docker-ce-stable -y

systemctl start docker

systemctl enable docker

查看是否开机运行:

systemctl list-unit-files|grep docker

2.2 确认

docker version

```
[root@docker01 ~]# docker version
Client:
Version:
                    18.09.0
                   1.39
 API version:
                    gol.10.4
 Go version:
                    4d60db4
 Git commit:
 Built:
                   Wed Nov 7 00:48:22 2018
 OS/Arch:
                    linux/amd64
 Experimental:
                    false
Server: Docker Engine - Community
Engine:
                   18.09.0
 Version:
 API version:
                    1.39 (minimum version 1.12)
 Go version:
                    gol.10.4
 Git commit:
                    4d60db4
 Built:
                   Wed Nov 7 00:19:08 2018
 OS/Arch:
                    linux/amd64
 Experimental:
                    false
```

2.3 ubuntu 安装(补充)

方法有很多,这里只说一种。

```
curl -sSL https://get.docker.com/ | sh
service start docker
sysv-rc-conf --list|grep docker
update-rc.d docker start 90 3 4 5 . stop 20 0 1 2 6 .
sysv-rc-conf --list|grep docker
docker version
```

第三章 修改配置

操作对象:

172.16.6.31

172.16.6.32

172.16.6.33

3.1 修改 hostname (可选)

按照规划,修改三台机器的 hostname 为 docker01、docker02、docker03

3.2 host 文件修改

三台机器的 host 文件分别添加如下内容

172.16.6.31 docker01

172.16.6.32 docker02

172.16.6.33 docker03

3.3 网络配置

Swarm 集群通信端口:

TCP2377

TCP7946

UDP 7946

UDP 4789

网络层要保证集群内部这些端口是相通的,比如 iptables 等配置。

第四章 swarm 启动

4.1 安装 swarm

在 manage 节点(172.16.6.31)上,执行如下命令安装 swarm

docker pull swarm

默认安装最新版(latest),我这里安装的是比 1.2.8 更新的一个版本,可到下面地址查看。 https://hub.docker.com/r/library/swarm/tags/

swarm ☆		
Last pushed: 4 months ago		
Repo Info Tags		
Tag Name	Compressed Size	Last Updated
1.2.9	4 MB	4 months ago
latest	4 MB	5 months ago
1.2.8	5 MB	a year ago
1.2.7	5 MB	a year ago

4.2 初始化

docker swarm init --advertise-addr 172.16.6.31

上面命令执行后,该机器自动加入到 swarm 集群。同时创建一个集群 token,获取全球唯一的 token,作为集群唯一标识。如图,token 是

SWMTKN-1-3ywwxc1twer3mqm3qhkvdqf5xo1z2j37ej67p0v42pen4xil6h-

27hwdp7hnwgdmtcwgpcky6q85

提示中还给出了:

其他 worker 节点如何加入这个集群的命令;

其他 manager 节点如何加入这个集群的命令。

--advertise-addr 参数表示其它 swarm 中的 worker 节点使用此 ip 地址与 manager 联系。

使用

docker node list

docker node Is

可以查看当前集群中已经有一个节点了,角色是 leader,即 manager 节点。

4.3 worker 节点加入集群

使用如下命令,将 worker 节点加入集群:

docker swarm join --token SWMTKN-1-

3ywwxc1twer3mqm3qhkvdqf5xo1z2j37ej67p0v42pen4xil6h-

27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377

[root@docker02 ~]# docker swarm join --token SMMTKN-1-3ywwxcltwer3mqm3qhkvdqf5xol22j37ej67p0v42pen4xil6h-27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377 This node joined a swarm as a worker. [root@docker02 ~]# [root@docker02 ~]# [

[root@docker03 ~]# docker swarm join --token SwMTKN-1-3ywwxcltwer3mqm3qhkvdqf5xolz2j37ej67p0v42pen4xil6h-27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377 This node joined a swarm as a worker.

在 manager 节点查看,集群有三个节点,其中 docker01 带有星号*标记,表示是 manager 节点

[root@docker01 ~]# docker no	ode list				
ID	HOSTNAME	STATUS	AVAILABILITY	MANAGER STATUS	ENGINE VERSION
j4737k9s35rvj09tij88ihuag *	docker01	Ready	Active	Leader	18.09.0
hbl8xfar2b909dy3hkukasavk	docker02	Ready	Active		18.09.0
pxlaq0t136a9izegt4i738yaj	docker03	Ready	Active		18.09.0
F+					

第五章 常用操作

5.1 节点离开集群

5.1.1 work 节点主动离开集群

worker 节点上执行命令,使 worker 节点离开集群

docker swarm leave

```
[root@docker02 ~]# docker swarm leave
Node left the swarm.
[root@docker02 ~]#
```

如图,使 docker02 离开集群,在 manage 节点查看,发现 docker 处于 down 状态

[root@docker01 ~]# docker no	de ls				
ID	HOSTNAME	STATUS	AVAILABILITY	MANAGER STATUS	ENGINE VERSIO
j4737k9s35rvj09tij88ihuag *	docker01	Ready	Active	Leader	18.09.0
hbl8xfar2b909dy3hkukasavk	docker02	Down	Active		18.09.0
pxlaq0t136a9izegt4i738yaj	docker03	Ready	Active		18.09.0
[root@docker01 ~]#					

5.1.2 从 swarm 删除 work 节点

如下如,可以删除一个处于 down 状态的节点

docker node rm ID|HOSTNAME

```
root@docker01 ~]# docker node ls
HOSTNAME
                                                                                         STATUS
                                                                                                                              AVAILABILITY
                                                                                                                                                                  MANAGER STATUS
                                                                                                                                                                                                       ENGINE VERSION
         ugwzxrhsrz5joq97ter
9s35rvj09tij88ihuag
                                                                                         Unknown
                                                                                                                             Active
Active
                                                                                                                                                                                                       18.09.0
18.09.0
18.09.0
18.09.0
                                                    docker01
bl8xfar2b909dy3hkukasavk
n3vwwkkgtdxnflvjk193r3yp
                                                    docker02
docker02
                                                                                                                             Active
Active
     q0t136a9izegt4i738yaj
ht@docker01 ~]#
root@docker01 ~]#
root@docker01 ~]#
root@docker01 ~]# docker node rm hbl8xfar2b909dy3hkukasavk
bl8xfar2b909dy3hkukasavk
root@docker01 ~]#
root@docker01 ~]#
root@docker01 ~]# docker node ls
                                                    HOSTNAME
                                                                                         STATUS
                                                                                                                              AVAILABILITY
                                                                                                                                                                  MANAGER STATUS
                                                                                                                                                                                                       ENGINE VERSION
          ugwzxrhsrz5joq97ter
9s35rvj09tij88ihuag
                                                                                                                             Active
Active
                                                                                         Unknown
                                                    docker01
                                                                                                                                                                                                       18.09.0
18.09.0
18.09.0
      wkkgtdxnflvjk193r3yp
µ0t136a9izegt4i738yaj
                                                    docker02
docker03
                                                                                                                             Active
Active
                                                                                         Ready
```

不能删除一个处于 ready 状态的集群,需要先执行 5.1.1 步骤,如果一定要删除,会报如下错误

```
[root@docker01 ~]# docker node rm un3vwwkkgtdxnflvjk193r3yp

Error response from daemon: rpc error: code = FailedPrecondition desc = node un3vwwkkgtdxnflvjk193r3yp is not down and can't be removed
[root@docker01 ~]#
[root@docker01 ~]#
```

可以使用-f参数,强制删除一个处于 ready 状态的集群

docker node rm -f \$ID

```
[root@docker01 ~]# docker node rm -f un3vwwkkgtdxnflvjkl93r3yp
un3vwwkkgtdxnflvjkl93r3yp
[root@docker01 ~]#
[root@docker01 ~]#
[root@docker01 ~]#
[root@docker01 ~]# docker node ls
ID HOSTNAME STATUS AVAILABILITY MANAGER STATUS ENGINE VERSION
C7mp3eugwzxrhsrz5joq97ter Unknown Active
j4737k9s35rvj09tij88ihuag * docker01 Ready Active Leader 18.09.0
pxlaq0tl36a9izegt4i738yaj docker03 Down Active 18.09.0
[root@docker01 ~]#
```

如果使用-f 强制删除一个处于 ready 状态的 worker 节点,如果要想再次加入,需要重新执行如下命令

docker swarm leave

测试效果如下图:

```
[root@docker02 ~]# docker swarm join --token SMMTKN-1-3ywwxc1twer3mqm3qhkvdqf5xo1z2j37ej67p0v42pen4xil6h-27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377
Error response from daemon: This node is already part of a swarm. Use "docker swarm leave" to leave this swarm and join another one.
[root@docker02 ~]#
[root@docker02 ~]# [root@docker02 ~]# docker swarm leave
Node left the swarm.
[root@docker02 ~]# docker swarm join --token SMMTKN-1-3ywwxc1twer3mqm3qhkvdqf5xo1z2j37ej67p0v42pen4xil6h-27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377
This node joined a swarm as a worker.
[root@docker02 ~]# [root@docker02 ~]#
[root@docker02 ~]# [root@docker02 ~]#
[root@docker02 ~]# [root@docker02 ~]#
```

5.1.3 manager 节点离开集群

当集群中只有最后一个 manager 节点时,使用如下命令可以强制离开集群,即销毁集群。

docker swarm leave -f

注意, 这时不可以使用如下命令删除

docker node rm -f I6oixj8ywv1pk5ngfmhwryyci

5.2 添加节点

5.2.1 添加 work 节点

在 manger 节点上使用

docker swarm join-token worker

获取 worker 的 token 及加入 worker 节点的命令

```
[root@docker01 ~]# docker swarm join-token worker
To add a worker to this swarm, run the following command:
    docker swarm join --token SWMTKN-1-3ywwxc1twer3mqm3qhkvdqf5xo1z2j37ej67p0v42pen4xil6h-27hwdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377
[root@docker01 ~]#
```

然后在 docker02 上运行改命令

```
[root@docker02 ~]# docker swarm join --token SWMTKN-1-3ywwxcltwer3mqm3qhkvdqf5xolz2j37ej67p0v42pen4xil6h-27hvdp7hnwgdmtcwgpcky6q85 172.16.6.31:2377
This node joined a swarm as a worker.
[root@docker02 ~]#
```

如下图,再次加入后,会重新分配一个 ID,原有的还是处于 down 状态

[root@docker01 ~]# docker no	de ls				
ID	HOSTNAME	STATUS	AVAILABILITY	MANAGER STATUS	ENGINE VERSION
c7mp3eugwzxrhsrz5joq97ter		Unknown	Active		
j4737k9s35rvj09tij88ihuag *	docker01	Ready	Active	Leader	18.09.0
hbl8xfar2b909dy3hkukasavk	docker02	Down	Active		18.09.0
un3vwwkkgtdxnflvjk193r3yp	docker02	Ready	Active		18.09.0
pxlaq0t136a9izegt4i738yaj	docker03	Ready	Active		18.09.0
[root@docker01 ~]#					
[root@docker01 ~]#					

对于如 5.1 主动离开的 worker 节点也可以使用这种方法,只是加入后会重新生成一个新的 ID、原有 ID 仍处于 down 状态、如上图。

5.2.2 添加 manager 节点

与 5.2 类似,不再演示,唯一的区别是,查询命令不同,如下。

docker swarm join-token manager

5.3 修改节点

5.3.1 节点的可用性

availablity 参数有

active: 调度器能够安排任务到该节点

drain: 调度器不能够安排任务到该节点,而且会停止已存在的任务,并将这些任务分配到

其他 Active 状态的节点

pause: 调度器不能够安排任务到该节点, 但是已经存在的任务会继续运行



可使用如下命令进行状态转换:

docker node update --availability drain \$ID|HOSTNAME docker node update --availability active \$ID|HOSTNAME docker node update --availability pause \$ID|HOSTNAME

5.3.1 状态转换

MANAGER STATUS 的三种状态

Leader: 为群体做出所有群管理和编排决策的主要管理者节点

Reachable: 如果 Leader 节点变为不可用,该节点有资格被选举为新的 Leader

Unavailable: 该节点不能和其他 Manager 节点产生任何联系, 这种情况下, 应该添加一个

新的 Manager 节点到集群,或者将一个 Worker 节点提升为 Manager 节点

提升节点:

docker node promote b10wegkpwtw9nr2t0aokzj804 docker node promote docker02

提升后变成 Reachable 状态

```
[root@docker01 ~]# docker node promote docker02
Node docker02 promoted to a manager in the swarm.
[root@docker01 ~]#
[root@docker01 ~]#
[root@docker01 ~]# docker node ls

ID HOSTNAME STATUS AVAILABILITY MANAGER STATUS ENGINE VERSION
19k2bso0tre4tj2fr74iia50k * docker01 Ready Active Leader 18.09.1
cjk3tie9qoamen8mmldf8tv85r docker02 Ready Active Reachable 18.09.1
jkwbd168rlxzqfa4ee517ryzq docker03 Ready Active 18.09.1
gmhhlrir23oc3kstibf44lsk5 docker04 Ready Active 18.09.1
[root@docker01 ~]#
```

降低节点:

docker node demote b10wegkpwtw9nr2t0aokzj804

第六章 服务管理

6.1 创建服务

manager 节点上操作:

docker service create --name my_web --replicas 3 --publish 8080:80 nginx:1.13 #创建 nginx 容器

docker service create --replicas 1 --name myping alpine ping <u>www.baidu.com</u> #创建 alpine 容器,执行 ping www.baidu.com 命令

docker service create 创建服务,以下是常见的选项:

- --name my_web 服务的名字,如果有多个副本,容器的名字以此为前缀
- --replicas 3 指定生成 3 个容器分片
- --mode global 在所有 worker 节点上都启动一个副本,和--replicas 参数冲突
- --publish 指定端口映射情况,类似于 docker run -p 参数,建议使用如下形式
- --publish published=8080,target=80 这种形式是新版风格
- --with-registry-auth 从私有仓库下载镜像而不是从官方,需要首先登陆,如下官网的例子
- \$ docker login registry.example.com
- \$ docker service create \
 - --with-registry-auth \
 - --name my_service \

registry.example.com/acme/my_image:latest

nginx 镜像名称,默认 latest 版本

注意:

启用服务的各个 worker 节点本地都会下载这个 nginx 镜像

6.2 查看服务

查看正在运行的服务列表:

docker service Is

```
[root@docker01 ~]# docker service ls

ID NAME MODE REPLICAS IMAGE PORTS

y0na80bujty5 helloworld replicated 1/1 alpine:latest

1n40fudxx5zz my_web replicated 3/3 nginx:latest *:9000->80/tcp

no2ueg017wqf myping replicated 1/1 alpine:latest

[root@docker01 ~]#

[root@docker01 ~]#
```

查看服务的详细信息:

docker service inspect --pretty my_web

```
[root@docker01 ~]# docker service inspect --pretty my_web
ID:
                 1n4ofudxz5zzw9bpq1dw7tgtp
                 my_web
Replicated
Name:
Service Mode:
Replicas:
Placement:
UpdateConfig:
 Parallelism:
 On failure:
                 pause
 Monitoring Period: 5s
 Max failure ratio: 0
 Update order:
                      stop-first
RollbackConfig:
 Parallelism:
 On failure: pause
Monitoring Period: 5s
Max failure ratio: 0
Rollback order: st
                     stop-first
                 nginx:latest@sha256:5d32f60db294b5deb55d078cd4feb410ad88e6fe77500c87d3970eca97f54dbafalse
ContainerSpec:
 Image:
 Init:
Resources:
Endpoint Mode: vip
Ports:
 PublishedPort = 9000
  Protocol = tcp
  TargetPort = 80
  PublishMode = ingress
```

查看正在运行服务的节点:

```
docker service ps my_web
 [root@docker01 ~]# docker service ps my_we
                             NAME
my_web.1
my_web.2
my_web.3
                                                            IMAGE
                                                                                                                        DESIRED STATE
                                                                                          NODE
                                                                                                                                                      CURRENT STATE
                                                                                          docker03
docker01
docker02
                                                                                                                                                     Running about an hour ago
Running about an hour ago
Running about an hour ago
hlpxts5rzse6
                                                            nginx:latest
                                                                                                                        Running
                                                           nginx:latest
nginx:latest
 wprhf6jx0ca3
fg7ph0kxtzt6
                                                                                                                       Running
Running
 [root@docker01 ~]#
```

6.3 扩容/缩容服务

即扩大或减少服务运行的副本数量,如下,扩容 my_web 的副本数从 3 到 5

docker service scale my_web=5

```
NAME
my_web.1
my_web.2
my_web.3
                                                                                                    IMAGE
                                                                                                                                                       NODE
docker03
docker01
docker02
                                                                                                                                                                                                          DESIRED STATE
Running
Running
Running
                                                                                                                                                                                                                                                            CURRENT STATE
Running about an hour ago
Running about an hour ago
Running about an hour ago
                                                                                                                                                                                                                                                                                                                                   ERROR
  lpxts5rzse6
prhf6jx0ca3
g7ph0kxtzt6
                                                                                                    nginx:latest
nginx:latest
nginx:latest
         ot@docker01 ~]#
ot@docker01 ~]#
ot@docker01 ~]#
  ~]#
~]# docker service ps my_web
NAME IMAGE
my_web.1 nginx:latest
my_web.2 nginx:latest
my_web.3 nginx:latest
my_web.4 nginx:latest
my_web.5 nginx:latest
                                                                                                                                                       NODE
docker03
docker01
docker02
docker01
                                                                                                                                                                                                           DESIRED STATE
                                                                                                                                                                                                                                                             CURRENT STATE
                                                                                                                                                                                                                                                            Running about an hour ago
Running about an hour ago
Running about an hour ago
Running 7 seconds ago
Running 7 seconds ago
                                                                                                                                                                                                          Running
Running
  prhf6jx0ca3
g7ph0kxtzt6
d86tcmg1uh7
4wl6x7wybtf
[root@docker01 ~]#
```

同样也可以使用此命令较少服务的副本数量。

6.4 删除服务

docker service rm my_web

[root@docker01 ~]# docker service rm my_web my_web

6.5 更新服务

例如使用如下命令创建 redis 服务, 版本是 3.0.6

docker service create \

- --replicas 3 \
- --name redis \
- --update-delay 30s \

redis:3.0.6

可以使用如下命令,对 redis 服务进行滚动更新。

docker service update --image redis:3.0.7 redis

默认情况下,调度程序一次更新 1 个任务。您可以传递该 --update-parallelism 标志以配置调度程序同时更新的最大服务任务数。

默认情况下,当对单个任务的更新返回状态时 RUNNING,调度程序会安排另一个任务进行更新,直到所有任务都更新为止。如果在更新任务期间的任何时间返回 FAILED,则调度程序会暂停更新。您可以使用或 --update-failure-action 标志来控制行为。

更新完成之后,查看服务,发现3.0.6都停止了,运行的都是3.0.7.

6.6 查看日志

```
docker service logs NAME
docker service logs –f NAME
```

6.7 回滚配置

比如修改了服务的副本数 4—>3,使用如下命令进行回滚操作

docker service rollback my_web

```
[root@docker01 ~]#
[root@docker01 ~]# docker service rollback my_web
my_web
service rolled back: rollback completed
```

回滚副本数量这个操作, 注意 4—>3—>4, 新的第四个节点相当于重新部署, 可能与其他三个节点不一致(比如修改了 html 页面)。

6.8 转移副本

接着上一节,使用如下命令

docker node update --availability drain docker01

将 docker01 节点设置为 drain 状态,则正如 5.3.1 所说,该节点将不再接受调度器的任务指派,并将已经指派过来(使用 swarm 分发而不是 docker run 启动的)的任务分配到其他 active 节点。

```
| Troot@docker01 ~]# docker service ps redis | ID NAME IMAGE NODE DESIRED STATE | CURRENT STATE gsc91lp44qeq redis.1 redis:3.0.7 docker03 Running Running 7 minutes ago 0ap6j2pycjjd \_redis.1 redis:3.0.6 docker03 Shutdown Shutdown 7 minutes ago Shutdown redis.2 redis:3.0.7 docker03 Running Running about a minute ago 0 krhuiypd3rit \_redis.2 redis:3.0.7 docker01 Shutdown Shutdown about a minute ago 0 krhuiypd3rit \_redis.2 redis:3.0.6 docker01 Shutdown Shutdown Shutdown about a minute ago 0 krhuiypd3rit \_redis.2 redis:3.0.6 docker01 Shutdown Shutdown Shutdown 6 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.7 docker02 Running Running 7 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker02 Shutdown Shutdown 8 minutes ago 0 krhuiypd3rit \_redis.3 redis:3.0.6 docker03 krhuiypd3rit \_redis.3 redis:3.0.6 do
```

此时,即使再次将其设置为 active 节点,只会对以后新的任务指派生效,而不会将已经调度出的任务再调度回来,如上图,不会将 docker03 上的 redis,再返回给一个给 docker01。

6.9 负载均衡测试

创建 4 个节点的 nginx,提供四个不同的首页内容

```
echo docker—01 >index.html
```

docker container cp index.html e2f62887015c:/usr/share/nginx/html

测试负载均衡, 发送 20 次请求到某个节点:

for i in {1..20}; do curl 172.16.6.33:8080 ;done

```
root@docker06 ~]# for i in {1..20}; do curl 172.16.6.33:8080 ;done
docker--02
docker-
docker-
docker-
docker-
docker
docker-
docker-
docker
docker
docker-
docker-
docker-
docker:
docker-
docker-
docker:
         02
docker--01
docker--03
```

返回内容符合前期规划。

测试发现,启动了四个 nginx 节点,只有两个可以正常接受请求,具体原因还待分析。

第七章 使用 swarm 模式路由

https://docs.docker.com/engine/swarm/ingress/#publish-a-port-for-a-service