Paddles (LSO) Comms Flow

vSFG7 SkyEye · Caucasus (Day / Night) + Foothold Syria, CVN-72 Abe · Marshal 306.300 → Paddles 128.300 AM · SkyEye main, 18 Oct 2026

Radios: Marshal 306.300 AM (COMM 1 CH 3) · **Paddles 128.300 AM** (no kneeboard preset yet: dial it on COMM 2). Paddles is SkyEye's LSO on the Abe, on Day, Night and Foothold. He talks you down the glideslope from Tacview: you fly, he calls. Replies below use Raider 302.

1. Marshal (306.300): get handed to Paddles

Pilot	Marshal
"Union Marshal, Raider 302, **three mile initial**" (or just "initial")	"Raider 302, Union Marshal, **contact paddles**, good luck." (or "switch to paddles" / "paddles has you")
"Raider 302, **switching paddles**" (optional; or "pushing paddles")	"Raider 302, Union Marshal, roger pushing paddles, good day."

Switch COMM 2 to 128.300. The rest of the recovery (check-in, stack, Charlie) is in the Comms Packet, Marshal cards.

2. Abeam (the 180)

Pilot	Paddles
"**302 abeam**" (or "Paddles, Raider 302, abeam")	"**Paddles contact, 302. In the groove at three-quarter mile, call the ball.**"
"Paddles, Raider 302, **radio check**" (or "comm check", "how copy")	"Raider 302, Paddles, loud and clear."

Give your modex or full callsign with abeam: Paddles answers with whichever you said.

3. The ball call (about 3/4 nm, on the glideslope)

Pilot	Paddles
"**302, Hornet ball, 5.5**" (modex, type, fuel state)	"**Roger ball.**"
"**302, Clara, 5.0**" (ball not in sight)	"Paddles contact, keep it coming."
No ball call by about 0.6 nm	"**Call the ball.**"

Any type works: Hornet, Super Hornet, Rhino, Tomcat, Viper, Goshawk ball. Say the modex first: with two jets in the groove it is how Paddles knows whose ball it is.

4. In the groove: Paddles calls, you fly (no readback)

You are...	Paddles says
A little high (0.7° or more)	"A little high."
High (1.2° or more)	"You're high." Still high 3 s later: "**You're high, bring it down.**"
Low (0.6° or more), far out	"You're low, power."
Low, inside about 0.6 nm	"**Power!**" Still low right after: "**POWER!**"
In close, well low (1°+) and still sinking	"**Power, power, POWER!**"
Coming up through the glideslope fast after a power call	"Easy with it."
Left of the landing line (1.5°+)	"Right for lineup." Far out and 3°+ left: "You're lined up left."
Right of the landing line (1.5°+)	"Come left." Far out and 3°+ right: "You're lined up right."
Off on-speed AoA by 2° (Hornet only)	"You're fast." / "You're slow."

Calls start at about 0.8 nm (1.3 nm once you've called the ball). One call at a time, at least 2 s apart, and the same call not again within 8 s. Low and lineup come before high: the most dangerous error gets the call. Over the ramp he says nothing but a wave-off.

5. Wave-offs and bolters

When	Paddles
Inside about 300 m (0.16 nm): more than 3 m below the glideslope, or 10 m off the landing line (300 - 600 m: 1.3° low or 5° off line)	"**Wave off, wave off, wave off.**"
Another aircraft on the landing area as you come inside about 550 m (0.3 nm)	"**Wave off, wave off, wave off, foul deck.**"
Touches down and rolls on well past the 4 wire	"**Bolter, bolter, bolter.**"
Trap	Nothing on the radio. Paddles logs the pass, his grade and the wire.

A wave-off is mandatory: power, climb straight ahead, then back to the pattern. After a bolter, fly the pattern and call the ball again on the next pass. Grades are not spoken yet; the squadron sees them in the server log next to DCS's own LSO grade.

Tips

Item	Detail
Your modex	Say it digit by digit ("three zero two" or "3-0-2"). The ball call needs only the modex, not the full callsign.
"Ball" heard as "bolt"	Speech recognition often writes "Hornet ball" as "Hornet bolt"; Paddles accepts it. Speak clearly and don't clip the start of the call.
Who is it?	Paddles is one voice (OpenAI), on 128.300 only, on the Caucasus Day and Night servers and Foothold (Syria).
No answer?	Wait 2-3 s, then repeat the ball call once. Check AM on 128.300. Report callsign, frequency and time on Discord.