# Basic

## **Evaluation Criteria**

- Scribe 5%
- Weekly Quizzes 20%
- Mid term 1 15%
- Mid term 2 15%
- Final Exam 45%

### **Protocol**

A protocol defines the format and the order of messages exchanged between two or more communicating entities, as well as the actions taken on the transmission and/or receipt of a message or other event.

## Packet Switching

- End systems exchange messages with each other.
- Long messages into smaller chunks of data known as packets.
- Between source and destination, each packet travels through communication links and packet switches
- Packets are transmitted over each communication link at a rate equal to the full transmission rate of the link. So, if a source end system or a packet switch is sending a packet of L bits over a link with transmission rate R bits/sec, then the time to transmit the packet is L/R seconds.
- Each packet can transfer via different path.

#### Store And Forward

Store-and-forward transmission means that the packet switch (router) must receive the entire packet before it can begin to transmit the first bit of the packet onto the outbound link (Maybe because we need to process header). Router can store multiple packets.

**Question:** Consider a simple network consisting of two end systems connected by a single router, as shown in the figure.

question Figure: [Kurose and Ross] Store-and-forward packet switching.

All links in the above figure have transmission rate R bits/sec. The source wants to send 4 packets of L bits each to the destination. If the source starts transmission of the first packet at time 0, at what time would the destination receive all the packets?

**Answer:** 2L/R + 3L/R = 5L/R.

## Delay in Packet-Switched Networks

- Processing Delay: The time required to examine the packets header and determine where to direct the packet is part of the processing delay. The processing delay can also include other factors, such as the time needed to check for bit-level errors in the packet that occurred in transmitting the packets bits from the upstream node to router A. Processing delay in high-speed routers are typically on the order of microseconds or less. After this nodal processing, the router directs the packet to the queue that precedes the link to router B.
- Queuing Delay: At the queue, the packet experiences a queuing delay as it waits to be transmitted onto the link. The length of the queuing delay of a specific packet will depend on the number of earlier-arriving packets that are queued and waiting for transmission onto the link. If the queue is empty and no other packet is currently being transmitted, then our packets queuing delay will be zero. On the other hand, if the traffic is heavy and many other packets are also waiting to be transmitted, the queuing delay will be long. Queuing delays can be on the order of microseconds to milliseconds in practice.
- Transmission Delay: Assuming that packets are transmitted in a first-come-first-served manner, as is common in packet-switched networks, our packet can be transmitted only after all the packets that have arrived before it have been transmitted. Denote the length of the packet by L bits, and denote the transmission rate of the link from router A to router B by R bits/sec. The transmission delay is L/R. This is the amount of time required to push (that is, transmit) all of the packets bits into the link.
- Propagation Delay: Once a bit is pushed into the link, it needs to propagate to router B. The time required to propagate from the beginning of the link to router B is the propagation delay. The bit propagates at the propagation speed of the link. The propagation speed depends on the physical medium of the link. The propagation delay is the distance between two routers divided by the propagation speed. That is, the propagation delay is d/s, where d is the distance between router A and router B and s is the propagation speed of the link. Once the last bit of the packet propagates to node B, it and all the preceding bits of the packet are stored in router B. The whole process then continues with router B now performing the forwarding.

## Circuit Switching

- Resources needed along a path (buffers, link transmission rate) to provide for communication between the end systems are reserved for the duration of the communication session between the end systems.
- A circuit in a link is implemented with either frequency-division multiplexing (FDM) or time-division multiplexing (TDM).
- In **FDM**, the frequency spectrum of a link is divided up among the connections established across the link. Specifically, the link dedicates a frequency band to each connection for the duration of the connection.
- TDM is considered to be a digital procedure which can be employed when the transmission medium data rate quantity is higher than the data rate requisite of the transmitting and receiving devices. In TDM, corresponding frames carry data to be transmitted from the different sources. Each frame consists of a set of time slots, and portions of each source is assigned a time slot per frame.
- Circuit Switching is basically used for real time applications
- Packet switching is better than circuit switching as even traditional applications of circuit switching such as phone calls is now being done with the help of packet switching which even allows for both of the things, i.e. internet and phone call to happen simultaneously (VoLTE). Also it can easily accommodate more sporadic users without change in configuration.

## **Protocol Layering**

Protocol Layering OSI Model Figure: [Kurose and Ross] The Internet protocol stack (a) and OSI (Open Systems Interconnection) reference model (b).

Layer interacts with layers only next to it.

Benefits of layering: \* We can modify a layer freely, i.e. tweak it. \* Layer acts as a wrapper which can be unwrapped at the other end.

### Application Layer

The application layer is where network applications and their application-layer protocols reside. (Like HTTP, FTP, DNS, etc) An application-layer protocol is distributed over multiple end systems, with the application in one end system using the protocol to exchange packets of information with the application in another end system. We'll refer to this packet of information at the application layer as a message.

### Transport Layer

The Internet's transport layer transports application-layer messages between application endpoints. In the Internet there are two transport protocols, TCP and UDP, either of which can transport application-layer messages. TCP provides a connection-oriented service to its applications. This service includes

guaranteed delivery of application-layer messages to the destination and flow control (that is, sender/receiver speed matching). TCP also breaks long messages into shorter segments and provides a congestion-control mechanism, so that a source throttles its transmission rate when the network is congested. The UDP protocol provides a connectionless service to its applications. This is a no-frills service that provides no reliability, no flow control, and no congestion control. We'll refer to a transport-layer packet as a segment.

### **Network Layer**

The Internet's network layer is responsible for moving network-layer packets known as datagrams from one host to another. The Internet's network layer includes the celebrated IP Protocol, which defines the fields in the datagram as well as how the end systems and routers act on these fields.

### Link Layer

The Internet's network layer routes a datagram through a series of routers between the source and destination. To move a packet from one node (host or router) to the next node in the route, the network layer relies on the services of the link layer. In particular, at each node, the network layer passes the datagram down to the link layer, which delivers the datagram to the next node along the route. At this next node, the link layer passes the datagram up to the network layer. Examples of linklayer protocols include Ethernet, WiFi. As datagrams typically need to traverse several links to travel from source to destination, a datagram may be handled by different link-layer protocols at different links along its route. We'll refer to the linklayer packets as frames.

### Physical Layer

While the job of the link layer is to move entire frames from one network element to an adjacent network element, the job of the physical layer is to move the individual bits within the frame from one node to the next. The protocols in this layer are again link dependent and further depend on the actual transmission medium of the link (for example, twisted-pair copper wire, single-mode fiber optics).

Encapsulation [Kurose and Ross] Hosts, routers, and link-layer switches; each contains a different set of layers, reflecting their differences in functionality.

Thus, we see that at each layer, a packet has two types of fields: header fields and a payload field. The payload is typically a packet from the layer above.