

Published on STAT 507 (https://onlinecourses.science.psu.edu/stat507)

Home > 10.3 - Sensitivity, Specificity, Positive Predictive Value, and Negative Predictive Value

10.3 - Sensitivity, Specificity, Positive Predictive Value, and Negative Predictive Value

In this example, two columns indicate the actual condition of the subjects, diseased or non-diseased. The rows indicate the results of the test, positive or negative.

Cell A contains true positives, subjects with the disease and positive test results. Cell D subjects do not have the disease and the test agrees.

A good test will have minimal numbers in cells B and C. Cell B identifies individuals without disease but for whom the test indicates 'disease'. These are false positives. Cell C has the false negatives.

If these results are from a population-based study, prevalence can be calculated as follows:

Prevalence of Disease= T_{disease}/ Total × 100

The population used for the study influences the prevalence calculation.

Sensitivity is the probability that a test will indicate 'disease' among those with the disease:

• Sensitivity: A/(A+C) × 100

Specificity is the fraction of those without disease who will have a negative test result:

• Specificity: D/(D+B) × 100

Sensitivity and specificity are characteristics of the test. The population does not affect the results.

A clinician and a patient have a different question: what is the chance that a person with a positive test truly has the disease? If the subject is in the first row in the table above, what is the probability of being in cell A as compared to cell B? A clinician calculates

Tratti					
	Disease (number)	Non Disease (number)	Total (number)		
Positive (number)	A (True Positive)	B (False Positive)	T _{Test} Positive		
Negative (number)	C (False Negative)	D (True Negative)	T _{Test} Negative		
	T _{Disease}	T _{Non Disease}	Total		

across the row as follows:

Positive Predictive Value: A/(A+B) × 100
 Negative Predictive Value: D/(D+C) × 100

Positive and negative predictive values are influenced by the prevalence of disease in the population that is being tested. If we test in a high prevalence setting, it is more likely that persons who test positive truly have disease than if the test is performed in a population with low prevalence..

Let's see how this works out with some numbers...

Hypothetical Example 1 - Screening Test A

100 people are tested for disease. 15 people have the disease; 85 people are not diseased. So, prevalence is 15%:

Prevalence of Disease:

 $T_{disease}$ / Total × 100, 15/100 × 100 = 15%

Predicted

Sensitivity is two-thirds, so the test is able to detect two-thirds of the people with disease. The test misses one-third of the people who have disease.

Sensitivity:
 A/(A + C) × 100
 10/15 × 100 = 67%

The test has 53% specificity. In other words, 45 persons out of 85 persons with negative results are truly negative and 40 individuals test positive for a disease which they do not have.

Specificity:
 D/(D + B) × 100
 45/85 × 100 = 53%

Observed

Truth

,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,				
	Disease (number)	Non Disease (number)	Total (number)	
Positive (number)	10 A (True Positive)	40 B (False Positive)	50 T _{Test Positive}	
Negative (number)	5 C (False Negative)	45 D (True Negative)	50 T _{Test Negative}	
	15 T _{Disease}	85 T _{Non Disease}	100 Total	

The sensivity and specificity are characteristics of this test. For a clinician, however, the important fact is among the people who test positive, only 20% actually have the disease.

Positive Predictive Value:
 A/(A + B) × 100

10/50 × 100 = 20%

For those that test negative, 90% do not have the disease.

 Negative Predictive Value: D/(D + C) × 100

$$45/50 \times 100 = 90\%$$

Now, let's change the prevalence..

Hypothetical Example 2 - Increased Prevalence, Same Test

This time we use the same test, but in a different population, a disease prevalence of 30%.

• Prevalence of Disease:

$$T_{disease}$$
/ Total × 10 30/100 × 100 = 30%

We maintain the same sensitivity and specificity because these are characteristic of this test.

Sensitivity:
 A/(A + C) × 100
 20/30 × 100 = 67%

Specificity:
 D/(D + B) × 100
 37/70 × 100 = 53%


Now let's calculate the predictive values:

Positive Predictive Value:
 A/(A + B) × 100
 20/53 × 100 = 38%

 Negative Predictive Value: D/(D + C) × 100 37/47 × 100 = 79% Truth

	Disease	Non Disease	Total
	(number)	(number)	(number)
Positive (number)	20 A (True Positive)	33 B (False Positive)	53 T _{Test Positive}
Negative (number)	10 C (False Negative)	37 D (True Negative)	47 Trest Negative
	30	70	100
	T _{Disease}	T _{Non Disease}	Total

Using the same test in a population with higher prevalence increases positive predictive value. Conversely, increased prevalence results in decreased negative predictive value. When considering predictive values of diagnostic or screening tests, recognize the influence of the prevalence of disease. The figure below depicts the relationship between disease prevalence and predictive value in a test with 95% sensitivity and 95% specificity:



Relationship between disease prevalence and predictive value in a test with 95% sensitivity and 85% specificity. (From Mausner JS, Kramer S: Mausner and Bahn Epidemiology: An Introductory Text. Philadelphia, WB Saunders, 1985, p. 221.)

Think About It!

Come up with an answer to this question and then click on the icon to the left to reveal the answer.

Under what circumstance would you really want to minimize the false positives?

Think About It!

Come up with an answer to this question and then click on the icon to the left to reveal the answer.

When would you want to minimize the false negatives?

What is a good test in a population? Actually, all tests have advantages and disadvantages, such that no test is perfect. There is no free lunch in disease screening and early detection.

Source URL: https://onlinecourses.science.psu.edu/stat507/node/71