How to identify the iSCSI software initiator node name (IQN) from a host operating system

Description

Every iSCSI node must have a node name. Node names typically take the iSCSI Qualified Name (IQN) format. The IQN-type designator is a logical name that is not linked to an IP address.

The following is an example format:

```
iqn.yyyymm.backward-naming-authority:unique-device-name
```

yyyy-mm is the month and year in which the naming authority acquired the domain name.

'backward-naming-authority' is the reverse domain name of the entity responsible for naming this device. An example reverse domain name is 'com.microsoft'.

'unique-device-name' is a free-format unique name for this device assigned by the naming authority.

The following example shows the iSCSI node name for an initiator that is an application server:

```
iqn.1991-05.com.microsoft:example
```

Note: Some initiators might provide variations on the preceding format.

An iSCSI initiator node name is used when associating an iSCSI host with a Data ONTAP initiator group (igroup) for the purpose of mapping a LUN to the host.

Procedure

The following are the procedures that can be used to identify the iSCSI initiator node name defined on a host for various operating system types.

Windows - GUI:

Open the **iSCSI Initiator Properties** dialog box:

```
Windows Server 2012 Server Manager > Dashboard > Tools > iSCSI Initiator >
Configuration
Windows Server 2008 Start > Administrative Tools > iSCSI Initiator >
Configuration
Windows Server 2003 Start > All Programs > Microsoft iSCSI Initiator >
Microsoft iSCSI Initiator
```

The exact label in the dialog box will differ depending on the Windows version.

The iSCSI initiator node appears similar to the following:

```
iqn.1991-05.com.microsoft:XXXXX
```

VMware ESXi - From vSphere Client:

1. Log in to the vSphere Client, and select an ESXi Host from the **Hosts and Clusters Inventory** panel.
2. Click the **Configuration** tab and click **Storage Adapters** in the **Hardware** panel. (A list of available storage adapters is displayed).
3. Select the vmhba under **iSCSI Software Adapter**.

The iSCSI initiator node name will be listed in the **Details** pane similar to the following:

```
iSCSI Name: iqn.1998-01.com.vmware:XXXXX-1-b6f00d9
```

Linux:

Run the following command:

```
cat /etc/iscsi/initiatorname.iscsi
```

The iSCSI initiator node name will be included in the resulting output similar to the following:

```
InitiatorName=iqn.1994-05.com.XXXXX
```

Solaris:

Run the following command:

```
iscsiadm list initiator-node
```

The iSCSI initiator node name will be included in the resulting output similar to the following:

```
Initiator node name: iqn.1986-03.com.XXX:01:0003bad935da.4906be64
```

AIX:

Run the following command:

```
lsattr -El iscsi0
```

The iSCSI initiator node name will be included in the resulting output similar to the following:

```
initiator_name iqn.XXX.YYY.ZZZ
```

HP-UX:

Run the following command:

```
iscsiutil -l
```

The iSCSI initiator node name will be included in the resulting output similar to the following:

```
Initiator Name :iqn.1986-03.com.hp:XXXXX
```

Reference:

https://kb.netapp.com/app/answers/answer_view/a_id/1032212/~/how-to-identify-the-iscsi-software-initiator-node-name-%28iqn%29-from-a-host