Install LMS Bridge in Moodle

Learning Mastery Support · free & open-source LTI 1.3 / Advantage tool · lmsbridge.app

You need LMS-admin access. Replace YOUR-HOST with your LMS Bridge address. These URLs (also at /api/v1/lti/config and the admin LMS (LTI) tab) are what the LMS needs:

OIDC login URL	`https://YOUR-HOST/api/v1/lti/login`
Launch / Target Link URI	`https://YOUR-HOST/api/v1/lti/launch`
Redirect URI	`https://YOUR-HOST/api/v1/lti/launch`
Public keyset (JWKS) URL	`https://YOUR-HOST/api/v1/lti/jwks`
Dynamic Registration URL	`https://YOUR-HOST/api/v1/lti/register`

Register (Dynamic Registration — recommended)

1. Site administration → Plugins → Activity modules → External tool → Manage tools.
2. Tool URL = https://YOUR-HOST/api/v1/lti/register → click Add LTI Advantage (not “Add Legacy LTI”).
3. Confirm in the LMS Bridge panel; the tool appears under Pending.
4. Activate it (Pending → Active) and set Show in activity chooser.

Manual alternative (“configure a tool manually”): Tool URL = /launch; LTI version = LTI 1.3; Public key type = Keyset URL = /jwks; Initiate login URL = /login; Redirection URI = /launch; Services: AGS = grade sync & column management, NRPS = retrieve members.

Moodle platform values (Tool configuration details → LMS Bridge)

Platform ID → issuer	`your Moodle base URL`
Client ID	`(generated by Moodle)`
Deployment ID	`(generated by Moodle)`
Auth request (auth_login_url)	`.../mod/lti/auth.php`
Access token (auth_token_url)	`.../mod/lti/token.php`
Public keyset (key_set_url)	`.../mod/lti/certs.php`

Identical across Moodle 4.0–5.2.

Instructor places it

Course → Edit mode → Add an activity or resource → LMS Bridge (or External tool → Preconfigured tool = LMS Bridge). Click Select content for deep linking.

After any launch, LMS Bridge auto-provisions the user, course, and role (no extra password). Free & open-source under AGPL-3.0. UI labels verified against current vendor docs (2025–2026); confirm against your LMS version. Full guide: docs/INSTALL_LTI.md.