
Chapter 9: Main Memory



Operating System Concepts – 10th Edition

Silberschatz, Galvin and Gagne ©2018





Objectives

- Explain the difference between a logical and a physical address and the role of the memory management unit (MMU) in address translation.
- Dynamic storage-allocation problem apply first-, best-, and worst-fit strategies for allocating memory contiguously.
- Explain the distinction between internal and external fragmentation.
- Translate logical to physical addresses in a paging system that includes a translation look-aside buffer (TLB).
- Describe hierarchical paging, and hashed paging
- Describe address translation for IA-32, x86-64, and ARMv8 architectures





- Background
- Contiguous Memory Allocation
- Segmentation
- Paging
- Structure of the Page Table
- Examples: the Intel 32 and 64-bit Architectures and ARM Architecture



Operating System Concepts - 10th Edition

9.2

Background

- Main memory is central to the operation of a modern computer system.
- Memory consists of a large array of bytes, each with its own address byte-addressable
- Program must be brought (from disk or secondary storage) into memory and placed within a process for it to run
- A typical instruction-execution cycle include
 - CPU first fetches an instruction from memory (or cache)
 - The instruction is then decoded and may cause operands to be fetched from memory.
 - After the instruction executed on the operands, results may be stored back in memory.
- The memory management unit or MMU only sees a stream of addresses
 - It does not know how they are generated, could be by the instruction counter, indexing, indirection, literal addresses, and so on or what they are for (instructions or data).
 - Accordingly, we are interested only in the sequence of memory addresses generated by a running program.





Background (Cont.)

- Main memory (including cache) and registers are the only storage CPU can access directly; in another word, CPU cannot access secondary storage such as disk directly, but through I/O controllers
- Memory management unit or MMU only sees a stream of addresses + read requests, or address + data and write requests
 - Registers can be accessed in one CPU clock (cycle)
 - Accessing main memory (through memory bus) may take many CPU clocks, causing a memory stall, when it does not yet have the data required to complete the instruction it is executing
 - Cache sits between main memory and CPU registers, residing on the CPU chip for fast access
- Protection of memory required to ensure correct operation
 - We must protect the operating system from access by user processes, as well as protect user processes from one another.
 - This protection must be provided by the hardware for performance




Operating System Concepts - 10th Edition

9

Silberschatz, Galvin and Gagne ©20

Hardware Address Protection

- Protection of memory space is accomplished by having CPU compare every address generated in user mode with these two registers
- The base and limit registers can be loaded only by the operating system, which uses a special privileged instruction (executed only in the kernel mode)
- The operating system, executing in kernel mode, however, is given unrestricted access to both operating-system memory and users' memory








Per-process memory space separated from each other

- Separate per-process memory space protecting the processes from each other is fundamental to have multiple processes loaded in memory for concurrent execution – multiprogramming system
- A pair of base and limit registers define the legal range of a process address space
 - For example, if the base register holds 300040 and the limit register is 120900, then the program can legally access all addresses from 300040 through 420939 (inclusive)



Operating System Concepts – 10th Edition

9.0



Silberschatz, Galvin and Gagne ©201



Address Binding

- Usually, a program resides on a disk as a binary executable file, which must be brought into memory and placed within a process (part of its address space) for it to run
- Most systems allow a user process to reside in any part of the physical memory. Although the computer may start at 00000, the first address of a user process need not be 00000
- A user program goes through several steps some of which may be optional before being executed. Addresses may be represented in different ways during these step:
 - Source code addresses usually symbolic the variable count
 - A compiler typically binds these symbolic addresses to relocatable addresses, such as "14 bytes from beginning of this module"
 - Linker or loader in turn binds the relocatable addresses to absolute addresses, i.e. 74014
 - Each binding is essentially a mapping from one address space to another






Multistep Processing of a User Program

Address binding of instructions and data to memory addresses can happen in three different stages

- Compile time: If memory location is known a priori. absolute code can be generated; must recompile code if starting location changes (e.g., "gcc"). MS-DOS uses this
- Link or Load time: Compiler must generate relocatable code if memory location is not known at compile time (e.g. Unix "ld" does link). The binding is delayed until load time. If the starting address changes, we need only reload the user code to incorporate this changed value
- **Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another. This needs hardware and operating system support for address maps (e.g., base and limit registers), e.g., dynamic libs. Most generalpurpose operating systems use this method.



Operating System Concepts - 10th Edition

Silberschatz, Galvin and Gagne ©2018



Address Translation and Protection

- In the old days of uni-programming, only one program can run at the time, thus it occupies "nearly" the entire physical memory
 - No address translation is needed, nor is there any protection
- In the earlier stage of multi-programming such as Windows 3.1 (1990-1992)
 - No address translation, binding occurs at link or loader time address adjusted when programs are loaded into memory. Bugs in programs can crash the system
 - Protection was added later using base and limit registers, preventing illegal access by another user program





Logical vs. Physical Address Space


- Recall: address space
 - All the addresses and space a process can "touch"
 - Each process has its own unique address space, different from kernel address space
- Consequently, there are two views of memory
 - Logical address generated by the CPU; also referred to as virtual address
 - Physical address address seen by the memory
 - The translation is done by memory management unit or MMU hardware device
- Translation makes it much easier to implement protection
 - To ensure a process can not access another process's address space.
- Logical and physical addresses are the same if compile-time and load-time addressbinding schemes are used (in old days); logical (virtual) and physical addresses differ only in execution-time address-binding scheme
 - Logical address space is the set of all logical addresses generated by a program
 - Physical address space is the set of all physical addresses generated by a program



Operating System Concepts – 10th Edition

Memory-Management Unit (MMU)

- MMU is a hardware mechanism that at runtime maps virtual address to physical address
- There are many different mapping methods, covered in the rest of this chapter
- To start, consider a simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
 - User programs never accesses the real physical addresses
- The user program deals with logical addresses; it never sees the real physical addresses
 - Execution-time binding occurs when reference is made to the actual location in memory



9.12





Contiguous Allocation

- Contiguous allocation is one of the early memory allocation methods
- Main memory is usually divided into two partitions one for operating system and one for user processes
- The operating system can be placed in either low memory addresses or high memory addresses, depending on many factors, such as the location of the interrupt vector
- Many operating systems (including Linux and Windows) place the operating system in high memory
- In a multi-programmed operating system, several user processes reside in memory at the same time. In contiguous memory allocation, each process contained in a single section of memory that is contiguous to the section containing the next process.



Operating System Concepts - 10th Edition


9.13

Silberschatz Galvin and Gagne ©201




Contiguous Allocation (Cont.)

- Multiple-partition allocations
 - Degree of multiprogramming is bounded by number of partitions
 - Variable-partition sizes (sized to a given process' needs)
 - Hole block of available memory; holes of various size are scattered throughout memory
 - When a process arrives, it is allocated memory from a hole large enough to accommodate it
 - Process exiting frees its partition, adjacent free partitions combined
 - Operating system maintains information about: a) allocated partitions; b) free partitions (hole)



Hardware Support for Relocation and Limit Registers

- Relocation register and limit register are used to protect user processes from each other, and from changing operating-system code and data
 - Relocation register contains value of the smallest physical address
 - Limit register contains range of logical addresses each logical address must be less than the limit register
 - MMU maps logical address dynamically



Operating System Concepts - 10th Edition

9.1

Silberschatz Galvin and Gagne @2018



Dynamic Storage-Allocation Problem

How to satisfy a request of (variable) size n from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough
- Best-fit: Allocate the *smallest* hole that is big enough
 - Must search entire list, unless ordered by size
 - Produces the smallest leftover hole intended not use it
- Worst-fit: Allocate the *largest* hole
 - Must also search entire list
 - Produces the largest leftover hole intended to reuse the remaining hole

Experiments have shown that both first fit and best fit are better than worst fit in terms of decreasing time and storage utilization. Neither first fit nor best fit is clearly better than the other in terms of storage utilization, but first fit is generally faster.



perating System Concepts - 10th Edition 9.15 Silberschatz, Galvin and Gagne ©2018 Operating System Concepts - 10th Edition

stem Concents – 10th Edition



Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiquous - scattered holes
 - The storage is fragmented into a large number of small holes.
- Internal Fragmentation memory allocated to a process may be larger than requested memory; this size difference is memory internal to a partition, but not being used



Operating System Concepts – 10th Edition



Fragmentation (Cont.)

- Reduce external fragmentation by compaction
 - Shuffle memory contents to place all free memory together in one large block
 - Compaction is possible only if relocation is dynamic, and is done at execution time. In another word, if relocation is static and is done at assembly or load time, compaction cannot be done
 - The compaction is expensive (time-consuming)
- The backing store has similar fragmentation problems, which will be discussed later
- Another solution is to permit logical address space of the processes to be *non-contiguous*, by dividing into multiple pieces (variable-sized segments or fixed-size pages), thus allowing a process to be allocated physical memory wherever such memory is available. These techniques include Segmentation and Paging



Operating System Concepts - 10th Edition

Segmentation-User View

- Memory-management scheme that supports user view of memory
- A program is a collection of segments. A segment is a logical unit such as:

main program procedure function

method

object


local variables, global variables

common block

stack


symbol table

arrays





Segmentation: Logical vs. Physical





Operating System Concepts - 10th Edition

Silberschatz, Galvin and Gagne ©2018

Operating System Concepts – 10th Edition

9.20



Segmentation Architecture

- The Logical address now consists of a two-tuple:
 - <segment-number, offset>,
- Segment table maps two-dimensional programmer-defined addresses (virtual address) into one-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory
 - limit specifies the length of the segment
- Both STBR and STLR stored in the PCB of a process
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates the number of segments used by a program;

segment number s is legal if s < STLR




Operating System Concepts – 10th Edition

Silberschatz, Galvin and Gagne ©2018

Segmentation Architecture (Cont.)

- Protection. each entry in segment table associates with:
 - validation bit = 0 ⇒ illegal segment
 - read/write/execute privileges
- A protection bit is associated with each segment; code sharing occurs at segment level
- Since segments vary in length, memory allocation for a segment is a dynamic storage-allocation problem
- External fragmentation still exists, but is much less severe than that in a contiquous allocation -since each segment is considerably smaller than the total memory space of a process






Operating System Concepts – 10th Edition

9.22




Example of Segmentation





Sharing of Segments



9.24



Operating System Concepts - 10th Edition



Summary - Segmentation

- Protection is easy in segmentation scheme in segment table
 - Code segment would be read-only, data and stack would be read-write (stores allowed), shared segment could be read-only or read-write
- Can address be outside the valid range?
 - Yes, this is how stack and heap are allowed to grow. For instance, stack takes fault, system automatically increases the size of stack
- The main problem with segmentation
 - It must fit variable-sized chunks into physical memory classical dynamic storage allocation problem
 - It may move processes multiple times to fit everything
 - External fragmentation



Operating System Concepts - 10th Edition

9.25

Silberschatz, Galvin and Gagne ©201



Address Translation Scheme

- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

page number	page offset			
р	d			
m - n	п			

 Total m bits logical address, the logical address space 2^m bytes, and the page size is 2ⁿ, the number of pages this logical address contains is 2^{m-n}





Paging

- Physical address space of a process can be non-contiguous; process is allocated physical memory whenever the physical memory space is available
 - Avoids external fragmentation
 - Avoids the problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
 - Usually the size is power of 2, between 4KB (12 bit offset) and 1 GB (30 bit offset) –
 defined by the hardware
- Divide logical memory into blocks of same size called pages the same size of a frame
- The OS needs to keep track of all free (physical) frames available in main memory
- To run a program of size N pages, need to find N free frames (non-contiguous) in memory and load the program into that
- A page table is used to translate logical to physical addresses keep track of allocated frames
- This, however, suffers from internal fragmentation in the last page/frame



Operating System Concepts – 10th Edition

9.26



Example of Paging Scheme

Suppose logical address of a system is

page number	page offset
р	d
20-bit	12-bit


- $\hfill\Box$ The page size 12 bits are used to offset into a page, the page size is $2^{12}=4\mbox{ KB}$
- 32 bits virtual address indicates virtual address space is $2^{32} = 4$ GB
- 20 bits page number, the number of page is 2²⁰





Paging Hardware

- The following outlines the steps taken by the MMU to translate a logical address generated by the CPU to a physical address:
 - Extract the page number p and use it as an index into the page table.
 - Extract the corresponding frame number f from the page table
 - 3. Replace the page number p in the logical address with the frame number f
- As the offset d does not change, it is not replaced, and the frame number and offset now comprise the physical address.




Operating System Concepts – 10th Edition

9.29



Paging Model of Logical and Physical Memory





Operating System Concepts - 10th Edition

9.30



Paging Example

- m=4 represents logical address of 16 bytes
- Logical address 0 is page 0, offset 0. Indexing into the page table, we find that page 0 is in frame 5. Thus, logical address 0 maps to physical address $20 = (5 \times 4) + 01$
- Logical address 3 (page 0, offset 3) maps to physical address 23 [= $(5 \times 4) + 3$].
- Logical address 4 is page 1, offset 0: according to the page table, page 1 is mapped to frame 6. Thus, logical address 4 maps to physical address $24 = (6 \times 4) + 0$].
- Logical address 13 maps to physical address 9.

0	a		0	
1	b			
0 1 2 3 4 5 6 7 8	c d			
3	d			
5	e f		4	
6		0 5		j k
7	g h i	1 6		ì
8	i	2 1	8	m
9	j	3 2		n
10	k			0
_11		page table		р
12 13	m n		12	
14	0			
15	p			
ogical r			16	
ogicai i	nemo	ory	10	
			20	a
				Ь
				a b c d
			24	e f g h
				a
				h
			28	
			_	
		phy	ysical	memory

n=2 and m=4 32-byte memory and 4-byte pages



Paging (Cont.)


- Calculating internal fragmentation
 - Page size = 2,048 bytes (2KB)
 - Process size = 72,766 bytes
 - 35 pages + 1,086 bytes
 - Internal fragmentation of 2,048 1,086 = 962 bytes
 - Worst case fragmentation = 1 frame 1 byte
 - On average fragmentation = 1 / 2 frame size
- So small frame sizes desirable?
 - The overhead involved in each page table entry reduces when page size increases.
 - Each page table entry takes memory to track, smaller page size leads to larger page table
- Page sizes has grow over the time
 - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
 - The programmer views memory as one single space, containing only this one program. But in fact, user program is scattered throughout physical memory, which also holds other programs.

9.32





Free Frames





Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table (starting address)
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
 - One for the page table (translation) and one for fetching the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)
- TLBs typically small (64 to 1,024 entries). Some CPUs implement separate instruction and data address TLBs
- On a TLB miss (if the page number is not in the TLB), value is loaded into the TLB for faster access next time. This can be done by hardware (MMU) or software (running kernel codes)
 - Replacement policies must be considered LRU, round-robin or even random are possible
 - Some entries can be wired down for permanent fast access, for example TLB entries for key kernel code for fast access



Operating System Concepts – 10th Edition

9.34

Associative Memory


Associative memory (TLB) – parallel search

Page #	Frame #

- Address translation (p, d)
 - Check all entries in parallel (hardware)
 - If p is in associative register, get frame # out
 - Otherwise get frame # from page table in memory, and also bring this entry to the TLB
- Locality on TLB
 - Instruction usually stays on the same page (sequential access nature)
 - Stack definitely has locality (pop in and out)
 - Data less locality, still quite a bit



Paging Hardware With TLB



9.36



Operating System Concepts – 10th Edition



Effective Access Time

- Associative Lookup = ε time unit
 - Usually < 10% of memory access time
- - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Effective Access Time (EAT)

EAT =
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$

= $2 + \varepsilon - \alpha$

- Consider α = 80%, ε = 20ns for TLB search, 100ns for memory access
 - EAT = 0.80 x 120 + 0.20 x 220 = 140ns
- Consider more realistic hit ratio -> α = 99%, ϵ = 20ns for TLB search, 100ns for memory access
 - EAT = 0.99 x 120 + 0.01 x 220 = 121ns



Operating System Concepts - 10th Edition

Silberschatz, Galvin and Gagne ©2018



Memory Protection

- Memory protection in paging is accomplished by protection bits associated with each frame. Normally, these bits are kept in the page table.
 - One bit can define a page to be read-write or read-only, or more bits to indicate execute-only
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space
 - "invalid" indicates that the page is not in the process' logical address space
 - The operating system sets this bit for each page to allow or disallow access to the page
- Any violations result in a trap to the kernel
 - Example: a 14-bit address space (0 to 16383). If a program only uses address 0 to 10468, with a page size 2KB, pages 0-5 are valid, pages 6-7 are invalid.
- Rarely does a process use all it address range, usually only a small fraction of the address space available. It would be wasteful to create a page table with entries for every page in the address range, and most of the table entries are unused but would take up memory space
 - use page-table length register (PTLR) to indicate the size of the page




Operating System Concepts - 10th Edition

9.38



Valid (v) or Invalid (i) Bit In A Page Table





Shared Pages


9.40

Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed

Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space







An Example: Intelx86 Page Table Entry

- What is in a Page Table Entry or PTE?
 - For page translation, each page table consists of a number of PTEs
 - Permission bits: valid, read-only, read-write, write-only
- Example: Intel x86 architecture PTE:
 - Address same format previous slide (10, 10, 12-bit offset)
 - Intermediate page tables called "Directories"

Page Frame Number (Physical Page Number)	Free (OS)	0	L	D	Α	PCD	PWT	U	w	Р
31-12	11-9	8	7	6	5	4	3	2	1	0

- P: Present (same as "valid" bit in other architectures)
- W: Writeable
- U: User accessible
- PWT: Page write transparent: external cache write-through
- PCD: Page cache disabled (page cannot be cached)
 - A: Accessed: page has been accessed recently
 - D: Dirty (PTE only): page has been modified recently
 - L: L=1⇒4MB page (directory only).

 Bottom 22 bits of virtual address serve as offset within a page



Operating System Concepts – 10th Edition

9.4

Silberschatz, Galvin and Gagne ©2018



Structure of the Page Table

- Memory structures for paging can grow huge using straight-forward methods
 - Consider a 32-bit logical address space as on modern computers
 - Page size of 4 KB (2¹²)
 - Page table would have 1 million entries (2³² / 2¹²)
 - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
 - > That amount of memory used to cost a lot
 - Page table cannot be allocated contiguously in main memory either, which will be allocated into multiple pages (frames) – paging the page table
 - Page size 4 MB (2²²) results in a page table with 1,000 entries, less of a problem
 - What about 64-bit logical address?
- Hierarchical Paging
- Hashed Page Tables



Operating System Concepts – 10th Edition

9.42

Silberschatz, Galvin and Gagne ©201




Hierarchical Page Tables

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- To page the page table



Two-Level Page-Table Scheme







Two-Level Paging Example

- A logical address (on 32-bit machine with 4K page size) is divided into:
 - a page number consisting of 20 bits
 - a page offset consisting of 12 bits
- Since the page table is paged, the page number is further divided into:
 - a 10-bit page number
 - a 10-bit page offset
- Thus, a logical address is as follows:

page nu	mber	page offset			
<i>p</i> ₁	p_2	d			
10	10	12			

- where p₁ is an index into the outer page table (in Intel architecture, this is called "directories", and p₂ is the displacement within the page of the inner page table
- because the address translation works from the outer page table inward, this scheme is also known as a forward-mapped page table



Operating System Concepts - 10th Edition

9.45

Silberschatz, Galvin and Gagne ©2018



64-bit Logical Address Space

- Even two-level paging scheme not sufficient
- If page size is 4 KB (2¹²)
 - Then page table has 2⁵² entries
 - If two level scheme, inner page tables could be 210 4-byte entries
 - Address would look like


outer page	inner page	page offset
<i>p</i> ₁	<i>p</i> ₂	d
42	10	12

- Outer page table has 2⁴² entries or 2⁴⁴ bytes
- One solution is to add a 2nd outer page table
- But in the following example the 2nd outer page table is still 2³⁴ bytes (16 GB) in size
 - And possibly 4 memory access to get to one physical memory location
 - The 64-bit UltraSPARC would require seven levels of paging a prohibitive number of memory accesses – to translate each logical address



4

Address-Translation Scheme





Operating System Concepts – 10th Edition

9.46

Silberschatz, Galvin and Gagne ©2018



Three-level Paging Scheme

outer page	inner page	offset
p_1	p_2	d
42	10	12


2nd outer page	outer page	inner page	offset
p_1	p_2	p_3	d
32	10	10	12





Hashed Page Tables

- Common in address spaces > 32 bits
- The virtual page number is hashed into a page table
 - This page table contains a chain of elements hashing to the same location
- Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element
- Virtual page numbers are compared in this chain searching for a match
 - If a match is found, the corresponding physical frame is extracted





Operating System Concepts – 10th Edition


9.49

Silberschatz, Galvin and Gagne ©2018



Example: The Intel IA-32 Architecture

- Supports both segmentation and segmentation with paging
 - Each segment can be 4GB (32bits), up to 16K segments per process (14 bits), divided into two partitions
 - First partition of up to 8 K segments are private to process (kept in local descriptor table (LDT))
 - Second partition of up to 8K segments shared among all processes (kept in global descriptor table (GDT))
- CPU generates logical address
 - Selector given to segmentation unit which produces linear addresses s for segment number, g indicates whether the segment is in LDT or GDT, p deals with protection



- · Linear address given to paging unit
 - > Which generates physical address in main memory
 - > Paging units form equivalent of MMU
 - > Pages sizes can be 4 KB or 4 MB



Example: The Intel 32 and 64-bit Architectures

- Dominant industry chips
 - 16-bit Intel 8086 (late 1970s) and 8088 was used in original IBM PC
- Pentium CPUs are 32-bit and called IA-32 architecture
 - It supports both segmentation and paging The CPU generates logical addresses, which are
 given to the segmentation unit. The segmentation unit produces a linear address for each
 logical address. The linear address is then given to the paging unit, which in turn generates the
 physical address in main memory.
- Current Intel CPUs are 64-bit and called IA-64 architecture
 - Currently most popular PC operating systems run on Intel chips, including Windows, MacOS, and Linux (Linux runs on several architectures as well)
 - Intel's dominance has not spread to mobile systems, where they mainly use ARM architecture
- Many variations in the chips, cover the main ideas here



Operating System Concepts – 10th Edition


9.50

Silberschatz, Galvin and Gagne ©2018



Intel IA-32 Segmentation

- Each entry in the LDT and GDT consists of an 8-byte segment descriptor with detailed information about a particular segment, including the base location and limit
- The segment register points to the appropriate entry in the LDT or GDT. The base and limit information about the segment is used to generate a linear address.



9.52






Intel IA-32 Segmentation

The linear address on the IA-32 is 32 bits long and is formed as follows

■ The limit is used to check for address validity. If the address is not valid, a memory fault is generated, trap to the operating system. If it is valid, the value of the offset is added to the value of the base, resulting in a 32-bit linear address.





Intel x86-64


- Current generation Intel x86-64 architecture
- 64 bits is ginormous (> 16 exabytes)
- In practice only implement 48 bit addressing
 - Page sizes of 4 KB, 2 MB, 1 GB
 - Four levels of paging hierarchy
- Can also use PAE (page address extension) so virtual addresses are 48 bits and physical addresses are 52 bits (4096 terabytes)

		page maj		page directory	,	page		page			
unused	_ k	level 4		pointer table	(directory		table	1	offset	
63	48 4	7	39.3	38 3	n 29	-	21 20		12 11		0





Intel IA-32 Paging Architecture



Operating System Concepts – 10th Edition


9.54

Silberschatz Galvin and Gagne ©2018



Example: ARM Architecture

- Dominant mobile platform chip (Apple iOS and Google Android devices for example)
- Modern, energy efficient, 32-bit CPU
- 4 KB and 16 KB pages
- 1 MB and 16 MB pages (termed sections)
- One-level paging for sections, two-level for smaller pages
- Two levels of TLBs
 - Outer level has two micro TLBs (one data, one instruction)
 - Inner is single main TLB
 - First inner is checked, on miss outers are checked, and on miss page table walk performed by CPU





Operating System Concepts – 10th Edition

End of Chapter 9



Operating System Concepts – 10th Edition