## **Switching Standard PD to SSD PD**

The following guide is the process that was used to switch the class of the persistent disk used by the database in production from standard to ssd.

- i. Take a manual backup of the database by following How to do a Manual Database Backup.
- ii. Delete the deployment: kubectl delete deployment backend-database
- iii. Delete the PVC: kubectl delete pvc backend-database-pv-claim
- iv. Manually generate the new manifests: kubails cluster manifests generate -tag \${COMMIT} --namespace master
  - Note: Specifically for the backend database manifests, the commit doesn't actually matter.
  - Note 2: Obviously, the new storage class must be specified in kubails.json before generating the new manifests.
- v. Deploy the database service again: kubails cluster manifests deploy backend-database --namespace master
- vi. Follow How to Restore a Postgres Dump to restore the backup taken in step 1.