

Hell Let Loose - RCON V2

Request Json Formatting

```
{
  "AuthToken": "bc711e97-e32e-4033-bf97-a8028a10cb94",
  "Version": 2,
  "Name": "command_name",
  "ContentBody": "command__data"
}
```

Request Parameters

Name	Type	Description
AuthToken	string	The AuthToken is a GUID which is created and retrieved from the Login request. The token must be sent with any server requests, except for ServerConnect and Login. The token is verified against the sever and will return a 401 status if no token is sent or the token is invalid.
Version	integer	As RCON tools are expanded commands may need updating.
Name	string	Name of the command to execute on the server.
ContentBody	string	Any data requirements for the request.

Response Json Format

```
HEADER_ID,
HEADER_CONTENT_LENGTH,
{
  "StatusCode": 200,
  "StatusMessage": "Successfully performed request."
  "Version": 2,
  "Name": "command_name",
  "ContentBody": "command_response_data"
}
```

Fixed Packet Header

The response header is an 8-byte fixed header that includes an ID and the content length of the Json package.

Name	Type	Description
ID	unsigned integer	Each response has its own ID. This ID increments with every request.
Content Length	unsigned integer	This is the length of the Json package, excluding the fixed header.

Response Parameters

Name	Type	Description
StatusCode	integer	The status of the server response whilst executing commands.
StatusMessage	string	Description of the status response
Version	integer	Version of the command that was processed.
Name	string	Name of the command that was processed.
ContentBody	string	Any response data from the server will be assigned in the body.

Status Codes

Server responses contain a status code, the status depends on whether the command was successfully executed on the server or if the command encountered an error.

Code	Description
200	OK
401	Unauthorized
400	Bad Request
500	Internal Error

Connecting to RCON V2

The server connect command will allow the server to start processing RCON V2 commands. Included in the server response body will be the XOR key used for encrypting/decrypting request and responses. The server connect command is currently the only non-encrypted command.

Request Example

```
{
  "AuthToken": "",
  "Version": 2,
  "Name": "ServerConnect",
  "ContentBody": ""
}
```

Response Example

```
{
  "statusCode": 200,
  "StatusMessage": "Successfully performed request.",
  "version": 2,
  "name": " ServerConnect",
  "contentBody": "OlguIHEAa4arqoOcaT0GbA\u003d\u003d "
}
```

XOR

C# Example

```
public static byte[] XORCipher(byte[] bytes)
{
    for (int i = 0; i < bytes.Length; i++)
    {
        bytes[i] ^= m_XORKey[i % m_XORKey.Length];
    }

    return bytes;
}
```

Logging in to RCON

Most commands require authentication before they can be executed. Calling the login command with a corresponding password will authenticate the server and generate a authentication token which is included in the response body.

Request Example

```
{
  "AuthToken": "",
  "Version": 2,
  "Name": "Login",
  "ContentBody": "[PASSWORD]"
}
```

Response Example

```
{
  "statusCode": 200,
  "StatusMessage": "Successfully performed request.",
  "version": 2,
  "name": "Login",
  "contentBody": "F95C9BC14AA1D8AE8BC328BEF230DF52"
}
```

RCON Commands

Name	ID	Description
Add Admin	AddAdmin	Add a player to the admin list.
Remove Admin	RemoveAdmin	Remove player from admin privileges.
Admin Log	AdminLog	Retrieve admin log.
Change Map	ChangeMap	Select a map to change the server map.
Change Sector Layout	ChangeSectorLayout	Configure the active sector layout
Add Map to Rotation	AddMapToRotation	Add a new map to the map rotation at an index.
Remove Map From Rotation	RemoveMapFromRotation	Remove map from the map rotation at an index.
Add Map to Sequence	AddMapToSequence	Add map to server map sequence.
Shuffle Map Sequence	ShuffleMapSequence	Randomises the server map queue.
Remove Map From Sequence	RemoveMapFromSequence	Remove map from the server map sequence.
Move Map in Sequence	MoveMapInSequence	Change the position on a map in the server queue
Server Connect	ServerConnect	Establishes an Rcon V2 connection with the server.
Login	Login	Authenticates a client to access the user.
Displayable Commands	DisplayableCommands	Retrieves the list of RCON commands.
Set Team Switch Cooldown	TeamSwitchCooldown	Set cooldown time for team switching.
Set Max Queued Players	SetMaxQueuedPlayers	Set the maximum number of queued players.
Set Idle Kick Duration	SetIdleKickDuration	Set how long a player can be idle before being kicked.
Send Server Message	SendServerMessage	Send a message to the server.
Server Information	ServerInformation	Retrieves various server information.
Server Broadcast	ServerBroadcast	Create a message to broadcast to the server.

Set High Ping Threshold	SetHighPingThreshold	Set the ping (in ms) that is considered too high for smooth gameplay.
Client Reference Data	ClientReferenceData	Retrieves argument details for a specific command.
Message Player	MessagePlayer	Create a message to send to a player in game.
Punish Player	PunishPlayer	Select a player to punish by killing.
Kick	Kick	Select player to kick and add a reason.
Temporary Ban	TempBan	Temporary ban a player from the server
Remove Temporary Ban	RemoveTempBan	Remove a temporary ban from a player.
Permanent Ban	PermanentBan	Permanently ban a player from the server.
Remove Permanent Ban	RemovePermanentBan	Remove permanent ban on a player
Set Auto Balance	AutoBalance	Enable or disable the auto balance.
Auto Balance Threshold	AutoBalanceThreshold	Set the threshold value for teams when using auto balance.
Reset Vote to Kick Threshold	ResetKickThreshold	Remove custom vote to kick thresholds and revert to default.
Enable Vote to Kick	VoteKickEnabled	Enable or disable the vote to kick functionality.
Set Vote to Kick Threshold	VoteKickThreshold	Set the vote to kick threshold.

Add Admin

Adds a player to an admin group.

Arguments

Parameter	Type
PlayerId	string
AdminGroup	string
Comment	string

Remove Admin

Removes the admin privileges from a player.

Arguments

Parameter	Type
PlayerId	string

Admin Log

Retrieves the admin log for the specified interval time (seconds).

Arguments

Parameter	Type
LogBackTrackTime	Int32
Filters	string

Change Map

Triggers a map change on the server.

Arguments

Parameter	Type
MapName	string

Change Sector Layout

Triggers a map restart and sets the objectives to the specified sectors.

Arguments

Parameter	Type
Sector_1	string
Sector_2	string
Sector_3	string
Sector_4	string
Sector_5	string

Add Map to Rotation

Adds a map to the map rotation at a specified index.

Arguments

Parameter	Type
MapName	string
Index	Int32

Remove Map from Rotation

Removes a map from the rotation list at a specified index.

Arguments

Parameter	Type
Index	Int32

Add Map to Sequence

Adds a map to the map sequence at a specified index.

Arguments

Parameter	Type
MapName	string
Index	Int32

Remove Map from Sequence

Remove a map from the map sequence at a specified index.

Arguments

Parameter	Type
Index	Int32

Shuffle Map Sequence

Randomises the map sequence.

Arguments

Parameter	Type
Enable	boolean

Move Map in Sequence

Moves a current map in the sequence to another location.

Arguments

Parameter	Type
CurrentIndex	Int32
NewIndex	Int32

Server Connect

Establishes connection with server and creates an RCON V2 session.

Login

Authenticates the RCON client with the server.

Arguments

Password is passed directly in the content body.

Displayable Commands

Retrieves a list of all commands in RCON V2.

Response

Name	Type	Description
Entries	array	List of commands available in V2.

Command Entry

Name	Type	Description
Id	string	ID of the command.
FriendlyName	string	Friendly name of the command.
IsClientSupported	boolean	Whether or not ClientReferenceData is supported for this command.

Set Team Switch Cooldown

Sets the cooldown time for allowing players to switch teams.

Arguments

Parameter	Type
TeamSwitchTimer	Int32

Set Max Queued Players

Sets the max number of players allowed to queue for the server.

Arguments

Parameter	Type
MaxQueuedPlayers	Int32

Set Idle Kick Duration

Sets the duration for kicking players for idling.

Arguments

Parameter	Type
IdleTimeoutMinutes	Int32

Send Server Message

Displays a message to all players on the server.

Arguments

Parameter	Type
Message	string

Server Information

Retrieves various information from the server.

Arguments

Parameter	Type
Name	string
Value	string

Request Example

```
{
  "AuthToken": "f95c9bc1-4aa1-d8ae-8bc3-28bef230df52",
  "Version": 2,
  "Name": "ServerInformation",
  "ContentBody": {
    "Name": "players"
    "Value": ""
  }
}
```

Response Example

```
{
  "statusCode": 200,
  "StatusMessage": "Successfully performed request."
  "version": 2,
  "name": "ServerInformation",
  "contentBody": "{
    "players": [
      {
        "name": "John Doe",
        "iD": "76561197960287930",
        "platform": "steam"
      }
    ]
  }"
}
```

Information Requests

Name	Value	Description
players	N/A	Retrieves a list of players in the server.
player	Player ID	Retrieves detailed information about a player.
maprotation	N/A	Retrieved a list of the maps in rotation.
mapsequence	N/A	Retrieved a list of the maps in the sequence.
session	N/A	Retrieves information about the current server session.
serverconfig	N/A	Retrieves information about the server.

Player Information

Name	Type	Description
Name	string	Platform name of player.
ClanTag	string	Players clan tag.
ID	string	Platform ID of the player.
Platform	string	Platform of the player.
EOSID	string	EOS ID of the player.
Level	Int32	Players career level.
Team	Int32	Players current team.
Role	Int32	Players current role.
Platoon	string	Players current platoon.
Kills	Int32	Players current kill count.
Deaths	Int32	Players current death count.
ScoreData	PlayerScoreData	Players current score.
Loadout	string	Players current loadout.
WorldPosition	vector	Players current world position.

Map Information

Name	Type	Description
Name	string	Name of the map.
GameMode	string	Name of the game mode.
TimeOfDay	string	Time variant of the map.
Id	string	ID of the map.
Position	Int32	Position in the rotation or sequence.

Session Information

Name	Type	Description
ServerName	string	Name of the server.
MapName	string	Current map playing on the server.
GameMode	string	Current game mode playing on the server.
MaxPlayerCount	Int32	Max players allowed on the server.
PlayerCount	Int32	Current player count on the server.
MaxQueueCount	Int32	Max players allowed to queue.
QueueCount	Int32	Current players queued for the server.
MaxVIPQueueCount	Int32	Max VIP count allowed to queue.
VIPQueueCount	Int32	Current queued VIP player count.

Server Configuration Information

Name	Type	Description
ServerName	string	Name of the server.
BuildNumber	string	Current build number for the server.
BuildRevision	string	Current build revision for the server.
SupportedPlatforms	Array<string>	Supported platforms on the server.

Server Broadcast

Broadcasts a message to the server.

Arguments

Parameter	Type
Message	string

Set High Ping Threshold

Sets the threshold for players with high ping.

Arguments

Parameter	Type
HighPingThresholdMs	Int32

Client Reference Data

Gets the data for creating dialogue options for commands that are client supported.

Arguments

Request Example

```
{
  "AuthToken": "f95c9bc1-4aa1-d8ae-8bc3-28bef230df52",
  "Version": 2,
  "Name": "ClientReferenceData",
  "ContentBody": "[Command ID]"
}
```

Response Content Body

Name	Type	Description
Name	string	ID of the command requested.
Text	string	Friendly name of the command requested.
Description	string	Description text of the command requested.
DialogueParameters	array	Retrieves information about the current server session.

Dialogue Parameter

Name	Type	Description
Type	string	Type of dialogue the parameter is meant for. Can either be: Combo, MultiSelect, Text or Number
Name	string	Name of the parameter.
Id	string	ID for the parameter. Used for creating request data for the server.
DisplayMember	string	Dialogue options for the parameter. Meant for client view.
ValueMember	string	Dialogue options for the parameter. Meant for server requests.

Message Player

Sends a message to a specific player.

Arguments

Parameter	Type
Message	string
PlayerId	string

Punish Player

Punishes a player by killing their character.

Arguments

Parameter	Type
PlayerId	string
Reason	string

Kick

Kicks a player from the server.

Arguments

Parameter	Type
PlayerId	string
Reason	string

Temporary Ban

Bans a player from the server for a certain duration.

Arguments

Parameter	Type
PlayerId	string
Duration	Int32
Reason	string
AdminName	string

Remove Temporary Ban

Removes a temporary ban from a player.

Arguments

Parameter	Type
PlayerId	string

Permanent Ban

Bans a player from a server permanently.

Arguments

Parameter	Type
PlayerId	string
Reason	string
AdminName	string

Remove Permanent Ban

Removes a permanent ban from a player.

Arguments

Parameter	Type
PlayerId	string

Set Auto Balance

Enables or disables team auto balancing for the sever.

Arguments

Parameter	Type
EnableAutoBalance	boolean

Auto Balance Threshold

Sets the player threshold number for team auto balancing.

Arguments

Parameter	Type
AutoBalanceThreshold	Int32

Enable Vote to Kick

Enables or disables the vote to kick functionality.

Arguments

Parameter	Type
Enabled	boolean

Reset Vote to Kick Threshold

Resets the vote to kick threshold.

Arguments

This command does not take any arguments.

Set Vote to Kick Threshold

Sets the vote to kick threshold.

Arguments

Parameter	Type
ThresholdValue	string