

Optimizing O2 Jobs

Optimize how YOU run on a shared environment







<u>Desktop Scenario</u>

Limited amount of computational resources available only to a single user.

Use all you can, even if not at peak efficiency.

HPC Cluster scenario

Large amount of computational resources shared between many users.


Using resources efficiently will benefit you and everyone in the system.



The O2 HPC cluster

The O2 cluster is composed of:

- Login Nodes, to connect remotely and submit jobs.
- *Compute nodes*, with high memory and multiple cores, to process many jobs simultaneously
- Storage nodes, for hosting the users data in O2
- *Scheduler*, handles O2 resources and dispatches jobs on computing nodes



O2 currently includes:

- 392 Compute Nodes - 12348 CPU cores - 108 TiB of RAM - 159 GPU cards



The Slurm scheduler



The Slurm scheduler handles resources allocation on the O2 cluster and also provides accounting information about past jobs and cluster utilization. Slurm periodically dispatches O2 jobs in two different ways:

• Direct Scheduling

At every cycle Slurm tries to dispatch pending jobs with the highest priority on available idle resources (memory, cpu cores, gpu). If it cannot find available resources to dispatch a given high priority job, Slurm will determine when and where the required resources will be available, and will schedule a future start time and node allocation for the high priority job.


• Backfill Scheduling

At every cycle Slurm tries to dispatch pending jobs with lower priority on available idle resources, <u>as long as</u> dispatching those lower priority jobs will not impact the expected start time of the higher priority jobs

In either cycle Slurm checks only a limited number of jobs per user, and it uses the "priority value" of each job as sorting criteria.



The Slurm scheduler





Why should you optimize your jobs?

There are three good reasons why you should invest some time and optimize how your jobs are being executed on a cluster environment.

1. Reduce pending time, increase your throughput and overall processing speed



2. Reduce the cost, if applicable



3. Avoid locking idle resources that could be allocated to other users



How to optimize your jobs

There are four factors that strongly impact jobs' efficiency in O2

Wasted resources on FAILED jobs



There were 6,44M of CPU hours from FAILED or CANCELLED jobs in 2021

Allocated but unused RAM



Allocated but unused CPU cores




• Overestimated or arbitrary wall-time




Allocating memory in O2 jobs

The scheduler allocates by default 1000 MiB of RAM for each requested CPU core.

Users can request a custom amount of memory per job using the flag --mem= and very often request much more memory than what is really needed.



VS



Allocating more memory than needed will:

- Unnecessarily increase the pending time of each job
- Consume more of your fair share, which will lower your jobs' priority
- Increase the utilization cost (when applicable)
- Stop other people's jobs from starting



Allocating memory in O2 jobs

There are two typical behaviors we see on the cluster:

- (A) users over-allocated memory for <u>all</u> jobs
- (B) users over-allocated memory for <u>99%</u> of the jobs. In this case it is always better to plan for the 99% and resubmit the failed 1%

In either case the users below would have <u>increased their throughput</u> and <u>reduced the cost</u> by requesting no more than 1/2 of the memory originally requested.

User	Njobs	AvgReqMem(GB)	AvgUsedMem(GB)	AbsMaxUsed(GB)	Njob>1/2Req	AvgCoreEff(%)	AvgWallTimeUsed(%)
	13	199.89	24.96	31.41	0	98.86	27.42
	61	48.24	0.17	1.00	0	98.61	3.92
	14	100.50	4.10	6.28	0	97.74	7.02
Α	430	50.00	1.39	3.99	0	99.61	3.93
	49	174.99	5.20	5.90	0	57.27	2.26
	7576	50.66	0.86	19.82	0	82.23	11.52
User	Njobs	AvgReqMem(GB)	AvgUsedMem(GB)	AbsMaxUsed(GB)	Njob>1/2Req	AvgCoreEff(%)	AvgWallTimeUsed(%)
	9307	24.68	3.93	81.19	17	95.78	3.09
В	252	62.20	11.02	32.53	1	85.54	6.26
	1110	113.92	27.36	181.75	13	27.30	3.67
week_ending_2			27.30	101.73	13	21.30	3.07
veek_ending_z	021-03-13 (LIND)					



Allocating CPU cores in O2 jobs

Users can request multiple CPU cores for their jobs. <u>Requesting more cores will not automatically increase the job's performance!</u>

The user requests several CPU assuming the job will run faster but...

- 1. The additional cores remain idle and no speedup is achieved. If your executable supports parallelization, make sure to pass any specific flag required.
- 2. The parallelization does not scale very well and the overall benefit cost balance is negative.

User	TotJobs	AverageCPU	Efficiency
	176	2.98	31.88 %
	126	9.49	14.88 %
	57	3.75	17.55 %
	301	7.86	68.09 %
	146	5.50	31.11 %
	31	6.00	53.57 %
	5	20.00	30.06 %

Allocating more CPU than needed will again:

- Unnecessarily increase the pending time
- Consume fair share, and lower jobs' priority
- Increase the utilization cost (when applicable)



Allocating wall-time in O2 jobs

The majority of users tend to overestimate the wall time required, often setting it to the maximum value allowed.

Requesting too much wall-time does not impact fair-share or cost, however it reduces the possibility of jobs being backfilled.

Combine together very small jobs in larger batches, with each job running at least for 15 minutes, very short jobs can spend more time pending than running.



90% of *COMPLETED* jobs used less than ½ of the requested wall-time

6925 0 0.31 % 0.04 short 100.00 % 15965 20 1.61 % 0.10 short 99.97 % medium 0.03 %	User	TotJobs	Njobs5X	%_Req_Time_Used	AVGelapsed	ı			%_Partion_	used			
		6925	0	0.31 %	0.04	1	short	100.00 %					
2302 172 1 90 % 0 76 short 61 21 % modium 39 66 % priority 0 17		15965	20	1.61 %	0.10	1	short	99.97 %	medium	0.03 %			
2302 172 1.80 % 0.76 short 61.21 % medium 38.66 % priority 0.13		2302	172	1.80 %	0.76	1	short	61.21 %	medium	38.66 %	priority	0.13 9	6
11064 2 1.96 % 0.02 short 99.99 % medium 0.01 %		11064	2	1.96 %	0.02	1	short	99.99 %	medium	0.01 %			

Allocating resources efficiently in O2 jobs

How can you check memory, cpu and wall-time utilization to optimize your future jobs?

1. Check the summary reports that RC sends weekly and adjust your required resources accordingly

Hello Raffaele.

Below you can find a short report about the memory, CPU and wall-time efficiencies for the **non-interactive** jobs you successfully completed (had state CD) over the last 7 days (since 2021-09-06).

We encourage you to check and, if needed, adjust the amount of memory, CPU and wall-time requested in order to maximize your job throughput and limit the amount of resources allocated but not used. Asking for fewer resources will usually make your jobs start running sooner, and will help other users' jobs run sooner as well.

User	Njobs	AvgReqMem(GB)	AvgUsedMem(GB)	AbsMaxUsed(GB)	Njob>1/2Req	AvgCoreEff(%)	AvgWallTimeUsed(%)
rp189	171	0.98	0.52	0.57	152	68.33	13.10

LEGEND

User

= your username (rp189)

Njobs = Number of jobs you ran over the last 7 days marked as completed. Failed, canceled and timed out jobs are not considered.

AvgRegMem = weighted average memory requested (in GB) by your jobs

AvgUsedMem = weighted average memory used (in GB) by your jobs

AbsMaxUsed = Absolute maximum amount of memory (in GB) used by your jobs

Njob>1/2Req = Number of jobs that used at least 1/2 or more memory than what was requested by the job. Ideally this number should match Njobs

AvgCoreEff(%) = Average CPU efficiency. Indicates how much CPU was actually used respect to the reserved CPU. Ideally this number should be at least > 70

Avgoried (%) = Average cro efficiency. Indicates now much cro was actually used respect to the reserved cro. Ideatty this number should be at least > 70

AvgWallTimeUsed(%) = Average percent of Wall—Time used. Indicates how much time your jobs actually ran respect to the requested wall—time. Ideally this number should be at least > 50

To get detailed information about resource usage for each job you can run the command O2sacct (O2sacct --help to get more info), and if you have any questions please let us know at rchelp@hms.harvard.edu (or respond to this email).

More information about job accounting and O2sacct can be found here: https://wiki.rc.hms.harvard.edu/display/O2/Get+information+about+current+and+past+jobs#Getinformationaboutcurrentandpastiobs-O2sacct

HMS Research Computing



Allocating resources efficiently in O2 jobs

How can you check memory, cpu and wall-time utilization to optimize your future jobs?

2. Use our *O2sacct* wrapper to see detailed information about a custom subset of jobs, see https://harvardmed.atlassian.net/l/c/XqnwHpgP for more details.

rp189@login03:~ 02sacct									
JobID	Partition	State	Nodelist	Start	TimeLimit	Elapsed	CPUefficiency_%	AllocTRES	MaxMemoryUsed
40740675	priority	COMPLETED	compute-e-16-233	2021-09-16T00:15:14	00:05:00	00:00:32	68.75	billing=1,cpu=1,mem=0.98G,node=1	
40740675.batch		COMPLETED	compute-e-16-233	2021-09-16T00:15:14		00:00:32	68.75	cpu=1,mem=0.98G,node=1	0.53G
40740675.extern		COMPLETED	compute-e-16-233	2021-09-16T00:15:14		00:00:32	0.00	billing=1,cpu=1,mem=0.98G,node=1	0
40741499	priority	COMPLETED	compute-a-16-164	2021-09-16T01:15:34	00:05:00	00:00:41	70.73	billing=1,cpu=1,mem=0.98G,node=1	
40741499.batch		COMPLETED	compute-a-16-164	2021-09-16T01:15:34		00:00:41	70.73	cpu=1,mem=0.98G,node=1	0.53G
40741499.extern		COMPLETED	compute-a-16-164	2021-09-16T01:15:34		00:00:42	0.00	billing=1,cpu=1,mem=0.98G,node=1	0
40743060	priority	COMPLETED	compute-a-16-162	2021-09-16T02:15:04	00:05:00	00:00:41	70.73	billing=1,cpu=1,mem=0.98G,node=1	
40743060.batch		COMPLETED	compute-a-16-162	2021-09-16T02:15:04		00:00:41	70.73	cpu=1,mem=0.98G,node=1	0.55G
40743060.extern		COMPLETED	compute-a-16-162	2021-09-16T02:15:04		00:00:41	0.00	billing=1,cpu=1,mem=0.98G,node=1	0
40743774	priority	COMPLETED	compute-a-16-162	2021-09-16T03:15:50	00:05:00	00:00:39	76.92	billing=1,cpu=1,mem=0.98G,node=1	
40743774.batch		COMPLETED	compute-a-16-162	2021-09-16T03:15:50		00:00:39	76.92	cpu=1,mem=0.98G,node=1	0.56G
40743774.extern		COMPLETED	compute-a-16-162	2021-09-16T03:15:50		00:00:39	0.00	billing=1,cpu=1,mem=0.98G,node=1	0



Allocating resources efficiently in O2 jobs

How can you check memory, cpu and wall-time utilization to optimize your future jobs?

3. Build your own custom query using Slurm native *sacct* command.

```
sacct -u $USER --units=G --format=<field1,field2,field3,...>
```

4. Ask for RCC help rchelp@hms.harvard.edu https://it.hms.harvard.edu/our-services/research-computing

login04:~ sacct -e			
Account	AdminComment	AllocCPUS	AllocGRES
AllocNodes	AllocTRES	AssocID	AveCPU
AveCPUFreq	AveDiskRead	AveDiskWrite	AvePages
AveRSS	AveVMSize	BlockID	Cluster
Comment	Constraints	ConsumedEnergy	ConsumedEnergyRaw
CPUTime	CPUTimeRAW	DBIndex	DerivedExitCode
Elapsed	ElapsedRaw	Eligible	End
ExitCode	Flags	GID	Group
JobID	JobIDRaw	JobName	Layout
MaxDiskRead	MaxDiskReadNode	MaxDiskReadTask	MaxDiskWrite
MaxDiskWriteNode	MaxDiskWriteTask	MaxPages	MaxPagesNode
MaxPagesTask	MaxRSS	MaxRSSNode	MaxRSSTask
MaxVMSize	MaxVMSizeNode	MaxVMSizeTask	McsLabel
MinCPU	MinCPUNode	MinCPUTask	NCPUS
NNodes	NodeList	NTasks	Priority
Partition	QOS	QOSRAW	Reason
ReqCPUFreq	ReqCPUFreqMin	ReqCPUFreqMax	ReqCPUFreqGov
ReqCPUS	ReqGRES	ReqMem	ReqNodes
ReqTRES	Reservation	ReservationId	Reserved
ResvCPU	ResvCPURAW	Start	State
Submit	Suspended	SystemCPU	SystemComment
Timelimit	TimelimitRaw	TotalCPU	TRESUsageInAve
TRESUsageInMax	TRESUsageInMaxNode	TRESUsageInMaxTask	TRESUsageInMin
TRESUsageInMinNode	TRESUsageInMinTask	TRESUsageInTot	TRESUsageOutAve
TRESUsageOutMax	$TRESUsage Out {\tt MaxNode}$	TRESUsageOutMaxTask	TRESUsageOutMin
TRESUsageOutMinNode	$TRESUsage 0 ut \verb MinTask $	TRESUsageOutTot	UID
User	UserCPU	WCKey	WCKeyID
WorkDir			



Questions?