VMware vCenter Converter Standalone 6.1 Release Notes

VMware vCenter Converter Standalone 6.1.1 | 16 FEB 2016 | Build 3533064

Note: Converter Standalone 6.1.1 | 16 FEB 2016 | Build 3533064 replaces the previously released VMware vCenter Converter Standalone 6.1 | 19 JAN 2016 | Build 3410145

Last Document Update: 16 FEB 2016

Check periodically for additions and updates to these release notes.

What's in the Release Notes

These release notes cover the following topics:

- Introduction to Converter Standalone
- · What's New
- Installation Notes
- Platforms
- Interoperability
- Supported Guest Operating Systems
- Prior Converter Standalone Releases
- Known Issues
- SDK Release Notes

Introduction to Converter Standalone

VMware vCenter Converter Standalone provides an easy-to-use solution to automate the process of creating VMware virtual machines from physical machines (running Windows and Linux) and other virtual machine formats. Through an intuitive wizard-driven interface and a centralized management console, Converter Standalone can quickly and reliably convert multiple local and remote physical machines without any disruptions or downtime.

Benefits

- Convert physical machines running Windows or Linux operating systems to VMware virtual machines quickly and without any disruption or downtime.
- Enable centralized management of remote conversions of multiple physical servers or virtual machines simultaneously.
- Ensure conversion reliability through quiesced snapshots of the guest operating system on the source machine before data migration.
- Enable non-disruptive conversions through hot cloning, with no source server downtime or reboot.

What's New

Note: The latest VMware vCenter Converter Standalone version is 6.1.1. If you are using VMware Converter Standalone 6.1, upgrade to VMware vCenter Converter Standalone 6.1.1 due to security fixes.

The VMware vCenter Converter Standalone 6.1 provides:

- Support for additional guest operating systems: Windows 10, Ubuntu 15.
- Offline conversions for HyperV 2012 R2 virtual machines.
- SSH key based authentication for the Linux sources during conversion.
- Support for VMware Workstation 12.

Top of Page

Installation Notes

You can download, install, and run VMware vCenter Converter Standalone in English only.

Users with limited rights cannot install Converter Standalone on Windows. You must log in as an administrator to install Converter Standalone.

Top of Page

Platforms

You can install VMware Converter Standalone 6.1 on the following platforms:

- Windows Vista SP2(32-bit and 64-bit)
- Windows Server 2008 SP2 (32-bit and 64-bit)
- Windows Server 2008 R2 (64-bit)
- Windows 7 (32-bit and 64-bit)
- Windows 8 (32-bit and 64-bit)
- Windows 8.1 (32-bit and 64-bit)
- · Windows Server 2012 (64-bit)
- Windows Server 2012 R2 (64-bit)
- Windows 10 (32-bit and 64-bit)

Top of Page

Interoperability

Converter Standalone 6.1 supports the following sources.

- Physical machine running an operating system noted in Supported Guest Operating Systems
- VMware Desktop products
 - Workstation 10.x, 11.x and 12.x
 - Fusion 6.x, 7.x and 8.x
 - Player 6.x, 7.x and 12.x
- VMware vCenter virtual machines
 - vSphere 6.0

- vSphere 5.5
- vSphere 5.1
- vSphere 5.0
- vSphere 4.1
- vSphere 4.0

Depending on the selected source, you can convert it to the following destinations.

- · VMware vCenter virtual machines
 - ESX 4.0 and 4.1
 - ESXi 4.0, 4.1, 5.0, 5.1, 5.5 and 6.0
 - vCenter Server 4.0, 4.1, 5.0, 5.1, 5.5 and 6.0
- VMware Desktop virtual machines
 - VMware Workstation 10.x, 11.x and 12.x
 - VMware Player 6.x and 7.x
 - VMware Fusion 6.x, 7.x and 12.x

Earlier releases of Converter Standalone (versions 3.x, 4.x and 5.x) might not be compatible with VMware vSphere 6.x.

Top of Page

Supported Guest Operating Systems

Converter Standalone 6.1 supports the following guest operating systems:

- Windows Vista SP2 (32-bit and 64-bit)
- Windows Server 2008 SP2 (32-bit and 64-bit)
- Windows Server 2008 R2 (64-bit)
- Windows 7 (32-bit and 64-bit)
- Windows 8 (32-bit and 64-bit)
- Windows 8.1 (32-bit and 64-bit)
- Windows Server 2012 (64-bit)
- Windows Server 2012 R2 (64-bit)
- Windows 10 (32-bit and 64-bit)
- CentOS 6.x (32-bit and 64-bit)
- CentOS 7.0 (64-bit)
- Red Hat Enterprise Linux 4.x (32-bit and 64-bit)
- Red Hat Enterprise Linux 5.x (32-bit and 64-bit)
- Red Hat Enterprise Linux 6.x (32-bit and 64-bit)
- Red Hat Enterprise Linux 7.x (64-bit)
- SUSE Linux Enterprise Server 10.x (32-bit and 64-bit)
- SUSE Linux Enterprise Server 11.x (32-bit and 64-bit)

- SUSE Linux Enterprise Server 12.x (64-bit)
- Ubuntu 12.04 (32-bit and 64-bit)
- Ubuntu 14.04.1 LTS(32-bit and 64-bit)
- Ubuntu 15.04 (32-bit and 64-bit)
- Ubuntu 15.10 (32-bit and 64-bit)

CAUTION: During cloning of powered on Linux machines, Converter Standalone 6.1 preserves the following source file systems on the destination: ext2, ext3, ext4, reiserfs, vfat, and xfs. All other source file systems are converted into ext3 or ext4 file systems on the destination virtual machine.

For more information about the operating systems supported by Converter Standalone and other system requirements, see the VMware vCenter Converter Standalone User's Guide.

Top of Page

Prior Releases of Converter Standalone

Features from prior releases of Converter Standalone are described in the release notes for each release. To view release notes for prior releases of Converter Standalone, click one of the following links:

- VMware Converter 6.0
- VMware Converter 5.5.3
- VMware Converter 5.5.2
- VMware Converter 5.5.1
- VMware Converter 5.5
- VMware Converter 5.1
- VMware Converter 5.0.1
- VMware Converter 5.0
- VMware vCenter Converter Standalone 4.3
- VMware vCenter Converter Standalone 4.0.1
- VMware vCenter Converter Standalone 4.0
- VMware Converter 3.0.3
- VMware Converter 3.0.2 Update 1
- VMware Converter 3.0.2

Top of Page

Known Issues

The Converter Standalone 6.1 release contains the following known issues:

- Installation
- General
- Windows Sources
- Linux Sources

Top of Page

Installation

- Converter Standalone installation fails when the selected installation folder name contains non-ASCII characters
- If the name of the Converter Standalone installation directory contains non-ASCII characters, you might experience conversion and configuration problems
- You must restart machines that run 64-bit Windows Vista or later before re-installing Converter Standalone
- Converter Standalone installer removes Workstation 6.5.x remote agents without notification
- · Users with limited rights cannot install Converter Standalone on Windows
- You cannot install vCenter Converter 4.2.1 on the same machine where you have already installed Converter Standalone 6.1

Converter Standalone installation fails when the selected installation folder name contains non-ASCII characters

Converter Standalone installation fails if the installation folder name contains non-ASCII characters and the OS locale is different than the locale of the characters. If there are characters from two different locales mixed in the folder name, the installation fails because there is always a character with different locale than the OS locale.

Workaround: Make sure that all the non-ASCII characters in the folder name are from the same locale as the OS locale.

If the name of the Converter Standalone installation directory contains non-ASCII characters, you might experience conversion and configuration problems

If the name of the Converter Standalone installation directory contains non-ASCII characters, the following issues might occur:

- Conversion and configuration of Windows virtual machines might fail with an error message Unable to reconfigure destination virtual machine. In the vmware-converter-worker.log, this error generates a message similar to Error 3 (error restoring key: Unknown error 3 (0x3) (3)) restoring registry key C:\ã-ā™āŸā•ā∢ān°...\data\SKUNKWORKS_FILLER into....
- If you try to convert a Linux physical machine, you might receive an error message in the Convert Machine wizard Unable to obtain hardware
 information.

You must restart machines that run 64-bit Windows Vista or later before re-installing Converter Standalone

If you uninstall Converter Standalone from a 64-bit Windows Vista, Windows Server 2008, or Windows 7 machine and do not restart it, a subsequent Converter Standalone installation might fail with the following error message:

Error 29144. Could not install service Vstor2 MntApi 1.0 Driver (shared). Please reboot and try to install again.

Workaround: Restart the Windows Vista, Windows Server 2008, or Windows 7 machine and try installing Converter Standalone again.

Converter Standalone installer removes Workstation 6.5.x remote agents without notification

When you use Workstation 6.5.x to hot-clone a Windows source machine, Workstation deploys a remote Workstation agent on the source. If you choose to leave the remote agent on that source and then install Converter Standalone on the same machine, the Converter Standalone installer uninstalls that agent without any warning messages.

Users with limited rights cannot install Converter Standalone on Windows

If you are logged in to Windows as a non-administrator user, the following error message is displayed while the InstallShield is extracting files for Converter Standalone installation:

Unable to save file:

C:\WINDOWS\Installer\

The system cannot find the path specified.

The error is displayed because limited users do not have the required write permissions.

Workaround: Select the %TEMP% directory to extract the installation files:

- 1. Click **OK** in the error message. A Save As dialog box appears.
- 2. Browse to the Temp folder of the current user (for example, C:\Documents and Settings\"username"\Local Settings\Temp) and click **OK**.

NOTE: You still need to log in as an administrator to install Converter Standalone.

You cannot install vCenter Converter 4.2.1 on the same machine where you have already installed Converter Standalone 6.1

If you install Converter Standalone 6.1 and then install vCenter Converter 4.2.1 server on the same machine, downloading the vCenter Converter 4.2.1 plug-in from vSphere Client fails.

Workaround: First install vCenter Converter 4.2.1 and then install Converter Standalone 6.1.

Top of Page

General

- Disk-based cloning of a powered off machine image to a Virtual Volumes datastore destination might fail
- Converter Standalone might display an incorrect version of the Windows operating system
- · Creation of virtual machine with thick destination disk type of certain size fails on VSAN datastore even if it seems to have enough space
- If you try to convert a source physical or virtual machine to a managed destination by using thick provisioned disks with large empty spaces on them, the conversion task might fail
- · When converting hosted virtual machines with unpartitioned disks, you might not be able to obtain hardware information about the source
- A running P2V conversion job fails if you create a new conversion job for the same Windows source machine and use a different port to deploy the Converter Standalone agent
- You cannot copy running conversion or configuration jobs
- Linked Cloning of source images greater than 2GB to a network share that does not support large files fails
- Creating a conversion job to convert a standalone VMware source with a VMDK file greater than 2GB from a network share that does not support large files, fails
- Converter Standalone cannot detect the power state of VMware Workstation or other VMware hosted source virtual machines if they are located on a read-only network share
- Conversion jobs from and to ESX hosts that are not connected to vCenter Servers fail if the number of disks on the source machine is more than nine
- Converting source volumes with unrecognized file systems might prevent the destination virtual machines from starting
- Converting standalone VMware sources with a VMDK file greater than 2GB to a hosted destination that resides on a network share that does not support large files, fails
- · Converter Standalone is unable to detect the system volume if it resides on a SCSI disk and IDE disks are present in the source machine
- If the hardware configuration of the source machine is modified while the Conversion wizard is open, you need to restart the conversion wizard if you want to view correct source details
- · Cloning a source that contains file system errors might result in a damaged virtual machine
- · Timeout on SSL handshake when converting over a WAN link
- User Account Control (UAC) prevents installing Converter Standalone agent if you are not using the default Administrator account to connect to a powered on source machine
- The Reconfigure Virtual Machine wizard does not display correctly the vDS port group name
- The reported network transfer rate might not be correct
- Adding a virtual machine to a domain might fail if you specify a fully qualified user name
- Conversion of a physical machine running Microsoft Windows XP or Windows Server 2003 with a BCD manager (Boot Manager for Windows Vista) and later might fail
- Submitting a job might fail with The specified parameter was not correct: "info.owner" message
- · You might not be able to convert more than nine disks at once

Disk-based cloning of a powered off machine image to a Virtual Volumes datastore destination might fail

You might not be able to perform a disk-based cloning of a powered off machine image to a Virtual Volumes datastore destination. The conversion might fail at 1%

with a message Operation expirienced network error if the size of the source disk is not a number that is a multiple of a MB. **Workaround:** Use volume-based cloning, if the option is available.

Converter Standalone might display an incorrect version of the Windows operating system

Converter Standalone might display incorrect operating system information for running machines or virtual machines with Windows 8.1 and Windows Server 2012 R2 and later.

- If the operating system is Windows 8.1, Windows 8 is displayed.
- If the operating system is Windows Server 2012 R2, Windows Server 2012 is displayed.

Workaround: None. Windows 8.1 and Windows Server 2012 R2 work as expected despite the incorrect operating system displayed.

Creation of virtual machine with thick destination disk type of certain size fails on VSAN datastore even if it seems to have enough space If you try to perform disk-based conversion with thick destination disk type of certain size on VSAN datastore, the creation of virtual machine might fail with the following error 'converter.fault.InsufficientManagedDiskSpace', even if it seems to have enough space.

Workaround: Change the destination disk type to thin.

If you try to convert a source physical or virtual machine to a managed destination by using thick provisioned disks with large empty spaces on them, the conversion task might fail

If you try to perform a disk-based cloning of a physical or virtual machine to a managed destination by using thick provisioned disks with large empty spaces on them, the conversion task might fail with an error message Unable to clone disk source_disk on the virtual machine virtual_machine_name. The following messages appear in the log file:

```
[03200 warning 'Default'] [,0] [NFC ERROR] NfcNetTcpRead: bRead: -1 [03200 warning 'Default'] [,0] [NFC ERROR] NfcNet_Recv: requested 264, recevied only 0 bytes [03200 warning 'Default'] [,0] [NFC ERROR] NfcFile_Stream: Failed to get message from source [03200 warning 'Default'] [,0] [NFC ERROR] NFC_NETWORK_ERROR
```

The destination ESX server must return an acknowledgement after each processed NFC write request. If the source sends a large block of zeroes that must be written it might take a long time for the ESX to return the acknowledgement. Thus, the Converter assumes that the operation has timed out and closes the connection, no matter that the ESX server is still writing to the target disk.

Workaround: Change the destination disk type to thin.

When converting hosted virtual machines with unpartitioned disks, you might not be able to obtain hardware information about the source When converting hosted virtual machines with unpartitioned disks, you might not be able to obtain hardware information about the source. In such case, the following error messages might appear in the worker log:

- [01628 warning 'Default'] Partition: Invalid sector magic number.
- [01628 warning 'Default'] ERROR: Failure during open: Reading disk signature
- [01628 error 'Default'] [BaseDiskSetComputer::DoOpen] OpenDisks failed, mntapi error: 32.

Workaround: Remove the unpartitioned disks from the conversion job.

A running P2V conversion job fails if you create a new conversion job for the same Windows source machine and use a different port to deploy the Converter Standalone agent

If, while running a P2V conversion job, you start creating another conversion job for the same powered on Windows source machine, and specify a port for the connection, Converter Standalone deploys the Converter Standalone agent using the port you specified. If the connection port is different from the one that is being used for the already running conversion job, both jobs fail. The following error message appears in the Job summary tab for the first conversion job: FAILED: A general system error occurred: No connection could be made because the target machine actively refused it. The following error message

appears in the Job summary tab for the second conversion job: FAILED: Unable to create a VSS snapshot of the source volume(s). Error code: 2147754774 (0x80042316).

You cannot copy running conversion or configuration jobs

If you open the Copy As New wizard for a running configuration or conversion job when the source is a virtual machine or a backup image and you click **Next**, the wizard displays the error message Unable to obtain hardware information for the selected machine.

Workaround: Wait for the job to complete before selecting Copy as New in its pop-up menu.

Linked Cloning of source images greater than 2GB to a network share that does not support large files fails

Creating linked clones from source images that are larger than 2GB to a network share that does not support large files (for example, to a Linux SMB share) fails. Converter Standalone does not split the source files into smaller chunks. If the source is larger than the supported file size on the destination, the conversion tasks fails.

Creating a conversion job to convert a standalone VMware source with a VMDK file greater than 2GB from a network share that does not support large files, fails

If you select a standalone virtual machine source with VMDK file greater than 2GB residing on a remote network location that does not support large files (for example, Linux SMB share), the following error message appears in the Converter wizard on clicking **Next** or **View source details**:

Unable to obtain hardware information for the selected machine.

Workaround: Map the network shared folder to the machine where Converter Standalone runs, and select the source from there.

Converter Standalone cannot detect the power state of VMware Workstation or other VMware hosted source virtual machines if they are located on a read-only network share

If the source machine is a Workstation or another VMware hosted source and is located on a network share with read-only permissions, Converter Standalone cannot detect if the source is powered on or suspended. This might lead to data inconsistency on the destination machine if changes are made to the powered on source virtual machine during conversion.

Workarounds:

- Verify that the source virtual machine is powered off prior to conversion.
- Provide write privileges to the network share where the source virtual machine resides.

Conversion jobs from and to ESX hosts that are not connected to vCenter Servers fail if the number of disks on the source machine is more than nine

When converting a source machine that has more than nine disks, conversion fails with the following error in the log file:

Error on logout (ignored): Operation timed out

SSLStreamImpl::BIORead (3BBA4E8) timed out.

The error is due to the limited number of NFC connections that can be established to ESX hosts that are not connected to vCenter Server instances.

Workaround: Connect to the destination ESX host through a vCenter Server. In this case, the number of source disks is limited to 27 for ESX and to 23 for ESX hosts.

Converting source volumes with unrecognized file systems might prevent the destination virtual machines from starting

While you are setting up a volume-based cloning task in one of the Converter Standalone wizards, the volume name might be missing in some rows of the **Source Volumes** tab. This means that Converter Standalone does not recognize the file system on those volumes. The destination virtual machine that is created as a result of such a conversion task might fail to start up. Nevertheless, Converter Standalone copies the source volume data to the destination using block-level copying. **Workaround:** configure the destination virtual machine after the conversion.

Converting standalone VMware sources with a VMDK file greater than 2GB to a hosted destination that resides on a network share that does not support large files, fails

If you select a standalone virtual machine source with VMDK file greater than 2GB and try to convert it to hosted destination residing on a remote network location that does not support large files (for example, Linux SMB or NFS share), the conversion job might fail with one of following error messages:

- Unable to connect to the virtual disk
- Remote server closed connection after 0 response bytes read
- An error occurred during an operation on a virtual disk

If conversion is successful, the following error message related to the VMDK file might appear when you power on the destination virtual machine: Internal Inconsistency errors

Workaround:

- 1. In the main application window of Converter Standalone, right-click the failed job and select Copy As New...
- 2. Go to the Options page and select **Data to Copy**.
- 3. In the Data to Copy pane, select the volumes to copy and click **Advanced**.
- 4. On the **Destination layout** tab, select **Split not pre-allocated** or **Split pre-allocated** as the destination disk type.
- 5. Click **Next** to view a summary of the conversion job.
- 6. On the Ready to Complete page, click **Finish** to resubmit the job.

Converter Standalone is unable to detect the system volume if it resides on a SCSI disk and IDE disks are present in the source machine

On source machines with SCSI and IDE disks, Converter is unable to detect the system volume if the system volume resides on a SCSI disk. Converter only checks the first IDE disk in such configurations.

If the hardware configuration of the source machine is modified while the Conversion wizard is open, you need to restart the conversion wizard if you want to view correct source details

Source machine details are retrieved per wizard session, as this is a time-consuming process. If some changes occur on the source machine (such as adding memory or hard drives) after this information is retrieved, the Conversion wizard does not show information about the changes.

Workaround: Restart the conversion wizard.

Cloning a source that contains file system errors might result in a damaged virtual machine

See Cloning a source that contains file system errors may result in a damaged copy (KB 1006689).

Timeout on SSL handshake when converting over a WAN link

Converter Standalone does not support conversion over a WAN. When trying to perform a conversion over a WAN link, you might experience an SSL timeout because the timeout for SSL handshakes is two minutes.

Workaround:

- 1. To avoid the two-minute handshake, perform a conversion to a hosted destination machine (for example, Workstation) in the same LAN.
- Copy the temporary virtual machine and send it over the WAN to the remote site.If the intended destination is a Workstation virtual machine, this completes the process.
- 3. If the intended destination is ESX, import the Workstation virtual machine to the ESX server.

User Account Control (UAC) prevents installing Converter Standalone agent if you are not using the default Administrator account to connect to a powered on source machine

If you are setting up a task to convert a powered on source machine that runs Windows Server 2008, Windows Vista, Windows 7, Windows Server 2012, or Windows 8 and you use a non-default Administrator account to log in to the source machine, the following error message might appear when you try to install Converter Standalone agent on the source machine: Insufficient permissions to connect to xxxxxxxx. Here xxxxxxxx is the IP address of the source machine. This is because Converter Standalone server cannot install Converter Standalone agent when UAC is enabled and you are logged in to the source as non-default Administrator user.

Workaround: Disable the UAC on the source machine before you start the Conversion wizard. You can search the Microsoft Web site for procedures on disabling the UAC depending on the source operating system. For Windows Server 2012 and Windows 8, in addition to disabling UAC, you must perform the following steps:

- 1. In the Windows Start menu, type gpedit.msc. The Local Group Policy Editor opens.
- 2. Navigate to Computer Configuration > Windows Settings > Security Settings > Local Policies > Security Options.
- 3. Disable the Run all administrators in Admin Approval Mode setting.
- 4. Restart.

The Reconfigure Virtual Machine wizard does not display correctly the vDS port group name

When you reconfigure a virtual machine that uses dvSwitch and you navigate to the Network interface settings pane, the Network name text box does not display the

name of the dvSwitch after the port group name. Only port group is displayed instead.

The reported network transfer rate might not be correct

The reported network transfer rate might be higher than the actual one because of the inherent compression used by the network protocol. This does not affect the network throttling.

Adding a virtual machine to a domain might fail if you specify a fully qualified user name

When configuring a virtual machine, you might not be able to add the virtual machine to a domain if you use a fully qualified user name (DOMAIN NAME\USER NAME).

Workaround: Specify the user name without including the domain name.

Conversion of a physical machine running Microsoft Windows XP or Windows Server 2003 with a BCD manager (Boot Manager for Windows Vista) and later might fail

If you try to convert a physical machine with a BCD manager, the P2V conversion might fail in the following cases:

- Microsoft Windows Vista or later is installed on the source physical machine, which is a dual-boot machine currently running Microsoft Windows XP or Windows Server 2003.
- Microsoft Windows Vista or later is installed as a second operating system on the source physical machine and later is removed, but the BCD manager is left on the source machine.

Workaround 1: In case of a dual-boot machine conversion:

- 1. Boot the later version of Windows (Windows Vista, Windows Server 2008, or Windows 7).
- 2. Perform a physical source conversion.
- 3. On the newly created virtual machine, boot a repair CD for the earlier version of Windows (Windows XP or Windows Server 2003).
- 4. Remove the BCD manager and revert the operating system to its compatible boot process.
- 5. Shut down the virtual machine and reconfigure it by using the Converter Standalone configuration wizard. Now you can boot the machine.

Workaround 2: In case of converting a source machine running Windows XP or Windows Server 2003 with a BCD manager:

- 1. On the source machine, boot a repair CD of the corresponding operating system.
- 2. Remove the BCD manager and revert the operating system to its compatible boot process.

For more information on how to repair BCD, see the Microsoft knowledge base article Windows no longer starts after you install an earlier version of the Windows operating system in a dual-boot configuration.

Submitting a job might fail with The specified parameter was not correct: "info.owner" message

If Converter Standalone is installed in a client-server mode and you have connected by using a username, which is the same as the computer name, submitting a job might fail with The specified parameter was not correct: "info.owner" message.

Workaround: Connect by using a different user account with administrative rights.

You might not be able to convert more than nine disks at once

On ESX 3.5 and 4.0, conversion might fail if you try to convert more than nine disks.

Workaround: Perform conversion in multiple steps to convert the disks in portions of up to nine. Then, attach all the disks to the target machine.

Windows Sources

- The P2V conversion of a Windows Vista source machine with the Min size option selected for some volumes fails with error 112: "There is not enough space on the disk."
- Customization is not applied on Windows source machines running Microsoft Windows 8, Windows 8.1 or Windows 10 guest operating systems
- Conversion job with no volume selected for shrinking fails with the following error message: 'An error occurred during the conversion: 'Block level cloning does not support shrinking volumes'

- Unsupported guest operating systems are labeled Other and fail to assign correct values for disk and network controllers
- If you convert a source machine with Windows 2008 and above operating system, some disk(s) may be be offline or read-only
- · Configuration of Windows virtual machines with multiple active partitions might not complete
- Conversion of a local powered on source machine fails at 1%
- Converter Standalone worker process stops responding if you try to copy a configuration job during guest operating system customization
- Subsequent P2V conversions of remote source machines that run 64-bit Windows Vista or later might fail after a successful conversion
- Converter Standalone does not preserve disabled network adapters during conversion of physical machine sources that run on Windows
- Microsoft Windows Vista reboots repeatedly after customization
- Converter Standalone does not support cloning powered on Windows Server 2008 sources with FAT/FAT32 volume file system
- Converter Standalone remote agent does not notify the user about Converter 3.0.x or 4.0.x remote agents that have been installed on the source system during remote hot cloning process
- Previous Converter versions cannot convert source machines that have Converter Standalone 6.0 agent installed on them
- Stopping Converter Standalone processes during file-level cloning might cause the machine that runs the Converter Standalone server service to restart
- · Converter Standalone does not change PIC HAL to APIC HAL during conversion of Windows source machines
- Owner name and organization are not displayed properly after customizing the guest operating system
- Converter can convert FAT/FAT32 volumes during hot cloning only if the source machine has at least one NTFS volume
- · Converter Standalone agent does not start automatically after reboot
- The source virtual machine does not have the appropriate drivers
- Sysprep deletes drive letter mappings during customization
- You cannot import a Windows source with "signature()" in the boot.ini file

The P2V conversion of a Windows Vista source machine with the Min size option selected for some volumes fails with error 112: "There is not enough space on the disk."

Checking the used space on the source machine shows that the data can fit on the destination volume.

Workaround: On the source machine, run the following command "vssadmin list shadowstorage" and check the text of the message. If it says "Allocated Shadow Copy Storage space: 300 MB" or some other value for allocated space on the problematic volume, it means that there are hidden shadow copy files placed in the volume. Increase the size of the destination volume with the required amount for the hidden files.

Customization is not applied on Windows source machines running Microsoft Windows 8, Windows 8.1 or Windows 10 quest operating systems

After the conversion of a Windows source machine with Windows 8, Windows 8.1 or Windows 10 guest operating system the selected customization options are not applied on the resulting VM. There is a c:\sysprep folder, and the c:\windows\system32\sysprep\panther\setuperr.log file contains similar lines: 2015-12-04 01:51:21, Error SYSPRP Failed to remove staged package Microsoft.Windows.Photos_15.1120.13270.0_x64__8wekyb3d8bbwe:

0x80070002. [gle=0x000000002] 2015-12-04 01:51:21, Error SYSPRP Failed to remove apps for the current user: 0x80070002.

2015-12-04 01:51:21, Error SYSPRP Exit code of RemoveAllApps thread was 0x2.

2015-12-04 01:51:21, Error SYSPRP Failed to remove all apps: 0x80070002.

2015-12-04 01:51:21, Error [0x0f0082] SYSPRP ActionPlatform::LaunchModule: Failure occurred while executing 'SysprepGeneralize'

from C:\Windows\System32\AppxSysprep.dll; dwRet = 0x2

2015-12-04 01:51:21, Error SYSPRP ActionPlatform::ExecuteAction: Error in executing action; dwRet = 0x2

2015-12-04 01:51:21, Error SYSPRP ActionPlatform::ExecuteActionList: Error in execute actions; dwRet = 0x2

2015-12-04 01:51:21, Error SYSPRP SysprepSession::Execute: Error in executing actions from

C:\Windows\System32\Sysprep\ActionFiles\Generalize.xml; dwRet = 0x2

2015-12-04 01:51:21, Error SYSPRP RunPlatformActions:Failed while executing SysprepSession actions; dwRet = 0x2

2015-12-04 01:51:21, Error [0x0f0070] SYSPRP RunExternalDlls:An error occurred while running registry sysprep DLLs, halting sysprep execution. dwRet = 0x2

2015-12-04 01:51:21, Error [0x0f00a8] SYSPRP WinMain:Hit failure while processing sysprep generalize internal providers; hr =

0x80070002

NOTE: The error code 0x80070002 and the application Microsoft.Windows.Photo are used as an example and might be different in the c:\windows\system32\sysprep\panther\setuperr.log file on the resulting VM.

This is a result of multiple users logging in to the machine and installing or updating the Metro Apps.

Workaround:For the only known workaround see the Microsoft knowledge base article Sysprep fails after you remove or update Windows Store apps that include built-in Windows images. Apply the workaround on the source machine and repeat the conversion.

The workaround does not always work on the destination machine and can cause mismatch in sysprep. After applying workaround on the destination machine, you must invoke the following command: c:\windows\system32\sysprep\sysprep.exe /generalize /oobe /reboot /unattend:c:\sysprep\sysprep.xml

Conversion job with no volume selected for shrinking fails with the following error message: 'An error occurred during the conversion: 'Block level cloning does not support shrinking volumes'

Converting a Windows source that has an LDM volume that is larger than 2TB and the first disk of the volume is an MBR disk fails with the following error message: 'An error occurred during the conversion: 'Block level cloning does not support shrinking volumes'. Converter attempts to create an MBR disk larger than 2TB on the destination but the limit of MBR disks is 2TB.

The error does not occur on LDM volumes with a GPT first disk, because the destination disk type supports sizes larger than 2 TB.

Workaround: Convert the LDM volume at file level. Trigger the file-level cloning by shrinking volume size.

Unsupported quest operating systems are labeled Other and fail to assign correct values for disk and network controllers

If you convert a virtual machine that is running on a Windows 8, Windows 8.1, or Windows 10 guest operating system to ESX version earlier than 6.0, the conversion results in a VM that cannot boot or does not have networking. The VM settings list the guest operating system as **Other** instead of Windows 8, Windows 8.1, or Windows 10.

Workaround 1: Select a destination ESX which supports Windows 8, Windows 8.1, or Windows 10.

Workaround 2: Manually select disk controller and network controller before conversion.

If you convert a source machine with Windows 2008 and above operating system, some disk(s) may be offline or read-only

If you convert a source machine with Windows 2008 and above operating system, some disk(s) in the destination VM may be offline or read-only. **Workaround:**

- If the disk is offline, in the Disk Management console diskmgmt.msc, right-click the disk and select Online.
- If the disk is read-only, run diskpart.exe with administrator's rights, and then run the following commands:
 - 1. DISKPART> list disk Lists all disks and their status: online/offline.
 - DISKPART> select disk # Where "#" is the number of disk in offline state.
 - 3. DISKPART> attribute disk clear readonly
 - 4. DISKPART> online disk
 - 5. Repeat steps 2-4 for every offline disk.
 - 6. DISKPART> exit

Configuration of Windows virtual machines with multiple active partitions might not complete

For Windows virtual machines with multiple active partitions, Converter Standalone might not recognize the boot partition and might not be able to complete the reconfiguration of the destination virtual machine. In such cases, after the conversion job is 96-98% complete, the conversion job status changes to Failed and an error message appears. For example:

FAILED: Unable to find the system volume, reconfiguration is not possible. In the Worker/Agent log this issue is identified by the following statement: [#### warning 'Default'] ERROR: [Mntapi_GetFirstBootDisk] more that *one* active volume found. Current active disk #0, another active disk #1.

Workaround 1: Mark all non-boot active partitions on the destination machine as inactive and run configuration on the destination machine.

1. Boot into Windows Recovery Console on the destination machine.

2. Run diskpart.exe.

The diskpart command prompt appears.

- 3. (Optional) To list the available disks, enter list disk.
- 4. Enter select disk <disk_number>.
- 5. (Optional) To list the partitions on the selected disk, enter list partition.
- 6. Enter select partition <partition_number>.
- 7. Enter inactive.
- 8. Repeat steps 4-7 to mark another partition as inactive.
- 9. Power off the destination machine.
- 10. Run Converter Standalone and configure the destination machine.

Workaround 2: Mark all non-boot active partitions on the source machine as inactive and attempt to run the conversion again.

- 1. On the source machine, run diskpart.exe. The diskpart command prompt appears.
- 2. (Optional) To list the available disks, enter list disk.
- 3. Enter select disk <disk_number>.
- 4. (Optional) To list the partitions on the selected disk, enter list partition.
- 5. Enter select partition <partition_number>.
- Enter inactive.
- 7. Repeat steps 2-6 to mark another partition as inactive.
- 8. Run Converter Standalone and start the conversion again.

Conversion of a local powered on source machine fails at 1%

If you select **This local machine** as a conversion source and a Converter Standalone agent from a previous Converter Standalone version is installed on the source machine, the conversion task fails at 1%. The following error message appears in the Status line of the **Task progress** tab:

FAILED: Unable to create a VSS snapshot of the source volume(s). Error code: 127 (0x0000007F).

This is because the Converter Standalone installer cannot upgrade previous versions of Converter Standalone agents.

Workaround: Manually uninstall Converter Standalone agent from the source machine and create a new conversion task.

Converter Standalone worker process stops responding if you try to copy a configuration job during guest operating system customization

If you right-click a running configuration job and select **Copy As New** while the destination machine is being customized, Converter Standalone worker process stops responding.

Workaround: Wait for the configuration job to complete before you copy it.

Subsequent P2V conversions of remote source machines that run 64-bit Windows Vista or later might fail after a successful conversion

If you convert successfully a remote source machine that runs 64-bit Windows Vista, Windows Server 2008, or Windows 7 operating system and then try converting it again, the conversion fails with the error message Converter Standalone Agent installation failed on x.x.x.x Error code: 1603, where x.x.x.x is the IP address of the source machine.

This error message might occur if automatic uninstall of remote Converter Standalone agent has been enabled during the first successful conversion.

Workaround: Restart the remote source machine and try running the conversion task again.

Converter Standalone does not preserve disabled network adapters during conversion of physical machine sources that run on Windows

During P2V conversion of Windows source machines, Converter Standalone does not detect disabled network adapters on the source and does not preserve them on the destination virtual machine.

Workaround: On the Options page of the Converter Standalone wizard, click Networks to add network adapters to the destination virtual machine.

Microsoft Windows Vista reboots repeatedly after customization

Providing wrong customization information might cause the destination virtual machine to reboot repeatedly if the source operating system is Microsoft Windows Vista. During conversion or configuration, if you choose to customize Microsoft Windows Vista and provide wrong customization information, for example an invalid serial key, the customized destination reboots repeatedly. This is a known issue with Microsoft Windows Vista.

Workaround: Make sure that the provided customization information is valid.

Converter Standalone does not support cloning of powered on sources with Windows Server 2008 or later with FAT/FAT32 volume file system VSS under Windows Server 2008 or later does not support FAT/FAT32. Trying to convert a FAT/FAT32 volume causes the conversion task to fail.

Workaround: Deselect all FAT/FAT32 volumes on the Options page of the Conversion wizard.

Converter Standalone remote agent does not notify the user about Converter 3.0.x or 4.0.x remote agents that have been installed on the source system during remote hot cloning process

If Converter Standalone is converting a remote machine source that already has a remote agent from Converter version 3.0.x or 4.0.x, it uninstalls the old remote agent without issuing a notification or warning message. This prevents older Converter versions from converting this source machine later.

Previous Converter versions cannot convert source machines that have Converter Standalone 6.0 agent installed on them

Converter Standalone 6.0 agent is deployed on the source machine during conversion. If Converter Standalone 6.0 agent is not uninstalled after the conversion, older Converter versions cannot deploy their agents on top of the newer Converter Standalone agent version. Therefore, you cannot use previous Converter versions to convert sources that have already been converted with Converter Standalone 6.0.

Workaround: Uninstall Converter Standalone 6.0 agent before trying to convert the source with an older Converter version.

Stopping Converter Standalone processes during file-level cloning might cause the machine that runs the Converter Standalone server service to restart

During file-level cloning of source systems that run Windows XP or Windows Server 2003, if any of the following Converter Standalone process is forcibly stopped, the machine on which the stopped process was running might automatically reboot.

- VMware Converter Standalone Integrated Worker
- VMware Converter Standalone Integrated Agent

This behavior is not consistent and depends on the Windows version and patch level.

Workaround: Do not stop any Converter Standalone services on the source machine during file-level cloning. For more information and hot fix, check the Microsoft site Error message when a Delayed Write Failure event is reported in Windows Server 2003: "Stop 0x00000019 - BAD_POOL_HEADER" or "Stop 0xCD PAGE FAULT BEYOND END OF ALLOCATION".

Converter Standalone does not change PIC HAL to APIC HAL during conversion of Windows source machines

If the source to convert is running a Programmable Interrupt Controller (PIC) HAL, Converter Standalone does not change the PIC HAL to an Advanced Programmable Interrupt Controller (APIC) HAL in the destination virtual machine. As a result, the destination virtual machine might not boot or might fail to perform as expected. To find out which HAL is running, go to Windows Device Manager and select **Computer** in the list of devices. If it displays Standard PC or Advanced Configuration and Power Interface (ACPI) PC, you are running a PIC HAL.

Workaround: VMware virtual machines are APIC computers. If your source computer is a PIC computer that runs a PIC HAL, you must update the HAL in the destination virtual machine to APIC HAL after the conversion. For more information on configuring the correct HAL, check the Microsoft Web site HAL options after Windows XP or Windows Server 2003 Setup.

Note: Microsoft does not support running a PIC HAL on an APIC computer. If your source is an APIC computer running a PIC HAL, you must configure the correct HAL on the source machine before starting the conversion.

Owner name and organization are not displayed properly after customizing the guest operating system

After customizing the guest operating system, Unicode characters used for owner name and organization on the Computer Information page do not appear the way they were set in the Conversion or the Configuration wizard.

For all Windows operating systems except Windows Vista, customization parameters such as user name and organization must use characters only from the local encoding of the default user profile of the guest. For example, you can use Japanese characters for the user name only on a guest whose default user profile's local encoding is set to Japanese. These restrictions do not apply to Windows Vista guests because Windows Vista uses a UTF-8 encoded XML file to store the Microsoft sysprep parameters. Earlier versions of Windows use the sysprep.inf file, and the Microsoft Windows mini-setup process reads that file in the local encoding only.

Workaround: Either avoid Unicode characters when assigning owner name and organization name for the destination virtual machine, or use the workaround described at: http://support.microsoft.com/kb/310441/.

Converter can convert FAT/FAT32 volumes during hot cloning only if the source machine has at least one NTFS volume

For source machines running under Windows versions earlier than Windows Server 2008, VSS can take snapshots of FAT/FAT32 volumes only if the source machine has at least one NTFS volume. For all operating systems that support volume-based cloning, you need at least one NTFS volume for VSS to work.

Converter Standalone agent does not start automatically after reboot

If the source machine starts up too slowly, Converter Standalone agent might not start automatically after the source machine is restarted. **Workaround:** Start the Converter Standalone agent manually:

- 1. Right-click My Computer and select Manage.
- 2. In the Computer Management window, select Services and Applications > Services on the left.
- 3. In the list on the right, double-click VMware Converter Standalone Agent.
- 4. Click Start to start the process.
- 5. Click **Apply** followed by **OK**.

The source virtual machine does not have the appropriate drivers

The following error message appears in the log file when reconfiguration fails because the appropriate drivers are missing from the source operating system: Unable to find symmpi.sys in the specified CAB files

This is usually observed in Windows Server 2003 SP1.

Workaround:

- 1. Back up the virtual machine created during the failed conversion.
- 2. Attach the VMDK file containing the system folder to another Windows Server 2003 virtual machine.
- 3. Replace the WINDOWS\Driver Cache\i386\driver.cab file in the destination virtual machine with a version of the driver.cab file that includes the missing driver from the helper virtual machine.
- 4. Detach the VMDK file from the helper virtual machine and run the Configure Machine wizard on the destination virtual machine.

Sysprep deletes drive letter mappings during customization

If you choose customization options and the destination virtual machine fails at a Please Wait screen after the second sysprep reboot, you need to rerun the conversion task without customization. This issue occurs because of a problem with Microsoft sysprep, which deletes the drive letter mappings, preventing access to certain files.

You cannot import a Windows source with "signature()" in the boot.ini file

You cannot import a Window source with "signature()" in the boot.ini file. If you import a Windows live source with "signature()" in the boot.ini file, and try to reconfigure and convert it, the reconfiguration fails and this results in a conversion error. If you try to convert the source without reconfiguration, the conversion succeeds but the destination cannot boot. For more information on "signature()" go to http://support.microsoft.com/kb/227704.

Top of Page

Linux Sources

- Converted SUSE Linux Enterprise Server 10 machine might not have network connectivity
- Converted powered on Linux machines cannot start up
- Linux P2V conversion fails in the beginning with the following error message: 'A general system error occured: <source_server_dns_name>: Connection closed by remote host'
- P2V conversions of SLES 9 sources cannot complete, if the root directory is located on an LVM disk
- Virtual machines cloned from SLES 11 SP1 sources to ESX/ESXi managed destinations boot in console mode
- X Server might fail to start in destination virtual machines converted from sources that run Linux

- Linked cloning of standalone VMware sources to Linux SMB shared destination fails
- The number of LVM logical volumes per volume group is limited to 12 for powered on Linux sources
- By default, the Linux P2V helper virtual machine is powered off when the conversion job finishes
- · Source volumes on top of volume managers other than LVM are not recognized during conversion of powered on Linux machines
- Converter Standalone does not recognize source volumes that reside on Linux Software RAID configurations
- By default, Converter Standalone has a 20 minute timeout when waiting for the helper virtual machine to start up during Linux P2V conversion
- Destination virtual machine might not boot if you change the disk controller type while converting a Linux virtual machine
- Linux P2V jobs on ESX 5.0 target hosts fail if the name of the virtual machine is not in ASCII symbols or in the Windows current system locale

Converted SUSE Linux Enterprise Server 10 machine might not have network connectivity

If you convert a SUSE Linux Enterprise Server 10 machine, the converted virtual machine might not have network connectivity.

Workaround:

- 1. In the /etc/udev/rules.d/30-net_persistent_names.rules.d/30-net_persistent_names.rules file, comment out the lines that start with SUBSYSTEM and contain the old MAC addresses.
- 2. Check the /etc/sysconfig/network directory. If there is no ifcfg-eth0 file and there is a file of the form ifcfg-if-mac_address, rename it to ifcfg-eth0.
- 3. Restart the network service.

Converted powered on Linux machines cannot start up

If you convert a powered on Linux machine that has a non-standard LVM filter saved in the /etc/lvm.conf file, the converted virtual machine might fail to start up. The following error message appears in the virtual machine console:

Unable to access resume device (dev//)

Workaround: Before the conversion, edit the filter in the lvm.conf file on the source Linux machine to allow all devices. For Red Hat Linux, the default value of the filter is ["a/.*/"].

Linux P2V conversion fails in the beginning with the following error message: 'A general system error occured: <source_server_dns_name>: Connection closed by remote host'

If the source machine sshd is configured to allow less than 3 unauthenticated connections, it may sever the converter connection.

Workaround: Check MaxStartups in /etc/ssh/sshd_config and ensure it is either commented out or its first number is 3 or higher.

P2V conversions of SLES 9 sources cannot complete, if the root directory is located on an LVM disk

When you select to convert a physical SLES 9 source, Converter Standalone cannot complete the conversion if the root directory is located on an LVM disk. After the conversion job is 99% complete, the job status changes to Failed and the following entry is added to the log:

FAILED: An error occurred during the conversion: 'Failed to restore original lvm in initrd image: /usr/lib/vmware-converter/restoreLvmInInitrd.sh failed with return code: 1, and message: * Unpacking initrd image /mnt/p2v-src-root//boot/initrd cpio: unsupported cpio format, use newc or crc ERROR: Unable to unpack initrd image /mnt/p2v-src-root//boot/initrd ' Workaround: Convert the LVM disk to a basic disk.

- 1. On the Options page of the Conversion wizard, click **Data to copy** in the options list.
- 2. Click Advanced and select the Destination layout tab.
- 3. Select the volume that contains the root directory and click **To basic**.

Virtual machines cloned from SLES 11 SP1 sources to ESX/ESXi managed destinations boot in console mode

After the conversion, the destination virtual machine cannot load the GNOME Display Manager and boots in console mode. The following warning message appears: GdmLocalIDisplayFactory: maximum number of X display failures reached: check X server log for errors.

Workaround: Recreate the xorg.conf file.

X Server might fail to start in destination virtual machines converted from sources that run Linux

When the destination virtual machine starts, X server might fail to start with an error Fatal X server Error. This is due to incompatibility issues between the

display driver used in the Linux source and the display adapter of the destination VMware virtual machine.

Workarounds:

- Install VMware Tools on the destination virtual machine.
- Configure the X server on the destination virtual machine to change the refresh rate and the display resolution.

Linked cloning of standalone VMware sources to Linux SMB shared destination fails

Linked cloning tasks of VMware standalone sources to SMB shared destinations that run on Linux fail with the following error: converter.fault.FileI0Fault.

The number of LVM logical volumes per volume group is limited to 12 for powered on Linux sources

During the conversion of powered on Linux machines, Converter Standalone converts LVM volume groups into new disks on the destination virtual machine. The number of LVM logical volumes on a source LVM volume group cannot exceed 12.

Workaround: Move volumes out of the new disk to other destination disks:

- 1. On the Options page of the Conversion wizard, click **Data to copy**.
- 2. From the Data copy type drop-down menu, select Select Volumes to copy and click Advanced.
- 3. On the **Destination layout** tab, select a volume to move and click **Move Up** or **Move Down** until it is moved to the destination disk. You can move volumes between disks only if they are not Active /boot or System / volumes.
- 4. (Optional) To create a new destination disk, click Add Disk.

By default, the Linux P2V helper virtual machine is powered off when the conversion job finishes

Workaround: Manually disable this option in the converter-worker.xml file.

- 1. On the machine where Converter Standalone server runs, browse to the converter-worker.xml file in the following location %ALLUSERSPROFILE%\Application Data\VMware\VMware Converter Standalone\.
- 2. Open the converter-worker.xml file in a text editor and change the powerOffHelperVm flag from true to false.
- 3. To restart Converter Standalone worker:

 Reboot the system or open the Services section in the Microsoft Management Console, find the VMware Converter Worker service and restart it.

Note: Care should be taken when this option is enabled and the helper VM network is configured to use a static IP address. After the conversion, the helper VM retains the statically configured IP because it is still running. Thus any subsequent Linux P2V jobs cannot use the same static IP until this helper VM is powered off, or at least has its network interface disabled.

Disabling the powerOffHelperVm flag is useful when the useSourcePasswordInHelperVm Converter Standalone worker flag is enabled. This allows users to log in to the helper virtual machine after conversion.

Source volumes on top of volume managers other than LVM are not recognized during conversion of powered on Linux machines

Converter Standalone recognizes only managed source volumes that run on the LVM volume manager. Other volume managers, including but not limited to Veritas Volume Manager (VxVM), are not recognized.

Converter Standalone does not recognize source volumes that reside on Linux Software RAID configurations

During cloning of powered on Linux machines, Converter Standalone does not recognize source volumes that are part of a Software RAID configuration (also referred to as multiple disk, or MD, configurations).

By default, Converter Standalone has a 20 minute timeout when waiting for the helper virtual machine to start up during Linux P2V conversion. This might cause a Linux P2V conversion task to fail due to connection timeout.

Workaround: Extend the timeout period (in seconds) by modifying the linuxP2VBootTimeout flag in the converter-worker.xml file.

- 1. On the machine where Converter Standalone server runs, browse to the converter-worker.xml file in the following location %ALLUSERSPROFILE%\Application Data\VMware\VMware Converter Standalone\.
- 2. Open the converter-worker.xml file in a text editor and replace the default value for linuxP2VBootTimeout with the necessary timeout value in milliseconds. **Note:** The timeout value is measured in seconds. To specify the timeout in minutes, multiply the number of minutes by 60 and use that value.

3. To restart Converter Standalone worker:

Reboot the system or open the Services section in the Microsoft Management Console, find the VMware Converter Worker service and restart it.

Destination virtual machine might not boot if you change the disk controller type while converting a Linux virtual machine

In Linux virtual machines, the root device can be defined using the block device name (such as /dev/sda1) in /boot/grub/grub.conf, /boot/grub/menu.lst, or /etc/fstab. If you change the disk controller type while converting the virtual machine, the destination virtual machine might not boot. This is because the root device now has a different name (for example, it might have been changed to /dev/hda1).

Workaround: Configure the destination virtual machine manually. At the minimum, change the root device name to reflect its new name in the destination virtual machine. To make your system more robust, use the volume label or UUID instead of the block device name.

Linux P2V jobs on ESX 5.0 target hosts fail if the name of the virtual machine is not in ASCII symbols or in the Windows current system locale If the target host is ESX 5.0, the name of the virtual machine must be in ASCII or in the Windows current system locale, otherwise the helper machine cannot be connected and the Linux P2V conversion fails.

Workaround: Before the conversion, enter the name of the virtual machine by using ASCII symbols. After the conversion is complete, you can rename the virtual machine.

Top of Page

SDK Release Notes

Converter Standalone SDK 6.1

The VMware vCenter Converter Standalone API provides language-neutral interfaces to the Converter Standalone server management framework. The Converter Standalone SDK is a ZIP file that contains the following items.

- Sample code demonstrating common use cases for programmatically managing Converter Standalone server. The sample code includes Java and C# source code files. See the respective Readme files (readme java.htm and readme dotnet.htm) for information about building and using the samples.
- The WSDL that defines the API available on Converter server.
- Batch files and shell scripts to automate the process of generating client-side stubs, and for rebuilding the sample applications. For C# developers, the Microsoft Visual Studio project files (.sln) have been included.
- Reference documentation, the VMware vCenter Converter Standalone API Reference Guide, which provides language-neutral descriptive information (object type definitions, properties, and method signatures, for example) for the VMware vCenter Converter Standalone 6.1 API.

Obtaining the Software

You can obtain the Converter Standalone SDK 6.1 from here.

Supported Platforms

The Converter Standalone 6.1 SDK is tested only on the supported Windows platforms. See Platforms.

Top of Page

Copyright © 2017 VMware, Inc. All rights reserved.

Terms of Use Privacy Accessibility Trademarks