# Linux 的软件安装

### 一、JDK 安装

注意:rpm 与软件相关命令相当于 window 下的软件助手管理软件 步骤:

(1) 查看当前 Linux 系统是否已经安装 java

输入 rpm -qa | grep java

java-1.6.0-openjdk-1.6.0.35-1.13.7.1.el6\_6.i686 tzdata-java-2015e-1.el6.noarch java-1.7.0-openjdk-1.7.0.79-2.5.5.4.el6.i686

(2)卸载两个 openJDK

输入 rpm -e -nodeps 要卸载的软件

[root@itheima23~]# rpm -e --nodeps java-1.7.0-openjdk-1.7.0.79-2.5.5.4.el6.i686 [root@itheima23 ~]# rpm -e --nodeps java-1.6.0-openjdk-1.6.0.35-1.13.7.1.el6\_6.i686

- (3)用 WinSCP 上传 JDK 到 Linux
- (4)解压 JDK 到/usr/local 下 tar -xvf jdk-8u144-linux-x64.tar.gz -C /usr/local
- (5)配置 JDK 环境变量, 打开/etc/profile 配置文件, 将下面配置拷贝进去

#set java environment

JAVA\_HOME=/usr/local/jdk1.8.0\_144

CLASSPATH=.:\$JAVA\_HOME/lib.tools.jar

PATH=\$JAVA HOME/bin:\$PATH

export JAVA HOME CLASSPATH PATH

(6)重新加载/etc/profile 配置文件 source /etc/profile

## 二、MySQL 安装

Linux 下彻底卸载 MySQL

1、停止 MySQL 服务

systemctl stop mysqld

## 2、查看当前安装 MySQL 情况

rpm -qa | grep -i mysql

```
[root@master ~]# rpm -qa|grep -i mysql
mysql-community-common-5.7.19-1.el7.x86_64
mysql-community-client-5.7.19-1.el7.x86_64
mysql57-community-release-el7-11.noarch
mysql-community-libs-5.7.19-1.el7.x86_64
mysql-community-server-5.7.19-1.el7.x86_64
```

### 3、按顺序卸载以下内容

```
rpm -ev mysql-community-server-5.7.19-1.el7.x86_64
rpm -ev mysql-community-client-5.7.19-1.el7.x86_64
rpm -ev mysql-community-libs-5.7.19-1.el7.x86_64
rpm -ev mysql57-community-release-el7-11.noarch
rpm -ev mysql-community-common-5.7.19-1.el7.x86_64
```

### 4、再次查看

rpm -qa|grep -i mysql 如果没有,则进行下一步。

# 5、查找之前老版本 mysql 的目录、并且删除老版本 mysql 的文件 和库

find / -name mysql

```
[root@master ~]# find / -name mysql
/var/lib/mysql
/var/lib/mysql/mysql
/usr/share/mysql
```

### 6、删除对应的目录

```
rm -rf /var/lib/mysql
rm -rf /var/lib/mysql/mysql
rm -rf /usr/share/mysql
```

注意:卸载后/etc/my.cnf 不会删除,需要进行手工删除rm-rf/etc/my.cnf

### 7、再次查找机器是否安装 mysql

rpm -qa|grep -i mysql

如果没有,则说明卸载彻底了,即可重新安装 MySQL。


## 8、安装 MySQL

Linux 下安装 MySQL(参考: http://www.centoscn.com/mysql/2016/0626/7537.html)

安装环境: CentOS7 64 位 MINI 版,安装 MySQL5.7

### 9、配置 YUM 源

在 MySQL 官网中下载 YUM 源 rpm 安装包: http://dev.mysql.com/downloads/repo/yum/



## 10、安装 yum 源

yum localinstall mysql57-community-release-el7-8.noarch.rpm

## 11、检查 MySQL 是否安装成功

yum repolist enabled | grep "mysql.\*-community.\*"

看到上图所示表示安装成功

### 12、安装

yum install mysql-community-server

```
已安装:
    mysql-community-server.x86_64 0:5.7.19-1.el7

作为依赖被安装:
    mysql-community-client.x86_64 0:5.7.19-1.el7
    mysql-community-common.x86_64 0:5.7.19-1.el7
    mysql-community-libs.x86_64 0:5.7.19-1.el7

完毕!
```

### 13、启动 MySQL 服务

systemctl start mysqld

#### 查看 MySQL 的启动状态

systemctl status mysqld

```
[root@master opt]# systemctl status mysqld
mysqld.service - MySQL Server
   Loaded: loaded (/usr/lib/systemd/system/mysqld.service; enabled; ve
ndor preset: disabled)
   Active: active (running) since 四 2017-07-27 09:14:29 CST; 11min ag
    Docs: man:mysqld(8)
          http://dev.mysql.com/doc/refman/en/using-systemd.html
  Process: 3708 ExecStart=/usr/sbin/mysqld --daemonize --pid-file=/var
/run/mysqld/mysqld.pid $MYSQLD_OPTS (code=exited, status=0/SUCCESS)
 Process: 3635 ExecStartPre=/usr/bin/mysqld_pre_systemd (code=exited,
 status=0/SUCCESS)
 Main PID: 3711 (mysqld)
   CGroup: /system.slice/mysqld.service
           └─3711 /usr/sbin/mysqld --daemonize --pid-file=/var/run/...
7月 27 09:14:22 master systemd[1]: Starting MySQL Server...
7月 27 09:14:29 master systemd[1]: Started MySQL Server.
```

### 14、修改 root 默认密码

mysql 安装完成之后,在/var/log/mysqld.log 文件中给 root 生成了一个默认密码。通过下面的方式找到 root 默认密码,然后登录 mysql 进行修改:

grep 'temporary password' /var/log/mysqld.log

```
2017-07-27T01:14:24.555799Z 1 [Note] A temporary password is generated for root@localhost: thpNYe=lN8FI
```

#### shell> mysql -uroot -p

#### mysgl> ALTER USER 'root'@'localhost' IDENTIFIED BY 'MySQL57pw!';

注意:mysql5.7默认安装了密码安全检查插件(validate\_password),默认密码检查策略要求密码必须包含:大小写字母、数字和特殊符号,并且长度不能少于8位。否则会提示ERROR 1819 (HY000): Your password does not satisfy the current policy requirements错误,如下图所示:

```
mysql> set password for 'yangxin'@'%'=password('123456abc!');
ERROR 1819 (HY000): Your password does not satisfy the current policy requirements
mysql>
```

通过 msyql 环境变量可以查看密码策略的相关信息: mysgl> show variables like '%password%';

```
mysql> show variables like '%password%'
 Variable name
                                           Value
 default password lifetime
                                           0
 disconnect on expired password
                                           ON
 log builtin as identified by password
                                          OFF
 mysql native password proxy users
                                           0FF
 old passwords
                                           0
 report password
 sha256 password proxy users
                                           OFF
 validate password check user name
                                           OFF
 validate password dictionary file
                                           8
 validate password length
 validate password mixed case count
 validate password number count
                                           1
 validate password policy
                                           MEDIUM
 validate password special char count
                                           1
14 rows in set (0.00 sec)
```

validate\_password\_policy:密码策略,默认为MEDIUM策略 validate\_password\_dictionary\_file:密码策略文件,策略为STRONG才需要 validate\_password\_length:密码最少长度 validate\_password\_mixed\_case\_count:大小写字符长度,至少1个 validate\_password\_number\_count:数字至少1个 validate\_password\_special\_char\_count:特殊字符至少1个 上述参数是默认策略MEDIUM的密码检查规则。

### 15、修改密码策略

在/etc/my.cnf 文件添加 validate\_password\_policy 配置,指定密码策略

#### 修改密码策略

在/etc/my.cnf文件添加validate\_password\_policy配置,指定密码策略

```
1 # 选择θ (LOW), 1 (MEDIUM), 2 (STRONG) 其中一种,选择2需要提供密码字典文件2 validate_password_policy=θ
```

如果不需要密码策略,添加my.cnf文件中添加如下配置禁用即可:

```
1 validate_password = off
```

重新启动mysql服务使配置生效:

```
1 systemctl restart mysqld
```

重新启动 mysql 服务使配置生效: systemctl restart mysqld

登录 mysql, 更改密码为 root
ALTER USER 'root'@'localhost' IDENTIFIED BY 'root';

### 16、设置开机启动

shell> systemctl enable mysqld shell> systemctl daemon-reload

1) 开启 mysql 的远程登录

默认情况下 mysql 为安全起见,不支持远程登录 mysql,所以需要设置开启远程登录 mysql 的权限

```
登录 mysql 后输入如下命令:
grant all privileges on *.* to 'root' @'%' identified by 'root';
flush privileges;
```

2) 开放 Linux 的对外访问的端口 3306 /sbin/iptables -I INPUT -p tcp --dport 3306 -j ACCEPT

## 三、Tomcat 的安装

#### 步骤:

- 1)上传 Tomcat 到 linux 上
- 2)解压 Tomcat 到/usr/local 下 tar -xvf apache-tomcat-8.0.52.tar.gz -C /usr/local

cd /usr/local mv apache-tomcat-8.0.52 tomcat8.0

3)开放 Linux 的对外访问的端口 8080 /sbin/iptables -I INPUT -p tcp --dport 8080 -j ACCEPT /etc/rc.d/init.d/iptables save

4)启动关闭 Tomcat

进入 tomcat 的 bin 下启动: ./startup.sh 进入 tomcat 的 bin 下关闭: ./shutdown.sh