# ANSI/ISO C++

Professional Programmers Handbook

The Technical Validation Group





# ANSI/ISO C++ Professional Programmer's Handbook

#### **Table of Contents:**

### **CHAPTER 1 - INTRODUCTION**

The Origins of C++

**ANSI Committee Established** 

C++ as Opposed to Other Object-Oriented Languages

Aim Of the Book

**Target Audience** 

Organization of the Book

## CHAPTER 2 - STANDARD BRIEFING: THE LATEST ADDENDA TO ANSI/ISO C++

Introduction

The Standard's Terminology

Addenda

**Deprecated Feature** 

**Conclusions** 

### **CHAPTER 3 - OPERATOR OVERLOADING**

Introduction

Operator Overloading Rules of Thumb

Restrictions on Operator Overloading

**Conversion Operators** 

Postfix and Prefix Operators

**Using Function Call Syntax** 

**Consistent Operator Overloading** 

Returning Objects by Value

**Multiple Overloading** 

Overloading Operators for Other User-Defined types

Overloading the Subscripts Operator

**Function Objects** 

**Conclusions** 

# CHAPTER 4 - SPECIAL MEMBER FUNCTIONS: DEFAULT CONSTRUCTOR, COPY CONSTRUCTOR, DESTRUCTOR, AND ASSIGNMENT OPERATOR

Introduction

Constructors

**Copy Constructor** 

**Simulating Virtual Constructors** 

**Assignment Operator** 

When Are User-Written Copy Constructors And Assignment Operators Needed?

Implementing Copy Constructor And Assignment Operator

**Blocking Object Copying** 

**Destructors** 

Constructors And Destructors Should Be Minimal

**Conclusions** 

### **CHAPTER 5 - OBJECT-ORIENTED PROGRAMMING AND DESIGN**

Introduction

**Programming Paradigms** 

**Techniques Of Object-Oriented Programming** 

Classes and Objects

**Designing Class Hierarchies** 

**Conclusions** 

### **CHAPTER 6 - EXCEPTION HANDLING**

Introduction

**Traditional Error Handling Methods** 

**Enter Exception Handling** 

**Applying Exception Handling** 

**Exceptions During Object's Construction and Destruction** 

**Global Objects: Construction and Destruction** 

**Advanced Exception Handling Techniques** 

**Exception Handling Performance Overhead** 

Misuses of Exception Handling Conclusions

### **CHAPTER 7 - RUNTIME TYPE IDENTIFICATION**

**Introduction** 

Structure Of This Chapter

Making Do Without RTTI

RTTI constituents

The Cost of Runtime Type Information

**Conclusions** 

### **CHAPTER 8 - NAMESPACES**

The Rationale Behind Namespaces

A Brief Historical Background

**Properties of Namespaces** 

Namespace Utilization Policy in Large-Scale Projects

Namespaces and Version Control

The Interaction of Namespaces with Other Language Features

Restrictions on Namespaces

**Conclusions** 

### **CHAPTER 9 - TEMPLATES**

Introduction

**Class Templates** 

**Function Templates** 

**Performance Considerations** 

**Interaction with Other Language Features** 

**Conclusions** 

### **CHAPTER 10 - STL AND GENERIC PROGRAMMING**

Introduction

**Generic Programming** 

Organization of STL Header Files

**Containers** 

**Iterators** 

<u>Algorithms</u>

**Function Objects** 

**Adaptors** 

Allocators

**Specialized Containers** 

**Associative Containers** 

Class auto\_ptr

**Nearly Containers** 

Class string

**Conclusions** 

### **CHAPTER 11 - MEMORY MANAGEMENT**

Introduction

Types of Storage

POD (Plain Old Data) and non-POD Objects

The Lifetime of a POD Object

The Lifetime of a non-POD Object

Allocation and Deallocation Functions

malloc() and free() Versus new and delete

new and delete

**Exceptions During Object Construction** 

**Alignment Considerations** 

The Size Of A Complete Object Can Never Be Zero

<u>User-Defined Versions of new and delete Cannot Be Declared in a Namespace</u>

Overloading new and delete in a Class

Guidelines for Effective Memory Usage

Explicit Initializations of POD Object

**Data Pointers Versus Function Pointers** 

**Pointer Equality** 

**Storage Reallocation** 

Local Static Variables

Global Anonymous Unions

The const and volatile Properties of an Object

**Conclusions** 

### **CHAPTER 12 - OPTIMIZING YOUR CODE**

Introduction

Before Optimizing Your Software

**Declaration Placement** 

**Inline Functions** 

Optimizing Memory Usage

**Speed Optimizations** 

A Last Resort

**Conclusions** 

### **CHAPTER 13 - C LANGUAGE COMPATIBILITY ISSUES**

**Introduction** 

Differences Between ISO C and the C Subset of ANSI/ISO C++

Quiet Differences Between C and C++

Migrating From C to C++

Designing Legacy Code Wrapper Classes

**Multilingual Environments** 

C and C++ Linkage Conventions

Minimize the Interface Between C and C++ Code

Mixing <iostream> Classes with <stdio.h> Functions

Accessing a C++ Object in C Code

**Conclusions** 

### **CHAPTER 14 - CONCLUDING REMARKS AND FUTURE DIRECTIONS**

Some of the Features that Almost Made It into the Standard

The Evolution of C++ Compared to Other Languages

Possible Future Additions to C++

Conclusions

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

### ANSI/ISO C++ Professional Programmer's Handbook

Contents

1

### Introduction

#### by Danny Kalev

- The Origins of C++
  - o C with Classes
  - Enter C++
  - o The Late 1980s: Opening the Floodgates
- ANSI Committee Established
  - Maturation
  - International Standardization
  - o Committee Drafts And Public Review
  - Feature Freeze and Finalization
- C++ as Opposed to Other Object-Oriented Languages
  - Backward Compatibility with Legacy Systems
  - o Performance
  - Object-Orientation and Other Useful Paradigms
  - Object-Oriented Programming
  - o Generic Programming
- Aim Of the Book
- Target Audience
- Organization of the Book

The precursors of object-oriented programming can be traced back to the late 1960's: Classes, inheritance and virtual member functions were integral features of Simula67, a programming language that was mainly used for writing event-driven simulations. When Smalltalk first appeared back in 1972, it offered a pure object-oriented programming environment. In fact, Smalltalk defined object-oriented programming. This style of programming was so innovative and revolutionary at the time that it took more than a decade for it to become a standard in the software industry. Undoubtedly, the emergence of C++ in the early '80s provided the most considerable contribution to this revolution.

### The Origins of C++

In 1979, a young engineer at Bell (now AT&T) Labs, Bjarne Stroustrup, started to experiment with extensions to C to make it a better tool for implementing large-scale projects. In those days, an average project consisted of tens of thousands of lines of code (LOC).

**NOTE:** Today, Microsoft's Windows 2000 (formerly NT 5.0) consists of more than 30 million lines of code (and counting).

When projects leaped over the 100,000 LOC count, the shortcomings of C became noticeably unacceptable. Efficient teamwork is based, among other things, on the capability to decouple development phases of individual teams from one another--something that was difficult to achieve in C.

#### C with Classes

By adding classes to C, the resultant language -- "C with classes" -- could offer better support for encapsulation and information hiding. A *class* provides a distinct separation between its internal implementation (the part that is more likely to change) and its external interface. A class object has a determinate state right from its construction, and it bundles together the data and operations that manipulate it.

### Enter C++

In 1983, several modifications and extensions had already been made to C with classes. In that year, the name "C++" was coined. Ever since then, the ++ suffix has become a synonym for object-orientation. (Bjarne Stroustrup could have made a fortune only by registering ++ as a trademark) It was also in that year that C++ was first used outside AT&T Labs. The number of users was doubling every few months -- and so was the number of compilers and extensions to the language.

### The Late 1980s: Opening the Floodgates

Between 1985 and 1989, C++ underwent a major reform. Protected members, protected inheritance, templates, and a somewhat controversial feature called multiple inheritance were added to the language. It was clear that C++ needed to become standardized.

### **ANSI Committee Established**

In 1989, the *American National Standards Institution (ANSI)* committee for the standardization of C++ was established. The official name of the committee was X3J16, and later it was changed to J16. Generally, standardization committees don't write a standard from scratch; rather, they adopt an existing de facto reference, and use it as their baseline. The ANSI C committee used *The C Programming Language* by Kernighan and Ritchie as a starting point. Likewise, the ANSI C++ committee used the *Annotated C++ Reference Manual* (ARM) by Ellis and Stroustrup as its base document. The ARM provided a clear and detailed starting point for the committee's work. The committee's policy was to not rush into establishing a half-baked standard that would become obsolete in a year or two. Instead, the policy was to allow the demands for changes to emerge from the users of the language, the C++ community. Nonetheless, the committee also initiated extensible modifications and changes to the language, such as *runtime type information* (RTTI) and the new cast notation.

#### **Maturation**

By that time, hundreds of thousands of people were using the language. C++ compilers were available for almost every platform. New C++-based frameworks, such as MFC and OWL, had emerged. The committee had to face enormous pressure from several directions. Some organizations were advocating new features and extensions to the language that were borrowed from other object-oriented languages, while other parties strove to keep it as efficient as possible. On top of this, C++ had to retain its backward compatibility with C, including the support of eight different flavors for integral types, cumbersome pointer syntax, structs, unions, global functions, and many other features that don't exactly go hand in hand with object orientated programming.

#### **International Standardization**

C++ standardization was a joint international endeavor in which national standardization bodies from all over the world were intensively involved. This is different from the standardization of C. C standardization was first carried out by ANSI as an American standard and was later adopted, with some modifications (mainly internationalization issues), as an international standard by the *International Standardization Organization (ISO)*. The international venture of C++ guaranteed a worldwide acceptance of the standard, albeit at the price of somewhat more complicated procedures. Thus, the committee's meetings were actually joint meetings of both the ANSI working group and the ISO working group. Officially, the ANSI working group served as an advisor to ISO. Therefore, two votes were taken on every technical issue: an ANSI vote, to decide what the ANSI recommendation was, and a subsequent ISO vote, to actually make the decision. Some important changes were made in order to meet the criteria for ISO approval, including the addition of wchar\_t as a built-in type, the templatization of the iostream library, the templatization of class string, and the introduction of the *locale library*, which encapsulates cultural-dependent differences.

#### **Committee Drafts And Public Review**

The committee's initiatory task was to produce a draft of the standard, known as the Committee Draft (CD). For that purpose, the committee convened three times a year, one week at a time, in different places of the world. The first CD received several disapproving votes as well as many comments from ISO. The committee resolved these technical issues and addressed the comments in the second CD. The second CD was approved by ISO; however, there were still 5 "nay" votes and accompanying comments. Following the ISO balloting, the CD's were made available to the public. The public review process enabled C++ users from all over the world to comment on the proposed CD and point out contradictions and omissions.

### **Feature Freeze and Finalization**

After the approval of the second CD in November 1996, the committee's task was mainly to respond to the 5 "nay" votes and the accompanying comments and turn them into "aye" votes. The resultant document was the Final Draft International Standard, or the FDIS. At the meeting of the standardization committee in November, 1997 at Morristown, New Jersey, the FDIS was unanimously approved. In 1998, after a few minor changes, the FDIS was approved by ISO and became an international standard. In accordance with ISO rules, after it was approved, the Standard entered a freeze period of five years; during this time, the only modifications that are allowed are error fixes. People who find such defects can submit a Defect Report to the committee for consideration.

## C++ as Opposed to Other Object-Oriented Languages

C++ differs from other object-oriented languages in many ways. For instance, C++ is not a root-based language, nor does it operate on a runtime virtual machine. These differences significantly broaden the domains in which C++ can be used.

### **Backward Compatibility with Legacy Systems**

The fact that legacy C code can be combined seamlessly with new C++ code is a major advantage. Migration from C to C++ does not force you to throw away good, functional C code. Many commercial frameworks, and even some components of the Standard Library itself, are built upon legacy C code that is wrapped in an object-oriented interface.

### **Performance**

Interpreted languages allow easier code porting, albeit at the cost of significant performance overhead. C++, on the other hand, uses the compile and link model it inherited from C. One of the goals of C++ designers has been to keep it as efficient as possible; a compile-and-link model enables very efficient code generation and optimization. Another performance factor is the use of a garbage collector. This feature is handy and prevents some common programming bugs; however, garbage collected languages are disqualifies for time-critical application development, where determinacy is paramount. For that

reason, C++ does not have a garbage collector.

### **Object-Orientation and Other Useful Paradigms**

In addition to object-oriented programming, C++ supports other useful programming styles, including procedural programming, object-based programming, and generic programming -- making it a multi-paradigm, general-purpose programming language.

#### **Procedural Programming**

Procedural programming is not very popular these days. However, there are some good reasons for C++ to support this style of programming, even today.

#### **Gradual Migration of C Programmers To C++**

C programmers who make their first steps in C++ are not forced to throw all their expertise away. Many primitives and fundamental concepts of C++ were inherited from C, including built-in operators and fundamental types, pointers, the notion of dynamic memory allocation, header files, preprocessor, and so on. As a transient phase, C programmers can still remain productive when the shift to C++ is made.

#### **Bilingual Environments**

C++ and C code can work together. Under certain conditions, this combination is synergetic and robust.

#### **Machine-Generated Code**

Many software tools and generators generate C code as an intermediate stage of application build. For example, SQL queries on most relational databases are translated into C code, which is in turn compiled and linked. There's not much point in forcing these generators to produce C++ code (although some do so) when the generated code is not going to be used by human programmers. Furthermore, many early C++ compilers were not really compilers in the true meaning of the word; they are better described as translators because they translated C++ code into intermediate C code that was later compiled and linked. In fact, any valid C++ programs can be translated directly into pure C code.

### **Object-Oriented Programming**

This is the most widely used style of programming in C++. The intent of this book is to deliver useful guidelines and rules of thumb for efficient, reliable, reusable, and easy to maintain object-oriented code. But there is no universal consensus as to what OO really is; the definitions vary among schools, languages, and users. There *is*, however, a consensus about a common denominator -- a combination of encapsulation, information hiding, polymorphism, dynamic binding, and inheritance. Some maintain that advanced object-oriented consists of generic programming support and multiple inheritance. These concepts will be discussed in depth in the chapters that follow.

### **Generic Programming**

Generic programming proceeds one step beyond object-oriented programming in pursuing reusability. Two important features of C++, templates and operator overloading, are the basis of generic programming. STL, a collection of generic algorithms and containers, is probably the most impressive manifestation of this paradigm.

### Aim Of the Book

This book is aimed at experienced C++ developers who seek a guide for enhancing their design and programming proficiency. It discloses facts and techniques and provides a knowledge base for advanced, Standard-compliant, and efficient use of C++. In addition, the book also explains the underlying mechanism behind the high-level features of the language, and it explains the philosophy behind the design and evolution of C++.

### **Target Audience**

The target audience is intermediate and advanced level C++ developers who want to improve their proficiency by acquiring new programming techniques and design idioms. On top of adding many new features to the language, the standardization committee has deprecated several features and library components. In this book, readers who want to develop long lasting, future-proof C++ software can find a comprehensive list of deprecated features and their recommended alternatives.

### Organization of the Book

- **Chapter 2**, "Standard Briefing: The Latest Addenda to ANSI/ISO C++," presents some of the key terms that are used in the C++ Standard, and which are used extensively in this book. Following this, the recent changes and extensions to C++ are described. Finally, Chapter 2 gives an overview of the deprecated features that are listed in the Standard, and suggests standard-conforming replacements for them.
- **Chapter 3**, "Operator Overloading," explores the benefits as well as the potential problems of operator overloading. It discusses the restrictions that apply to operator overloading and explains how to use conversion operators.
- **Chapter 4**, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator," explains the semantics of the special member functions and their role in class design. It also demonstrates several techniques and guidelines for an effective usage of these special member functions.
- **Chapter 5**, "Object-Oriented Programming and Design," provides a brief survey of the various programming styles that are supported by C++, focusing on the principles of object-oriented design and programming.
- **Chapter 6**, "Exception Handling," first describes traditional error handling methods and their disadvantages, and then presents standard exception handling. A brief historical account of the design of

exception handling is provided and, finally, exception handling-related performance issues are discussed.

- Chapter 7, "Runtime Type Information," discusses the three components of runtime type information (RTTI), namely typeid, dynamic\_cast and class type\_info. In addition, it explains when the use of RTTI is necessary. Finally, it discusses the performance overhead associated with runtime type information.
- **Chapter 8**, "Namespaces," elucidates the rationale behind the addition of namespaces to the language and the problems that namespaces solve. Then it demonstrates how namespaces are used in practice, and how they interact with other language features.
- **Chapter 9**, "Templates," discusses various aspects of designing and implementing templates, including class templates, function templates, and template issues that are of special concern (such as pointers to members, virtual member functions within a template class, inheritance relations, and explicit instantiations).
- **Chapter 10**, "STL and Generic Programming," is an introduction to the Standard Template Library and to generic programming in general. It discusses the principles of generic programming, focusing on STL as an exemplary framework of generic programming. This chapter also demonstrates the use of STL components: containers, algorithms, iterators, allocators, adapters, binders, and function objects. The most widely used STL components, std::vector and std::string, are explored in detail.
- **Chapter 11**, "Memory Management," explains the memory model of C++. It describes the three types of data storage: static, automatic, and free store. This chapter also delves into the semantics of operators new and delete and their underlying implementation. In addition, it demonstrates the use of advanced memory management techniques and guides you in avoiding common memory-related errors.
- **Chapter 12**, "Optimizing Your Code," is dedicated to code optimization. It provides useful guidelines and tips for writing more efficient code, and it proceeds toward more aggressive optimization techniques for minimizing space and accelerating runtime speed.
- **Chapter 13**, "C Language Compatibility Issues," demonstrates how to migrate from C to C++ and, in particular, how to migrate from procedural programming to object-orientation. It lists the differences between the C subset of C++ and ISO C. Finally, it delves into the underlying representation of C++ objects in memory and their compatibility with C structs.
- **Chapter 14**, "Concluding Remarks and Future Directions," seals this book. It describes the principles and guidelines in the design and evolution of C++ throughout the last two decades, and compares it to the evolution of other, less successful programming languages. Then it lists features that almost made it into the Standard. Next, it discusses possible future extensions, including automated garbage collection, object persistence, and concurrency. Other hypothetical future extensions that are described are dynamically linked libraries, rule-based programming, and extensible member functions.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

## ANSI/ISO C++ Professional Programmer's Handbook

Contents

2

## Standard Briefing: The Latest Addenda to ANSI/ISO C++

#### by Danny Kalev

- Introduction
  - Understanding the ANSI/ISO Standard
  - o Purpose and Structure of This Chapter
- The Standard's Terminology
  - Arguments and Parameters
  - Translation Unit
  - o Program
  - Well-Formed Program
  - lvalues and rvalues
  - Behavior Types
  - The One Definition Rule
  - o <u>Linkage Types</u>
  - Side effect
- Addenda
  - New Typecast Operators
  - o Built-in bool Type
  - Exception Handling
  - Memory Management
  - Constructors and Destructors
  - Local Definitions and Scoping Rules
  - Namespaces

- o <u>Templates</u>
- The Standard Template Library
- Internationalization and Localization
- o Miscellaneous
- Deprecated Feature
  - Use of an Operand of Type bool with the Postfix ++ Operator
  - Use of static to Declare Objects in Namespace Scope
  - Access Declarations
  - o Implicit Conversion from const to non-const Qualification for String Literals
  - o Standard C Headers in the form <name.h>
  - o <u>Implicit int Declarations</u>
  - Other Deprecated Features
- Conclusions

### Introduction

C++ today is very different from what it was in 1983, when it was first named "C++". Many features have been added to the language since then; older features have been modified, and a few features have been deprecated or removed entirely from the language. Some of the extensions have radically changed programming styles and concepts. For example, downcasting a base to a derived object was considered a bad and unsafe programming practice before the standardization of Runtime Type Information. Today, downcasts are safe, and sometimes even unavoidable. The list of extensions includes const member functions, exception handling, templates, new cast operators, namespaces, the Standard Template Library, bool type, and many more. These have made C++ the powerful and robust multipurpose programming language that it is today.

The evolution of C++ has been a continuous and progressive process, rather than a series of brusque revolutions. Programmers who learned C++ only three or five years ago and haven't caught up with the extensions often discover that the language slips through their fingers: Existing pieces of code do not compile anymore, others compile with a plethora of compiler warnings, and the source code listings in object-oriented magazines seem substantially different from the way they looked not so long ago. "Namespaces? never heard of these before," and "What was wrong with C-style cast? Why shouldn't I use it anymore?" are some of the frequently asked questions in various C++ forums and conferences.

### **Understanding the ANSI/ISO Standard**

But even experienced C++ programmers who have kept up with changes by subscribing to newsgroups, reading magazines and books, or exchanging emails with the company's guru might still find that the C++ nomenclature in professional literature is sometimes unclear. The ANSI/ISO Standard is written in a succinct and technical jargon that is jocularly called *standardese* -- which is anything but plain English. For instance, the *One Definition Rule* (article 3.2 in the Standard), which defines under what conditions separate definitions of the same entity are valid, is explained in textbooks in a simpler -- although sometimes less accurate -- manner, when compared to the Standard text. The use of standardese ensures the accuracy that is needed for writing compilers and checking the validity of programs. For this purpose, the Standard defines numerous specific terms that are used extensively throughout the volume; for instance, it distinguishes between a *template id* and a *template name*, whereas an average programmer simply refers to both as templates. Familiarity with these specific terms is the key to reading and interpreting the

Standard correctly.

### **Purpose and Structure of This Chapter**

The purposes of this chapter are threefold. First, it presents some of the key terms that are used extensively throughout the Standard and throughout this book, for example, *undefined behavior* and *deprecated features*. (Note that topic-specific terms such as *argument-dependent lookup* and *trivial constructor* are presented in their relevant chapters rather than here.) Then, the new features that have been added to C++ -- such as bool type, new typecast operators, and mutable data members -- are discussed. Because these topics are not explained elsewhere in this book, they are presented here in detail, along with code samples. After that comes a list of other newly added features that are covered extensively in other chapters of the book.

These topics are presented here only briefly. The intent is to provide you with an *executive summary* -- a panorama of the latest addenda to the ANSI/ISO C++ Standard -- that you can use as a checklist of topics. When reading the brief topics overview, you might come across an unfamiliar topic; in these instances, you are always referred to the chapter that discusses the topic in further detail. Finally, there is an overview the deprecated features and a list of suggested replacements for them.

### The Standard's Terminology

This part explains some of the key terms in the Standard that are used throughout the book. These terms appear in italics when they are presented for the first time. Note that these definitions are not exact quotations from the Standard; rather, they are interpretive definitions.

#### **Arguments and Parameters**

The words *arguments* and *parameters* are often used interchangeably in the literature, although the Standard makes a clear distinction between the two. The distinction is chiefly important when discussing functions and templates.

#### Argument

An argument is one of the following: an expression in the comma-separated list that is bound by the parentheses in a function call; a sequence of one or more preprocessor tokens in the comma-separated list that is bound by the parentheses in a function-like macro invocation; the operand of a throw-statement or an expression, type, or template-name in the comma-separated list that is bound by the angle brackets in a template instantiation. An argument is also called an *actual parameter*.

#### **Parameter**

A parameter is one of the following: an object or reference that is declared in a function declaration or definition (or in the catch clause of an exception handler); an identifier from the comma-separated list that is bound by the parentheses immediately following the macro name in a definition of a function-like macro; or a template-parameter. A parameter is also called a *formal parameter*.

The following example demonstrates the difference between a parameter and an argument:

```
void func(int n, char * pc); //n and pc are parameters
template <class T> class A {}; //T is a a parameter
int main()
{
   char c;
```

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++

```
char *p = &c;
func(5, p); //5 and p are arguments
A<long> a; //'long' is an argument
A<char> another_a; //'char' is an argument
return 0;
}
```

#### **Translation Unit**

A translation unit contains a sequence of one or more declarations. The Standard uses the term translation unit rather than source file because a single translation unit can be assembled from more than a single source file: A source file and the header files that are #included in it are a single translation unit.

### **Program**

A *program* consists of one or more translation units that are linked together.

### **Well-Formed Program**

A *well-formed program* is one that is constructed according to the Standard's syntax and semantic rules and that obeys the One Definition Rule (explained in the following section). An *ill-formed program* is one that does not meet these requirements.

#### Ivalues and rvalues

An *object* is a contiguous region of storage. An *lvalue* is an expression that refers to such an object. The original definition of lvalue referred to an object that can appear on the left-hand side of an assignment. However, const objects are lvalues that cannot be used in the left-hand side of an assignment. Similarly, an expression that can appear in the right-hand side of an expression (but not in the left-hand side of an expression) is an *rvalue*. For example

```
#include <string>
using namespace std;
int& f();
void func()
  int n;
  char buf[3];
 n = 5; // n is an lvalue; 5 is an rvalue
 buf[0] = 'a'; // buf[0] is an lvalue, 'a' is an rvalue
 string s1 = "a", s2 = "b", s3 = "c"; // "a", "b", "c" are rvalues
  s1 = // lvalue
      s2 +s3; //s2 and s3 are lvalues that are implicitly converted to rvalues
  s1 = //lvalue
      string("z"); //temporaries are rvalues
  int * p = new int; //p is an lvalue; 'new int' is an rvalue
  f() = 0; //a function call that returns a reference is an lvalue
  s1.size(); //otherwise, a function call is an rvalue expression
```

An Ivalue can appear in a context that requires an rvalue; in this case, the Ivalue is implicitly converted to an rvalue. An rvalue cannot be converted to an Ivalue. Therefore, it is possible to use every Ivalue expression in the example as

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++ an rvalue, but not vice versa.

### **Behavior Types**

The Standard lists several types of program behaviors, which are detailed in the following sections.

#### Implementation-Defined Behavior

Implementation-defined behavior (for a well-formed program and correct data) is one that depends on the particular implementation; it is a behavior that each implementation must document. For example, an implementation documents the size of fundamental types, whether a char can hold negative values, and whether the stack is unwound in the case of an uncaught exception. Implementation-defined behavior is also called implementation-dependent behavior.

#### **Unspecified Behavior**

Unspecified behavior (for a well-formed program and correct data) is one that depends on the particular implementation. The implementation is not required to document which behavior occurs (but it is allowed to do so). For example, whether operator new calls to the Standard C library function malloc() is unspecified. Following is another example: The storage type for the temporary copy of an exception object is allocated in an unspecified way (however, it cannot be allocated on the free store).

Implementation-defined behavior and unspecified behavior are similar. Both refer to consistent behavior that is implementation-specific. However, unspecified behavior usually refers to the underlying mechanism of the implementation, which users generally do not access directly. Implementation-dependent behavior refers to language constructs that can be used directly by users.

#### **Undefined Behavior**

*Undefined behavior* is one for which the Standard imposes no requirements. This definition might sound like an understatement because undefined behavior indicates a state that generally results from an erroneous program or erroneous data. Undefined behavior can be manifested as a runtime crash or as an unstable and unreliable program state -- or it might even pass unnoticed. Writing to a buffer past its boundary, accessing an out-of-range array subscript, dereferencing a dangling pointer, and other similar operations result in undefined behavior.

#### Conclusions

Unspecified behavior and implementation-defined behavior are consistent -- albeit nonportable -- behaviors that are left intentionally unspecified by the C++ Standard, usually to allow efficient and simple compiler implementation on various platforms. Conversely, undefined behavior is always undesirable and should never occur.

#### The One Definition Rule

A class, an enumeration, an inline function with external linkage, a class template, a nonstatic function template, a member function template, a static data member of a class template, or a template specialization for which some template parameters are not specified can be defined more than once in a program -- provided that each definition appears in a different translation unit, and provided that the definitions meet the requirements that are detailed in the following sections.

#### **Token-by-Token Identity**

Each definition must contain the same sequence of tokens. For example

On the other hand, white spaces and comments are immaterial:

```
//file fisrt.cpp
inline int C::getVal () { return 5; }
  //file sec.cpp
inline int C::getVal () { /*complies with the ODR*/
return 5; }
```

#### **Semantic Equivalence**

Each token in the identical sequences of the separate definitions has the same semantic contents. For example

```
//file first.cpp
typedef int I;
inline I C::getVal () { return 5; }
//file second.cpp
typedef unsigned int I;
inline I C::getVal () { return 5; } //error; different semantic content for I
```

### **Linkage Types**

A name that refers to an object, reference, type, function, template, namespace, or value that is declared in another scope is said to have *linkage*. The linkage can be either *external* or *internal*. Otherwise, the name has no linkage.

#### **External Linkage**

A name that can be referred to from other translation units or from other scopes of the translation unit in which it was defined has *external linkage*. Following are some examples:

```
void g(int n) {} //g has external linkage
int glob; //glob has external linkage
extern const int E_MAX=1024; //E_MAX has external linkage
namespace N
{
  int num; //N::num has external linkage
  void func();//N::func has external linkage
}
class C {}; //the name C has external linkage
```

#### **Internal Linkage**

A name that can be referred to by names from other scopes in the translation unit in which it was declared, but not from other translation units, has *internal linkage*. Following are some examples:

```
static void func() {} //func has internal linkage
union //members of a non-local anonymous union have internal linkage
{
   int n;
   void *p;
};
const int MAX=1024; //non-extern const variables have internal linkage
typedef int I; //typedefs have internal linkage
```

#### Names With No Linkage

A name that can only be referred to from the scope in which it is declared has no linkage. For example

```
void f()
{
  int a; //a has no linkage
  class B {/**/}; //a local class has no linkage
}
```

#### Side effect

A *side effect* is a change in the state of the execution environment. Modifying an object, accessing a volatile object, invoking a library I/O function, and calling a function that performs any of these operations are all side effects.

### Addenda

This part details the new features -- and extensions to existing features -- that have been adopted by the C++ Standard in recent years.

### **New Typecast Operators**

C++ still supports C-style cast, as in

```
int i = (int) 7.333;
```

Nonetheless, C-style cast notation is problematic for several reasons. First, the operator () is already used excessively in the language: in a function call, in precedence reordering of expressions, in operator overloading, and in other syntactic constructs. Second, C-style cast carries out different operations in different contexts -- so different that you can hardly tell which is which. It can perform an innocuous standard cast, such as converting an enum value to an int; but it can also cast two nonrelated types to one another. In addition, a C-style cast can be used to remove the const or volatile qualifiers of an object (and in earlier stages of C++, the language was capable of performing dynamic casts as well).

Because of these multiple meanings, the C-style cast is opaque. Sometimes it is very difficult for a reader to clearly understand the intent of the code author who uses a C-style cast operation. Consider the following example:

```
#include <iostream>
using namespace std;
void display(const unsigned char *pstr)
{
```

The new cast operators make the programmer's intention clearer and self-documenting. In addition, they enable the compiler to detect mistakes that cannot be detected with C-style cast. The new cast operators are intended to replace C-style cast; C++ programmers are encouraged to use them instead of C-style cast notation. These operators are detailed in the following sections.

#### static\_cast

static\_cast <Type> (Expr) performs well-behaved and reasonably well-behaved casts. One of its uses is to indicate explicitly a type conversion that is otherwise performed implicitly by the compiler.

For example

```
class Base{};
class Derived : public Base {};
void func( Derived * pd)
{
   Base * pb = static_cast<Base *> (pd); //explicit
}
```

A pointer to a derived object can be automatically converted to a pointer to a public base. The use of an explicit cast makes the programmer's intent clearer.

static\_cast can be used to document user-defined conversion. For example

```
class Integer
{
   public: operator int ();
};
void func(Integer& integer)
{
   int num = static_cast<int> (integer); //explicit
}
```

Narrowing conversions of numeric types can also be performed explicitly by a static\_cast. For example

```
void func()
{
  int num = 0;
  short short_num = static_cast<short> (num);
}
```

This conversion is somewhat riskier than the previous conversions. A short might not represent all the values that an int can hold; an explicit cast is used here, instead of an implicit conversion, to indicate that a type conversion is

performed. Casting an integral value to an enum is also a dangerous operation because there is no guarantee that the value of an int can be represented in an enum. Note that in this case, an explicit cast is necessary:

```
void func()
{
  enum status {good, bad};
  int num = 0;
  status s = static_cast<status> (num);
}
```

You can use static\_cast to navigate through class hierarchies. Unlike dynamic\_cast, however, it relies solely on the information that is available at compile time -- so don't use it instead of dynamic\_cast. Using static\_cast for this purpose is safer than using C-style cast because it does not perform conversions between nonrelated classes. For example

```
class A{};
class B{};
A *pa;
B * pb = static_cast<B *> (pa); //error, pointers are not related
```

#### const\_cast

const\_cast <T> (Expr) removes only the const or volatile qualifiers of Expr and converts them to type T. T must be the same type of Expr, except for the missing const or volatile attributes. For example

```
#include <iostream>
using namespace std;
void print(char *p) //parameter should have been declared as const; alas,
{
   cout<<p;
}
void f()
{
   const char msg[] = "Hello World\n";
   char * p = const_cast<char *> (msg); //remove constness
   print(p);
}
```

const\_cast can also convert an object to a const or volatile one:

```
void read(const volatile int * p);
int *p = new int;
read( const_cast<const volatile int *> (p) ); //explicit
```

Note that the removal of the const qualifier of an object does not guarantee that its value can be modified; it only guarantees that it can be used in a context that requires a non-const object. So that you understand these limitations, the following sections examines const semantics in further detail.

#### (f)const Semantics

There are actually two types of const: *true* const and *contractual* const. A true const object is an Ivalue that was originally defined as const. For example

```
const int cn = 5; // true const
const std::string msg("press any key to continue"); // true const
```

On the other hand, an object with contractual const quality is one that was defined without the const qualifier, but that is treated as though it were const. For example

```
void ReadValue(const int& num)
{
   cout<<num; // num may not be modified in ReadValue()
}
int main()
{
   int n =0;
   ReadValue(n); //contractual const, n is treated as if it were const
}</pre>
```

When a true const variable is explicitly cast to a non-const variable, the result of an attempt to change its value is undefined. This is because an implementation can store true const data in the read-only memory, and an attempt to write to it usually triggers a hardware exception. (Using an explicit cast to remove constness does not change the physical memory properties of a variable.) For example

```
const int cnum = 0; //true const, may be stored in the machine's ROM
const int * pci = &cnum;
int *pi = const_cast<int*> (pci); // brute force attempt to unconst a variable
cout<< *pi; //OK, value of cnum is not modified
*pi = 2; //undefined, an attempt to modify cnum which is a true const variable</pre>
```

On the other hand, casting away the contractual constness of an object makes it possible to modify its value safely:

```
int num = 0;
const int * pci = # // *pci is a contractual const int
int *pi = const_cast<int*> (pci); // get rid of contractual const
*pi = 2; // OK, modify num's value
```

To conclude, const\_cast is used to remove the const or volatile qualities of an object. The resultant value can be used in a context that requires a non-const or volatile object. The cast operation is safe as long as the resultant value is not modified. It is possible to modify the value of the resultant object only if the original operand is not truly const.

#### reinterpret\_cast

reinterpret\_cast <to> (from) is used in low-level, unsafe conversions. reinterpret\_cast merely returns a low-level reinterpretation of the bit pattern of its operand. Note, however, that reinterpret\_cast cannot alter the cv-qualification of its operand. The use of reinterpret\_cast is dangerous and highly non-portable -- use it sparingly. Following are examples of reinterpret\_cast uses.

reinterpret\_cast can be used to convert two pointers of completely nonrelated types, as in

```
#include <cstdio>
void mem_probe()
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++
long n = 1000000L; long *pl = &n;
unsigned char * pc = reinterpret_cast <unsigned char *> (pl);
printf("%d %d %d %d", pc[0], pc[1], pc[2], pc[3]); //memory dump
}
reinterpret_cast can cast integers to pointers, and vice versa. For example

void *pv = reinterpret_cast<void *> (0x00fffd);
int ptr = reinterpret_cast<int> (pv);
```

reinterpret\_cast can also be used for conversions between different types of function pointers. The result of using the resultant pointer to call a function with a nonmatching type is undefined.

Do not use reinterpret\_cast instead of static\_cast -- the results might be undefined. For example, using reinterpret\_cast to navigate through the class hierarchy of a multiply-inherited object is likely to yield the wrong result. Consider the following:

```
class A
{
  private:
    int n;
};
class B
{
  private:
    char c;
};
class C: public A, public B
{};
void func(B * pb)
{
    C *pc1 = static_cast<C*> (pb); //correct offset adjustment
    C *pc2 = reinterpret_cast<C*> (pb); //no offset calculated
}
int main()
{
    B b;
    func(&b);
}
```

On my machine, pc1 is assigned the value 0x0064fdf0, whereas pc2 is assigned 0x0064fdf4. This demonstrates the difference between the two cast operators. Using the information that is available at compile time, static\_cast converts a pointer to B to a pointer to C. It does so by causing pc1 to point at the start of C by subtracting the offset of the subobject B. On the other hand, reinterpret\_cast simply assigns the binary value of pb to pc2, without any further adjustments; for this reason, it yields the wrong result.

#### dynamic\_cast

In pre-standard C++, as was noted earlier, C-style cast was used to perform a dynamic cast as well. The cast was either static or dynamic, depending on the type of the operand. The Standardization committee, however, opposed this approach. An expensive runtime operation that looked exactly like a static cast (that is, penalty-free) can mislead the users. For this purpose, a new operator was introduced to the language: dynamic\_cast (dynamic\_cast is

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++

discussed in further detail in Chapter 7, "Runtime Type Identification"). The name and the syntax of dynamic\_cast were chosen to look markedly different from C-style cast. All other new typecast operators follow this model. Following is an example of dynamic\_cast:

```
Derived *p = dynamic_cast<derived *> (&base); //pointer form
Derived & rd = dynamic_cast<derived &> (base); //reference form
```

#### **Conclusions**

The new typecasting operators are clearer and more explicit in their intended purpose. A name such as dynamic\_cast, for example, warns its users about its incurred runtime overhead. Most importantly, though, the new cast operators are safer because they give the compiler a chance to detect the programmer's mistakes.

Users might find the proliferation of cast operators somewhat confusing. In particular, the choice between static\_cast and reinterpret\_cast might not seem immediately clear. How to choose? As a rule, static\_cast is the first choice. If the compiler refuses to accept it, use reinterpret\_cast instead.

### **Built-in bool Type**

The built-in bool data type was added to the Standard after consideration of several other proposals. None of these was found satisfactory. Following is an overview some of these proposals, which is in turn followed by a discussion of the characteristics of the bool type.

#### typedef Boolean

One suggestion was to use a typedef for a Boolean data type:

```
typedef int bool;
```

However, a typedef that relies on another built-in type of the language renders the Boolean type unusable with some language features. For example, using it in function overloading can result in ambiguities:

```
void f(bool);
void f(int);//error, redefinition of void f(bool);
```

In addition, a typedef is not strongly-typed. Consequently, it is impossible to ensure that only Boolean values are assigned to it in a context that requires Boolean values.

#### enum Type

An alternative solution was to use an enum type:

```
enum bool { false, true};
```

enums are strongly-typed. However, the committee wanted to ensure backward compatibility with old code that used int values as a Boolean data type. For example

```
#include <ctype.h>
enum bool {false, true};
void f()
{
   enum bool b;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++ b = islower('a'); //compile time error, int assigned to an enum }
```

#### Class bool

A third suggestion was to use a class such as the following:

```
class bool
{
private:
   int val;
public:
   operator int();
};
```

Such a class guarantees type uniqueness, so it can be used to overload functions and to specialize templates. In addition, it is backward compatible with Boolean integers. There are, however, several drawbacks to the class approach. First, users are required to #include a dedicated header and to link their programs with the compiled code of the class. Worse yet, the conversion operator might interfere with user-defined conversion operators that are defined in other classes. Finally, a full-blown class that defines constructors and conversion operators is significantly less efficient than a fundamental type. For these reasons, the Standardization committee decided to add a new built-in type.

#### A Built-in Type bool

bool is an implementation-dependent integral type that can hold either a true or a false value. A standardized Boolean type has several advantages:

- **Portability** -- All Standard compliant compilers support bool type. When code is ported to different platforms, it will work as expected.
- **Readability** -- The use of explicit keywords such as true, false, and bool is self-documenting and is more evident than the use of int values.
- Type Distinctness -- Because bool is a distinct type, the following functions are now also distinct:

```
void f(bool b);
void f(int n);
```

• **Performance** -- Memory usage can be optimized by the implementation, which is allowed to use a single byte to represent a bool instead of an int. In addition, the use of a built-in type rather than a class also ensures the highest performance.

With the introduction of the bool data type, built-in operators were modified accordingly to work with bool values. The logical operators &&, | |, and ! now take bool values as arguments and return bool results. Similarly, the relational operators <, >, <=, >=, ==, and != return bool results. In addition, iostream classes were adjusted to support the new type.

#### (f) Viewing bool Variables as Literals

By default, iostream objects display bool variables as 0 and 1. It is possible to override the default setting by inserting the formatting flag boolalpha to the stream object. Subsequently, the symbolic representations false and true are displayed instead of 0 and 1. For example

```
#include <iostream>
```

```
using namespace std;
int main()
{
  bool b = true;
  cout<<b; // default setting; display 1
  cout<<boolalpha; //henceforth, display 'true' and 'false' instead of 1 and 0
  cout<<b; // output: true
  cout<<!b; // output: false
  return 0;
}</pre>
```

### **Exception Handling**

Exception handling is used to report and handle runtime errors. Supplementary features, namely *exception specifications* and *function* try *blocks*, were added to the Standard in recent years. The following sections provide a brief overview of these features. (Exception handling and the supplementary features are discussed in more detail in Chapter 6, "Exception Handling.")

#### **Exception Specification**

A function can indicate the potential exceptions it can throw by specifying a list of these exceptions. Exception specifications are particularly useful when users of such a function can only view its prototype but cannot access its source file. Following is an example of specifying an exception:

#### **Function try Blocks**

A *function* try *block* is a function whose body consists of a try block and its associated handlers. A function try block enables you to catch exceptions that might be thrown by a base class constructor or by a constructor of a member object. The original specification of exception handling did not enable users to handle exceptions thrown from a constructor or a member initialization list locally; a function try block fixes this loophole. Following is an example of a function try block:

### **Memory Management**

The Standard now defines three different versions of operator new: plain new, nothrow new, and placement new. Each of these operators has an array version as well. The Standard also defines six matching types of operator delete that correspond the specific versions of new. Memory management and the recently added versions of new and delete are discussed in further detail in Chapter 11, "Memory Management."

#### Operator new Throws an Exception in Case of a Failure

In earlier stages of C++, operator new returned a NULL pointer when it failed to allocate the requested amount of memory. The C++ standardization committee changed the specification of operator new so that it throws an exception of type std::bad\_alloc, rather than returning a NULL pointer, when it fails. A program that uses operator new directly or indirectly has to handle a potential std::bad\_alloc exception. For example

```
void f(int size) //standard-conforming usage of operator new
  char *p = new char [size];
  //...use p safely
 delete [] p;
 return;
#include <stdexcept>
#include <iostream>
using namespace std;
const int BUF_SIZE = 1048576L;
int main()
  try
    f(BUF_SIZE);
  catch(bad_alloc& ex) //handle exception thrown from f()
    cout << ex. what() << endl;
    //...other diagnostics and remedies
  return -1;
```

#### nothrow new

The Standard also defines an exception-free version of operator new, which returns a NULL pointer in case of a failure rather than throwing an exception. This version of new takes an additional argument named nothrow. For example

```
#include <new>
#include <string>
using namespace std;
void f(int size) // demonstrating nothrow new
{
   char *p = new (nothrow) char [size]; //array nothrow new
```

```
if (p == 0)
{
    //...use p
    delete [] p;
}
string *pstr = new (nothrow) string; //plain nothrow new
if (pstr == 0)
{
    //...use pstr
    delete [] pstr;
}
return;
```

#### Placement new

An additional version of operator new enables the user to construct an object at a predetermined memory position. This version is called placement new. Following is an example of using placement new:

#### **Constructors and Destructors**

Fundamental types can be initialized by a special constructor. In addition, the Standard also defines a pseudo destructor for each of these types (see Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator").

### **Constructors of Fundamental Types**

Variables of fundamental types can be initialized by invoking their constructor explicitly. For example

```
void f()
{
  int n = int(); // zero initialized
  char c = char(); // also zero initialized
  double d = double(0.5); //other initializers are allowed
}
```

This language extension enables uniform treatment in templates for fundamental types and user-defined types.

#### **Explicit Constructors**

A constructor that takes a single argument is, by default, an implicit conversion operator that converts its argument to

an object of its class. In order to avoid such implicit conversions, a constructor that takes one argument can be declared explicit. For example

```
class C
{
public:
   explicit C(int size); // disallow implicit conversion
};
```

#### **Pseudo Destructors**

A *pseudo destructor* is a syntactic construct whose sole purpose is to satisfy the need for generic algorithms and containers. It is a no-op code, and has no real effect on its object. For example

```
typedef int N;
void f()
{
  N i = 0;
  i.N::~N(); // pseudo destructor invocation
  i = 1; // i was not affected by the invocation of the pseudo destructor
}
```

### **Local Definitions and Scoping Rules**

The scoping rules for a variable that is defined in a for statement were changed. Additionally, it is now possible to define and initialize variables inside an if condition.

#### The Scope of a Local Loop Counter

C++ allows declaration of variables wherever they are needed, enabling immediate initializations. A good example is a loop counter, which can be declared inside a for statement. For example

In earlier stages of C++, a local variable declared in this way remained accessible in its enclosing block. This was a source for bugs and name hiding. Consequently, the standard has been revised to fix this loophole, so to speak; local variables that are created this way are inaccessible outside their for statement. In the preceding example, the variable i goes out of scope when the loop is exited.

#### **Declaring Variables Inside an if Condition**

You can define and initialize a variable inside the condition of an if statement. For example

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++
```

The advantage of declaring the pointer pd locally is obvious: It is always initialized with an appropriate value, and it isn't visible to other parts of the program that are not to use it (see Chapter 12, "Optimizing Your Code").

### **Namespaces**

Namespaces were the latest feature to be added to the language. Namespaces are used to prevent name conflicts and to facilitate configuration management and version control in large-scale projects. Most of the components of the Standard Library are grouped under namespace std. There are three methods for injecting namespace members into a scope: a using directive, a using declaration, or a fully qualified name. Argument-dependent lookup, or Koenig lookup, simplifies the use of namespaces by automating the name lookup process. Namespaces are discussed in more detail in Chapter 8, "Namespaces."

### **Templates**

A *template* is a mold from which related functions or classes are instantiated. Templates have come a long way since they were first introduced to the language in 1991. Back then, they were merely clever macros. However, the adoption of STL required considerable extensions to this feature. An overview of these extension is provided in the following sections. Templates are discussed in detail in Chapter 9, "Templates."

#### **Template-Template Argument**

A template can now take a template as an argument. For example

```
int send(const std::vector<char*>& );
int main()
{
   std::vector <std::vector<char*> > msg_que(10);
   //...fill msg_que
   for (int i =0; i < 10; i++) //transmit messages
      send(msg_que[i]);
   return 0;
}</pre>
```

#### **Default Type Arguments**

Templates can have default type arguments. For example

```
template <class T, class S = size_t > class C //using a default type
```

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++ { / \* \* / };

#### **Member Templates**

Templates can be nested; a template can be declared within another class or a class template. Such a template is called a *member template*. Following is an example:

```
template < class T > class C
{
public:
    template < class T2 > int func(const T2&); //declaration of a member template
    //...
};
template < class T > template < class T2 > int C < T > :: func(const T2& s) // definition
{
    //...
}
```

#### The typename Keyword

To support member templates and template inheritance, the keyword typename was added to the language. By default, the compiler assumes that a qualified name refers to a non-type. The typename keyword instructs the compiler to supersede this default interpretation and resolve the ambiguity in favor of a typename instead.

#### **Exported Templates**

It is possible to compile a template definition only once, and to subsequently use only the template's declaration in other translation units. To compile a template separately and then use its declaration, the template has to be *exported*. This is done by preceding the template's definition with the keyword export.

### The Standard Template Library

According to Bjarne Stroustrup, the most important change in C++ since 1991 is not a language change; it is the addition of the standard library. The *Standard Template Library*, or *STL*, comprises a substantial part of the Standard Library. STL is collection of generic containers -- such as vector, list, and stack -- and a rich collection of generic algorithms for sorting, finding, merging, and transforming these containers. Chapter 10, "STL and Generic Programming," is dedicated to STL.

#### Internationalization and Localization

The current C++ Standard is an international Standard approved by ISO. To qualify as such, Standard C++ has been fully internationalized. Internationalization consists of several modifications and extensions. These include the addition of the keyword wchar\_t (wchar\_t was already defined in ISO C as a typedef but it wasn't a reserved keyword). In addition, the standard stream and string classes have been templatized to support both narrow and wide characters. Finally, the <locale> library defines template classes and declares functions that encapsulate and manipulate locale-related information such as monetary, numeric, and time conventions. The locale feature sets are encapsulated in classes (or *facets*) that the users can extend.

#### Wide Character Streams

C++ provides four standard I/O streams that are automatically instantiated before a program's outset. They are defined in the header <iostream>:

```
cin    // standard input stream of char
cout    // standard output stream of char
cerr    // standard unbuffered output stream for error messages
clog    // standard output stream for error messages
```

Each of these four streams now has a corresponding wide-character version:

```
wcin
wcout
wcerr
wclog
```

#### **Miscellaneous**

Two additional extensions were recently added to the Standard: the initialization of const static data members inside the class body and the mutable storage specifier. Both of these extensions are discussed in the following sections.

#### **Initialization of const static Data Members**

const static data members of an integral type can now be initialized inside their class. In this case, the initialization is also a definition, so no further definitions are required outside the class body. For example

#### A mutable Object Member

A const member function cannot modify the state of its object. However, auxiliary data members (flags, reference counters) sometimes have to be modified by a const member function. Such data members can be declared mutable. A mutable member is never const, even if its object is const; therefore, it can be modified by a const member function. The following example demonstrates the use of this feature:

```
class Buffer
{
private:
   void * data; //raw data buffer to be transmitted on some network
   size_t size;
   mutable int crc;//used to verify that no errors occurred during transmission
public:
   int GetCrc() const;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 2 - Standard Briefing: The Latest Addenda to ANSI/ISO C++
    void Transmit() const; //computation of crc is done here
};
void f()
{
    Buffer buffer;
    //...fill buffer with data
    buffer.Transmit(); //crc can be modified here; non-mutable members may not
```

There is no point in calculating the crc value every time a few more bytes are appended to buffer. Instead, it is computed by the member function Transmit() right before buffer is sent. However, Transmit() is not supposed to modify its object's state so that it is declared as a const member function. In order to allow assignment of the correct crc value, the data member crc is declared mutable; hence, it can be modified by a const member function.

### **Deprecated Feature**

A *deprecated feature* is one that the current edition of the Standard regards as normative, but that is not guaranteed to be part of the Standard in future revisions. Again, this is somewhat understating the intent of this definition. One of the consequences of the evolution and standardization of a programming language is the gradual removal of undesirable, dangerous, or redundant features and constructs. By deprecating a feature, the standardization committee expresses the desire to have the feature removed from the language. Removing it from the language altogether is impractical because existing code will not compile anymore. The deprecation gives the user sufficient time to replace a deprecated feature with a Standard-endorsed feature. The Standard lists the features that are discussed in the following sections as deprecated.

### Use of an Operand of Type bool with the Postfix ++ Operator

Applying postfix ++ to a variable of type bool is still allowed for backward compatibility with old code that uses plain int or some typedef, as in

```
bool done = false;
while(!done)
{
   if(condition)
     //...do something
   else done++; //deprecated
}
```

Incrementing a bool always yields true, regardless of the original value. However, this practice is deprecated; therefore, it might not be supported in the future. Remember that applying -- (decrement operator) to a bool variable is illegal.

### Use of static to Declare Objects in Namespace Scope

The use of the keyword static to declare a function or an object local to a translation unit is deprecated. Instead, use an *unnamed namespace* for that purpose (more on this in Chapter 8).

#### **Access Declarations**

The access of a member of a base class can be changed in a derived class by an access declaration. For example

```
class A
{
  public:
    int k;
    int l;
};
class D: public A
{
  private:
        A::1; // access declaration changes access of A::1 to private; deprecated
};
The use of access declarations is deprecated. Use a using declaration instead:

class D: public A // using-declaration version
{
  private:
        using A::1; // using declaration changes the access of A::1 to private
};
void func()
{
        D d;
        d.1 = 0; //error; cannot access private member
```

### Implicit Conversion from const to non-const Qualification for String Literals

A string literal can be implicitly converted from type pointer to const char to type pointer to char. Similarly, a wide string literal can be implicitly converted from type pointer to const wchar\_t to pointer to wchar\_t. For example

```
char *s = "abc"; //string literal implicitly converted to non-const; deprecated
```

The type of the literal "abc" is const char[], but s is a pointer to non-const char. Such implicit conversions from const to non-const qualifications for string literals are deprecated because they might lead to the following erroneous code:

```
strcpy(s, "cde"); //undefined behavior
The preferred form is
const char *s = "abc"; //OK
```

#### Standard C Headers in the form <name.h>

For compatibility with the Standard C library, C++ still supports the naming convention of C headers in the form <xxx.h> -- but this naming convention is now deprecated (this is discussed in more detail in Chapter 8). For example

```
#include <stdlib.h> //deprecated
```

Use the newer naming convention, <cxxx>, instead:

```
#include <cstdlib> //OK, 'c' prefixed and ".h" omitted
```

The reason for this is that ".h" headers inject all their names into the global namespace, whereas the newer convention headers, <cname>, keep their names in namespace std.

#### Implicit int Declarations

The default type for missing declarations such as the following is int:

```
static k =0; //'int' type deduced; deprecated
const c =0; //'int' type deduced; deprecated
```

This convention is now considered deprecated. Instead, use explicit type names:

```
static int k = 5; const int c = 0;
```

#### Other Deprecated Features

The Standard deprecates some of the members of old iostream classes (article 4.6). In addition, it deprecates three types in the header <strstream> that associate stream buffers with character array objects (article 4.7).

From a user's point of view, deprecated features are not to be used in new code because future versions of the language will flag it as an error. In the interim period, compilers can issue a warning about its use.

#### **Conclusions**

As you have seen, standard C++ is quite different from what it used to be four, five, or ten years ago. Many of the changes and modifications have been initiated by software vendors (the bool data type, for instance). Others have been initiated by the Standardization committee (for example, the new cast operators and STL). During the hectic standardization process, complaints about "randomly accepted changes" on the one hand, and "missing features" on the other hand, were often heard. However, the Standardization committee has been very thoughtful and prudent in selecting these extensions and modifications. Fortunately, the approval of the Standard by ISO in 1998 ensures its stability for at least five years. This freeze period enables both compiler vendors and language users to digest the current Standard and use it effectively. In doing so, one usually finds that C++ is better today than it ever was.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

3

# **Operator Overloading**

#### by Danny Kalev

- Introduction
- Operator Overloading Rules of Thumb
  - Members and Nonmembers
  - Operator's Interface
  - Operator Associativity
- Restrictions on Operator Overloading
  - o Operators Can Only Be Overloaded for User-Defined Types
  - o Invention of New Operators Is Not Allowed
  - o Precedence and Argument Number
  - Default Parameters
  - o Operators That Cannot Be Overloaded
- Conversion Operators
  - Standard Versus User-Defined Conversions
- Postfix and Prefix Operators
- Using Function Call Syntax
- Consistent Operator Overloading
- 'Returning Objects by Value
- Multiple Overloading
- Overloading Operators for Other User-Defined types
- Overloading the Subscripts Operator
- Function Objects
- Conclusions

#### Introduction

A built-in operator can be extended to support user-defined types as well. Such an extension *overloads* the predefined meaning of an operator rather than overrides it. Although ordinary functions can offer the same functionality, operator overloading provides a uniform notational convention that is clearer than the ordinary function call syntax. For example

```
Monday < Tuesday; //overloaded <
Greater than(Monday, Tuesday);</pre>
```

The history of operator overloading can be traced back to the early days of Fortran. Fortran, the first high-level programming language, presented the concept of operator overloading in a way that was revolutionary back in the mid-1950s. For the first time, built-in operators such as + or - could be applied to various data types: integers, real and complex. Until then, assembly languages -- which didn't even support operator notation -- had been the only choice for programmers. Fortran's operator overloading was limited to a fixed set of built-in data types; they could not be extended by the programmer. Object-based programming languages offered user-defined overloaded operators. In such languages, it is possible to associate a set of operators with a user-defined type. Object-oriented languages usually incorporate operator overloading as well.

The capability to redefine the meaning of a built-in operator in C++ was a source of criticism. People -- mostly C programmers making the migration to C++ -- felt that overloading an operator was as dangerous as enabling the programmer to add, remove, or change keywords of the language. Still, notwithstanding the potential Tower of Babel that might arise as a result, operator overloading is one of the most fundamental features of C++ and is mandatory for generic programming (generic programming is discussed in Chapter 10, "STL and Generic Programming."). Today, even languages that tried to make do without operator overloading are in the process of adding this feature.

This chapter explores the benefits as well as the potential problems of operator overloading. It also discusses the few restrictions that apply to operator overloading. Finally, it presents conversion operators, which are a special form of overloaded operators.

An overloaded operator is essentially a function whose name is an operator preceded by the keyword operator. For example

```
class Book
{
private:
  long ISBN;
public:
//...
  long get_ISBN() const { return ISBN;}
};
bool operator < (const Book& b1, const Book& b2) // overload operator <
{
  return b1.get_ISBN() < b2.get_ISBN();
}</pre>
```

# **Operator Overloading Rules of Thumb**

C++ enforces few restrictions on operator overloading. For instance, it does not prohibit a programmer from overloading the operator ++ in order to perform a decrement operation on its object (to the dismay of its users, who would instead expect operator ++ to perform an increment operation). Such misuses and puns can lead to a cryptic coding style that is almost unintelligible. Often, the source code that contains the definition of an overloaded operator is not accessible to its users; therefore, overloading an operator in an unexpected, nonintuitive manner is not recommended.

The other extreme, avoiding operator overloading altogether, is not a practical choice either because it means giving up an important tool for data abstraction and generic programming. When you are overloading an operator to support a user-defined type, therefore, it is recommended that you adhere to the basic semantics of the corresponding built-in operator. In other words, an overloaded operator has the same side effects on its operands and manifests the same interface as does the corresponding built-in operator.

#### **Members and Nonmembers**

Most of the overloaded operators can be declared either as nonstatic class members or as nonmember functions. In the following example, the operator == is overloaded as a nonstatic class member:

```
class Date
{
private:
   int day;
   int month;
   int year;
public:
   bool operator == (const Date & d ); // 1: member function
};
```

Alternatively, it can be declared as a friend function (the criteria for choosing between a member and a friend will be discussed later in this chapter):

```
bool operator ==( const Date & d1, const Date& d2); // 2: nonmember function
class Date
{
private:
   int day;
   int month;
   int year;
public:
   friend bool operator ==( const Date & d1, const Date& d2);
};
```

Nonetheless, the operators [], (), =, and -> can only be declared as nonstatic member functions; this ensures that their first operand is an Ivalue.

#### **Operator's Interface**

When you overload an operator, adhere to the interface of its built-in counterpart. The interface of an operator consists of the number of operands to which it applies, whether any of these operands can be altered by the operator, and the result that is returned by the operator. For example, consider operator ==. Its built-in version can be applied to a wide variety of fundamental types, including int, bool, float, and char, and to pointers. The underlying computation process that is required for testing whether the operands of operator == are equal is an implementation-detail. However, it can be generalized that the built-in == operator tests its left and right operands for equality and returns a bool value as its result. It is important to note also that operator == does not modify any of its operands; in addition, the order of the operands is immaterial in the case of operator ==. An overloaded operator == should conform to this behavior, too.

#### **Operator Associativity**

Operator == is binary and symmetrical. An overloaded version of == conforms to these qualities. It takes two operands, which are of the same type. Indeed, one can use operator == to test the equality of two operands of distinct fundamental types, for example char and int. However, C++ automatically applies *integral promotion* to the operands in this case; as a result, the seemingly distinct types are promoted to a single common type before they are compared. The symmetrical quality implies that an overloaded operator == is to be defined as a friend function rather than a member function. So that you can see why, here's a comparison of two different versions of the same overloaded operator ==:

```
class Date
{
  private:
    int day;
    int month;
    int year;

public:
    Date();
    bool operator == (const Date & d) const; // 1 asymmetrical
    friend bool operator ==(const Date& d1, const Date& d2); //2 symmetrical
};

bool operator ==(const Date& d1, const Date& d2);
```

The overloaded operator == that is declared as a member function in (1) is inconsistent with the built-in operator == because it takes two arguments of different types. The compiler transforms the member operator == into the following:

```
bool Date::operator == (const Date *const, const Date&) const;
```

The first argument is a const this pointer that points to a const object (remember that this is always a const pointer; it points to a const object when the member function is also const). The second argument is a reference to const Date. Clearly, these are two distinct types for which no standard conversion exists. On the other hand, the friend version takes two arguments of the same type. There are practical implications to favoring the friend version over the member function. STL algorithms rely on a symmetrical version of the overloaded operator ==. For example, containers that store objects that do not have symmetrical operator == cannot be sorted.

Another example, built-in operator +=, which also takes two operands, modifies its left operand but leaves the right operand unchanged. The interface of an overloaded += needs to reflect the fact that it modifies its object but not its right operand. This is reflected by the declaration of the function parameter as const, whereas the function itself is a

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading

non-const member function. For example

```
class Date
{
private:
   int day;
   int month;
   int year;
public:
   Date();
   //built-in += changes its left operand but not its right one
   //the same behavior is maintained here
   Date & operator += (const Date & d);
};
```

To conclude, it can be said that every overloaded operator must implement an interface that is similar to the one that is manifested by the built-in operator. The implementer is free to define the underlying operation and hide its details -- as long as it conforms to the interface.

# **Restrictions on Operator Overloading**

As was previously noted, an overloaded operator is a function that is declared with the operator keyword, immediately followed by an *operator id*. An operator id can be one of the following:

```
new delete new[] delete[]
+ - * / % ^ & | ~
! = < > += -= *= /= %=
^= &= |= << >> >>= <<= == !=
<= >= && || ++ -- , ->* ->
() []
```

In addition, the following operators can be overloaded both in their unary and binary forms:

```
+ - * &
```

Overloaded operators are inherited in the same manner as other base class functions. Note that these rules do not apply to the assignment operator, which is implicitly declared for a class if it is not declared by the user. Therefore, a base class assignment operator is always hidden by the copy assignment operator of the derived class. (The assignment operator is discussed in Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator.")

#### Operators Can Only Be Overloaded for User-Defined Types

An overloaded operator must take at least one argument of a user-defined type (operators new and delete are an exception -- see Chapter 11, "Memory Management," for more details). This rule ensures that users cannot alter the meaning of expressions that contain only fundamental types. For example

```
int i,j,k;
k = i + j; //always uses built-in = and +
```

#### **Invention of New Operators Is Not Allowed**

An overloaded operator extends a built-in one, so you cannot introduce new operators into the language (conversion operators differ from ordinary overloaded operators in this respect). The following example attempts to overload the @ operator, but does not compile for that reason:

```
void operator @ (int); //illegal, @ is not a built-in operator or a type name
```

#### **Precedence and Argument Number**

Neither the precedence nor the number of arguments of an operator can be altered. For example, an overloaded && must have exactly two arguments -- as does the built-in && operator. In addition, the precedence of an operator cannot be altered when it is overloaded. A sequence of two or more overloaded operators, for instance t2<t1/t2, is evaluated according to the precedence rules of the built-in operators. Because the division operator ranks higher than the less operator, the expression is always interpreted as t2<(t1/t2).

#### **Default Parameters**

Unlike ordinary functions, overloaded operators cannot declare a parameter with a default value (operator () is the exception to this rule; it is discussed later).

```
class Date
{
private:
  int day;
  int month;
  int year;
public:
  Date & operator += (const Date & d = Date() ); //error, default argument
};
```

This rule might seem arbitrary, but it captures the behavior of built-in operators, which never have default operands either.

#### **Operators That Cannot Be Overloaded**

There are several operators that cannot be overloaded. They are characterized by the fact that they take a name, rather than an object, as their right operand. These operators are:

- Direct member access, operator.
- Deference pointer to class member, operator . \*
- Scope resolution, operator ::
- Size of, operator sizeof

The conditional operator ?: cannot be overloaded either.

Additionally, the new type cast operators -- static\_cast<>, dynamic\_cast<>, reinterpret\_cast<>, and const\_cast<> -- and the # and ## preprocessor tokens cannot be overloaded.

# **Conversion Operators**

It is not uncommon to find C++ and C code used together. For instance, legacy systems that were originally written in C can be wrapped by an object-oriented interface. Such bilingual systems often need to support a dual interface at the same time -- one that caters to an object-oriented environment and another that caters to C environment. Classes that implement specific numeric entities -- such as complex numbers and binary numbers -- and nibbles also tend to use conversion operators to enable smoother interaction with fundamental types.

Strings are a classic example of the need for a dual interface. A string object might have to be used in contexts that support only null-terminated char arrays. For example

```
class Mystring
private:
  char *s;
  int size;
public:
 Mystring(const char *);
 Mystring();
//...
};
#include <cstring>
#include "Mystring.h"
using namespace std;
int main()
 Mystring str("hello world");
 int n = strcmp(str, "Hello"); //compile time error:
                                 //str is not of type const char *
 return 0;
```

C++ offers an automatic means of type conversion for such cases. A conversion operator can be thought of as a user-defined typecasting operator; it converts its object to a different type in contexts that require that specific type. The conversion is done automatically. For example

```
class Mystring  //now with conversion operator
{
private:
   char *s;
   int size;
public:
   Mystring();
   operator const char * () {return s; } //convert Mystring to a C-string
//...
};
int n = strcmp(str, "Hello"); //OK, automatic conversion of str to const char *
```

Conversion operators differ from ordinary overloaded operators in two ways. First, a conversion operator does not have a return value (not even void). The return value is deduced from the operator's name.

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading

Secondly, a conversion operator takes no arguments.

Conversion operators can convert their object to any given type, fundamental and user-defined alike:

```
struct DateRep //legacy C code
 char day;
  char month;
 short year;
};
class Date // object-oriented wrapper
private:
 DateRep dr;
public:
  operator DateRep () const { return dr;} // automatic conversion to DateRep
extern "C" int transmit_date(DateRep); // C-based communication API function
int main()
 Date d;
  //...use d
  //transmit date object as a binary stream to a remote client
  int ret_stat = transmit_date; //using legacy communication API
 return 0;
```

#### **Standard Versus User-Defined Conversions**

The interaction of a user-defined conversion with a standard conversion can cause undesirable surprises and side effects, and therefore must be used with caution. Examine the following concrete example.

A non-explicit constructor that takes a single argument is also a conversion operator, which casts its argument to an object of this class. When the compiler has to resolve an overloaded function call, it takes into consideration such user-defined conversions in addition to the standard ones. For example

'Suppose you add, at a later stage, another overloaded version of f ( ):

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading
```

```
void f (double);
```

Now the same function call resolves differently:

```
f(5.f); // now calls f(double), not f(Numeric)
```

This is because float is promoted to double automatically in order to match an overloaded function signature. This is a standard type conversion. On the other hand, the conversion of float to Numeric is a user-defined conversion. User-defined conversions rank lower than standard conversions -in overload resolution; as a result, the function call resolves differently.

Because of this phenomenon and others, conversion operators have been severely criticized. Some programming schools ban their usage altogether. However, conversion operators are a valuable -- and sometimes inevitable -- tool for bridging between dual interfaces, as you have seen.

## **Postfix and Prefix Operators**

For primitive types, C++ distinguishes between ++x; and x++; as well as between --x; and x--;. Under some circumstances, objects have to distinguish between prefix and postfix overloaded operators as well (for example, as an optimization measure. See Chapter 12, "Optimizing Your Code"). Postfix operators are declared with a dummy intargument, whereas their prefix counterparts take no arguments. For example

```
class Date
{
public:
    Date& operator++(); //prefix
    Date& operator--(); //prefix
    Date& operator++(int unused); //postfix
    Date& operator--(int unused); //postfix
};
void f()
{
Date d, d1;
d1 = ++d;//prefix: first increment d and then assign to d1
d1 = d++; //postfix; first assign, increment d afterwards
}
```

# **Using Function Call Syntax**

An overloaded operator call is merely "syntactic sugar" for an ordinary function call. You can use the explicit function call instead of the operator syntax as follows:

```
bool operator==(const Date& d1, const Date& d2);
void f()
{
   Date d, d1;
   bool equal;
   d1.operator++(0); // equivalent to: d1++;
   d1.operator++(); // equivalent to: ++d1;
   equal = operator==(d, d1);// equivalent to: d==d1;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading

Date&(Date::*pmf) (); //pointer to member function

pmf = & Date::operator++;
}
```

# **Consistent Operator Overloading**

Whenever you overload operators such as + or -, it might become necessary to support the corresponding += and -= operators as well. The compiler does not do that for you automatically. Consider the following example:

```
class Date
{
public:
   Date& operator + (const Date& d); //note: operator += not defined
};
Date d1, d2;
d1 = d1 + d2; //fine; uses overloaded + and default assignment operator
d1 += d2; //compile time error: 'no user defined operator += for class Date'
```

Theoretically, the compiler could synthesize a compound operator += by combing the assignment operator and the overloaded + operator so that the expression d1 += d2; is automatically expanded into d1 = d1+d2;. However, this is undesirable because the automatic expansion might be less efficient than a user-defined version of the operator. An automated version creates a temporary object, whereas a user-defined version can avoid it. Moreover, it is not difficult to think of situations in which a class has an overloaded operator +, but does not have operator += intentionally.

# **Returning Objects by Value**

For the sake of efficiency, large objects are usually passed to -- or returned from -- a function by reference or by their address. There are, however, a few circumstances in which the best choice is still to return an object by value. Operator + is an example of this situation. It has to return a result object, but it cannot modify any of its operands. The seemingly natural choice is to allocate the result object on the free store and return its address. Nevertheless, this is not such a good idea. Dynamic memory allocation is significantly slower than local storage. It also might fail and throw an exception, which then has to be caught and handled. Even worse, this solution is error prone because it is unclear who is responsible for deleting this object -- the creator or the user?

Another solution is to use a static object and return it by reference. For example

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading
```

```
static Year result;
result = Year(this->getYear() + other.getYear() );
return result;
}
```

Static objects solve the ownership problem, but they are still problematic: On each invocation of the overloaded operator, the same instance of the static object is being modified and returned to the caller. The same object can be returned by reference to several more users, who do not know that they are holding a shared instance that has just been modified behind their back.

Finally, the safest and most efficient solution is still to return the result object by value:

```
class Year
{
  private:
    int year;
  public:
    Year(int y = 0) : year(y) {}
    Year operator + (const Year& other) const; //return Year object by value int getYear() const;
    void setYear(int y);
};
Year Year::operator + (const Year& other) const
{
    return Year(this->getYear() + other.getYear() );
}
```

# **Multiple Overloading**

Overloaded operators obey the rules of function overloading. Therefore, it is possible to overload an operator more than once. When is it useful? Consider the following Month class and its associated operator ==:

```
class Month
{
private:
   int m;
public:
   Month(int m = 0);
};
bool operator == (const Month& m1, const Month &m2);
```

It is possible to use the overloaded operator == to compare a plain int value and a Month object due to the implicit conversion of int to Month. For example

```
void f()
{
  int n = 7;
  Month June(6);
  bool same =
    (June == n); //calls bool operator == (const Month& m1, const Month &m2);
}
```

This works fine, but it i's inefficient: The argument n is first converted to a temporary Month object, which is then compared with the object June. You can avoid the unnecessary construction of a temporary object by defining additional overloaded versions of operator ==:

```
bool operator == (int m, const Month& month);
bool operator == (const Month& month, int m);
```

Consequently, the expression June == n will now invoke the following overloaded operator:

```
bool operator == (const Month& month, int m);
```

This overloaded version does not create a temporary object, so it's more efficient. The same performance considerations led the C++ Standardization committee to define three distinct versions of operator == for std::string (see Chapter 10, ""STL and Generic Programming"") and other classes of the Standard Library.'

# Overloading Operators for Other User-Defined types

You can overload an operator for enum types as well. For example, it may be useful to overload operators such as ++ and -- so that they can iterate through the enumerator values of a given enum type. You can do it like this:

```
#include <iostream>
using namespace std;
enum Days
  Monday,
  Tuesday,
  Wednesday,
  Thursday,
  Friday,
  Saturday,
  Sunday
};
Days& operator++(Days& d, int) // postfix ++
  if (d == Sunday)
    return d = Monday; //rollover
  int temp = d; //convert to an int
  return d = static_cast<Days> (++temp);
int main()
Days day = Monday;
 for (;;) //display days as integers
   cout << day << endl;
   day++;
   if (day == Sunday)
     break;
 return 0;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading
```

If you prefer to view the enumerators in their symbolic representation rather than as integers, you can overload the operator << as well:

```
ostream& operator<<(ostream& os, Days d) //display Days in symbolic form
  switch
  case Monday:
    return os<<"Monday";
  case Tuesday:
    return os<<"Tuesday";
  case Wednesday:
    return os<<"Wednesday";
  case Thursday:
    return os<<"Thursady";
  case Friday:
    return os<<"Friday";
  case Saturday:
    return os<<"Satrurday";
  case Sunday:
    return os<<"Sunday";
 default:
    return os<<"Unknown";
```

# **Overloading the Subscripts Operator**

For various classes that contain arrays of elements, it's handy to overload the subscript operator to access a single element. Remember always to define two versions of the subscript operator: a const version and a non-const version. For example

```
class Ptr_collection
{
private :
  void **ptr_array;
  int elements;
public:
   Ptr_collection() {}
   //...
  void * operator [] (int index) { return ptr_array[index];}
  const void * operator [] (int index) const { return ptr_array[index];}
};
void f(const Ptr_collection & pointers)
{
  const void *p = pointers[0]; //calls const version of operator []
  if ( p == 0)
    return;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 3 - Operator Overloading
```

```
else
{
    //...use p
}
```

# **Function Objects**

A function object is implemented as a class that contains an overloaded version of the function call operator. An instance of such a class can be used just like a function. Ordinary functions can have any number of arguments; therefore, operator () is exceptional among other operators because it can have an arbitrary number of parameters. In addition, it can have default arguments. In the following example, a function object implements a generic increment function:

```
#include <iostream>
using namespace std;
class increment
{
    //a generic increment function
    public : template < class T > T operator() (T t) const { return ++t;}
};
void f(int n, const increment& incr)
{
    cout << incr(n); //output 1
}
int main()
{
    int i = 0;
    increment incr;
    f(i, incr);
    return 0;
}</pre>
```

### **Conclusions**

The concept of operator overloading is neither new nor C++ exclusive. It is one of the most fundamental facilities for implementing abstract data types and compound classes. In many ways, overloaded operators in C++ behave like ordinary member functions: They are inherited, they can be overloaded more than once, and they can be declared as either nonstatic members or as nonmember functions. However, several restrictions apply to overloaded operators. An overloaded operator has a fixed number of parameters, and it cannot have default arguments. In addition, the associativity and the precedence of an operator cannot be altered. Built-in operators have an interface, consisting of the number of operands to which the operator can be applied, whether the operator modifies any of its operands, and result that is returned by the operator. When you are overloading an operator, it is recommended that you conform to its built-in interface.

Conversion operators are a special type of overloaded operators. They differ from ordinary overloaded operators in two respects: They do not have a return value and they do not take any arguments.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

4

# Special Member Functions: Default Constructor, Copy Constructor, Destructor, And Assignment Operator

#### by Danny Kale

- Introduction
- Constructors
  - Calling An Object's Member Function From Its Constructor
  - Trivial Constructors
  - o Avoid Reduplicating Identical Pieces Of Constructors' Code
  - o Is A Default Constructor Always Necessary?
  - Eligibility For STL Containment
  - o When Are Default Constructors Undesirable?
  - o Constructors Of Fundamental Types
  - o explicit Constructors
  - o Blocking Undesirable Object Instantiation
  - Using Member Initialization Lists
  - o The Exception Specification Of An Implicitly-Declared Default Constructor
- Copy Constructor
  - o Implicitly-Defined Copy Constructors
  - o <u>Implementation-Required Initializations</u>
- Simulating Virtual Constructors
  - o Covariance of Virtual Member Functions
- Assignment Operator
  - o <u>Implicitly-Defined Assignment Operator</u>

- o Simulating Inheritance Of Assignment Operator
- When Are User-Written Copy Constructors And Assignment Operators Needed?
- Implementing Copy Constructor And Assignment Operator
- Blocking Object Copying
- Destructors
  - Explicit Destructor Invocation
  - Pseudo Destructors
  - o Pure Virtual Destructors
- Constructors And Destructors Should Be Minimal
- Conclusions

#### Introduction

Objects are the fundamental unit of abstraction in object-oriented programming. An object, in the broader sense, is a region of memory storage. Class objects have properties that are determined when the object is created. Conceptually, every class object has four *special member functions*: default constructor, copy constructor, assignment operator, and destructor. If these members are not explicitly declared by the programmer, the implementation implicitly declares them. This chapter surveys the semantics of the special member functions and their role in class design and implementation. This chapter also examines several techniques and guidelines for effective usage of the special member functions.

#### **Constructors**

A constructor is used to initialize an object. A default constructor is one that can be invoked without any arguments. If there is no user-declared constructor for a class, and if the class does not contain const or reference data members, the implementation implicitly declares a default constructor for it.

An implicitly-declared default constructor is an inline public member of its class; it performs the initialization operations that are needed by the implementation to create an object of this type. Note, however, that these operations do not involve initialization of user-declared data members or allocation of memory from the free store. For example

```
class C
{
private:
   int n;
   char *p;
public:
   virtual ~C() {}
};
void f()
{
   C obj; // 1 implicitly-defined constructor is invoked
}
```

The programmer did not declare a constructor in class C -- an implicit default constructor was declared and defined by the implementation in order to create an instance of class C in the line numbered 1. The synthesized constructor does not initialize the data members n and p, nor does it allocate memory for the latter. These data members have an indeterminate value after obj has been constructed.

This is because the synthesized default constructor performs only the initialization operations that are required by the implementation -- not the programmer -- to construct an object. In this case, C is a polymorphic class. An object of this type contains a pointer to the virtual function table of its class. The virtual pointer is initialized by the implicitly-defined constructor.

Other implementation-required operations that are performed by implicitly-defined constructors are the invocation of a base class constructor and the invocation of the constructor of embedded objects. The implementation does not declare a constructor for a class if the programmer has defined one. For example

```
class C
{
private:
   int n;
   char *p;
public:
   C() : n(0), p(NULL) {}
   virtual ~C() {}
};
void f2()
{
   C obj; // 1 user-defined constructor is invoked}
}
```

Now the data members of the object obj are initialized because the user-defined constructor was invoked to create it. Note, however, that the user-defined constructor only initializes the data members n and p. Obviously, the virtual pointer must have been initialized as well -- otherwise, the program will be ill-formed. But when did the initialization of the virtual pointer take place? The compiler augments the user-defined constructor with additional code, which is inserted into the constructor's body before any user-written code, and performs the necessary initialization of the virtual pointer.

#### Calling An Object's Member Function From Its Constructor

Because the virtual pointer is initialized in the constructor before any user-written code, it is safe to call member functions (both virtual and nonvirtual) of an object from its constructor. It is guaranteed that the invoked virtual is the one that is defined in the current object (or of the base class, if it has not been overridden in the current object). However, virtual member functions of objects that are derived from the one whose constructor is executing are not called. For example

```
class A
{
public:
    virtual void f() {}
    virtual void g() {}
};
class B: public A
{
public:
    void f () {} // overriding A::f()
    B()
    {
      f();    // calls B::f()
      g();    // g() was not overriden in B, therefore calling A::g()
    }
}
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator
```

```
};
class C: public B
{
public:
   void f () {} //overriding B::f()
};
```

Please note that if the object's member functions refer to data members of the object, it is the 'programmer's responsibility to initialize these data members first -- most preferably with a *member-initialization list* (member-initialization lists are discussed next). For example

```
class C
{
private:
   int n;
   int getn() const { cout<<n<<endl; }
public:
   C(int j) : n(j) { getn(); } //Fine: n initialized before getn() is called
};</pre>
```

#### **Trivial Constructors**

As you have observed, compilers synthesize a default constructor for every class or struct, unless a constructor was already defined by the user. However, in certain conditions, such a synthesized constructor is redundant:

An implementation can instantiate Empty and Person objects without a constructor. In such cases, the explicitly-declared constructor is said to be *trivial*, which means that the implementation does not need it in order to create an instance of its class. A constructor is considered trivial when all the following hold true:

- Its class has no virtual member functions and no virtual base classes.
- All the direct base classes of the constructor's class have trivial constructors.
- All the member objects in the constructor's class have trivial constructors.

You can see that both Empty and Person fulfill these conditions; therefore, each of them has a trivial constructor. The compiler suppresses the automatic synthesis of a trivial constructor, thereby producing code that is as efficient in terms of size and speed as that which is produced by a C compiler.

#### **Avoid Reduplicating Identical Pieces Of Constructors' Code**

It is very common to define a class that has more than one constructor. For instance, a string class can define one constructor that takes const char \* as an argument, another that takes an argument of type size\_t to indicate the initial capacity of the string, and a default constructor.

```
class string
{
private:
    char * pc;
    size_t capacity;
    size_t length;
    enum { DEFAULT_SIZE = 32};
public:
    string(const char * s);
    string(size_t initial_capacity );
    string();
//...other member functions and overloaded operators
};
```

Each of the three constructors performs individual operations. Nonetheless, some identical tasks -- such as allocating memory from the free store and initializing it, or assigning the value of capacity to reflect the size of the allocated storage -- are performed in every constructor. Instead of repeating identical pieces of code in each of the constructors, it is better to move the recurring code into a single nonpublic member function. This function is called by every constructor. The results are shorter compilation time and easier future maintenance:

```
class string
private:
  char * pc;
  size_t capacity;
  size_t length;
  enum { DEFAULT_SIZE = 32};
  // the following function is called by every user-defined constructor
  void init( size_t cap = DEFAULT_SIZE);
public:
  string(const char * s);
  string(size_t initial_capacity );
  string();
//...other member functions and overloaded operators
};
void string::init( size_t cap)
  pc = new char[cap];
  capacity = cap;
string::string(const char * s)
  size_t size = strlen (s);
  init(size + 1); //make room for null terminating character
  length = size;
  strcpy(pc, s);
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator
}
string::string(size_t initial_capacity)
{
  init(initial_capacity);
  length=0;
```

#### Is A Default Constructor Always Necessary?

A class might have no default constructor. For example

string::string()

length = 0;

init();

```
class File
{
private:
    string path;
    int mode;
public:
    File(const string& file_path, int open_mode);
    ~File();
};
```

Class File has a user-defined constructor that takes two arguments. The existence of a user-defined constructor blocks the synthesis of an implicitly-declared default constructor. Because the programmer did not define a default constructor either, class File does not have a default constructor. A class with no default constructor limits its users to a narrower set of allowed uses. For instance, when an array of objects is instantiated, the default constructor -- and only the default constructor -- of each array member is invoked. Therefore, you cannot instantiate arrays thereof unless you use a complete initialization list:

Was the lack of a default constructor in class File intentional? Maybe. Perhaps the implementer considered an array of File objects undesirable because each object in the array needs to somehow acquire its path and open mode. However, the lack of a default constructor

imposes restrictions that are too draconian for most classes.

#### **Eligibility For STL Containment**

In order to qualify as an element in an STL container, an object must possess a copy constructor, an assignment operator, and a destructor as public members (more on this in Chapter 10, "STL and Generic Programming").

A default constructor is also required for certain STL container operations, as you saw in the preceding example.

Many operating systems store the files in a directory as a linked list of file objects. By omitting a default constructor from File, the implementer severely compromises the capability of its users to implement a file system as a std::list<File>.

For a class such as File, whose constructor must initialize its members with user-supplied values, it might still be possible to define a default constructor. Instead of supplying the necessary path and open mode as constructor arguments, a default constructor can read them from a sequential database file.

#### When Are Default Constructors Undesirable?

Still, a default constructor can be undesirable in some cases. One such case is a singleton object. Because a singleton object must have one and only one instance, it is recommended that you block the creation of built-in arrays and containers of such objects by making the default constructor inaccessible. For example

```
#include<string>
using namespace std;
int API_getHandle(); //system API function
class Application
{
private:
    string name;
    int handle;
    Application(); // make default constructor inaccessible
public:
    explicit Application(int handle);
    ~Application();
};
int main()
{
    Application theApp( API_getHandle() ); //ok
    Application apps[10]; //error, default constructor is inaccessible
}
```

Class Application does not have a default constructor; therefore, it is impossible to create arrays and containers of Application objects. In this case, the lack of a default constructor is intentional (other implementation details are still required to ensure that a single instance -- and only a single instance -- of Application is created. However, making the default constructor inaccessible is one of these details).

#### **Constructors Of Fundamental Types**

Fundamental types such as char, int, and float have constructors, as do user-defined types. You can initialize a variable by explicitly invoking its default constructor:

```
int main()
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator

{
    char c = char();
    int n = int ();
```

The value that is returned by the explicit invocation of the default constructor of a fundamental type is equivalent to casting 0 to that type. In other words,

```
char c = char();
is equivalent to

char c = char(0);

Of course, it is possible to initialize a fundamental type with values other than 0:

float f = float (0.333);
char c = char ('a');

Normally, you use the shorter notation:
```

```
char c = 'a';
float f = 0.333;
```

return 0;

However, this language extension enables uniform treatment in templates for fundamental types and user-defined types. Fundamental types that are created on the free store using the operator new can be initialized in a similar manner:

```
int *pi= new int (10);
float *pf = new float (0.333);
```

#### **explicit Constructors**

A constructor that takes a single argument is, by default, an implicit conversion operator, which converts its argument to an object of its class (see also Chapter 3, "Operator Overloading"). Examine the following concrete example:

```
class string
{
private:
   int size;
   int capacity;
   char *buff;
public:
   string();
   string(int size); // constructor and implicit conversion operator
   string(const char *); // constructor and implicit conversion operator
   ~string();
};
```

Class string has three constructors: a default constructor, a constructor that takes int, and a constructor that constructs a string from const char \*. The second constructor is used to create an empty string object with an initial preallocated buffer at the specified size. However, in the case of class string, the automatic conversion is dubious. Converting an int into a string object doesn't make sense, although this is exactly what this constructor does.

Consider the following:

```
int main()
{
   string s = "hello"; //OK, convert a C-string into a string object
   int ns = 0;
   s = 1; // 1 oops, programmer intended to write ns = 1,
}
```

In the expression s=1;, the programmer simply mistyped the name of the variable ns, typing s instead. Normally, the compiler detects the incompatible types and issues an error message. However, before ruling it out, the compiler first searches for a user-defined conversion that allows this expression; indeed, it finds the constructor that takes int. Consequently, the compiler interprets the expression s=1; as if the programmer had written

```
s = string(1);
```

You might encounter a similar problem when calling a function that takes a string argument. The following example can either be a cryptic coding style or simply a programmer's typographical error. However, due to the implicit conversion constructor of class string, it will pass unnoticed:

'In order to avoid such implicit conversions, a constructor that takes one argument needs to be declared explicit:

```
class string
{
//...
public:
    explicit string(int size); // block implicit conversion
    string(const char *); //implicit conversion
    ~string();
};
```

An explicit constructor does not behave as an implicit conversion operator, which enables the compiler to catch the typographical error this time:

```
int main()
{
   string s = "hello"; //OK, convert a C-string into a string object
   int ns = 0;
   s = 1; // compile time error; this time the compiler catches the typo
}
```

Why aren't all constructors automatically declared explicit? Under some conditions, the automatic type conversion is useful and well behaved. A good example of this is the third constructor of string:

```
string(const char *);
```

The implicit type conversion of const char \* to a string object enables its users to write the following:

```
string s;
s = "Hello";
```

The compiler implicitly transforms this into

```
string s;
//pseudo C++ code:
s = string ("Hello"); //create a temporary and assign it to s
```

On the other hand, if you declare this constructor explicit, you have to use explicit type conversion:

```
class string
{
//...
public:
    explicit string(const char *);
};
int main()
{
    string s;
    s = string("Hello"); //explicit conversion now required return 0;
}
```

Extensive amounts of legacy C++ code rely on the implicit conversion of constructors. The C++ Standardization committee was aware of that. In order to not make existing code break, the implicit conversion was retained. However, a new keyword, explicit, was introduced to the languageto enable the programmer to block the implicit conversion when it is undesirable. As a rule, a constructor that can be invoked with a single argument needs to be declared explicit. When the implicit type conversion is intentional and well behaved, the constructor can be used as an implicit conversion operator.

#### **Blocking Undesirable Object Instantiation**

Sometimes it might be useful to disable programmers from instantiating an object of a certain class, for example, a class that is meant to be used only as a base class for others. A protected constructor blocks creation of class instances, yet it does so without disallowing derived objects' instantiation:

```
class CommonRoot
{
protected:
    CommonRoot(){}//no objects of this class should be instantiated
    virtual ~CommonRoot();
};
class Derived: public CommonRoot
{
public:
    Derived();
};
int main()
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator
```

```
Derived d; // OK, constructor of d has access to //any protected member in its base class CommonRoot cr; //compilation error: attempt to //access a protected member of CommonRoot }
```

The same effect of blocking instantiation of a class can be achieved by declaring pure virtual functions. However, these add runtime and space overhead. When pure virtual functions aren't needed, you can use a protected constructor instead.

#### **Using Member Initialization Lists**

class Cellphone //1: mem-init

A constructor might have a member initialization (mem-initialization for short) list that initializes the data members of the class. For example

```
{
private:
   long number;
   bool on;
public:
   Cellphone (long n, bool ison) : number(n), on(ison) {}
};

The constructor of Cellphone can also be written as follows:

Cellphone (long n, bool ison) //2 initialization within constructor's body {
   number = n;
   on = ison;
}
```

There is no substantial difference between the two forms in the case of Cellphone's constructor. This is due to the way mem-initialization lists are processed by the compiler. The compiler scans the mem-initialization list and inserts the initialization code into the constructor's body before any user-written code. Thus, the constructor in the first example is expanded by the compiler into the constructor in the second example. Nonetheless, the choice between using a mem-initialization list and initialization inside the constructor's body is significant in the following four cases:

- Initialization of const members
- Initialization of reference members
- Passing arguments to a constructor of a base class or an embedded object
- Initialization of member objects

In the first three cases, a mem-initialization list is mandatory; in the fourth case, it is optional. Consider the concrete examples that are discussed in the following paragraphs.'

#### const Data Members

const data members of a class, including const members of a base or embedded subobject, must be initialized in a mem-initialization list.

```
class Allocator
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator
```

```
{
private:
   const int chunk_size;
public:
   Allocator(int size) : chunk_size(size) {}
};
```

#### **Reference Data Members**

A reference data member must be initialized by a mem-initialization list.

```
class Phone;
class Modem
{
private:
   Phone & line;
public:
   Modem(Phone & ln) : line(ln) {}
};
```

#### Invoking A Constructor Of A Base Or A Member Object With Arguments

When a constructor has to pass arguments to the constructor of its base class or to the constructor of an embedded object, a mem-initializer must be used.

```
class base
{
private:
   int numl;
   char * text;
public:
   base(int n1, char * t) {numl = n1; text = t; } //no default constructor
};
class derived: public base
{
private:
   char *buf;
public:
   derived (int n, char * t) : base(n, t) //pass arguments to base constructor
   { buf = (new char[100]);}
};
```

#### **Embedded Objects**

Consider the following example:

```
#include<string>
using std::string;
class Website
{
private:
   string URL
```

```
unsigned int IP
public:
   Website()
   {
     URL = "";
     IP = 0;
   }
};
```

Class Website has an embedded object of type std::string. The syntax rules of the language do not force the usage of mem-initialization to initialize this member. However, the performance gain in choosing mem-initialization over initialization inside the constructor's body is significant. Why? The initialization inside the constructor's body is very inefficient because it requires the construction of the member URL; a temporary std::string object is then constructed from the value "", which is in turn assigned to URL. Finally, the temporary object has to be destroyed. The use of a mem-initialization list, on the other hand, avoids the creation and destruction of a temporary object (the performance implications of mem-initialization lists are discussed in further detail in Chapter 12, "Optimizing Your Code").

#### ""The Order Of A Mem-Initialization List Must Match The Order Of Class Member Declarations

Due to the performance difference between the two forms of initializing embedded objects, some programmers use mem-initialization exclusively -- even for fundamental types. It is important to note, however, that the order of the initialization list has to match the order of declarations within the class. This is because the compiler transforms the list so that it coincides with the order of the declaration of the class members, regardless of the order specified by the programmer. For example

```
class Website
{
private:
   string URL; //1
   unsigned int IP; //2
public:
   Website() : IP(0), URL("") {} // initialized in reverse order
};
```

In the mem-initialization list, the programmer first initializes the member IP, and then URL, even though IP is declared after URL. The compiler transforms the initialization list to the order of the member declarations within the class. In this case, the reverse order is harmless. When there are dependencies in the order of initialization list, however, this transformation can cause unexpected surprises. For example

```
class string
{
private:
   char *buff;
   int capacity;
public:
   explicit string(int size) :
   capacity(size), buff (new char [capacity]) {} undefined behavior
};
```

The mem-initialization list in the constructor of string does not follow the order of declaration of string's members. Consequently, the compiler transforms the list into

```
explicit string(int size) :
buff (new char [capacity]), capacity(size) {}
```

The member capacity specifies the number of bytes that new has to allocate; but it has not been initialized. The results in this case are undefined. There are two ways to avert this pitfall: Change the order of member declarations so that capacity is declared before buff, or move the initialization of buff into the constructor's body.

#### The Exception Specification Of An Implicitly-Declared Default Constructor

An implicitly-declared default constructor has an *exception specification* (exception specifications are discussed in Chapter 6, ""Exception Handling""). The exception specification of an implicitly-declared default constructor contains all the exceptions of every other special member function that the constructor invokes directly. For example

```
struct A
{
    A(); //can throw any type of exception
};
struct B
{
    B() throw(); //not allowed to throw any exceptions
};
struct C : public B
{
    //implicitly-declared C::C() throw;
}
struct D: public A, public B
{
    //implicitly-declared D::D();
};
```

The implicitly-declared constructor in class C is not allowed to throw any exceptions because it directly invokes the constructor of class B, which is not allowed to throw any exceptions either. On the other hand, the implicitly-declared constructor in class D is allowed to throw any type of exception because it directly invokes the constructors of classes A and B. Since the constructor of class A is allowed to throw any type of exception, D's implicitly-declared constructor has a matching exception specification. In other words, D's implicitly-declared constructor allows all exceptions if any function that it directly invokes allows all exceptions; it allows no exceptions either. As you will see soon, the same rules apply to the exception specifications of other implicitly-declared special member functions.

## **Copy Constructor**

A copy constructor is used to initialize its object with another object. A constructor of a class C is a copy constructor if its first argument is of type C&, const C&, volatile C&, or const volatile C&, and if there are no additional arguments or if all other arguments have default values. If there is no user-defined copy constructor for a class, the implementation implicitly declares one. An implicitly-declared copy constructor is an inline public member of its class, and it has the form

```
C::C(const C&);
```

if each base class of C has a copy constructor whose first argument is a reference to a const object of the base class type, and if all the nonstatic embedded objects in C also have a copy constructor that takes a reference to a const object of their type. Otherwise, the implicitly-declared copy constructor is of the following type:

```
C::C(C\&);
```

An implicitly-declared copy constructor has an exception specification. The exception specification contains all the exceptions that might be thrown by other special functions that the copy constructor invokes directly.

#### **Implicitly-Defined Copy Constructors**

A copy constructor is said to be *trivial* if it is implicitly declared, if its class has no virtual member functions and no virtual base classes, and if its entire direct base classes and embedded objects have trivial copy constructors. The implementation implicitly defines an implicitly-declared, nontrivial copy constructor to initialize an object of its type from a copy of an object of its type (or from one derived from it). The implicitly-defined copy constructor performs a memberwise copy of its subobjects, as in the following example:

```
#include<string>
using std::string;
class Website //no user-defined copy constructor
{
  private:
    string URL;
    unsigned int IP;
public:
    Website() : IP(0), URL("""") {}
};
int main ()
{
    Website site1;
    Website site2(site1); //invoke implicitly-defined copy constructor
}
```

The programmer did not declare a copy constructor for class Website. Because Website has an embedded object of type std::string, which happens to have a user-defined copy constructor, the implementation implicitly defines a copy constructor for class Website and uses it to copy construct the object site2 from site1. The synthesized copy constructor first invokes the copy constructor of std::string, and then performs a bitwise copying of the data members of site1 into site2.

Novices are sometimes encouraged to define the four special member functions for every class they write. As can be seen in the case of the Website class, not only is this unnecessary, but it is even undesirable under some conditions. The synthesized copy constructor (and the assignment operator, as you are about to see) already do the "right thing". They automatically invoke the constructors of base and member subobjects, they initialize the virtual pointer (if one exists), and they perform a bitwise copying of fundamental types. In many cases, this is exactly the programmer's intention anyway. Furthermore, the synthesized constructor and copy constructor enable the implementation to create code that is more efficient than user-written code because it can apply optimizations that are not always possible otherwise.

#### Implementation-Required Initializations

Like ordinary constructors, copy constructors -- either implicitly-defined or user-defined -- are augmented by the compiler, which inserts additional code into them to invoke the copy constructors of direct base classes and embedded objects. It is guaranteed, however, that virtual base subobjects are copied only once.

# **Simulating Virtual Constructors**

Unlike ordinary member functions, a constructor has to know the exact type of its object at compile time in order to construct it properly. Consequently, a constructor cannot be declared virtual. Still, creating an object without knowing its exact type is useful in certain conditions. The easiest way to simulate virtual construction is by defining a virtual member function that returns a constructed object of its class type. For example

```
class Browser
public:
  Browser();
  Browser( const Browser&);
  virtual Browser* construct()
    { return new Browser; } //virtual default constructor
  virtual Browser* clone()
    { return new Browser(*this); } //virtual copy constructor
  virtual ~Browser();
//...
};
class HTMLEditor: public Browser
public:
  HTMLEditor ();
  HTMLEditor (const HTMLEditor &);
  HTMLEditor * construct()
    { return new HTMLEditor; }//virtual default constructor
  HTMLEditor * clone()
    { return new HTMLEditor (*this); } //virtual copy constructor
  virtual ~HTMLEditor();
  //...
```

The polymorphic behavior of the member functions clone() and construct() enables -you to instantiate a new object of the right type, without having to know the exact type of the source object.

```
void create (Browser& br)
{
  br.view();
  Browser* pbr = br.construct();
  //...use pbr and br
  delete pbr;
}
```

pbr is assigned a pointer to an object of the right type -- either Browser or any class publicly derived from it. Note that the object br does not delete the new object it has created; this is the user's responsibility. If it did, the lifetime of the reproduced objects would depend on the lifetime of their originator -- which would significantly compromise the usability of this technique.

#### **Covariance of Virtual Member Functions**

The implementation of virtual constructors relies on a recent modification to C++, namely virtual functions' covariance. An overriding virtual function has to match the signature and the return type of the function it overrides. This restriction was recently relaxed to enable the return type of an overriding virtual function to co-vary with its class type. Thus, the return type of a public base can be changed to the type of a derived class. The covariance applies only to pointers and references.

**CAUTION:** Please note that some compilers do not support virtual member functions' covariance yet.

# **Assignment Operator**

A user-declared assignment operator of class C is a nonstatic, nontemplate member function of its class, taking exactly one argument of type C, C&, const C&, volatile C&, or const volatile C&.

#### **Implicitly-Defined Assignment Operator**

If there is no user-defined assignment operator for a class, the implementation implicitly declares one. An implicitly-declared assignment operator is an inline public member of its class, and it has the form

```
C& C::operator=(const C&);
```

if each base class of C has an assignment operator whose first argument is a reference to a const object of base class type, and if all the nonstatic embedded objects in C also have an assignment operator that takes a reference to a const object of their type. Otherwise, the implicitly-declared assignment operator is of the following type:

```
C& C::operator=(C&);
```

An implicitly-declared assignment operator has an exception specification. The exception specification contains all the exceptions that might be thrown by other special functions that the assignment operator invokes directly. An assignment operator is said to be *trivial* if it is implicitly declared, if its class has no virtual member functions or virtual base classes, and if its direct base classes and embedded objects have a trivial assignment operator.

#### Simulating Inheritance Of Assignment Operator

Because an assignment operator is implicitly declared for a class if it is not declared by the programmer, the assignment operator of a base class is always hidden by the assignment operator of a derived class. In order to extend -- rather than override -- the assignment operator in a derived class, you must first invoke the assignment operator of the base explicitly, and then add the operations that are required for the derived class. For example

```
class B
{
private:
   char *p;
public:
   enum {size = 10};
   const char * Getp() const {return p;}
   B() : p ( new char [size] ) {}
   B& operator = (const C& other);
   {
     if (this != &other)
```

```
strcpy(p, other.Getp() );
    return *this;
}
};
class D : public B
{
private:
    char *q;
public:
    const char * Getq() const {return q;}
    D(): q ( new char [size] ) {}
    D& operator = (const D& other)
    {
        if (this != &other)
        {
            B::operator=(other); //first invoke base's assignment operator explicitly strcpy(q, (other.Getq())); //add extensions here
        }
        return *this;
    }
};
```

# When Are User-Written Copy Constructors And Assignment Operators Needed?

The synthesized copy constructor and assignment operator perform a memberwise copy. This is the desirable behavior for most uses. However, it can be disastrous for classes that contain pointers, references, or handles. In such cases, you have to define a copy constructor and assignment operator to avoid *aliasing*. Aliasing occurs when the same resource is used simultaneously by more than one object. For example

```
#include <cstdio>
using namespace std;
class Document
private:
 FILE *pdb;
public:
 Document(const char *filename) {pdb = fopen(filename, "t");}
 Document(FILE *f =NULL) : pdb{}
 ~Document() {fclose(pdb);} //bad, no copy constructor
                             //or assignment operator defined
void assign(Document& d)
 Document temp("letter.doc");
 d = temp; //Aliasing; both d and temp are pointing to the same file
}//temp's destructor is now called and closes file while d is still using it
int main()
 Document doc;
 assign(doc);
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator return 0;

//doc now uses a file which has just been closed. disastrous

}//OOPS! doc's destructor is now invoked and closes 'letter.doc' once again
```

Because the implementer of class Document did not define a copy constructor and assignment operator, the compiler defined them implicitly. However, the synthesized copy constructor and assignment operator result in aliasing. An attempt to open or close the same file twice yields undefined behavior. One way to solve this problem is to define an appropriate copy constructor and assignment operator. Please note, however, that the aliasing results from the reliance on low-level language constructs (file pointers in this case), whereas an embedded fstream object can perform the necessary checks automatically. In that case, a user-written copy constructor and assignment operator are unnecessary. The same problem occurs when bare pointers to char are used as data members instead of as string objects. If you use a pointer to char rather than std::string in class Website, you face an aliasing problem as well.

# Implementing Copy Constructor And Assignment Operator

Another conclusion that can be drawn from the preceding example is that whenever you define a copy constructor, you must also define the assignment operator. When you define only one of the two, the compiler creates the missing one -- but it might not work as expected.

#### The "Big Three Rule" or the "Big Two Rule"?

The famous "Big Three Rule" says that if a class needs any of the Big Three member functions (copy constructor, assignment operator, and destructor), it needs them all. Generally, this rule refers to classes that allocate memory from the free store. However, many other classes require only that the Big Two (copy constructor and assignment operator) be defined by the user; the destructor, nonetheless, is not always required. Examine the following example:

```
class Year
{
private:
    int y;
    bool cached; //has the object been cached?
public:
    //...
    Year(int y);
    Year(const Year& other) //cached should not be copied
    {
        y = other.getYear();
    }
    Year& operator =(const Year&other) //cached should not be copied
    {
        y = other.getYear();
        return *this;
    }
    int getYear() const { return y; }
};//no destructor required for class Year
```

Class Year does not allocate memory from the free store, nor does it acquire any other resources during its construction. A destructor is therefore unnecessary. However, the class needs a user-defined copy constructor and assignment operator to ensure that the value of the member that is cached is not copied because it is calculated for every individual object separately.

When a user-defined copy constructor and assignment operator are needed, it is important to implement them in a way

that prevents self-assignment or aliasing. Usually, it is sufficient to fully implement only one of the two, and then define the other by means of the first. For example

```
#include <cstring>
using namespace std;
class Person
private:
  int age;
  char * name;
public:
  int getAge () const { return age;}
  const char * getName() const { return name; }
  Person (const char * name = NULL, int age =0) {}
  Person & operator= (const Person & other);
  Person (const Person& other);
Person & Person::operator= (const Person & other)
  if (&other != this) //guard from self assignment
  {
     size_t len = strlen( other.getName());
     if (strlen (getName() ) < len)</pre>
        delete [] name; //release current buffer
        name = new char [len+1];
    strcpy(name, other.getName());
    age = other.getAge();
  return *this;
Person::Person (const Person & other)
 *this=other; //OK, use user-defined assignment operator is invoked
```

# **Blocking Object Copying**

There are situations in which enabling the user to copy or assign a new value to an object is undesirable. You can disable both by explicitly declaring the assignment operator and copy constructor as private:

```
class NoCopy
{
private:
   NoCopy& operator = (const NoCopy& other) { return *this; }
   NoCopy(const NoCopy& other) {/*..*/}
public:
   NoCopy() {}
//...
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator
```

```
};
void f()
{
  NoCopy nc; // fine, default constructor called
  NoCopy nc2(nc); //error; attempt to call a private copy constructor
  nc2 = nc; //also a compile time error; operator= is private
}
```

## **Destructors**

A destructor destroys an object of its class type. It takes no arguments and has no return type (not even void). const and volatile qualities are not applied on an object under destruction; therefore, destructors can be invoked for const, volatile, or const volatile objects. If there is no user-defined destructor for a class, the implementation implicitly declares one. An implicitly-declared destructor is an inline public member of its class and has an exception specification. The exception specification contains all the exceptions that might be thrown by other special functions that the destructor invokes directly.

A destructor is trivial if it is implicitly declared and if its entire direct base classes and embedded objects have trivial destructors. Otherwise, the destructor is nontrivial. A destructor invokes the destructors of the direct base classes and member objects of its class. The invocation occurs in the reverse order of their construction. All destructors are called with their qualified name, ignoring any possible virtual overriding destructors in more derived classes. For example

```
#include <iostream>
using namespace std;
class A
public:
  virtual ~A() { cout<<"destroying A"<<endl;}</pre>
class B: public A
public:
  ~B() { cout<<"destroying B"<<endl;}
int main()
  B b;
  return 0;
This program displays
destroying B
destroying A
This is because the compiler transforms the user-defined destructor of class B into
~B()
    //user-written code below
  cout<<"destroying B"<<endl;</pre>
    //pseudo C++ code inserted by the compiler below
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator this->A::~A(); // destructor called using its qualified name
```

Although the destructor of class A is virtual, the qualified call that is inserted into the destructor of class B is resolved statically (calling a function with a qualified name bypasses the dynamic binding mechanism).

## **Explicit Destructor Invocation**

Destructors are invoked implicitly in the following cases:

- For static objects at program termination
- For local objects when the block in which the object is created exits
- For a temporary object when the lifetime of the temporary object ends
- For objects allocated on the free store using new, through the use of delete
- During stack unwinding that results from an exception

A destructor can also be invoked explicitly. For example:

```
class C
{
public:
~C() {}
};
void destroy(C& c)
{
   c.C::~C(); //explicit destructor activation
}
```

A destructor can also be explicitly invoked from within a member function of its object:

```
void C::destroy()
{
  this->C::~C();
}
```

In particular, explicit destructor invocation is necessary for objects that were created by the placement new operator (placement new is discussed in Chapter 11, "Memory Management").

#### **Pseudo Destructors**

Fundamental types have constructors, as you have seen. In addition, fundamental types also have a *pseudo destructor*. A pseudo destructor is a syntactic construct whose sole purpose is to satisfy the need of generic algorithms and containers. It is a no-op code that has no real effect on its object. If you examine the assembly code that your compiler produces for a pseudo destructor invocation, you might discover that the compiler simply ignored it. A pseudo destructor invocation is shown in the following example:

```
typedef int N;
int main()
{
  N i = 0;
  i.N::~N(); //pseudo destructor invocation
```

```
ANSI/ISO C++ Professional Programmer's Handbook - 4 - Special Mem...nstructor, Copy Constructor, Destructor, And Assignment Operator

i = 1; //i was not affected by the invocation of the pseudo destructor
```

```
i = 1; //i was not affected by the invocation of the pseudo destructor
return 0;
}
```

The variable i is defined and initialized. In the following statement, the pseudo destructor of the non-class type N is explicitly invoked but it has no effect on its object. Like the constructors of fundamental types, pseudo destructors enable the user to write code without having to know if a destructor actually exists for a given type.

#### **Pure Virtual Destructors**

Unlike ordinary member functions, a virtual destructor is not overridden when it is redefined in a derived class. Rather, it is extended. The lower-most destructor first invokes the destructor of its base class; only then is it executed. Consequently, when you try to declare a pure virtual destructor, you might encounter compilation errors, or worse -- a runtime crash. In this respect, pure virtual destructors are exceptional among pure virtual functions -- they have to be defined. You can refrain from declaring a destructor with the pure specifier, making it only virtual. However, this is an unnecessary design compromise. You can enjoy both worlds by forcing an interface whose members are all pure virtual, including the destructor -- and all this without experiencing runtime crashes. How is it done?

First, the abstract class contains only a declaration of a pure virtual destructor:

```
class Interface
{
public:
   virtual void Open() = 0;
   virtual ~Interface() = 0;
};
```

Somewhere outside the class declaration, the pure virtual destructor has to be defined as follows:

```
Interface::~Interface()
{} //definition of a pure virtual destructor; should always be empty
```

## **Constructors And Destructors Should Be Minimal**

When you are designing a class, remember that it might serve as a base for other subclasses. It can also be used as a member object in a larger class. As opposed to ordinary member functions, which can be overridden or simply not called, the base class constructor and destructor are automatically invoked. It is not a good idea to force users of a derived and embedded object to pay for what they do not need, but are forced to accept. In other words, constructors and destructors should contain nothing but the minimal functionality needed to construct an object and destroy it. A concrete example can demonstrate that: A string class that supports serialization should not open/create a file in its constructor. Such operations need to be left to a dedicated member function. When a new derived class -- such as ShortString, which holds a fixed length string -- is created, its constructor is not forced to perform superfluous file I/O that is imposed by the constructor of its base class.

## **Conclusions**

The constructor, copy constructor, assignment operator, and destructor automate most of the tedium that is associated with creating, copying, and destroying objects. The symmetry between a constructor and a destructor in C++ is rare among object-oriented programming languages, and it serves as the basis for advanced design idioms (as you will see in the next chapter, "Object Oriented Programming and Design").

Each C++ object possesses the four member functions, which can be declared by the programmer or declared implicitly

by the implementation. An implicitly-declared special member function can be trivial, which means that the implementation does not have to define it. The synthesized special member functions perform only operations that are required by the implementation. User-written special member functions are automatically augmented by the compiler -- to ensure the proper initialization of base and embedded subobjects -- and the virtual pointer. Fundamental types have constructors and pseudo destructors, which facilitate generic programming.

In many cases, the synthesized special member functions do the "right thing". When the default behavior is unfitted, the programmer has to define one or more of the special functions explicitly. Often, however, the need for user-written code derives from combining low-level data structures with a high-level interface, and might indicate a design flaw. Declaring a constructor explicit ensures that it will not serve as an implicit conversion operator.

A mem-initialization list is necessary for the initialization of const and reference data members, as well as to pass arguments to a base or embedded subobject. In all other cases, a mem-initialization list is optional but can enhance performance. Constructors and assignment operators can be used in several ways to control instantiation and copying of objects. Destructors can be invoked explicitly. Destructors that are declared pure virtual have to be defined.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

5

# **Object-Oriented Programming and Design**

by Danny Kalev

- Introduction
- Programming Paradigms
  - Procedural Programming
  - o Object-Based Programming
  - Object-Oriented Programming
- Techniques Of Object-Oriented Programming
  - o Class Design
  - o The "Resource Acquisition Is Initialization" Idiom
- Classes and Objects
- Designing Class Hierarchies
  - o Private Data Members Are Preferable To Protected Ones
  - o <u>Declaring Virtual Base Class Destructors</u>
  - Virtual Member Functions
  - Abstract Classes and Interfaces
  - o <u>Use Derivation Instead of Type-Fields</u>
  - Overloading A Member Function Across Class Boundaries
  - o Deciding Between Inheritance and Containment
  - o The Holds-a Relation
  - o Empty Classes
  - o <u>Using structs as A Shorthand for Public Classes</u>
  - o Friendship

- Nonpublic Inheritance
- Common Root Class
- Forward Declarations
- Local Classes
- Multiple Inheritance
- Conclusions

## Introduction

C++ is the most widely used object-oriented programming language today. The success of C++ has been a prominent factor in making object-oriented design and programming a de facto standard in today's software industry. Yet, unlike other object-oriented programming languages (some of them have been around for nearly 30 years), C++ does not enforce object-oriented programming -- it can be used as a "better C", as an *object-based* language, or as a generic programming language. This flexibility, which is unparalleled among programming languages, makes C++ a suitable programming language in any domain area -- real time, embedded systems, data processing, numerical computation, graphics, artificial intelligence, or system programming.

This chapter begins with a brief survey of the various programming styles that are supported by C++. Next, you will focus on various aspects of object-oriented design and programming.

# **Programming Paradigms**

A programming paradigm defines the methodology of designing and implementing software, including the building blocks of the language, the interaction between data structures and the operations applied to them, program structure, and how problems are generally analyzed and solved. A programming language provides the linguistic means (keywords, preprocessor directives, program structure) as well as the extra-linguistic capabilities, namely standard libraries and programming environment, to support a specific programming paradigm. Usually, a given programming language is targeted for a specific application domain, for example, string manipulation, mathematical applications, simulations, Web programming and so on. C++, however, is not confined to any specific application domain. Rather, it supports many useful programming paradigms. Now, for a discussion of some of the most prominent programming paradigms supported in C++.

## **Procedural Programming**

C++ is a superset of ISO C. As such, it can be used as a procedural programming language, albeit with tighter type checking and several enhancements that improve design and coding: reference variables, inline functions, default arguments, and bool type. Procedural programming is based on separation between functions and the data that they manipulate. In general, functions rely on the physical representation of the data types that they manipulate. This dependency is one of the most problematic aspects in the maintenance and extensibility of procedural software.

## **Procedural Programming Is Susceptible To Design Changes**

Whenever the definition of a type changes (as a result of porting the software to a different platform, changes in the customer's requirement, and so on), the functions that refer to that type have to be modified accordingly. The

opposite is also true: When a function is being changed, its arguments might be affected as well; for instance, instead of passing a struct by value, it might be passed by address to optimize performance. Consider the following:

```
struct Date //pack data in a compact struct
{
   char day;
   char month;
   short year;
};
bool isDateValid(Date d); //pass by value
void getCurrentDate(Date * pdate); //changes its argument, address needed
void initializeDate (Date* pdate); //changes its argument, address needed
```

Data structures, such as Date, and the group of associated functions that initialize, read, and test it are very common in software projects in which C is the predominant programming language. Now suppose that due to a change in the design, Date is required to also hold the current time stamp in seconds. Consequently, a change in the definition of Date is made:

```
struct Date
{
  char day;
  char month;
  short year;
  long seconds;
}; //now less compact than before
```

All the functions that manipulate Date have to be modified to cope with change. An additional change in the design adds one more field to store millionths of a second in order to make a unique timestamp for database transactions. The modified Date is now

```
struct Date
{
  char day;
  char month;
  short year;
  long seconds;
  long millionths;
};
```

Once more, all the functions that manipulate Date have to be modified to cope with the change. This time, even the interface of the functions changes because Date now occupies at least 12 bytes. Functions that are passed a Date by value are modified to accept a pointer to Date.

```
bool isDateValid(Date* pd); // pass by address for efficiency
```

## **Drawbacks of Procedural Programming**

This example is not fictitious. Such frequent design changes occur in almost every software project. The budget

and time overhead that are produced as a result can be overwhelming; indeed, they sometimes lead to the project's discontinuation. The attempt to avoid -- or at least to minimize -- these overheads has led to the emergence of new programming paradigms.

Procedural programming enables only a limited form of code reuse, that is, by calling a function or using a common user-defined data structure. Nonetheless, the tight coupling between a data structure and the functions that manipulate it considerably narrows their reusability potential. A function that computes the square root of a double cannot be applied to a user-defined struct that represents a complex, for example. In general, procedural programming languages rely on static type checking, which ensures better performance than dynamic type checking -- but it also compromises the software's extensibility.

Procedural programming languages provide a closed set of built-in data types that cannot be extended. User-defined types are either unsupported or they are "second class citizens" in the language. The user cannot redefine built-in operators to support them. Furthermore, the lack of abstraction and information hiding mechanisms force users to expose the implementation details. Consider the standard C functions atof(), atoi(), and atol(), which convert a C-string to double, int, and long, respectively. Not only do they force the user to pay attention to the physical data type of the return value (on most machines these days, an int and a long are identical anyway), they also prohibit the use of other data types.

#### **Why Procedural Programming Still Matters**

In spite of its noticeable drawbacks, procedural programming is still the preferred programming paradigm in some specific application domains, such as embedded and time critical systems. Procedural programming is also widely used in machine generated code because code reuse, extensibility, and maintenance are immaterial in this case. Many SQL interpreters, for example, translate the high-level SQL statements into C code that is then compiled.

Procedural programming languages -- such as C, Pascal, or Fortran -- produce the most efficient machine code among high-level programming languages. In fact, development teams that are reluctant to adopt object orientation often point to performance degradation as the major deterring factor.

The evolution of C++ is unique among programming languages. The job of its creators might have been a lot easier had they chosen to design it from scratch, without guaranteeing backward compatibility with C. Yet this backward compatibility is one of the its strengths: It enables organizations and programmers to benefit from C++ without having to trash hundreds of millions of lines of working C code. Furthermore, C programmers can easily become productive in C++ even before they have fully mastered object-oriented programming.

## Object-Based Programming

The limitations of procedural programming have led researchers and developers alike to find better methods of separating implementation details from interfaces. Object-based programming enables them to create user-defined types that behave like first class citizens. User-defined types can bundle data and meaningful operations in a single entity -- a *class*. Classes also support information hiding, thereby separating implementation details such as physical representation and underlying bookkeeping from the set of services that a class provides, or its *interface*. Users of a class are allowed to access its interface, but they cannot access its implementation details. The separation between the implementation -- which might vary rather frequently due to design changes, portability, and efficiency -- and the stable interface is substantial. This separation ensures that changes in the design are localized to a single entity -- the class implementation; the class users, on the other hand, are not affected. To assess the importance of object-based programming, examine a simple minded Date class:

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design
```

```
class Date
{
private:
   char day;
   char month;
   short year;
public:
   bool isValid();
   Date getCurrent();
   void initialize();
};
```

#### **Object-Based Programming Localizes Changes In Implementation Details**

Now suppose that you have to change the definition of Date to support time:

```
class Date
{
private:
   char day;
   char month;
   short year;
   long secs;
public:
   bool isValid();
   Date getCurrent();
   void initialize ();
};
```

The addition of a new data member does not affect the interface of Date. The users of Date don't even know that a new field has been added; they continue to receive the same services from the class as before. Of course, the implementer of Date has to modify the code of the member functions to reflect the change. Therefore, Date::initialize() has to initialize one more field. Still, the change is localized only to the definition of Date::initialize() because users cannot access the underlying representation of Date. In procedural programming, however, users can access the data members of Date directly.

## **Abstract Data Types**

Classes such as Date are sometimes called *concrete types*, or *abstract data types* (not to be confused with *abstract classes*; see the sidebar titled "Abstract Data Types Versus Abstract Classes" later in this chapter).

These classes can meet a vast variety of needs in clean and easy-to-maintain capsules that separate implementation from interface. C++ provides the necessary mechanisms for data abstraction in the form of classes, which bundle data with a full set of associated operations. Information hiding is achieved by means of the private access specifier, which restricts the access to data members to class members exclusively.

## **Operator Overloading**

In object-based languages, the user can extend the definition of a built-in operator to support a user-defined type (operator overloading is discussed in Chapter 3, "Operator Overloading"). This feature provides a higher level of

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

abstraction by rendering user-defined types a status of built-in types. For example

```
class Date
{
private:
   char day;
   char month;
   short year;
   long secs;
public:
   bool operator < (const Date& other);
   bool operator == (const Date& other);
   //...other member functions
};</pre>
```

#### **Characteristics of Object-Based Programming**

In a way, object-based programming can be thought of as a subset of object-oriented programming; that is, some common principles are adhered to in both paradigms. Unlike object-oriented programming, however, object-based programming does not use inheritance. Rather, each user-defined class is a self-contained entity that is neither derived from a more general type, nor does it serve as a base for other types. The lack of inheritance in this paradigm is not coincidental. Proponents of object-based programming claim that inheritance complicates design, and that it might propagate bugs and deficiencies in a base class to its subclasses. Furthermore, inheritance also implies polymorphism, which is a source for additional design complexities. For instance, a function that takes a base object as an argument also knows how to handle any object that is publicly derived from that base.

#### **Advantages of Object-Based Programming**

Object-based programming overcomes most of the shortcomings of procedural programming. It localizes changes, it decouples implementation details from the interface, and it supports user-defined types. The Standard Library provides a rich set of abstract data types, including string, complex, and vector. These classes are designed to provide an abstraction for very specific uses, for example, character manipulations and complex numbers arithmetic. They are not derived from a more general base class, and they are not meant to be used as a base for other classes.

#### **Abstract Data Types Versus Abstract Classes**

The terms *abstract data type* and *abstract class* refer to two entirely different concepts, although both of them use the word *abstract* due to a historical accident. An abstract data type (also called a *concrete type*) is a self-contained, user-defined type that bundles data with a set of related operations. It behaves in the same way as does a built-in type. However, it is not extensible nor does it exhibit dynamic polymorphism. In contrast, an abstract class is anything but an abstract data type. It is not a data type (normally, abstract classes do not contain any data members), nor can you instantiate an object thereof. An abstract class is merely a skeletal interface, that specifies a set of services or operations that other (nonabstract) classes implement. Unfortunately, the distinction between the two concepts is often confused. Many people erroneously use the term *abstract data type* when they are actually referring to an abstract class.

## **Limitations of Object-Based Programming**

Object-based programming is advantageous for specific uses. However, it cannot capture real-world relationships that exist among objects. The commonality that exists among a floppy disk and a hard disk, for instance, cannot be expressed directly in an object-based design. A hard disk and a floppy disk can both store files; they can contain directories and subdirectories, and so on. However, the implementer has to create two distinct and autonomous entities in this case, without sharing any common features that the two have.

## **Object-Oriented Programming**

Object-oriented programming overcomes the limitations of object-based programming by providing the necessary constructs for defining *class hierarchies*. A class hierarchy captures the commonality among similar -- and yet distinct -- types. For example, the classes Mouse and a Joystick are two distinct entities, yet they share many common features that can be factored out into a common class, PointingDevice, which serves as a base class for both. Object-oriented programming is based on the foundations of object-based programming such as information hiding, abstract data typing, and encapsulation. In addition, it supports inheritance, polymorphism, and dynamic binding.

#### **Characteristics of Object-Oriented Programming**

Object-oriented programming languages differ from one another, sometimes considerably. Smalltalk programmers who migrate to C++, for instance, find the differences between the two languages somewhat daunting. The same can be said, of course, for C++ programmers who migrate to Smalltalk or Eiffel. However, several common characteristics that exist in all object-oriented programming languages distinguish them from non-object-oriented ones. These characteristics are presented in the following sections.

#### **Inheritance**

Inheritance enables a derived class to *reuse* the functionality and interface of its base class. The advantages of reuse are enormous: faster development time, easier maintenance, and simpler extensibility. The designer of class hierarchies captures the generalizations and commonality that exist among related classes. The more general operations are located in classes that appear higher in the derivation graph. Often, the design considerations are application-specific. For instance, the classes Thesaurus and Dictionary might be treated differently in an online ordering system of a bookstore and a computerized library of the linguistics department in some university. In the bookstore's online ordering system, the classes Thesaurus and Dictionary can inherit from a common base class called Item:

```
#include <string>
#include <list>
using namespace std;
class Review{/*...*/};
class Book
{
private:
   string author;
   string publisher;
   string ISBN;
   float list_price;
   list<Review> readers_reviews;
public:
   Book();
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design
  const string& getAuthor() const;
  //...
};
Classes Dictionary and Thesaurus are defined as follows:
class Dictionary : public Book
private:
 int languages; //bilingual, trilingual etc.
 //...
class Thesaurus: public Book
private:
 int no_of_entries;
//...
};
However, the computerized library of the linguistics department might use a different hierarchy:
class Library_item
private:
  string Dewey_classification;
  int copies;
  bool in_store;
  bool can_be_borrowed;
  string author;
  string publisher;
  string ISBN;
public:
  Library_item();
  const string& getDewey_classification() const;
  //...
class Dictionary : public Library_item
private:
 int languages;
 bool phonetic_transciption;
 //...
class Thesaurus: public Library_item
private:
 int entries;
 int century; //historical period of the language, e.g., Shakespeare's era
//...
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design
```

These two hierarchies look different because they serve different purposes. However, the crucial point is that the common functionality and data are "elevated" to the base class that is extended by more specialized classes. Introducing a new class, for example Encyclopedia, to either the bookstore ordering system or the computerized library of the linguistics department is much easier in an object-oriented environment. That is because most of the functionality of the new class already exists in the base class, whatever it might be. On the other hand, in an object-based environment, every new class has to be written from scratch.

#### **Polymorphism**

Polymorphism is the capability of different objects to react in an individual manner to the same message. Polymorphism is widely used in natural languages. Consider the verb *to close*: It means different things when applied to different objects. Closing a door, closing a bank account, or closing a program's window are all different actions; their exact meaning depends on the object on which the action is performed. Similarly, polymorphism in object-oriented programming means that the interpretation of a message depends on its object. C++ has three mechanisms of static (compile-time) polymorphism: operator overloading, templates, and function overloading.

#### **Operator Overloading**

Applying operator +=, for example, to an int or a string is interpreted by each of these objects in an individual manner. Intuitively, however, you can predict what results will be, and you can find some similarities between the two. Object-based programming languages that support operator overloading are, in a limited way, polymorphic as well.

#### **Templates**

A vector<int> and a vector<string> react differently; that is, they execute a different set of instructions when they receive the same message. However, you can expect similar behavior (templates are discussed in detail in Chapter 9, "Templates"). Consider the following example:

```
vector < int > vi; vector < string > names;
string name("Bjarne");
vi.push_back( 5 ); // add an integer at the end of the vector
names.push_back (name); //add a string at the end of the vector
```

#### **Function Overloading**

Function overloading is a third form of polymorphism. In order to overload a function, a different list of parameters is used for each overloaded version. For example, a set of valid overloaded versions of a function named f () might look similar to the following:

```
void f(char c, int i);
void f(int i, char c); //order of parameters is significant
void f(string & s);
void f();
void f(int i);
void f(char c);
```

Note, however, that a function that differs only by its returned type is illegal in C++:

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design int f(); //error; differs from void f(); above only by return type int f(float f); //fine - unique signature
```

#### **Dynamic Binding**

Dynamic binding takes the notion of polymorphism one step further. In dynamic binding, the meaning of a message depends on the object that receives it; yet, the exact type of the object can be determined only at runtime. Virtual member functions are a good example of this. The specific version of a virtual function might not be known at compile time. In this case, the call resolution is delayed to runtime, as in the following example:

The function identify can receive any object that is publicly derived from class base -- even objects of subclasses that were defined after identify was compiled.

Dynamic binding has numerous advantages. In this example, it enables the user to extend the functionality of base without having to modify identify in any way. In procedural and object-based programming, such flexibility is nearly impossible. Furthermore, the underlying mechanism of dynamic binding is automatic. The programmer doesn't need to implement the code for runtime lookup and dispatch of a virtual function, nor does he or she need to check the dynamic type of the object.

# **Techniques Of Object-Oriented Programming**

Up until now, the discussion has focused on the general characteristics of object-oriented programming and design. This part presents C++-specific practical techniques and guidelines of object-oriented programming.

## **Class Design**

Classes are the primary unit of abstraction in C++. Finding the right classes during analysis and design is perhaps the most important phase in the lifetime of an object-oriented software system. The common guidelines for finding classes state that a class should represent a real-world object; others maintain that nouns in natural languages should represent classes. This is true to some extent, but nontrivial software projects often have classes that exist nowhere except the programming domain. Does an exception represent a real-world object? Do function objects (which are discussed in Chapter 10, "STL and Generic Programming") and smart pointers have an equivalent outside the programming environment? Clearly, the relationship between real-world entities and objects is not 1:1.

#### Finding the Classes

The process of finding the right classes is mostly derived from the functional requirements of the application domain. That is, a designer can decide to represent a concept as a class (rather than, for example, a member function within a different class or a global function) when it serves the needs of the application. This is usually done by means of CRC (Class, Responsibility, Collaboration) cards or any other method.

#### **Common Design Mistakes with Classes**

No two object-oriented languages are alike. The programming language also affects the design. As you learned in Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator," C++ has a distinct symmetry between constructors and destructors that most other object-oriented languages do not have. Objects in C++ can automatically clean up after themselves. C++ also enables you to create local objects with automatic data storage. In other languages, objects can only be created on heap memory. C++ is also one of just a few languages that support multiple inheritance. C++ is a strongly-typed language with static type checking. As much as design gurus insist on separating pure design from implementation artifacts (that is, language-specific behavior), such language-specific features do affect the overall design. But of course, design mistakes do not result only from the interference of other languages.

Object-orientation is not a panacea. Some common pitfalls can lead to monstrous applications that need constant maintenance, that perform unsatisfactorily, and that only eventually -- or never -- reach production. Some of these design mistakes are easy to detect.

## **Gigantic Classes**

There are no standardized methods for measuring the size of a class. However, many small specialized classes are preferred to a bulky single class that contains hundreds of member functions and data members. But such bulky classes do get written. Class std::string has a fat interface of more than 100 member functions; clearly, this is an exception to the rule and, to be honest, many people consider this to be a compromise between conflicting design approaches. Still, ordinary programs rarely use all these members. More than once I've seen programmers extending a class with additional member functions and data members instead of using more plausible object-oriented techniques such as subclassing. As a rule, a class that exceeds a 20-30 member function count is suspicious.

Gigantic classes are problematic for at least three reasons: Users of such classes rarely know how to use them properly; the implementation and interface of such classes tend to undergo extensive changes and bug-fixes; and they are not good candidates for reuse because the fat interface and intricate implementation details can fit only a very limited usage. In a sense, large classes are very similar to large functions -- they are noncohesive and difficult to maintain.

#### **Exposing Implementation Details**

Declaring data members with public access is, almost without exception, a design flaw. Still, even vendors of popular frameworks resort to this deprecated programming style. It might be tempting to use public data members because it saves the programmer the bother of writing trivial accessors and mutators (getters and setters, respectively). This approach cannot be recommended, however, because it results in maintenance difficulties and it compromises the class's reliability. Users of such classes tend to rely heavily on their implementation details; even if they normally avoid such dependencies, they might feel that the exposure of the implementation details implies that they are not supposed to change. Sometimes there is no other choice -- the class implementer has not defined any other method of accessing data members of a class. The process of modifying or extending such classes becomes a maintenance nightmare. Infrastructure components, such as Date or string classes, can be used dozens of times within a single source file. It is not hard to imagine what it is like when dozens of programmers, each producing dozens of source files, have to chase every source line that refers to any one of these classes. This is exactly what caused the notorious Year 2000 Bug. If, on the other hand, data members are declared private, users cannot access them directly. When the implementation details of the class are modified, only accessors and mutators need to be modified, but the rest of the code remains intact.

There is another danger in exposing implementation details. Due to indiscriminate access to data members and helper functions, users can inadvertently tamper with the object's internal data members. They might delete memory (which is supposed to be deleted by the destructor), or they might change the value of a file handle, and so on, with disastrous results. Therefore, it is always a better design choice to hide implementation details of an object.

## The "Resource Acquisition Is Initialization" Idiom

Many objects of various kinds share a similar characterization: They must be acquired by means of initialization prior to their usage; then they can be used, and then they have to be released explicitly. Objects such as File, CommunicationSocket, DatabaseCursor, DeviceContext, OperatingSystem, and many others have to be opened, attached, initialized, constructed, or booted, respectively, before you can use them. When their job is done, they have to be flushed, detached, closed, released, or logged out, respectively. A common design mistake is to have the user request explicitly for the initialization and release operations to take place. A much better choice is to move all initialization action into the constructor and all release actions into the destructor. This technique is called *resource acquisition is initialization* (*The C++ Programming Language, 3rd ed.*, page 365). The advantage is a simplified usage protocol. Users can start using the object right after it has been created, without bothering with whether the object is valid or whether further arbitrary initialization actions have to be taken. Furthermore, because the destructor also releases all its resources, users are free from that hassle too. Please note that this technique usually requires an appropriate exception handling code to cope with exceptions that are thrown during construction of the object.

## Classes and Objects

Unlike some other object-oriented programming languages, C++ makes a clear distinction between a class, which is a user-defined type, and an object, which is an instance thereof. There are several features for manipulating the state of a class rather than the state of individual objects. These features are discussed in the following sections.

#### **Static Data Members**

A static member is shared by all instances of its class. For that reason, it is sometimes termed a *class variable*. Static members are useful in synchronization objects. For example, a file lock can be implemented using a

static data member. An object that is trying to access this file has to check first whether the file is being processed by another user. If the file is available, the object turns the flag on and user can process the file safely. Other users are not allowed to access the file until the flag is reset to false. When the object that is processing the file is finished, it has to turn off the flag, enabling another object to access it.

```
class fileProc
{
private:
   FILE *p;
   static bool Locked;
public:
//...
  bool isLocked () const;
   //...
};
bool fileProc::Locked;
```

#### **Static Member Functions**

A static member function in a class can access only other static members of its class. Unlike ordinary member functions, a static member function can be invoked even when no object instance exists. For example

```
class stat
{
private:
    int num;
public:
    stat(int n = 0) {num=n;}
    static void print() {cout <<"static member function" <<endl;
};
int main()
{
    stat::print(); //no object instance required
    stat s(1);
    s.print();//still, a static member function can be called from an object
    return 0;
}</pre>
```

Static members are used in the following cases:

- When all other data members of an object are also static
- When the function does not depend on any other object member (like print(), in the previous example)
- As a wrapper of a global function

#### A Pointer to Member Cannot Refer To a Static Member Function

It is illegal to assign the address of a static class member to a pointer to member. However, you can take the address of a static member function of a class and treat it as if it were an ordinary function. For example

```
class A
{
public:
    static void f();
};
int main()
{
    void (*p) () = &A::f; //OK, ordinary pointer to function
}
```

You can do this because a static member function is essentially an ordinary function, which doesn't take an implicit this argument.

#### **Defining a Class Constant**

When you need a constant integer member in a class, the easiest way to create one is by using a const static member of an integral type; unlike other static data members, such a member can be initialized within the class body (see also Chapter 2, "Standard Briefing: The Latest Addenda to ANSI/ISO C++"). For example

```
class vector
{
private:
   int v_size;
   const static int MAX 1024; //a single MAX is shared by all vector objects
   char *p;
public:
   vector() {p = new char[MAX]; }
   vector( int size)
   {
      if (size <= MAX)
        p = new char[size];
      else
        p = new char[MAX];
   }
};</pre>
```

# **Designing Class Hierarchies**

After identifying a set of potential classes that might be required for the application, it is important to correctly identify the interactions and relationships among the classes to specify inheritance, containment, and ownership. The design of class hierarchies, as opposed to designing concrete types, requires additional considerations that are discussed in this section.

## **Private Data Members Are Preferable To Protected Ones**

Data members of a class are usually a part of its implementation. They can be replaced when the internal implementation of the class is changed; therefore, they need to be hidden from other classes. If derived classes need to access these data members, they need to use accessor methods instead of directly accessing data members of a base class. Consequently, no modification is required for derived classes when a change is made in the base

class.

Here's an example:

```
class Date
{
private:
   int d,m,y //how a date is represented is an implementation detail
public:
   int Day() const {return d; }
};
class DateTime : public Date
{
private:
   int hthiss;
   int minutes;
   int seconds;
public:
//...additional member functions
};
```

Now assume that class Date is used mostly on display devices, so it has to supply some method of converting its d,m,y members into a displayable string. In order to enhance performance, a design modification is made: Instead of the three integers, a single string now holds the date representation. Had class DateTime relied on the internal implementation of Date, it would have had to be modified as well. But because it can access Date's data members only through access methods, all that is required is a small change in the Date::Day() member function. Please note that accessor methods are usually inlined anyway, so their use does not incur additional runtime overhead.

## **Declaring Virtual Base Class Destructors**

A base class needs to have its destructor declared virtual. In doing so, you ensure that the correct destructor is always called, even in the following case:

```
class Base
{
private:
    char *p;
public:
    Base() { p = new char [200]; }
    ~ Base () {delete [] p; } //non virtual destructor, bad
};
class Derived : public Base
{
private:
    char *q;
public:
    Derived() { q = new char[300]; }
    ~Derived() { delete [] q; }
```

```
//...
};
void destroy (Base & b)
{
   delete &b;
}
int main()
{
   Base *pb = new Derived(); //200 + 300 bytes allocated
   //... meddle with pb
   destroy (*pb); //00PS! only the destructor of Base is called
   //were Base's destructor virtual, the correct destructor would be called
   return 0;
}
```

#### **Virtual Member Functions**

Virtual member functions enable subclasses to extend or override the behavior of a base class. Deciding which members in a class can be overridden by a derived class is not a trivial issue. A class that overrides a virtual member function is only committed to adhere to the prototype of the overridden member function -- not to its implementation. A common mistake is to declare all member functions as virtual "just in case". In this respect, C++ makes a clear-cut distinction between abstract classes that provide pure interfaces as opposed to base classes that provide implementation as well as an interface.

#### **Extending A Virtual Function in A Derived Class**

There are cases in which you want a derived class to extend a virtual function defined in its base class rather than override it altogether. It can be done quite easily in the following way:

```
class shape
{
    //...
public:
    virtual void draw();
    virtual void resize(int x, int y) { clearscr(); /*...*/ }};
class rectangle: public shape
{
    //...
public:
    virtual void resize (int x, int y)
    {
        shape::resize(x, y); //explicit call to the base's virtual function //add functionality int size = x*y;
        //...
};
};
```

The overriding function in a derived class should invoke an overridden function of its base class using its

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

fully-qualified name.

#### **Changing Access Specification of A Virtual Function**

The access specification of a virtual member function that is defined in a base class can be changed in a derived class. For example

```
class Base
{
public:
    virtual void Say() { cout<<"Base";}
};
class Derived : public Base
{
private: //access specifier changed; legal but not a good idea
    void Say() {cout <<"Derived";} // overriding Base::Say()
};</pre>
```

Although this is legal, it does not work as expected when pointers or references are used; a pointer or reference to Base can also be assigned to any object that is publicly derived from Base:

```
Derived d;
Base *p = &d;
p->Say(); //OK, invokes Derived::Say()
```

Because the actual binding of a virtual member function is postponed to runtime, the compiler cannot detect that a nonpublic member function will be called; it assumes that p points to an object of type Base, in which Say() is a public member. As a rule, do not change the access specification of a virtual member function in a derived class.

#### Virtual Member Functions Should Not Be Private

As you saw previously, it is customary to extend virtual functions in a derived class by first invoking the base class's version of that function; then extend it with additional functionality. This can't be done when a virtual function is declared private.

## **Abstract Classes and Interfaces**

An abstract class is one that has at least one *pure virtual member function*, that is, a non-implemented placeholder that must be implemented by its derived class. Instances of an abstract class cannot be created because it is intended to serve as a design skeleton for concrete classes that are derived from it, and not as an independent object. See the following example:

```
class File //abstract class; serves as interface
{
public:
   int virtual open() = 0; //pure virtual
   int virtual close() = 0; //pure virtual
};
class diskFile: public File
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

{
    private:
        string filename;
        //...

public:
    int open() {/*...*/}
    int close () {/*...*/}
```

## **Use Derivation Instead of Type-Fields**

};

Suppose that you have to implement an internationalization helper class that manages the necessary parameters of every natural language that is currently supported by a word processor. A naive implementation might rely on type-fields to indicate the specific language that is currently being used (for example, the interface language in which menus are displayed).

```
class Fonts {/*...*/};
class Internationalization
{
private:
   Lang lg; //type field
   FontResthisce fonts
public:
   enum Lang {English, Hebrew, Danish}
   Internationalization(Lang lang) : lg(lang) {};
   Loadfonts(Lang lang);
};
```

Every modification in Internationalization affects all its users, even when they are not supposed to be affected. When adding support for a new language, the users of the already-supported languages have to recompile (or download, which is worse) the new version of the class. Moreover, as time goes by and support for new languages is added, the class becomes bigger and more difficult to maintain, and it tends to contain more bugs. A much better design approach is to use derivation instead of type-fields. For example

```
class Internationalization //now a base class
{
  private:
    FontResthisce fonts
public:
    Internationalization ();
    virtual int Loadfonts();
    virtual void SetDirectionality();
};
class English : public Internationalization
{
  public:
    English();
    Loadfonts() { fonts = TimesNewRoman; }
    SetDirectionality(){}//do nothing; default: left to right
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

};

class Hebrew : public Internationalization

{

public:
    Hebrew();
    Loadfonts() { fonts = David; }
    SetDirectionality() { directionality = right_to_left;}

};
```

Derivation simplifies class structure and localizes the changes that are associated with a specific language to its corresponding class without affecting others.

## **Overloading A Member Function Across Class Boundaries**

A class is a namespace. The scope for overloading a member function is confined to a class but not to its derived classes. Sometimes the need arises to overload the same function in its class as well as in a class that is derived from it. However, using an identical name in a derived class merely hides the base class's function, rather than overloading it. Consider the following:

```
class B
{
  public:
    void func();
};
class D : public B
{
  public:
    void func(int n); //now hiding B::f, not overloading it
};
D d;
d.func();//compilation error. B::f is invisible in d;
d.func(1); //OK, D::func takes an argument of type int
```

In order to overload -- rather than hide -- a function of a base class, the function name of the base class has to be injected explicitly into the namespace of the derived class by a *using declaration*. For example

```
class D : public B
{
  using B::func; // inject the name of a base member into the scope of D
  public:
    void func(int n); // D now has two overloaded versions of func()
  };
  D d;
  d.func ( ); // OK
  d.func ( 10 ); // OK
```

## **Deciding Between Inheritance and Containment**

When designing a class hierarchy, you often face a decision between inheritance, or *is-a*, and containment, or *has-a*, relation. The choice is not always immediately apparent. Assume that you are designing a Radio class, and you already have the following classes implemented for you in some library: Dial and ElectricAppliance. It is obvious that Radio is derived from ElectricAppliance. However, it is not so obvious that Radio is also derived from Dial. In such cases, check whether there is always a 1:1 relationship between the two. Do all radios have one and only one dial? They don't. A radio can have no dials at all -- a transmitter/receiver adjusted to a fixed frequency, for example. Furthermore, it might have more than one dial -- FM and AM dials. Hence, your Radio class needs to be designed to have Dial(s) rather than being derived from Dial. Note that the relationship between Radio and ElectricAppliance is 1:1 and corroborates the decision to derive Radio from ElectricAppliance.

#### The Holds-a Relation

Ownership defines the responsibility for the creation and the destruction of an object. An object is an owner of some other resource if and only if it has the responsibility for both constructing and destroying it. In this respect, an object that contains another object also owns it because its constructor is responsible for the invocation of the embedded object's constructor. Likewise, its destructor is responsible for invoking the embedded object's destructor. This is the well-known has-a relationship. A similar relationship is *holds-a*. It is distinguished from has-a by one factor: ownership. A class that indirectly contains -- by means of a reference or a pointer -- another object that is constructed and destroyed independently is said to hold that object. Here's an example:

```
class Phone { /*...*/};
class Dialer {/*...*/};
class Modem
private:
  Phone* pline;
  Dialer& dialer;
public:
  Modem (Phone *pp, Dialer& d) : pline(pp), dialer {}
//Phone and Dialer objects are constructed and destroyed
//independently of Modem
};
void f()
  Phone phone;
  Dialer dialer;
  Modem modem(&phone, dialer);
  //...use modem
```

Modem uses Phone and Dialer. However, it is not responsible for constructing or destroying them.

## **Empty Classes**

A class that contains no data members and no member functions is an *empty class*. For example

```
class PlaceHolder {};
```

An empty class can serve as a placeholder for a yet-to-be defined class. Imagine an interface class that serves as a base for other classes; instead of waiting for its full implementation to be completed, it can be used this way in the interim. Additionally, an empty class can also be used as a means of forcing derivation relationship among classes that are not originally descended from one base class. (This is a bottom-up design). Finally, it can be used as a dummy argument to distinguish between overloaded versions of a function. In fact, one of the standard versions of operator new (see also Chapter 11, "Memory Management") uses this technique:

```
#include <new>
using namespace std;
int main()
{
   try
   {
     int *p = new int[100]; //exception-throwing new
   }
   catch(bad_alloc & new_failure) {/*..*/}
   int *p = new (nothrow) int [100]; // exception-free version of if (p)
   {/*..*/}
   return 0;
}
```

The nothrow argument is of type nothrow\_t, which is an empty class by itself.

## Using structs as A Shorthand for Public Classes

Traditionally, structs serve as data aggregates. However, in C++ a struct can have constructors, a destructor, and member functions -- just like a class. The only difference between the two is the default access type: By default, a class has private access type to its members and derived objects, whereas a struct has public access. Consequently, structs are sometimes used as shorthand for classes, whose members are all public. Abstract classes are a good example of classes that have all public members.

```
#include <cstdio>
using namespace std;
struct File //interface class. all members are implicitly public
{
    virtual int Read() = 0;
    File(FILE *);
    virtual ~File() = 0;
};
class TextFile: File //implicit public inheritance; File is a struct
{
private:
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design
```

```
string path;
public:
   int Flush();
   int Read();
};
class UnicodeFile : TextFile //implicit private inheritance
{
public:
   wchar_t convert(char c);
};
```

## Friendship

A class can grant access to its members on a selective basis bydeclaring external classes and functions as friends. A friend has full access to all the grantor's members, including private and protected ones. Friendship is sometimes unjustly criticized for exposing implementation details. However, this is radically different from declaring data members as public because friendship enables the class to declare explicitly which clients can access its members; in contrast, a public declaration provides indiscriminate access to a member. Here's an example:

Remember that friendship is not inherited, so nonpublic members of any class that is derived from Date are not accessible to operator ==.

## **Nonpublic Inheritance**

When a derived class inherits from a nonpublic base, the is-a relationship between a derived object and its nonpublic base does not exist. For example:

```
class Mem_Manager {/*..*/};
class List: private Mem_Manager {/*..*/};
void OS_Register( Mem_Manager& mm);
int main()
{
   List li;
   OS_Register( li ); //compile time error; conversion from
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

//List & to Mem_Manager& is inaccessible
return 0;
```

Class List has a private base, Mem\_Manager, which is responsible for its necessary memory bookkeeping. However, List is not a memory manager by itself. Therefore, private inheritance is used to block its misuse. Private inheritance is similar to containment. As a matter of fact, the same effect might have been achieved by making Mem\_Manager a member of class List. Protected inheritance is used in class hierarchies for similar purposes.

#### **Common Root Class**

In many frameworks and software projects, all classes are forced to be descendants of one common root class, which is usually named Object. This design policy prevails in other OO languages such as Smalltalk and Java, whose classes are derived from class Object implicitly. However, imitating this in C++ incurs many compromises and potential bugs. It creates artificial kinship among classes that have absolutely nothing in common. Bjarne Stroustrup addresses the issue: "Now what is the common relationship between a smile, the driver of my CD-ROM reader, a recording of Richard Strauss' Don Juan, a line of text, my medical records, and a real-time clock? Placing them all in a single hierarchy when their only shared property is that they are programming artifacts (they are all "objects") is of little fundamental value and can cause confusion." (*The C++ Programming Language, 3rd ed.*, page 732).

If you are looking for genericity, that is, if you need an algorithm/container/function that works for every data type, you might find that templates serve you better. Moreover, a common root design policy also forces you to refrain from multiple inheritance entirely because any class that is derived simultaneously from two or more base classes faces the *dreadful derivation diamond* problem: It embeds more than one base subobject. Finally, the common root class usually serves as a means of implementing exception handling and RTTI, both of which are integral parts of C++ anyway.

## **Forward Declarations**

Consider the following common situation in which classes refer to one another:

An attempt to compile this header file causes compilation errors because the compiler does not recognize the identifier Account as a class name when class Report is compiled. Even if you relocate the declaration of class Account and place it before class Report, you encounter the same problem: Report is referred to from Account. For that purpose, a *forward declaration* is required. A forward declaration instructs the compiler to

hold off reporting such errors until the entire source file has been scanned. For example

```
//file: bank.h
class Acount; //forward declaration
class Report
{
public:
    void Output(const Account& account); //fine
};
class Account
{
private:
    Report rep;
public:
    void Show() {Report::Output(*this);}
};
```

The forward declaration in the beginning of the source file enables class Report to refer to class Account even though its definition has not yet been seen. Note that only references and pointers can refer to a forward-declared class.

#### **Local Classes**

A class can be declared inside a function or a block. In such cases, it is not visible from anywhere else, and instances thereof can only be created within the scope in which it is declared. This can be useful if you need to hide an ancillary object that is not to be accessible or used anywhere else. For example

```
void f(const char *text)
{
  class Display //local helper class; visible only in f()
  {
    const char *ps;
  public:
    Display(const char *t) : ps(t) {}
    ~Display() { cout<<ps; }
  };
Display ucd(text); //local object of type Display
}</pre>
```

A local class has no linkage.

## **Multiple Inheritance**

Multiple inheritance was introduced to C++ in 1989. It isn't an exaggeration to say that it has been the most controversial feature ever added to C++. The opponents of multiple inheritance maintain that it adds an unnecessary complexity to the language, that every design model that uses multiple inheritance can be modeled with single inheritance, and that it complicates compiler writing. Of the three arguments, only the third one is true. Multiple inheritance is optional. Designers who feel that they can make do without it are never forced to use it. The added level of complexity that is ascribed to multiple inheritance is not a compelling argument either

because the same criticism is applicable to other language features such as templates, operator overloading, exception handling, and so on.

Multiple inheritance enables the designer to create objects that are closer to their real-world reality. A fax modem card is essentially a modem and a fax combined in one. Similarly, a fax\_modem class that is publicly derived from both fax and modem represents the concept of a fax/modem better than a single inheritance model does. But the most compelling argument in favor of multiple inheritance is that some designs cannot be realized without it. For example, implementing the Observer pattern in Java is nearly impossible because Java lacks multiple inheritance ("Java vs. C++ -- A Critical Comparison," C++ Report, January 1997). Observer is not the only pattern that relies on multiple inheritance -- Adapter and Bridge also do (ibid.).

#### **Using Multiple Inheritance to Conjoin Features**

Derived classes can combine the functionality of several base classes simultaneously, by means of multiple inheritance. Trying to achieve the same effect using single inheritance can be very difficult, to say the least. For example

#### **Virtual Inheritance**

Multiple inheritance can lead to a problem known as the *DDD* (or *dreadful diamond of derivation*), as shown in the following case:

```
class ElectricAppliance
{
  private:
    int voltage,
    int Hertz;

public:
    //...constructor and other useful methods
    int getVoltage () const { return voltage; }
    int getHertz() const {return Hertz; }
};

class Radio : public ElectricAppliance {/*...*/};

class Tape : public ElectricAppliance {/*...*/};

class RadioTape: public Radio, public Tape { /*...*/};

int main()
{
    RadioTape rt;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 5 - Object-Oriented Programming and Design

//the following statement is a compilation Error - ambiguous call.

//Two copies getVoltage() exist in rt: one from Radio and one

//from Tape. Furthermore, which voltage value should be returned?

int voltage = rt.getVoltage();

return 0;
```

The problem is obvious: rt is derived simultaneously from two base classes, each of which has its own copy of the methods and data members of ElectricAppliance. Consequently, rt has two copies of ElectricAppliance. This is the DDD. However, giving up multiple inheritance leads to a design compromise. In such cases, where reduplication of data and methods from a common base class is undesirable, use virtual inheritance:

```
class Radio : virtual public ElectricAppliance {/*...*/};
class Tape : virtual public ElectricAppliance {/*...*/};
class RadioTape: public Radio, public Tape
{/*...*/};
```

Now class RadioTape contains a single instance of ElectricAppliance that is shared by Radio and Tape; therefore, there are no ambiguities and no need to give up the powerful tool of multiple inheritance.

```
int main()
{
   RadioTape rt;
   int voltage = rt.getVoltage(); //now OK
   return 0;
}
```

How does C++ ensure that only a single instance of a virtual member exists, regardless of the number of classes derived from it? This is implementation-dependent. However, all implementations currently use an additional level of indirection to access a virtual base class, usually by means of a pointer.

```
//Note: this is a simplified description of iostream classes class ostream: virtual public ios \{\ /*..*/\ \} class istream: virtual public ios \{\ /*..*/\ \} class iostream: public istream, public ostream \{\ /*..*/\ \}
```

In other words, each object in the iostream hierarchy has a pointer to the shared instance of the ios subobject. The additional level of indirection has a slight performance overhead. It also implies that the location of virtual subobjects is not known at compile time; therefore, RTTI might be needed to access virtual subobjects in some circumstances (this is discussed further in Chapter 7, "Runtime Type Identification").

When multiple inheritance is used, the memory layout of such an object is implementation-dependent. The compiler can rearrange the order of the inherited subobjects to improve memory alignment. In addition, a virtual base can be moved to a different memory location. Therefore, when you are using multiple inheritance, do not assume anything about the underlying memory layout of an object.

## Non-virtual Multiple Inheritance

Virtual inheritance is used to avoid multiple copies of a base class in a multiply-inherited object, as you just saw.

However, there are cases in which multiple copies of a base are needed in a derived class. In such cases, virtual inheritance is intentionally avoided. For example, suppose you have a scrollbar class that serves as a base for two other subclasses:

```
class Scrollbar
{
private:
   int x;
   int y;
public:
   void Scroll(units n);
   //...
   };
class HorizontalScrollbar : public Scrollbar {/*..*/};
class VerticalScrollbar : public Scrollbar {/*..*/};
```

Now imagine a window that has both a vertical scrollbar and a horizontal one. It can be implemented and used in the following way:

The user can scroll such a window up and down as well as left and right. For this purpose, the window object has to have two distinct Scrollbar subobjects. Therefore, virtual inheritance is intentionally avoided in this case.

## **Choosing Distinct Names for Member Functions**

When two or more classes serve as base classes in multiple inheritance, you want to choose a distinct name for each member function in order to avoid name ambiguity. Consider the following concrete example:

```
class AudioStreamer //real-time sound player
{
public:
   void Play();
   void Stop();
};
class VideoStreamer //real-time video player
{
public:
   void Play();
   void Stop();
};
class AudioVisual: public AudioStreamer, public VideoStreamer {/*...*/};
AudioVisual player;
player.play(); //error: AudioStreamer::play() or VideoStreamer::play() ?
```

One way to overcome the ambiguity is specifying the function's fully-qualified name:

```
Player.AudioStreamer::play(); //fine but tedious
```

However, a preferable solution is the use of distinct names for member functions in the base classes:

```
class AudioStreamer
{
public:
    void au_Play(); };
class VideoStreamer
{
public:
    void vd_Play();
};
Player.au_play(); //now distinct
```

## **Conclusions**

C++ is used today in fields as diverse as embedded systems, database engines, Web engines, financial systems, artificial intelligence, and more. This versatility can be attributed to its flexibility of programming styles, backward compatibility with C, and the fact that it is the most efficient object-oriented programming language in existence.

As a procedural programming language, C++ offers a tighter type-checking than C does. It also provides better memory management, inline functions, default arguments, and reference variables, which make it a "better C".

Object-based programming solves some of the noticeable weaknesses of procedural programming by bundling data types and the set of operations that are applied to them in a single entity. The separation of implementation details from an interface localizes changes in the design, thereby yielding more robust and extensible software. However, it does not support class hierarchies.

Object-oriented programming relies on encapsulation, information hiding, polymorphism, inheritance, and dynamic binding. These features enable you to design and implement class hierarchies. The advantages of object-oriented programming over object-based programming are faster development time, easier maintenance, and simpler extensibility.

C++ supports advanced object-oriented programming features such as multiple inheritance, static and dynamic polymorphism, and a clear-cut distinction between a class and an object. Object-oriented design begins with locating the classes and their interrelations: inheritance, containment, and ownership. The symmetry between constructors and destructors is the basis for useful design idioms such as "initialization is acquisition" and smart pointers.

An additional programming paradigm that is supported in C++, generic programming, is not directly related to object-oriented programming. In fact, it can be implemented in procedural languages as well. Nonethless, the combination of object-oriented programming and generic programming makes C++ a very powerful language indeed, as you will read in Chapter 10.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

6

# **Exception Handling**

#### by Danny Kalev

- Introduction
- Traditional Error Handling Methods
  - o Returning an Error Code
  - o Turning on a Global Flag
  - o Terminating the Program
- Enter Exception Handling
  - o The Challenges of Implementation of Exception Handling
- Applying Exception Handling
  - Exception Handling Constituents
  - Stack Unwinding
  - o Passing Exception Objects to a Handler
  - Exception Type Match
  - Exceptions as Objects
  - Exception Specification
- Exceptions During Object's Construction and Destruction
  - o Throwing Exceptions From A Destructor is Dangerous
- Global Objects: Construction and Destruction
- Advanced Exception Handling Techniques
  - Standard Exceptions
  - o Exception Handlers Hierarchy
  - o Rethrowing an Exception
  - Function try Blocks

- O Use auto\_ptr<> to Avoid Memory Leaks
- Exception Handling Performance Overhead
  - Additional Runtime Type Information
  - o Toggling Exception Handling Support
- Misuses of Exception Handling
- Conclusions

## Introduction

Large software applications are built in layers. At the lowest level, you usually find library routines, API functions, and proprietary infrastructure functions. At the highest level, there are user interface components that enable a user to, for instance, fill out a data sheet in a spreadsheet application. Consider an ordinary flight-booking application: its topmost layer consists of GUI components that display contents on the user's screen. These high-level components interact with data access objects, which in turn encapsulate database API routines. At a lower level, the database API routines interact with the database engine. The database engine itself invokes system services that deal with low-level hardware resources such as physical memory, file system, and security modules. In general, severe runtime errors are detected in these lower code layers, which cannot -- or should not -- attempt to handle these errors on their own. The handling of severe runtime errors is the responsibility of higher-level components. In order to handle an error, however, higher-level components have to be informed that an error has occurred. Essentially, error handling consists of detecting an error and notifying the software components that are in charge. These components in turn handle the error and attempt to recover from it.

## **Traditional Error Handling Methods**

In its earlier stages, C++ did not have a built-in facility for handling runtime errors. Instead, the traditional C methods were used for that purpose. These methods can be grouped into three design policies:

- Return a status code with agreed-upon values to indicate either success or failure.
- Assign an error code to a global variable and have other functions examine it.
- Terminate the program altogether.

Each of these methods has significant drawbacks and limitations in an object-oriented environment. Some of them might be totally unacceptable, particularly in large-scale applications. The following sections examine each of these methods more closely in order to assess their inherent limitations and hazards.

## **Returning an Error Code**

To some extent, this method can be useful in small programs in which an agreed-upon, closed set of error codes exists, and in which a rigorous policy of reporting errors and checking the returned status of a function is applied. However, this method has some noticeable limitations; for example, neither the error types nor their enumerated values are standardized. Thus, in one library the implementer might choose a return value of 0 (meaning *false*, perhaps) to indicate an error, whereas another vendor might choose 0 to indicate success and any nonzero value to indicate an error condition. Usually, the return codes are shared in a common header file in the form of symbolic constants so that some commonality can be maintained throughout an application or a development team. These codes are not standardized, however.

Needless to say, the process of combining noncompatible software libraries from different vendors or programmers

becomes very difficult and confusing when conflicting error codes are used. Another disadvantage is that every returned code has to be looked up and interpreted -- a tedious and costly operation. This policy requires that the return value of every function be checked every time by every caller; failing to do so might lead to runtime disasters. When an error code is detected, a return statement disrupts the normal execution flow and passes the error code on to the caller. The additional code that wraps every function call (to examine the return status and decide whether to continue normally) can easily double the size of the program and cause serious difficulties in the software's maintenance and readability. Worse yet, returning an error value is sometimes impossible. For instance, constructors do not return values, so they cannot use this method to report the failed construction of an object.

# **Turning on a Global Flag**

An alternative approach for reporting runtime errors is to use global flags, which indicate whether the last operation ended successfully. Unlike the return code policy, this method is standardized. The C <errno.h> header file defines a mechanism for examining and assigning the value of a global integer flag, erro. Note that the inherent drawbacks of this policy are not negligible. In a multithreaded environment, the error code that is assigned to erro by one thread can be inadvertently overwritten by another thread before the caller has had a chance to examine it. In addition, the use of an error code instead of a more readable message is disadvantageous because the codes might not be compatible among different environments. Finally, this method requires a well-disciplined programming style that relies on constant checking of the current value of erro.

The global flag policy is similar to the function return value policy: Both provide a mechanism for reporting an error, but neither guarantees that the error is actually handled. For example, a function that fails to open a file can indicate a failure by assigning an appropriate value to erro. However, it cannot prevent another function from attempting to write into the file or close it. Furthermore, if erro indicates an error and the programmer detects and handles it as is expected, erro still has to be reset explicitly. A programmer might forget to do so, thereby causing other functions, which assume that the error has not been handled, to attempt to rectify the problem -- with unpredictable results.

## **Terminating the Program**

The most drastic method of handling a runtime error is simply to terminate the program immediately when a severe error has been detected. This solution averts some of the drawbacks of the previous two methods; for example, there is no need for repetitive examination of the status that is returned from every function call, nor does the programmer have to assign a global flag, test its value, and clear it in a repetitive and error-prone manner. The standard C library has two functions that terminate a program: exit() and abort().exit() can be called to indicate successful termination of a program (as the final statement in main()), or it can be called in the case of a runtime error. Before returning control to the environment, exit() first flushes open streams and closes open files. abort(), on the other hand, indicates abnormal program termination. It terminates immediately, without flushing streams or closing open files.

Critical applications cannot just halt abruptly on every occurrence of a runtime error. It would be disastrous if a life support machine stopped functioning just because its controller detected a division by zero; likewise, the embedded computer that controls the automatic functions of a manned space shuttle should not halt just because it temporarily loses communication with ground control. Similarly, applications such as the billing system of a telephone company or a banking application cannot break down altogether whenever a runtime exception occurs. Robust, real world applications can -- and must -- do better than that.

Program termination is problematic even for applications, such as an operating system, that are expected to abort in the case of serious runtime errors. A function that detects the error usually does not have the necessary information to estimate the severity of the error. A memory allocation function, for example, cannot tell whether an allocation request has failed because the user is currently using a debugger, a Web browser, a spreadsheet, and a word processor all at once, or because the system has become unstable due to a severe hardware fault. In the first scenario, the system can simply display a message, requesting that the user close unnecessary applications. In the second scenario, a more

drastic measure might be required. Under this policy, however, the allocation function simply aborts the program (the operating system kernel, in this case), regardless of the severity of the error. This is hardly applicable in nontrivial applications. Good system design has to ensure that runtime errors are detected and reported, but it also has to ensure a minimal level of fault tolerance.

Terminating the program might be acceptable under extreme conditions or during debugging phases. However, abort() and exit() are never to be used in an object-oriented environment, even during debugging, because they are unaware of the C++ object model.

#### exit() and abort() Do Not Destroy Objects

An object can hold resources that are acquired by the constructor or a member function: memory allocated on the free store, file handles, communication ports, database transaction locks, I/O devices, and so on. These resources have to be properly released by the object that uses them when it's done. Usually, these resources are released by the destructor. This design idiom is called *resource initialization is acquisition* (this is discussed in greater detail in Chapter 5, "Object-Oriented Program and Design"). Local objects that are created on the stack are destroyed automatically when their block or function exits. Neither abort() nor exit(), however, invokes the destructors of local objects. Therefore, an abrupt program termination caused by calling these functions can cause irreversible damage: A database can be corrupted, files can be lost, and valuable data can evaporate. For this reason, do not use either abort() or exit() in an object-oriented environment.

# **Enter Exception Handling**

As you have observed, none of the traditional error handling methods of C are adequate for C++; one of the goals of C++ was to enable better and safer large-scale software development than is offered by C.

The designers of C++ were aware of the considerable difficulties resulting from the lack of a proper error handling mechanism. They sought a solution that was free from all the ailments of C's traditional error handling. The suggested mechanism was based on the automatic transfer of control to the system when an exception is triggered. The mechanism had to be simple, and it had to free the programmer from the drudgery of constantly examining a global flag or the returned value of a function. Additionally, it had to ensure that the code sections that handle the exception are automatically informed when an exception occurs. Finally, it had to ensure that when an exception is not handled locally, local objects are properly destroyed and their resources are released before the exception is propagated to a higher handler.

In 1989, after several years of research and a plethora of draft proposals, exception handling was added to C++. C++ is not the first language to offer structured runtime error handling support. Back in the 1960s, PL/1 offered a built-in exception handling mechanism; Ada provided its own version of exception handling in the early 1980s, as did several other languages. But none of these exception handling models fit the C++ object model and program structure. Therefore, the proposed exception handling for C++ was unique, and it has served as a model for newer languages that have appeared since.

Implementing an exception handling mechanism turned out to be a real challenge. The first C++ compiler, cfront, ran on UNIX. Like many UNIX compilers, it was a translator that first transformed C++ code into C, and then compiled the resultant C code. Release 4.0 of cfront was supposed to include exception handling. However, the implementation of an exception handling mechanism that met all the requirements got so complicated that the development team of cfront 4.0 decided to abandon the project entirely after spending a whole year designing it. cfront 4.0 was never released; however, exception handling became an integral part of Standard C++. Other compilers that started to appear later supported it. The following section explains why it was it so difficult to implement exception handling under cfront, and under any other compiler in general.

# The Challenges of Implementation of Exception Handling

The difficulties in implementing exception handling arise from several factors. First, the implementation must ensure that the proper handler for a specific exception is found.

Secondly, exception objects can be polymorphic; in that case, the implementation also considers handlers of base classes when it cannot locate a matching handler for a derived object. This requirement implies a sort of runtime type checking to recover the dynamic type of the exception object. Yet C++ did not have any runtime type checking facilities whatsoever before exception handling was developed; these facilities had to be created from scratch for that purpose.

As an additional complication, the implementation must invoke the destructors of all local objects that were constructed on the path from a try block to a throw expression before control passes to the appropriate handler. This process is called *stack unwinding* (the stack unwinding process is discussed in further detail later in this chapter). Because early C++ compilers translated the C++ source file into pure C and only then compiled the code into machine code, the implementers of exception handling had to implement runtime type identification and stack unwinding in C. Fortunately, these obstacles have all been overcome.

# **Applying Exception Handling**

Exception handling is a flexible and sophisticated tool. It overcomes the drawbacks of C's traditional error handling methods and it can be used to handle a variety of runtime errors. Still, exception handling, like other language features, can easily be misused. To use this feature effectively, it is important to understand how the underlying runtime machinery works and what the associated performance penalties are. The following sections delve into exception handling internals and demonstrate how to use this tool to create robust, bulletproof applications.

**CAUTION:** Some of the code samples in the following sections use new exception handling features such as function try blocks and exception specifications. Several compilers do not support these features yet; therefore, it is recommended that you read the technical documentation of your compiler to check whether it fully supports exception handling.

## **Exception Handling Constituents**

Exception handling is a mechanism for transferring control from a point in a program where an exception occurs to a matching handler. Exceptions are variables of built-in data types or class objects. The exception handling mechanism consists of four components: a try *block*, a sequence of one or more *handlers* associated with a try block, a throw *expression*, and the exception itself. The try block contains code that might throw an exception. For example

```
try
{
  int * p = new int[1000000]; //may throw std::bad_alloc
}
```

A try block is followed by a sequence of one or more catch statements, or handlers, each of which handles a different type of exception. For example

```
try
{
  int * p = new int[1000000]; //may throw std::bad_alloc
  //...
}
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
```

```
catch(std::bad_alloc& )
{
}
catch (std::bad_cast&)
{
}
```

A handler is invoked only by a throw expression that is executed in the handler's try block or in functions that are called from the handler's try block. A throw expression consists of the keyword throw and an assignment expression. For example

```
try
{
  throw 5; // 5 is assigned to n in the following catch statement
}
catch(int n)
{
}
```

A throw expression is similar to a return statement. An *empty throw* is a throw statement without an operand. For example

throw;

An empty throw inside a handler indicates a *rethrow*, which is discussed momentarily. Otherwise, if no exception is presently being handled, executing an empty throw calls terminate().

# Stack Unwinding

When an exception is thrown, the runtime mechanism first searches for an appropriate handler in the current scope. If such a handler does not exist,

the current scope is exited and the block that is higher in the calling chain is entered into scope. This process is iterative: It continues until an appropriate handler has been found. An exception is considered to be handled upon its entry to a handler. At this point, the stack has been unwound and all the local objects that were constructed on the path from a try block to a throw expression have been destroyed. In the absence of an appropriate handler, the program terminates. Note, however, that C++ ensures proper destruction of local objects only when the thrown exception is handled. Whether an uncaught exception causes the destruction of local objects during stack unwinding is implementation-dependent. To ensure that destructors of local objects are invoked in the case of an uncaught exception, you can add a catch all statement in main(). For example

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
{
}
return 0;
```

The stack unwinding process is very similar to a sequence of return statements, each returning the same object to its caller.

# Passing Exception Objects to a Handler

An exception can be passed by value or by reference to its handler. The memory for the exception that is being thrown is allocated in an unspecified way (but it is not allocated on the free store). Some implementations use a dedicated exception stack, on which exception objects are created. When an exception is passed by reference, the handler receives a reference to the exception object that is constructed on the exception stack. Passing an exception by reference ensures its polymorphic behavior. Exceptions that are passed by value are constructed on the stack frame of the caller. For example

```
#include <cstdio>
class ExBase {/*...*/};
class FileEx: public ExBase {/*...*/};
void Write(FILE *pf)
{
   if (pf == NULL) throw FileEx();
    //... process pf normally
}
int main ()
{
   try
   {
     Write(NULL); //will cause a FileEx exception to be thrown
   }
   catch(ExBase& exception) //catch ExBase or any object derived from it
   {
     //diagnostics and remedies }
}
```

Repeatedly copying objects that are passed by value is costly because the exception object can be constructed and destroyed several times before a matching handler has been found. However, it occurs only when an exception is thrown, which only happens in abnormal and -- hopefully -- rare situations. Under these circumstances, performance considerations are secondary (exception handling performance is discussed at the end of this chapter) to maintaining an application's integrity.

# **Exception Type Match**

The type of an exception determines which handler can catch it. The matching rules for exceptions are more restrictive than are the matching rules for function overloading. Consider the following example:

```
try
{
   throw int();
}
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling catch (unsigned int) //will not catch the exception from the previous try-block {
```

The thrown exception is of type int, whereas the handler expects an unsigned int. The exception handling mechanism does not consider these to be matching types; as a result, the thrown exception is not caught. The matching rules for exceptions allow only a limited set of conversions: For an exception E and a handler taking T or T&, the match is valid under one of the following conditions:

- T and E are of the same type (const and volatile specifiers are ignored)
- T is an unambiguous public base class of.

If E and T are pointers, the match is valid if E and T are of the same type or if E points to an object that is publicly and unambiguously derived from the class that is pointed to by T. In addition, a handler of type array of T or function returning T is transformed into pointer to T or pointer to function returning T, respectively.

## **Exceptions as Objects**

As you have probably noticed, the traditional convention of returning an integer as an error flag is problematic and unsatisfactory in OOP. The C++ exception handling mechanism offers more flexibility, safety, and robustness. An exception can be a fundamental type such as int or a char \*. It can be a full-fledged object as well, with data members and member functions. Such an object can provide the exception handler with more options for recovery. A clever exception object, for example, can have a member function that returns a detailed verbal description of the error, instead of letting the handler to look it up in a table or a file. It can have member functions that enable the program to recover from the runtime error after the error has been handled properly. Consider a logger class that appends new records to an existing log file: If it fails to open the log file, it throws an exception. When it is caught by the matching handler, the exception object can have a member function, which creates a dialog box. The operator can choose recovery measures from the dialog box, including creation of a new log file, redirecting the logger to an alternative file, or simply allowing the system to run without a logger.

## **Exception Specification**

A function that might throw an exception can warn its users by specifying a list of the exceptions that it can throw. Exception specifications are particularly useful when users of a function can view its prototype but cannot access its source file. Following is an example of specifying an exception:

If your function never throws any exceptions, it can be declared as follows:

```
bool equals (int, int) throw(); //no exception is thrown from this function 
Note that a function that is declared without an exception specification such as
```

```
bool equals (int, int);
```

guarantees nothing about its exceptions: It might throw any exception, or it might throw no exceptions. Exception Specifications Are Enforced At Runtime

An exception specification may not be checked at compile time,

but rather at runtime. When a function attempts to throw an exception that it is not allowed to throw according to its exception specification, the exception handling mechanism detects the violation and invokes the standard function unexpected(). The default behavior of unexpected() is to call terminate(), which terminates the program. A violation of an exception specification is most likely a bug, and should not occur -- this is why the default behavior is program termination. The default behavior can be altered, nonetheless, by using the function set\_unexpected().

Because exception specifications are enforced only at runtime, the compiler might deliberately ignore code that seemingly violates exception specifications. Consider the following:

In this example, the function g(), which is not allowed to throw any exception, invokes the function f(). f(), however, is free to throw any exception because it has no exception specification. If f() throws an exception, it propagates through g(), thereby violating g()'s guarantee not to throw any exception. It might seem surprising that exception specifications are enforced only at runtime because at least some of the violations can be caught at compile time and flagged as errors. This is not the case, however. There are several compelling reasons for the runtime checking policy.. In the preceding example, f() can be a legacy f() function. It is impossible to enforce every f() function to have an exception specification. Forcing the programmer to write unnecessary try and catch(...) blocks in g() "just in case" is impractical as well -- what if the programmer knows that f() doesn't throw any exception at all and the code is therefore safe? By enforcing exception specifications at runtime, f() are the implementation.

#### **Concordance of Exception Specification**

C++ requires exception specification concordance in derived classes. This means that an overriding virtual function in a derived class has to have an exception specification that is at least as restrictive as the exception specification of the overridden function in the base class. For example

```
// various exception classes
class BaseEx{};
class DerivedEx: public BaseEx{};
class OtherEx {};
class A
{
 public:
    virtual void f() throw (BaseEx);
    virtual void g() throw (BaseEx);
    virtual void h() throw (DerivedEx);
    virtual void i() throw (DerivedEx);
    virtual void j() throw(BaseEx);
    virtual void j() throw(BaseEx);
};
class D: public A
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
```

The same concordance restrictions apply to pointers to functions. A pointer to a function that has an exception specification can be assigned only to a function that has an identical or a more restrictive exception specification. This implies that a pointer to function that has no exception specification cannot be assigned to a function that has one. Note, however, that an exception specification is not considered part of the function type. Therefore, you cannot declare two distinct functions that differ only in their exception specification. For example

```
void f(int) throw (Y);
void f(int) throw (Z); //error; redefinition of 'void f(int)'
```

For the same reason, declaring a typedef that contains an exception specification is also an error:

```
typedef void (*PF) (int) throw(Exception); // error
```

# **Exceptions During Object's Construction and Destruction**

Constructors and destructors are invoked automatically; in addition, they cannot return values to indicate a runtime error. Seemingly, the most plausible way of reporting runtime errors during object construction and destruction is by throwing an exception. However, there are additional factors that you have to consider before throwing an exception in these cases. You should be particularly cautious about throwing an exception from a destructor.

# Throwing Exceptions From A Destructor is Dangerous

Throwing an exception from a destructor is not recommended. The problem is that a destructor might be invoked due to another exception as part of the stack unwinding. If a destructor that was invoked due to another exception also throws an exception of its own, the exception handling mechanism invokes terminate(). If you really have to throw an exception from a destructor, it is advisable to check first whether another uncaught exception is currently being processed.

### **Checking for an Uncaught Exception**

A thrown exception is considered caught when its corresponding handler has been entered (or, if such a handler cannot be found, when the function unexpected() has been invoked). In order to check whether a thrown exception is currently being processed, you can use the standard function uncaught\_exception() (which is defined in the standard header <stdexcept>). For example

Still, a better design choice is to handle exceptions within a destructor rather than let them propagate into the program. For example

```
void cleanup() throw (int);
class C
{
public:
    ~C();
};
C::~C()
{
    try
    {
      cleanup();
    }
    catch(int)
    {
      //handle the exception within the destructor
    }
}
```

If an exception is thrown by cleanup(), it is handled inside the destructor. Otherwise, the thrown exception will propagate outside the destructor, and if the destructor has been invoked while unwinding the stack due to another exception, terminate() will be called.

# **Global Objects: Construction and Destruction**

Conceptually, the construction of global objects takes place before program outset. Therefore, any exception that is thrown from a constructor of a global object can never be caught. This is also true for a global object's destructor -- the destruction of a global object executes after a program's termination. Hence, an exception that is thrown from a global object's destructor cannot be handled either.

# **Advanced Exception Handling Techniques**

The simple try-throw-catch model can be extended even further to handle more complicated runtime errors. This section discusses some of the more advanced uses of exception handling, including exception hierarchies, rethrowing exceptions, function try blocks and the auto\_ptr class.

# **Standard Exceptions**

C++ defines a hierarchy of standard exceptions that are thrown at runtime when abnormal conditions arise. The standard exception classes are derived from std::exception (defined in the <stdexcept> header). This hierarchy enables the application to catch these exceptions in a single catch statement:

```
catch (std::exception& exc)
{
   // handle exception of type std::exception as well as
   //any exception derived from it
}
```

The standard exceptions that are thrown by built-in operators of the language are

//a function is violatedAll standard exceptions have provided the member function what (), which returns a const char \* with an implementation-dependent verbal description of the exception. Note, however, that the standard library has an additional set of exceptions that are thrown by its components.

## **Exception Handlers Hierarchy**

Exceptions are caught in a bottom-down hierarchy: Specific (most derived classes) exceptions are handled first, followed by groups of exceptions (base classes), and, finally, a catch all handler. For example

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
  catch(exception& std_ex)
{
    cout<< std_ex.what() <<endl;
}
  catch(...) // exceptions that are not handled elsewhere are caught here
{
    cout<<"unrecognized exception"<<endl;</pre>
```

Handlers of the most derived objects must appear before the handlers of base classes. This is because handlers are tried in order of appearance. It is therefore possible to write handlers that are never executed, for example, by placing a handler for a derived class after a handler for a corresponding base class. For example

```
catch(std::exception& std_ex) //bad_alloc exception is always handled here
{
    //...handle the exception
}
catch(std::bad_alloc& alloc_failure) //unreachable
{
    cout<<"memory allocation failure";
}</pre>
```

# **Rethrowing an Exception**

return 0;

An exception is thrown to indicate an abnormal state. The first handle to catch the exception can try to fix the problem. If it fails to do so, or if it only manages to perform a partial recovery, it can still rethrow the exception, thereby letting a higher try block handle it. For that purpose, try blocks can be nested in a hierarchical order, enabling a rethrown exception from a lower catch statement to be caught again. A rethrow is indicated by a throw statement without an operand. For example

```
#include <iostream>
#include <string>
using namespace std;
enum {SUCCESS, FAILURE};
class File
 public: File (const char *) {}
 public: bool IsValid() const {return false; }
 public: int OpenNew() const {return FAILURE; }
class Exception {/*..*/}; //general base class for exceptions
class FileException: public Exception
 public: FileException(const char *p) : s(p) {}
 public: const char * Error() const { return s.c_str(); }
 private: string s;
};
void func(File& );
int main()
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
  try //outer try
    File f ("db.dat");
    func; // 1
catch(...) // 7
  //this handler will catch the re-thrown exception;
  //note: the same exception type is required
    cout << "re-thrown exception caught";
  return 0;
void func(File & f)
  try //inner try
      if (f.IsValid() == false )
      throw FileException("db.dat"); // 2
  catch(FileException &fe) // 3
//first chance to cope with the exception
    cout<<"invalid file specification" <<fe.Error()<<endl;</pre>
    if (f.OpenNew() != SUCCESS) (5)
     //re-throw the original exception and let a higher handler deal with it
    throw; // 6
```

In the preceding example, the function func() is called from the try block inside main() (1). The second try block inside func() throws an exception of type FileException (2). This exception is caught by the catch block inside func() (3). The catch block attempts to remedy the situation by opening a new file. This attempt fails (5), and the FileException is rethrown (6). Finally, the rethrown exception is caught -- this time, by the catch(...) block inside main() (7).

# **Function try Blocks**

A *function* try *block* is a function whose body consists of a try block and its associated handlers. A function try block enables a handler to catch an exception

that is thrown during the execution of the *initializer expressions* in the constructor's member initialization list or during the execution of the constructor's body. Note, however, that unlike handlers of ordinary exceptions, the handler of a function try block merely catches the exception -- it cannot continue the object's construction normally. This is because the partially constructed object is destroyed as a result of the stack unwinding. In addition, the handler of a function try block cannot execute a return statement (eventually, the handler must exit by a throw). What is the use of a function try block then? The handler enables you to throw a different exception than the one that it just caught, thereby preventing a violation of the exception specification. For example

```
class X{};
```

In this example, a string object is first constructed as a member of class C. string might throw a bad\_alloc exception during its construction. The function try block catches the bad\_alloc exception and throws instead an exception of type X, which satisfies the exception specification of C's constructor.

# Use auto\_ptr<> to Avoid Memory Leaks

The Standard Library supplies the class template auto\_ptr<> (discussed in Chapter 10, "STL and Generic Programming"), which automatically deallocates memory that is allocated on the free store in much the same manner as local objects are reclaimed in case of exiting their scope. When an auto\_ptr<> is instantiated, it can be initialized with a pointer to an object that is allocated on the free store. When the current scope is exited, the destructor of the auto\_ptr<> object automatically deletes the object that is bound to it. By using auto\_ptr<>, you can avoid memory leakage in the case of an exception. Furthermore, auto\_ptr<> can simplify programming by sparing the bother of explicitly deleting objects that were allocated on the free store. auto\_ptr<> is defined in the standard <memory> header file.

For example

```
#include <memory>
#include <iostream>
using namespace std;
class Date{ public: const char * DateString(); };
void DisplayDate()
{
         //create a local object of type auto_ptr<Date>
        auto_ptr<Date> pd (new Date); //now pd is owned by the template object cout<< pd-> DateString();
         //pd is automatically deleted by the destructor of auto_ptr;
}
```

In the preceding example, the auto\_ptr<> instance, pd, can be used like an ordinary pointer to Date. The overloaded operators \*, ->, and & of auto\_ptr<> provide the pointer-like syntax. pd's bound object is automatically destroyed when DisplayDate() exits.

# **Exception Handling Performance Overhead**

By nature, exception handling relies heavily on runtime type checking. When an exception is thrown, the implementation has to determine whether the exception was thrown from a try block (an exception can be thrown from a program section that is not enclosed within a try block -- by operator new, for example). If indeed the

exception was thrown from a try block, the implementation compares the type of the exception and attempts to find a matching handler in the current scope. If a match is found, control is transferred to the handler's body. This is the optimistic scenario. What if the implementation cannot find a matching handler for the exception, though, or what if the exception was not thrown from a try block? In such a case, the current function is unwound from the stack and the next active function in the stack is entered. The same process is reiterated until a matching handler has been found (at that point, all the automatic objects that were created on the path from a try block to a throw expression have been destroyed). When no matching handler can be found in the program, terminate() is invoked and the program terminates.

# **Additional Runtime Type Information**

The exception handling mechanism has to store additional data about the type of every exception object and every catch statement in order to perform the runtime matching between an exception and its matching handler. Because an exception can be of any type, and because it can be polymorphic as well, its dynamic type must be queried at runtime, using *runtime type information* (*RTTI*). RTTI, imposes an additional overhead in terms of both execution speed and program size (see Chapter 7, "Runtime Type Information"). Yet RTTI alone is not enough. The implementation also requires runtime *code* information, that is, information about the structure of each function. This information is needed to determine whether an exception was thrown from a try block. This information is generated by the compiler in the following way: The compiler divides each function body into three parts: one that is outside a try block with no active objects, a second part that is also outside a try block but that has active objects that have to be destroyed during stack unwinding, and a third part that is within a try block.

# **Toggling Exception Handling Support**

The technicalities of exception handling implementation vary among compilers and platforms. In all of them, however, exception handling imposes additional overhead even when no exception is ever thrown. The overhead lies in both execution speed and program size. Some compilers enable you to toggle exception handling support. When it is turned off, the additional data structures, lookup tables, and auxiliary code are not generated. However, turning off exception handling is rarely an option. Even if you do not use exceptions directly, you are probably using them implicitly: Operator new, for example, might throw a std::bad\_alloc exception when it fails -- and so do other built-in operators; STL containers might throw their own exceptions, and so might other functions of the Standard Library. Code libraries that are supplied by third party vendors might use exceptions as well. Therefore, you can safely turn off exception handling support only when you are porting pure C code into a C++ compiler. As long as pure C code is used, the additional exception handling overhead is unnecessary and can be avoided.

# **Misuses of Exception Handling**

Exception handling is not confined to errors. Some programmers might use it simply as an alternative control structure to for loops or while and do blocks. For example, a simple application that prompts the user to enter data until a certain condition has been fulfilled can be (rather naively) implemented as follows:

```
#include <iostream>
using namespace std;
class Exit{}; //used as exception object
int main()
{
  int num;
  cout<< "enter a number; 99 to exit" <<endl;
  try
  {</pre>
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 6 - Exception Handling
```

```
while (true) //infinitely
{
    cin>>num;
    if (num == 99)
        throw Exit(); //exit the loop
    cout<< "you entered: " << num << "enter another number " <<endl;
    }
}
catch (Exit& )
{
    cout<< "game over" <<endl;
}
return 0;</pre>
```

In the preceding example, the programmer locates an infinite loop within a try block. The throw statement breaks the loop and transfers control to the following catch statement. This style of programming is not recommended, however. It is very inefficient due to the excess overhead of exception handling. Furthermore, it is rather verbose and might have been much simpler and shorter had it been written with a break statement. In demo apps such as this one, the difference is mostly a stylistic one. In large-scale applications, the use of exception handling as an alternative control structure imposes a significant performance overhead.

Simple runtime errors that can be handled safely and effectively without the heavy machinery of exception handling need to also be treated by traditional methods. For example, a password entry dialog box should not throw an exception if the user mistyped his or her password. It is much simpler to redisplay the password entry dialog again with an appropriate error message. On the other hand, if the user enters wrong passwords dozens of times in a row, this can indicate a malicious break-in attempt. In this case, an exception should be thrown. The appropriate handler can page the system administrator and security officer.

# **Conclusions**

The exception handling mechanism of C++ overcomes the problems associated with the traditional methods. It frees the programmer from writing tedious code that checks the success status of every function call. Exception handling also eliminates human mistakes. Another important advantage of exception handling is the automatic unwinding of the stack, which ensures that local active objects are properly destroyed and their resources are released.

Implementing an exception handling mechanism was not a trivial task. The need to query the dynamic type of exception led to the introduction of RTTI into C++. The additional overhead of exception handling derives from the RTTI data structures, the "scaffolding" code that is generated by the compiler, and other implementation-dependent factors. Exceptions can be grouped into categories; the standard exception classes are a good example of this. In recent years, a few loopholes in the exception handling mechanism have been fixed. The first was the addition of exception specifications to functions' prototypes. The second was the introduction of a function try block, which enables the program to handle an exception that is thrown during the execution of the initializer expressions in the constructor's member initialization list or during the execution of the constructor's body.

Exception handling is a very powerful and flexible tool for handling runtime errors effectively. However, use it judiciously.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

7

# Runtime Type Identification

by Danny Kalev

- Introduction
- Structure Of This Chapter
- Making Do Without RTTI
  - Virtual member functions can provide a reasonable level of dynamic typing without the need for additional RTTI support. A well-designed class hierarchy can define a meaningful operation for every virtual member function that is declared in the base class.
- RTTI constituents
  - o RTTI Is Applicable to Polymorphic Objects Exclusively
  - Class type\_info
  - Operator typeid
  - Operator dynamic cast<>
  - o Other Uses of dynamic cast<>
- The Cost of Runtime Type Information
  - Memory Overhead
  - o Runtime Type Information of Polymorphic Objects
  - Additional Overhead
  - o RTTI Support Can Usually Be Toggled
  - o typeid Versus dynamic\_cast<>
- Conclusions

# Introduction

Originally, C++ did not provide standardized support for runtime type information (RTTI). Furthermore, its creators balked at the idea of adding RTTI support for at least two reasons. First, they wanted to preserve backward compatibility with C. Secondly, they were concerned about efficiency. Other RTTI-enabled languages, such as Smalltalk and Lisp, were characterized by their notoriously sluggish performance. The performance penalty of dynamic type checking results from the

relatively slow process of retrieving the object's type at runtime as well as from the additional information that the system needs to store for every type. C++ designers wanted to preserve the efficiency of C.

Another claim against the addition of RTTI to the language was that, in many cases, the use of virtual member functions could serve as an alternative to explicit runtime type checking. However, the addition of multiple inheritance (and consequently, of virtual inheritance) to C++ gave overwhelming ammunition to the proponents of RTTI (multiple inheritance is discussed in Chapter 5, "Object-Oriented Programming and Design"); it became apparent that under some circumstances, static type checking and virtual functions were insufficient.

Eventually, the C++ standardization committee approved the addition of RTTI to the language. Two new operators, dynamic\_cast<> and typeid, were introduced. In addition, the class std::type\_info was added to the Standard Library.

# Structure Of This Chapter

This chapter consists of three major parts. The limitations of virtual functions are presented first. Then, the standard RTTI constituents are explained and exemplified. Finally, RTTI performance and design issues are discussed.

# Making Do Without RTTI

Virtual member functions can provide a reasonable level of dynamic typing without the need for additional RTTI support. A well-designed class hierarchy can define a meaningful operation for every virtual member function that is declared in the base class.

Suppose you have to develop a file manager application as a component of a GUI-based operating system. The files in this system are represented as icons that respond to the right click of a mouse, displaying a menu with options such as open, close, read, and so on. The underlying implementation of the file system relies on a class hierarchy that represents files of various types. In a well-designed class hierarchy, there is usually an abstract class serving as an interface:

```
class File //abstract, all members are pure virtual
{
  public: virtual void open() =0;
  public: virtual void read() =0;
  public: virtual void write() =0;
  public: virtual ~File () =0;
};
File::~File () //pure virtual destructor must be defined
{}
```

At a lower level in the hierarchy, you have a set of derived classes that implement the common interface that they inherit from File. Each of these subclasses represents a different family of files. To simplify the discussion, assume that there are only two file types in this system: binary .exe files and text files.

```
class BinaryFile : public File
{
  public:
    void open () { OS_execute(this); } //implement the pure virtual function
    //...other member functions
};
class TextFile : public File
{
  public:
    void open () { Activate_word_processor (this); }
    //...other member functions of File are implemented here
    void virtual print(); // an additional member function
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 7 - Runtime Type Identification };
```

The pure virtual function open() is implemented in every derived class, according to the type of the file. Thus, in a TextFile object, open() activates a word processor, whereas a BinaryFile object invokes the operating system's API function OS execute(), which in turn executes the program that is stored in the binary file.

There are several differences between a binary file and a text file. For example, a text file can be printed directly on a screen or a printer because it consists of a sequence of printable characters. Conversely, a binary file with an .exe extension contains a stream of bits; it cannot be printed or displayed directly on a screen. It must be converted to a text file first, usually by a utility that translates the binary data into their symbolic representations. (For instance, the sequence 0110010 in an executable file can be replaced by a corresponding move esp, ebp assembly directive.) In other words, an executable file must be converted to a text file in order to be viewed or printed. Therefore, the member function print () appears only in class TextFile.

In this file manager, right-clicking the mouse on a file icon opens a menu of messages (options) to which the object can respond. For that purpose, the operating system has a function that takes a reference to a File:

```
OnRightClick (File & file); //operating system's API function
```

Obviously, no object of class File can be instantiated because File is an abstract class (see Chapter 5). However, the function OnRightClick() can accept any object that is derived from File. When the user right-clicks on a file icon and chooses the option Open, for instance, OnRightClick invokes the virtual member function open of its argument, and the appropriate member function is called. For example

```
OnRightClick (File & file)
{
   switch (message)
   {
     //...
   case m_open:
     file.open();
   break;
   }
}
```

So far, so good. You have implemented a polymorphic class hierarchy and a function that does not depend on the dynamic type of its argument. In this case, the language support for virtual functions was sufficient for your purposes; you did not need any explicit runtime type information (RTTI). Well, not exactly. You might have noticed the lack of file printing support. Look at the definition of class TextFile again:

```
class TextFile : public File
{
public:
   void open () { Activate_word_processor (this); }
   void virtual print();
};
```

The member function print() is not a part of the common interface that is implemented by all files in your system. It would be a design error to move print() to the abstract class File because binary files are nonprintable and cannot define a meaningful operation for it. Then again, OnRightClick() has to support file printing when it handles a text file. In this case, ordinary polymorphism in the form of virtual member functions will not do. OnRightClick() only knows that its argument is derived from File. However, this information is not sufficient to tell whether the actual object is printable. Clearly, OnRightClick() needs more information about the dynamic type of its argument in order to properly handle file printing. This is where the need for runtime type information arises. Before delving into the implementation of OnRightClick(), an overview of RTTI constituents and their role is necessary.

## RTTI constituents

The operators typeid and dynamic\_cast<> offer two complementary forms of accessing the runtime type information of their operand. The operand's runtime type information itself is stored in a type\_info object. This section exemplifies how these three constituents are used.

## RTTI Is Applicable to Polymorphic Objects Exclusively

It is important to realize that RTTI is applicable solely to polymorphic objects. A class must have at least one virtual member function in order to have RTTI support for its objects. C++ does not offer RTTI support for non-polymorphic classes and primitive types. This restriction is just common sense -- a fundamental type such as double or a concrete class such as string cannot change its type at runtime. Therefore, there is no need to detect their dynamic types because they are identical to their static types. But there is also a practical reason for confining RTTI support to polymorphic classes exclusively, as you will see momentarily.

As you probably know, every object that has at least one virtual member function also contains a special data member that is added by the compiler (more on this in Chapter 13, "C Language Compatibility Issues"). This member is a pointer to the virtual function table. The runtime type information is stored in this table, as is a pointer to a std::type\_info object.

# Class type\_info

For every distinct type, C++ instantiates a corresponding RTTI object that contains the necessary runtime type information. The RTTI object is an instance of the standard class std::type\_info or an implementation-defined class derived from it. (std::type\_info is defined in the standard header <typeinfo>). This object is owned by the implementation and cannot be altered in any way by the programmer. The interface of type\_info looks similar to the following (namespaces will be covered in Chapter 8, "Namespaces"):

In general, all instances of the same type share a single type\_info object. The most widely used member functions of type\_info are name() and operator==. But before you can invoke these member functions, you have to access the type\_info object itself. How is it done?

## **Operator typeid**

Operator typeid takes either an object or a type name as its argument and returns a matching const type\_info object. The dynamic type of an object can be examined as follows:

```
OnRightClick (File & file)
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 7 - Runtime Type Identification
```

```
if ( typeid( file) == typeid( TextFile ) )
{
    //received a TextFile object; printing should be enabled
}
else
{
    //not a TextFile object, printing disabled
}
```

To understand how it works, look at the highlighted source line:

```
if ( typeid( file) == typeid( TextFile ) ).
```

The if statement tests whether the dynamic type of the argument file is TextFile (the static type of file is File, of course). The leftmost expression, typeid(file), returns a type\_info object that holds the necessary runtime type information that is associated with the object file. The rightmost expression, typeid(TextFile), returns the type information that is associated with class TextFile. When typeid is applied to a class name rather than an object, it always returns a type\_info object that corresponds to that class name. As you saw earlier, type\_info overloads the operator ==. Therefore, the type\_info object that is returned by the leftmost typeid expression is compared to the type\_info object that is returned by the rightmost typeid expression. If indeed file is an instance of TextFile, the if statement evaluates to true. In this case, OnRightClick displays an additional option in the menu -- print (). If, on the other hand, file is not a TextFile, the if statement evaluates to false, and the print() option is disabled. This is all well and good, but a typeid-based solution has a drawback. Suppose that you want to add support for a new type of files, for example HTML files. What happens when the file manager application has to be extended? HTML files are essentially text files. They can be read and printed. However, they differ from plain text files in some respects. An open message applied to an HTML file launches a browser rather than a word processor. In addition, HTML files have to be converted to a printable format before they can be printed. The need to extend a system's functionality at a minimal cost is a challenge that is faced by software developers every day. Object-oriented programming and design can facilitate the task. By subclassing TextFile, you can reuse its existing behavior and implement only the additional functionality that is required for HTML files:

This is, however, only half of the story. OnRightClick() fails badly when it receives an object of type HTMLFile. Look at it again to see why:

```
OnRightClick (File & file) //operating system's API function
{
  if ( typeid( file) == typeid( TextFile ) )
  {
    //we received a TextFile object; printing should be enabled
  }
  else //OOPS! we get here when file is of type HTMLFile
  {
    }
}
```

typeid returns the exact type information of its argument. Therefore, the if statement in OnRightClick() evaluates to false when the argument is an HTMLFile. But a false value implies a binary file! Consequently, printing is disabled. This onerous bug is likely to occur every time you add support for a new file type. Of course, you can modify OnRightClick() so that it performs another test:

However, this solution is cumbersome and error prone. Furthermore, it imposes an unacceptable burden on the programmers who maintain this function. Not only are they required to clutter up OnRightClick() with additional code every time a new class is derived from File, but they also have to be on guard to detect any new class that has been derived from File lately. Fortunately, C++ offers a much better way to handle this situation.

**NOTE:** You can use typeid to retrieve the type information of non-polymorphic objects and fundamental types. However, the result refers to a type\_info object that represents the static type of the operand. For example

```
#include<typeinfo>
#include <iostream>
#include <string>
using namespace std;
typedef int I;
void fundamental()
{
   cout<<typeid(I).name()<<endl; //display 'int'
}
void non_polymorphic()
{
   cout<<typeid(string).name()<<endl;
}</pre>
```

**NOTE:** Note however, that applying dynamic\_cast to fundamental types or non-polymorphic classes is a compile time error.

# Operator dynamic\_cast<>

It is a mistake to allow OnRightClick() to take care of every conceivable class type. In doing so, you are forced to modify OnRightClick() any time you add a new file class or modify an existing class. In software design, and in object-oriented design in particular, you want to minimize such dependencies. If you examine OnRightClick() closely, you can see that it doesn't really know whether its argument is an instance of class TextFile (or of any other class, for that matter). Rather, all it needs to know is whether its argument is a TextFile. There is a big difference between the two -- an object is-a TextFile if it is an instance of class TextFile or if it is an instance of any class derived from TextFile. However, typeid is incapable of examining the derivation hierarchy of an object. For this purpose, you have to use the operator dynamic\_cast<> takes two arguments: The first is a type name, and the second argument is an object, which dynamic\_cast<> attempts to cast at runtime to the desired type. For example

If the attempted cast succeeds, either the second argument is an instance of the class name that appears as the second argument or it is an object derived from it. The preceding dynamic\_cast<> expression succeeds if file *is-a* TextFile. This is exactly the information needed by OnRightClick to operate properly. But how do you know whether dynamic\_cast<> was successful?

#### **Pointer Cast and Reference Cast**

try

There are two flavors of dynamic\_cast<>. One uses pointers and the other uses references. Accordingly, dynamic\_cast<> returns a pointer or a reference of the desired type when it succeeds. When dynamic\_cast<> cannot perform the cast, it returns a NULL pointer or, in the case of a reference, it throws an exception of type std::bad\_cast. Look at the following pointer cast example:

C++ does not have NULL references. Therefore, when a reference dynamic\_cast<> fails, it throws an exception of type std::bad\_cast. That is why you always need to place a reference dynamic\_cast<> expression within a try-block and include a suitable catch-statement to handle std::bad\_cast exceptions (see also Chapter 6, "Exception Handling"). For example

```
TextFile tf = dynamic_cast < TextFile &> (file);
  //use tf safely,
catch (std::bad_cast)
  //dynamic_cast<> failed
Now you can revise OnRightClick() to handle HTMLFile objects properly:
OnRightClick (File & file)
  try
    TextFile temp = dynamic_cast<TextFile&> (file);
    //display options, including "print"
    switch (message)
    case m_open:
      temp.open(); //either TextFile::open or HTMLFile::open
    break;
    case m_print:
      temp.print();//either TextFile::print or HTMLFile::print
    break;
    }//switch
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 7 - Runtime Type Identification
```

```
}//try
catch (std::bad_cast& noTextFile)
{
    // treat file as a BinaryFile; exclude"print"
}
}// OnRightClick
```

The revised version of OnRightClick() handles an object of type HTMLFile appropriately because an object of type HTMLFile *is-a* TextFile. When the user clicks on the open message in the file manager application, the function OnRightClick() invokes the member function open() of its argument, which behaves as expected because it was overridden in class HTMLFile. Likewise, when OnRightClick() detects that its argument is a TextFile, it displays a print option. If the user clicks on this option, OnRightClick() sends the message print to its argument, which reacts as expected.

## Other Uses of dynamic\_cast<>

Dynamic type casts are required in cases in which the dynamic type of an object -- rather than its static type -- is necessary to perform the cast properly. Note that any attempt to use a static cast in these cases is either flagged as an error by the compiler, or -- even worse -- it might result in undefined behavior at runtime.

#### **Cross casts**

A *cross cast* converts a multiply-inherited object to one of its secondary base classes. To demonstrate what a cross cast does, consider the following class hierarchy:

The static type of pa is "pointer to A", whereas its dynamic type is "pointer to D". A simple static\_cast<> cannot convert a pointer to A into a pointer to B because A and B are unrelated (your compiler issues an error message in this case). A brute force cast, (for example reinterpret\_cast<> or C-style cast), has disastrous results at runtime because the compiler simply assigns pa to pb. However, the B subobject is located at a different address within D than the A subobject. To perform the cross cast properly, the value of pb has to be calculated at runtime. After all, the cross cast can be done in a translation unit that doesn't even know that class D exists! The following program demonstrates why a dynamic cast, rather than compile-time cast, is required:

```
int main()
{
   A *pa = new D;
   B *pb = (B*) pa; // disastrous; pb points to the subobject A within d
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 7 - Runtime Type Identification
```

The program displays two lines of output; the first shows that the memory addresses of pa and pb are identical. The second line shows that the memory addresses of pa and pb are different after performing a dynamic cast as required.

#### **Downcasting From a Virtual Base**

A *downcast* is a cast from a base to a derived object. Before the introduction of RTTI to the language, downcasts were regarded as a bad programming practice. They were unsafe, and some even viewed the reliance on the dynamic type of an object a violation of object-oriented principles (see also Chapter 2, "Standard Briefing: the Latest Addenda to ANSI/ISO C++"). dynamic\_cast<> enables you to use safe, standardized, and simple downcasts from a virtual base to its derived object. Look at the following example:

V is a virtual base for classes A and B. D is multiply-inherited from A and B. Inside main(), pv is declared as a "pointer to V" and its dynamic type is "pointer to D". Here again, as in the cross cast example, the dynamic type of pv is needed in order to properly downcast it to a pointer to A. A static\_cast<> would be rejected by the compiler. As you read in Chapter 5, the memory layout of a virtual subobject might be different from that of a nonvirtual subobject. Consequently, it is impossible to calculate at compile time the address of the subobject A within the object pointed to by pv. As the output of the program shows, pv and pa indeed point to different memory addresses.

# The Cost of Runtime Type Information

Runtime Type Information is not free. To estimate how expensive it is in terms of performance, it is important to understand how it is implemented behind the scenes. Some of the technical details are platform-dependent. Still, the basic model that is presented here can give you a fair idea of the performance penalties of RTTI in terms of memory overhead and execution speed.

## **Memory Overhead**

Additional memory is needed to store the type\_info object of every fundamental and user-defined type. Ideally, the implementation associates a single type\_info object with every distinct type. However, this is not a requirement, and under some circumstances -- for example, dynamically linked libraries -- it is impossible to guarantee that only one type\_info object per class exists. Therefore, an implementation can create more than one type\_info object per type.

As was previously noted, there is a practical reason that dynamic\_cast<> is applicable only to polymorphic objects: An object does not store its runtime type information directly (as a data member, for example).

## **Runtime Type Information of Polymorphic Objects**

Every polymorphic object has a pointer to its virtual functions table. This pointer, traditionally named vptr, holds the address of a dispatch table that contains the memory addresses of every virtual function in this class. The trick is to add another entry to this table. This entry points at the class's type\_info object. In other words, the vptr data member of a polymorphic object points at a table of pointers, in which the address of type\_info is kept at a fixed position. This model is very economical in terms of memory usage; it requires a single type\_info object and a pointer for every polymorphic class. Note that this is a fixed cost, regardless of how many instances of the class actually exist in the program. The cost of retrieving an object's runtime type information is therefore a single pointer indirection, which might be less efficient than direct access to a data member; still, though, it is equivalent to a virtual function invocation.

#### **Additional Overhead**

A pointer indirection, a type\_info object, and a pointer per class sound like a reasonable price to pay for RTTI support. This is not the full picture, however. The type\_info objects, just like any other object, have to be constructed. Large programs that contain hundreds of distinct polymorphic classes have to construct an equivalent number of type\_info objects as well.

## **RTTI Support Can Usually Be Toggled**

This overhead is imposed even if you never use RTTI in your programs. For this reason, most compilers enable you to switch off their RTTI support (check the user's manual to see the default RTTI setting of your compiler and how it can be modified). If you never use RTTI in your programs, iyou can turn off your compiler's RTTI support. The results are smaller executables and a slightly faster code.

# typeid Versus dynamic\_cast<>

Until now, this chapter has discussed the indirect cost of RTTI support. It is now time to explore the cost of its direct usage -- that is, applying typeid and dynamic\_cast<>.

A typeid invocation is a constant time operation. It takes the same length of time to retrieve the runtime type information of every polymorphic object, regardless of its derivational complexity. In essence, calling typeid is similar to invoking a virtual member function. For instance, the expression typeid(obj) is evaluated into something similar to the following:

```
return *(obj->__vptr[0]); //return the type_info object whose address // is stored at offset 0 in the virtual table of obj
```

Note that the pointer to a class's type\_info object is stored at a fixed offset in the virtual table (usually 0, but this is implementation-dependent).

Unlike typeid, dynamic\_cast<> is not a constant time operation. In the expression dynamic\_cast<T&> (obj), where T is the target type and obj is the operand, the time that is needed to cast the operand to the target type depends on the complexity of the class hierarchy of obj. dynamic\_cast<> has to traverse the derivation tree of the obj until it has located the target object in it. When the target is a virtual base, the dynamic cast becomes even more complicated (albeit unavoidable, as you have seen); consequently, it takes longer to execute. The worst case scenario is when the operand is a deeply derived object and the target is a nonrelated class type. In this case, dynamic\_cast<> has to traverse the entire

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 7 - Runtime Type Identification

derivation tree of obj before it can confidently decide that obj cannot be cast to a T. In other words, a failed dynamic\_cast<> is an O(n) operation, where n is the number of base classes of the operand.

You might recall the conclusion that from a design point of view, dynamic\_cast<> is preferable to typeid because the former enables more flexibility and extensibility. Notwithstanding that, the runtime overhead of typeid can be less expensive than dynamic cast<>, depending on the derivational complexity of the entities involved.

# **Conclusions**

The RTTI mechanism of C++ consists of three components: operator typeid, operator dynamic\_cast<>, and class std::type\_info. RTTI is relatively new in C++. Some existing compilers do not support it yet. Furthermore, compilers that support it can usually be configured to disable RTTI support. Even when there is no explicit usage of RTTI in a program, the compiler automatically adds the necessary "scaffolding" to the resultant executable. To avert this, you can usually switch off your compiler's RTTI support.

From the object-oriented design point of view, operator dynamic\_cast<> is preferable to typeid because it enables more flexibility and robustness, as you have seen. However, dynamic\_cast<> can be slower than typeid because its performance depends on the proximity of its target and operand, as well as on the derivational complexity of the latter. When complex derivational hierarchies are used, the incurred performance penalty might be noticeable. It is recommended, therefore, that you use RTTI judiciously. In many cases, a virtual member function is sufficient to achieve the necessary polymorphic behavior. Only when virtual member functions are insufficient should RTTI be considered.

Following are a few additional notes to keep in mind when using RTTI:

- In order to enable RTTI support, an object must have at least one virtual member function. In addition, switch on your compiler's RTTI support (please consult your user's manual for further information) if it isn't already on.
- Make sure that your program has a catch-statement to handle std::bad\_cast exceptions whenever you are using dynamic\_cast<> with a reference. Note also that an attempt to dereference a null pointer in a typeid expression, as in typeid(\*p) where p is NULL, results in a std::bad\_typeid exception being thrown.
- When you are using dynamic\_cast<> with a pointer, always check the returned value.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

8

# **Namespaces**

by Danny Kalev

- The Rationale Behind Namespaces
- A Brief Historical Background
  - o Large-Scale Projects Are More Susceptible to Name Clashes
- Properties of Namespaces
  - Fully Qualified Names
  - o A using Declaration and a using Directive
  - Namespaces Can Be Extended
  - o Namespace Aliases
  - o Koenig Lookup
  - Namespaces in Practice
- Namespace Utilization Policy in Large-Scale Projects
- Namespaces and Version Control
  - Namespaces Do not Incur Additional Overhead
- The Interaction of Namespaces with Other Language Features
  - Scope Resolution Operator Should Not Be Used To Designate Global Names
  - o Turning an External Function into A File-Local Function
  - Standard Headers Names
- Restrictions on Namespaces
  - o Namespace std Can Not Be Modified
  - o User-Defined new and delete Cannot Be Declared in a Namespace
- Conclusions

Namespaces were introduced to the C++ Standard in 1995. This chapter explains what namespaces are and why they were added to the language. You will see how namespaces can avoid name conflicts and how they facilitate configuration management and version control in large-scale projects. Finally, you will learn how namespaces interact with other language features.

# The Rationale Behind Namespaces

In order to understand why namespaces were added to the language in the first place, here's an analogy: Imagine that the file system on your computer did not have directories and subdirectories at all. All files would be stored in a flat repository, visible all the time to every user and application. Consequently, extreme difficulties would arise: Filenames would clash (with some systems limiting a filename to eight characters, plus three for the extension, this is even more likely to happen), and simple actions such as listing, copying, or searching files would be much more difficult. In addition, security and authorization restrictions would be severely compromised.

Namespaces in C++ are equivalent to directories. They can be nested easily, they protect your code from name conflicts, they enable you to hide declarations, and they do not incur any runtime or memory overhead. Most of the components of the C++ Standard Library are grouped under namespace std. Namespace std is subdivided into additional namespaces such as std::rel\_ops, which contains the definitions of STL's overloaded operators.

# A Brief Historical Background

In the early 1990s, when C++ was gaining popularity as a general purpose programming language, many vendors were shipping proprietary implementations of various component classes. Class libraries for string manipulations, mathematical functions, and data containers were integral parts of frameworks such as MFC, STL, OWL, and others. The proliferation of reusable components caused a name-clashing problem. A class named vector, for instance, might appear in a mathematical library and in another container library that were both used at the same time; or a class named string might be found in almost every framework and class library. It was impossible for the compiler to distinguish between different classes that had identical names. Similarly, linkers could not cope with identical names of member functions of classes with indistinguishable names. For example, a member function

```
vector::operator==(const vector&);
```

might be defined in two different classes -- the first might be a class of a mathematical library, whereas the other might belong to some container library.

## Large-Scale Projects Are More Susceptible to Name Clashes

Name-clashes are not confined to third party software libraries. In large-scale software projects, short and elegant names for classes, functions, and constants can also cause name conflicts because it is likely that the same name might be used more than once to indicate different entities by different developers. In the pre-namespace era, the only workaround was to use various affixes in identifiers' names. This practice, however, is tedious and error prone. Consider the following:

Namespaces enable you to use convenient, short, and intelligible names safely. Instead of repeating the unwieldy affixes time after time, you can group your declarations in a namespace and factor out the recurring affix as follows:

```
//file excelSoftCompany.h
namespace excelSoftCompany { // a namespace definition
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 8 - Namespaces class string {/*..*/}; class vector {/*..*/};
```

Namespace members, like class members, can be defined separately from their declarations. For example

```
#include <iostream>
using namespace std;
namespace A
{
   void f(); //declaration
}
void A::f() //definition in a separate file
{
   cout<<"in f"<<endl;
}
int main()
{
   A::f();
   return 0;
}</pre>
```

# **Properties of Namespaces**

Namespaces are more than just name containers. They were designed to allow fast and simple migration of legacy code without inflicting any overhead. Namespaces have several properties that facilitate their usage. The following sections discuss these properties.

## **Fully Qualified Names**

A namespace is a scope in which declarations and definitions are grouped together. In order to refer to any of these from another scope, a *fully qualified name* is required. A fully qualified name of an identifier consists of its namespaces, followed by a scope resolution operator (::), its class name, and, finally, the identifier itself. Because both namespaces and classes can be nested, the resulting name can be rather long -- but it ensures unique identification:

```
unsigned int maxPossibleLength =
  std::string::npos; //a fully qualified name. npos is a member of string; //string
belongs to namespace std
  int *p = ::new int; //distinguish global new from overloaded new
```

However, repeating the fully qualified name is tedious and less readable. Instead, you can use a *using declaration* or a *using directive*.

## A using Declaration and a using Directive

A using declaration consists of the keyword using, followed by a namespace::member. It instructs the compiler to locate every occurrence of a certain identifier (type, operator, function, constant, and so on) in the specified namespace, as if the fully qualified name were supplied. For example

```
#include <vector> //STL vector; defined in namespace std
int main()
{
   using std::vector; //using declaration; every occurrence of vector //is looked up
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 8 - Namespaces
in std
   vector <int> vi;
  return 0;
A using directive, on the other hand, renders all the names of a specified namespace accessible in the scope of the directive.
It consists of the following sequence: using namespace, followed by a namespace name. For example
#include <vector> // belongs to namespace std
#include <iostream> //iostream classes and operators are also in namespace std
int main()
  using namespace std; // a using-directive; all <iostream> and <vector>
//declarations now accessible
  vector <int> vi;
  vi.push_back(10);
  cout<<vi[0];
  return 0;
Look back at the string class example (the code is repeated here for convenience):
//file excelSoftCompany.h
namespace excelSoftCompany
  class string {/*..*/};
  class vector {/*..*/};
```

You can now access your own string class as well as the standard string class in the same program as follows:

```
#include <string> // std::string
#include "excelSoftCompany.h"
int main()
{
  using namespace excelSoftCompany;
  string s; //referring to class excelSoftCompany::string
  std::string standardstr; //now instantiate an ANSI string
  return 0;
}
```

## Namespaces Can Be Extended

The C++ standardization committee was well aware of the fact that related declarations can span across several translation units. Therefore, a namespace can be defined in parts. For example

```
//file proj_const.h
namespace MyProj
{
   enum NetProtocols
   {
     TCP_IP,
     HTTP,
     UDP
   }; // enum
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 8 - Namespaces

}
  //file proj_classes.h
namespace MyProj
{ // extending MyProj namespace
  class RealTimeEncoder{ public: NetProtocols detect(); };
  class NetworkLink {}; //global
  class UserInterface {};
}
```

In a separate file, the same namespace can be extended with additional declarations.

The complete namespace MyProj can be extracted from both files as follows:

```
//file app.cpp
#include "proj_const.h"
#include "proj_classes.h"
int main()
{
  using namespace MyProj;
  RealTimeEncoder encoder;
  NetProtocols protocol = encoder.detect();
  return 0;
}
```

## **Namespace Aliases**

As you have observed, choosing a short name for a namespace can eventually lead to a name clash. However, very long namespaces are not easy to use. For this purpose, a *namespace alias* can be used. The following example defines the alias ESC for the unwieldy <code>Excel\_Software\_Company</code> namespace. Namespace aliases have other useful purposes, as you will see soon.

# **Koenig Lookup**

Andrew Koenig, one of the creators of C++, devised an algorithm for resolving namespace members' lookup. This algorithm, also called *argument dependent lookup*, is used in all standard-compliant compilers to handle cases such as the following:

**CAUTION:** Please note that some existing compilers do not yet fully support Koenig lookup. Consequently, the following programs -- which rely on Koenig lookup -- might not compile under compilers that are not fully

```
namespace MINE
{
  class C {};
  void func;
}
MINE::C c; // global object of type MINE::C
int main()
{
  func( c ); // OK, MINE::f called
  return 0;
}
```

Neither a using declaration nor a using directive exists in the program. Still, the compiler did the right thing -- it correctly identified the unqualified name func as the function declared in namespace MINE by applying Koenig lookup.

Koenig lookup instructs the compiler to look not just at the usual places, such as the local scope, but also at the namespace that contains the argument's type. Therefore, in the following source line, the compiler detects that the object c, which is the argument of the function func(), belongs to namespace MINE. Consequently, the compiler looks at namespace MINE to locate the declaration of func(), "guessing" the programmer's intent:

```
func( c ); // OK, MINE::f called
```

Without Koenig lookup, namespaces impose an unacceptable tedium on the programmer, who has to either repeatedly specify the fully qualified names or use numerous using declarations. To push the argument in favor of Koenig lookup even further, consider the following example:

The using declaration injects std::cout into the scope of main(), thereby enabling the programmer to use the nonqualified name cout. However, the overloaded << operator, as you might recall, is not a member of std::cout. It is a friend function that is defined in namespace std, and which takes a std::ostream object as its argument. Without Koenig lookup, the programmer has to write something similar to the following:

```
std::operator<<(cout, "hello");</pre>
```

Alternatively, the programmer can provide a using namespace std; directive. None of these options are desirable, however, because they clutter up code and can become a source of confusion and errors. (using directives are the least favorable form for rendering names visible in the current scope because they make all the members of a namespace visible indiscriminately). Fortunately, Koenig lookup "does the right thing" and saves you from this tedium in an elegant way.

Koenig lookup is applied automatically. No special directives or configuration switches are required to activate it, nor is there any way to turn it off. This fact has to be kept in mind because it can have surprising results in some circumstances. For example

```
namespace NS1
{
  class B{};
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 8 - Namespaces
```

```
void f;
};
void f(NS1::B);
int main()
{
   NS1::B b;
   f;   // ambiguous; NS1::f() or f(NS1::B)?
   return 0;
}
```

A Standard-compliant compiler should issue an error on ambiguity between NS1::f(NS1::B) and f(NS1::B). However, noncompliant compilers do not complain about the ambiguous call; they simply pick one of the versions of f(). This, however, might not be the version that the programmer intended. Furthermore, the problem might arise only at a later stage of the development, when additional versions of f() are added to the project -- which can stymie the compiler's lookup algorithm. This ambiguity is not confined to global names. It might also appear when two namespaces relate to one another -- for instance, if a namespace declares classes that are used as parameters of a class member function that is declared in a different namespace.

## **Namespaces in Practice**

The conclusion that can be drawn from the previous examples is that namespaces, like other language features, must be used judiciously. For small programs that contain only a handful of classes and a few source files, namespaces are not necessary. In most cases, such programs are coded and maintained by a single programmer, and they use a limited number of components. The likelihood of name clashes in this case is rather small. If name clashes still occur, it is always possible to rename the existing classes and functions, or simply to add namespace later.

On the other hand, large-scale projects -- as was stated previously -- are more susceptible to name clashes; therefore, they need to use namespaces systematically. It is not unusual to find projects on which hundreds of programmers on a dozen or so development teams are working together. The development of Microsoft Visual C++ 6.0, for example, lasted 18 months, and more than 1000 people were involved in the development process. Managing such a huge project requires well documented coding policies -- and namespaces are one of the tools in the arsenal.

# Namespace Utilization Policy in Large-Scale Projects

To see how namespaces can be used in configuration management, imagine an online transaction processing system of an imaginary international credit card company, Unicard. The project comprises several development teams. One of them, the database administration team, is responsible for the creation and maintenance of the database tables, indexes, and access authorizations. The database team also has to provide the access routines and data objects that retrieve and manipulate the data in the database. A second team is responsible for the graphical user interface. A third team deals with the international online requests that are initiated by the cinemas, restaurants, shops, and so on where tourists pay with their international Unicard. Every purchase of a cinema ticket, piece of jewelry, or art book has to be confirmed by Unicard before the card owner is charged. The confirmation process involves checking for the validity of the card, its expiration date, and the card owner's balance. A similar confirmation procedure is required for domestic purchases. However, international confirmation requests are transmitted via satellite, whereas domestic confirmations are usually done on the telephone.

In software projects, code reuse is paramount. Because the same business logic is used for both domestic and international confirmations, the same database access objects need to be used to retrieve the relevant information and perform the necessary computations. Still, an international confirmation also involves a sophisticated communication stack that receives the request that is transmitted via satellite, decrypts it, and returns an encrypted response to the sender. A typical implementation of satellite-based confirmation application can be achieved by means of combining the database access objects with the necessary communication objects that encapsulate protocols, communication layers, priority management, message queuing, encryption, and decryption. It is not difficult to imagine a name conflict resulting from the simultaneous use of the communication components and the database access objects.

For example, two objects -- one encapsulating a database connection and the other referring to a satellite connection -- can have an identical name: Connection. If, however, communication software components and database access objects are

declared in two distinct namespaces, the potential of name clashes is minimized. Therefore, com::Connection and dba::Connection can be used in the same application simultaneously. A systematic approach can be based on allocating a separate namespace for every team in a project in which all the components are declared. Such a policy can help you avoid name clashes among different teams and third party code used in the project.

# **Namespaces and Version Control**

Successful software projects do not end with the product's rollout. In most projects, new versions that are based on their predecessors are periodically released. Moreover, previous versions have to be supported, patched, and adjusted to operate with new operating systems, locales, and hardware. Web browsers, commercial databases, word processors, and multimedia tools are examples of such products. It is often the case that the same development team has to support several versions of the same software product. A considerable amount of software can be shared among different versions of the same product, but each version also has its specific components. Namespace aliases can be used in these cases to switch swiftly from one version to another.

Continuous projects in general have a pool of infrastructure software components that are used ubiquitously. In addition, every version has its private pool of specialized components. Namespace aliases can provide *dynamic namespaces*; that is, a namespace alias can point at a given time to a namespace of version X and, at another time, it can refer to a different namespace. For example

```
namespace ver_3_11 //16 bit
{
   class Winsock{/*..*/};
   class FileSystem{/*..*/};
};
namespace ver_95 //32 bit
{
   class Winsock{/*..*/};
   class FileSystem{/*..*/};
} int main()//implementing 16 bit release
{
   namespace current = ver_3_11; // current is an alias of ver_3_11 using current::Winsock;
   using current::FileSystem;
   FileSystem fs; // ver_3_11::FileSystem
   //...
   return 0;
}
```

In this example, the alias current is a symbol that can refer to either ver\_3\_11 or ver\_95. To switch to a different version, the programmer only has to assign a different namespace to it.

# Namespaces Do not Incur Additional Overhead

Namespace resolution, including Koenig lookup, are statically resolved. The underlying implementation of namespaces occurs by means of *name mangling*, whereby the compiler incorporates the function name with its list of arguments, its class name, and its namespace in order to create a unique name for it (see Chapter 13, "C Language Compatibility Issues," for a detailed account of name mangling). Therefore, namespaces do not incur any runtime or memory overhead.

# The Interaction of Namespaces with Other Language Features

Namespaces interact with other features of the language and affect programming techniques. Namespaces made some features in C++ superfluous or undesirable.

# Scope Resolution Operator Should Not Be Used To Designate Global Names

In some frameworks (MFC, for instance), it is customary to add the scope resolution operator, ::, before a global function's name to mark it explicitly as a function that is not a class member (as in the following example):

```
void String::operator = (const String& other)
{
    ::strcpy (this->buffer, other.getBuff());
}
```

This practice is not recommended. Many of the standard functions that were once global are now grouped inside namespaces. For example, strcpy now belongs to namespace std, as do most of the Standard Library's functions. Preceding these functions with the scope resolution operator might confuse the lookup algorithm of the compiler; furthermore, doing so undermines the very idea of partitioning the global namespace. Therefore, it is recommended that you leave the scope resolution operator off the function's name.

## **Turning an External Function into A File-Local Function**

In standard C, a nonlocal identifier that is declared to be static has *internal linkage*, which means that it is accessible only from within the translation unit (source file) in which it is declared (see also Chapter 2, "Standard Briefing: The Latest Addenda to ANSI/ISO C++"). This technique is used to support information hiding (as in the following example):

```
//File hidden.c
static void decipher(FILE *f); // accessible only from within this file
    // now use this function in the current source file
decipher ("passwords.bin");
    //end of file
```

Although it is still supported in C++, this convention is now considered a *deprecated feature*. Future releases of your compiler might issue a warning message when they find a static identifier that is not a member of a class. In order to make a function accessible only from within its translation unit, use an *unnamed namespace* instead. The following example demonstrates the process:

Although names in an unnamed namespace might have external linkage, they can never be seen from any other translation unit; the net effect of this is that the names of an unnamed namespace appear to have static linkage. If you declare another function with the same name in an unnamed namespace of another file, the two functions are hidden from one another, and their names do not clash.

### **Standard Headers Names**

All Standard C++ header files now have to be included as follows:

```
#include <iostream> //note: no ".h" extension
```

That is, the .h extension is omitted. Standard C header files also obey this convention, with the addition of the letter c to their name. Therefore, a C standard header that was formerly named  $< x \times x \cdot h >$  is now  $< c \times x \times >$ . For example

```
#include <cassert> //formerly: <assert.h> note the prefix 'c' and the //omission of
".h"
```

The older convention for C headers, <xxx.h>, is still supported; however, it is now considered deprecated and, therefore, is not to not be used in new C++ code. The reason for this is that C <xxx.h> headers inject their declarations into the global namespace. In C++, however, most standard declarations are grouped under namespace std, as are the <cxxx> Standard C headers. No inference is to be drawn from the actual name convention that is used on the physical location of a header file or its underlying name. In fact, most implementations share a single physical file for the <xxx.h> and its corresponding <cxxx> notation. This is feasible due to some under-the-hood preprocessor tricks. Recall that you need to have a using declaration, a using directive, or a fully qualified name in order to access the declarations in the new style standard headers. For example

```
#include <cstdio>
using namespace std;
void f()
{
    printf ("Hello World\n");
}
```

# **Restrictions on Namespaces**

The C++ Standard defines several restrictions on the use of namespaces. These restrictions are meant to avert anomalies or ambiguities that can create havoc in the language.

### Namespace std Can Not Be Modified

Generally, namespaces are open, so it is perfectly legal to expand existing namespaces with additional declarations and definitions across several files. The only exception to the rule is namespace std. According to the Standard, the result of modifying namespace std with additional declarations -- let alone the removal of existing ones -- yields undefined behavior, and is to be avoided. This restriction might seem arbitrary, but it's just common sense -- any attempt to tamper with namespace std undermines the very concept of a namespace dedicated exclusively to standard declarations.

### User-Defined new and delete Cannot Be Declared in a Namespace

The Standard prohibits declarations of new and delete operators in a namespace. To see why, consider the following example:

```
char *pc; //global
namespace A
{
  void* operator new ( std::size_t );
  void operator delete ( void * );
  void func ()
  {
    pc = new char ( 'a'); //using A::new
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 8 - Namespaces

} //A

void f() { delete pc; } // call A::delete or //::delete?
```

Some programmers might expect the operator A::delete to be selected because it matches the operator new that was used to allocate the storage; others might expect the standard operator delete to be called because A::delete is not visible in function f(). By prohibiting declarations of new and delete in a namespace altogether, C++ avoids any such ambiguities.

### **Conclusions**

Namespaces were the latest addition to the C++ Standard. Therefore, some compilers do not yet support this feature. However, all compiler vendors will incorporate namespace support in the near future. The importance of namespaces cannot be over-emphasized. As you have seen, any nontrivial C++ program utilizes components of the Standard Template Library, the iostream library, and other standard header files -- all of which are now namespace members.

Large-scale software projects can use namespaces cleverly to avoid common pitfalls and to facilitate version control, as you have seen.

C++ offers three methods for injecting a namespace constituent into the current scope. The first is a using directive, which renders all the members of a namespace visible in the current scope. The second is a using declaration, which is more selective and enables the injection of a single component from a namespace. Finally, a fully qualified name uniquely identifies a namespace member. In addition, the argument-dependent lookup, or Koenig lookup, captures the programmer's intention without forcing him or her to use wearying references to a namespace.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

# 9 Templates

### by Danny Kalev

- Introduction
- Class Templates
  - Declaration of a Class Template
  - Instantiation and Specialization
  - Template Arguments
  - Default Type Arguments
  - Static Data Members
  - o Friendship
  - Partial Specialization
  - o Explicit Specialization of a Class Template
  - o Specializations of Class Template Functions
- Function Templates
  - Function-Like Macros
  - o void Pointers
  - A Common Root Base
- Performance Considerations
  - Type Equivalence
  - o Avoiding Unnecessary Instantiations
  - Explicit Template Instantiation
  - Exported Templates
- Interaction with Other Language Features
  - o The typename Keyword

- o Inheritance Relationship of Templates
- Virtual Member Functions
- o Pointers to Members of a Class Template
- Conclusions

# Introduction

A template is a mold from which the compiler generates a family of classes or functions. C++ programming styles and concepts have changed considerably since the first implementation of templates back in 1991 (in cfront 2.0). Initially, templates were viewed as a support for generic container classes such as Array and List. In recent years, the experience of using templates has shown that this feature is most useful in designing and implementing general-purpose libraries such as the Standard Template Library. Templatized libraries and frameworks are both efficient and portable. With the widespread usage of templates, C++ has added more sophisticated constructs to control their behavior and performance, including partial specializations, explicit specializations, template members, exported templates, default type arguments, and more.

This chapter discusses various aspects of designing and implementing templates. First, class templates are explained. Function templates come next. Finally, template issues of special concern -- such as pointers to members, virtual member functions within a template class, inheritance relations, and explicit instantiations -- are discussed.

# **Class Templates**

Many algorithms and data structures can be defined independently of the concrete data type that they manipulate. Often, the reliance on a hardwired data type is merely a programming artifact. The concept of a complex number, for instance, is not exclusively limited to the fundamental type double. Rather, it is applicable to every floating-point type. Designing a type-independent class that abstracts the concept of a complex number has many advantages because it enables users to choose the desired level of precision for a specific application without having to reduplicate code manually. In addition, type-independent classes are more portable among different platforms and locales.

### **Declaration of a Class Template**

A class template is declared using the keyword template, followed by a *template parameter list* that is enclosed in angular brackets and a declaration or a definition of the class. For example

```
template <class T> class Vector; //declaration
template <class T> class Vector //definition
{
  private:
    size_t sz;
    T * buff;
public:
    explicit Vector<T>(size_t s = 100);
    Vector<T> (const Vector <T> & v); //copy constructor
    Vector<T>& operator= (const Vector<T>& v); //assignment operator
    ~Vector<T>(); //destreutor
    //other member functions
    T& operator [] (unsigned int index);
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates

const T& operator [] (unsigned int index) const;

size_t size() const;

};
```

Member functions of a class template can be defined outside the class body. In this case, they have to be explicitly declared as member functions of their class template. For example

```
//definitions of Vector's member functions
//follow the class declaration
template <class T> Vector<T>::Vector<T> (size t s) //constructor definition
: sz(s),
buff (new T[s])
{}
template <class T> Vector<T>::Vector<T> (const Vector <T> & v) //copy ctor
 sz = 0;
 buff = 0;
  *this = v; //use overloaded assignment operator
template <class T> Vector<T>& Vector<T>::operator= // assignment operator
(const Vector <T> & v)
  if (this == &v)
    return *this;
  this->Vector<T>::~Vector<T>(); //call destructor
 buff = new T[v.size()]; //allocate sufficient storage
  for (size_t i =0; i < v.size(); i++)</pre>
    buff[i] = v[i]; //memberwise copy
  sz = v.size();
 return *this;
template <class T> Vector<T>::~Vector<T> () //destructor
 delete [] buff;
template <class T> inline T& Vector<T>::operator [] (unsigned int i)
 return buff[i];
template <class T> inline const T& Vector<T>::operator [] //const version
(unsigned int i) const
 return buff[i];
template <class T> inline size_t Vector<T>::size () const
 return sz;
//Vector.hpp
```

The prefix template <class T> indicates that T is a *template parameter*, which is a placeholder for a yet unspecified type. The keyword class is of particular interest because the corresponding argument for the parameter

T is not necessarily a user-defined type; it can also be a fundamental type, such as char or int. If you prefer a more neutral term, you can use the typename keyword instead (typename also has other uses, though, as you will see next):

```
template <typename T> class Vector //typename instead of class
                                    //no semantic difference between the two forms
  //...
template <typename T> Vector<T>::Vector<T> (size_t s)
: sz(s), buff (new T[s]) {}
Within the scope of Vector, qualification with the parameter T is redundant, so the member functions can be
declared and defined without it. The constructor, for example, can be declared as follows:
template <class T> class Vector
public:
Vector (size_t s = 100); // equivalent to Vector <T>(size_t s = 100);
};
Similarly, the constructor's definition can omit the redundant parameter:
// equivalent to template <class T> Vector<T>::Vector<T>(size_t s)
template <class T> Vector<T>::Vector (size_t s) :
buff (new T[s]), sz(s)
{}
```

### **Instantiation and Specialization**

A class template is not a class. The process of instantiating a class from a class template and a type argument is called *template instantiation*. A *template id*, that is, a template name followed by a list of arguments in angular brackets (for example, Vector<int>), is called a *specialization*. A specialization of a class template can be used exactly like any other class. Consider the following examples:

```
void func (Vector <float> &); //function parameter
size_t n = sizeof( Vector <char>); //sizeof expression
class myStringVector: private Vector<std::string> //base class
{/*...*/};
#include <iostream>
#include <typeinfo>
#include <string>
using namespace std;
cout<<typeid(Vector< string>).name(); //typeid expression
Vector<int> vi; // creating an object
```

The compiler instantiates only the necessary member functions of a given specialization. In the following example, points of member instantiation are numbered:

```
#include <iostream>
#include "Vector.hpp"
```

The compiler generates code only for the following Vector member functions, which are used either explicitly or implicitly in the program:

```
Vector<int>::Vector<int> (size_t s) //1: constructor
: sz(s), buff (new int[s]) {}
inline int& Vector<int>::operator [] (unsigned int idx) //2: operator []
{
   return buff[idx];
}
Vector<int>::~Vector<int> () //3: destructor
{
   delete [] buff;
}
```

In contrast, code for the member function size\_t Vector<int>::size() const is not generated by the compiler because it is not required. For some compilers, it might be simpler to instantiate all the class members at once whether they are needed or not. However, the "generate on demand" policy is a Standard requirement, and has two functions:

- Efficiency -- It is not uncommon for certain class templates to define hundreds of member functions (STL containers, for example); normally, however, fewer than a dozen of these are actually used in a program. Generating the code for unused member functions times the number of specializations used in the program can easily bloat the size of the executable -- and it might unnecessarily increase compilation and linkage time.
- Flexibility -- In some cases, not every type supports all the operations that are defined in a class template. For example, a container class can use ostream's operator << to display members of fundamental types such as char and int and user-defined types for which an overloaded version of << is defined. However, a POD (plain old data) struct for which no overloaded version of << exists can still be stored in such a container as long as the << is not invoked.

## **Template Arguments**

A template can take type parameters, that is, symbols that represent an as yet unspecified type. For example

```
template <class T > class Vector {/*...*/};
```

A template can also take ordinary types such as int and long as parameters:

```
template <class T, int n> class Array
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates
private:
  T a[n];
  int size;
public:
  Array() : size (n) {}
  T& operator [] (int idx) { return a[idx]; }
};
Note, however, that when an ordinary type is used as a parameter, the template argument must be a constant or a
constant expression of an integral type. For example
void array_user()
  const int cn = 5;
  int num = 10;
  Array<char, 5> ac; // OK, 5 is a const
  Array<float, cn> af; // OK, cn is const
  Array<unsigned char, sizeof(float)> auc; // OK, constant expression used
  Array<bool, num> ab; // error, num is not a constant
Besides constant expressions, other arguments that are allowed are a non-overloaded pointer to member and the
address of an object or a function with external linkage. This also implies that a string literal cannot be used as a
template argument because it has internal linkage. For example:
template <class T, const char *> class A
{/*...*/};
void array_user()
  const char * p ="illegal";
  A<int, "invalid"> aa; // error, string literal used as a template argument
  A<int, p> ab; // also an error, p doesn't have external linkage
A template can take a template as an argument. For example
int send(const Vector<char*>& );
int main()
  Vector <Vector<char*> > msg_que(10); //a template used as an argument
  //...fill msg_que
  for (int i =0; i < 10; i++) //transmit messages</pre>
    send(msg_que[i]);
  return 0;
Note that when a template is used as an argument, the space between the left two angular brackets is mandatory:
```

file:///D|/Cool Stuff/old/ftp/1/1/ch09/ch09.htm (6 von 22) [12.05.2000 14:46:22]

Otherwise, the >> sequence is parsed as the right shift operator.

Vector <Vector<char\*> > msg\_que(10);

A typedef can be used to avert this mishap and improve readability, both for the compiler and for the human reader:

```
typedef Vector<char *> msg;
Vector<msg> msg_que;
```

### **Default Type Arguments**

Class templates can have default type arguments.

As with default argument values of a function, the default type of a template gives the programmer more flexibility in choosing the optimal type for a particular application. For instance, the Vector template can be optimized for special memory management tasks. Instead of using the hard-coded size\_t type for storing the size of a Vector, it can have a size type as a parameter. For most purposes, the default type size\_t is used. However, for managing extremely large memory buffers on the one hand -- or very small ones on the other hand -- the programmer is free to choose other suitable data types instead. For example

```
template <class T, class S = size_t > class Vector
private:
  S sz;
 T * buff;
public:
  explicit Vector(S s = 100): sz(s), buff(new T[s]){}
  ~Vector();
  //other member functions
 S size() const;
template <class T, class S> Vector<T,S>::~Vector<T,S>()//destructor definition
 delete [] buff;
template <class T, class S> S Vector<T,S>::size() const
 return sz;
int main()
 Vector <int> ordinary;
 Vector <int, unsigned char> tiny(5);
 return 0;
```

An additional advantage of a default size type is the capability to support implementation-dependent types. On a machine that supports 64-bit integers, for instance, programmers can use Vector to easily manipulate very large memory buffers:

```
Vector <int, unsigned __int64> very_huge;
```

The fact that the programmer does not have to make any changes to the definition of Vector to get the appropriate specialization cannot be overemphasized. Without templates, such a high level of automation is very difficult to

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates achieve.

### **Static Data Members**

Templates can have static data members. For example

```
template < class T > class C
{
public:
    static T stat;
};
template < class T > T C < T > :: stat = 5; // definition
A static data member can be accessed as follows:

void f()
{
    int n = C < int > :: stat;
}
```

### Friendship

A friend of a class template can be a function template or class template, a specialization of a function template or class template, or an ordinary (nontemplate) function or class. The following sections discuss the various types of friendship that a class template can have.

### **Nontemplate Friends**

Nontemplate friend declarations of a class template look quite similar to friend declarations of a nontemplate class. In the following example, the class template Vector declares the ordinary function f () and class Thing as its friends:

```
class Thing;
template <class T> class Vector
{
public:
   //...
   friend void f ();
   friend class Thing;
};
```

Each specialization of Vector has the function f() and class Thing as friends.

### **Specializations**

You can declare a specialization as a friend of a class template. In the following example, the class template Vector declares the specialization C<void\*> as its friend:

```
template <class T> class C{/*...*/};
template <class T> class Vector
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates

public:
    //...
    friend class C<void*>; //other specializations are not friends of Vector
```

### **Template Friends**

};

A friend of a class template can be a template by itself. For instance, you can declare a class template as a friend of another class template:

```
template <class U> class D{/*...*/};
template <class T> class Vector
{
public:
   //...
template <class U> friend class D;
};
```

Every specialization of D is a friend of every specialization of Vector. You can also declare a function template as a friend (function templates will be discussed in further detail shortly). For instance, you might add an overloaded operator == function template to test the equality of two Vector objects. Consequently, for every specialization of Vector, the implementation will generate a corresponding specialization of the overloaded operator ==. In order to declare a friend template function, you first have to forward declare the class template and the friend function template as follows:

```
template <class T> class Vector; // class template forward declaration
   // forward declaration of the function template to be used as a friend
template <class T> bool operator== (const Vector<T>& v1, const Vector<T>& v2);
```

Next, the friend function template is declared inside the class body:

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates
    if(v1[i] != v2[i])
    return false;
}
return true;
```

## **Partial Specialization**

It is possible to define a *partial specialization* of a class template. A partial specialization provides an alternative definition of the *primary template*. It is used instead of the primary definition when the arguments in any specialization match those that are given in the partial specialization. For instance, a partial specialization of Vector can handle pointer types exclusively. Thus, for specializations of fundamental types and user-defined types, the primary Vector class is used. For pointers, the partial specialization is used instead of the primary class template. A pointer partial specialization can optimize the manipulation of pointers in several ways.

In addition, some operations that manipulate pointers involve dereferencing and the use of operator ->, neither of which is used with non-pointer types.

A partial specialization is defined as follows:

```
//filename: Vector.hpp
template <class T> class Vector <T*> //partial specialization of Vector <T>
{
    private:
        size_t size;
        void * p;

public:
        Vector();
        ~Vector();
        //...member functions
        size_t size() const;
};
//Vector.hpp
```

A partial specialization is indicated by the parameter list that immediately follows the class template name (remember that the primary template is declared without the list after its name). Compare these two forms:

```
template <class T> class Vector //primary template
{};
template <class T> class Vector <T*> //partial specialization
{};
```

Partial specializations of a class template that has several parameters are declared as follows:

```
template<class T, class U, int i> class A \{\ \}; // primary template<class T, int i> class A<T, T*, i> \{\ \}; // partial specialization template<class T> class A<int, T*, 8> \{\ \}; // another partial specialization Partial specializations must appear after the primary declaration of a class template, and its parameter cannot contain default types.
```

## **Explicit Specialization of a Class Template**

An explicit specialization of a class template provides an alternative definition of the primary template. It is used instead of the primary definition if the arguments in a particular specialization match those that are given in the explicit specialization. When is it useful? Consider the Vector template: The code that is generated by the compiler for the specialization Vector<br/>bool> is very inefficient. Instead of storing every Boolean value in a single bit, it occupies at least an entire byte. When you are manipulating large amounts of bits, for example in logical operations or digital signal processing, this is unacceptable. In addition, bit-oriented operations can be performed more efficiently using the bitwise operators. Obviously, there are significant advantages to defining a Vector template that is specifically adjusted to manipulate bits. Following is an example of an explicit specialization Vector<br/>bool> that manipulates bits rather than bytes:

```
template <> class Vector <bool> //explicit specialization
private:
  size_t sz;
 unsigned char * buff;
public:
  explicit Vector(size_t s = 1) : sz(s),
   buff (new unsigned char [(sz+7U)/8U] ) {}
 Vector<bool> (const Vector <bool> & v);
 Vector<bool>& operator= (const Vector<bool>& v);
  ~Vector<bool>();
  //other member functions
 bool& operator [] (unsigned int index);
  const bool& operator [] (unsigned int index) const;
  size_t size() const;
};
void bitmanip()
 Vector< bool> bits(8);
bits[0] = true; //assign
bool seventh = bits[7]; //retrieve
```

The template<> prefix indicates an explicit specialization of a primary template. The template arguments for a specialization are specified in the angular brackets that immediately follow the class name. The specialization hierarchy of Vector that has been defined thus far is as follows:

```
template <class T> class Vector //primary template
{};
template <class T> class Vector <T*> //partial specialization
{};
template <> class Vector <bool> //explicit specialization
{};
```

Fortunately, the Standard Template Library already defines a specialization of std::vector<bool> for manipulating bits optimally, as you will read in the next chapter, "STL and Generic Programming."

# **Specializations of Class Template Functions**

The overloaded operator == of class Vector performs a plausible comparison between two Vector objects when their elements are either fundamental types or objects that overload operator ==. However, a comparison of two objects that store C strings is likely to yield the wrong result. For example

```
#include "Vector.hpp"
extern const char msg1[] = "hello";
extern const char msg2[] = "hello";
int main()
{
    Vector<const char *> v1(1), v2(1); //the same number of elements
    v1[0] = msg1;
    v2[0] = msg2;
    bool equal = (v1 == v2); //false, strings are equal but pointers aren't
    return 0;
}
```

**NOTE:** Whether identical string literals are treated as distinct objects is implementation-dependent. Some implementations might store the constants msg1 and msg2 at the same memory address (on such implementations, the expression bool equal = (v1 == v2); yields true). However, the discussion here assumes that msg1 and msg2 are stored in two distinct memory addresses.

Although v1 and v2 have the same number of elements and their elements hold the same string value, operator == returns false because it compares the addresses of the strings rather than the strings themselves. You can alter this behavior by defining a specialized version of operator == for type const char \* exclusively, which compares the strings rather than their addresses. The compiler picks the specialized version only when objects of type Vector<const char \*> are compared. Otherwise, it uses the primary version of operator ==. It is not necessary to add the declaration of the specialized friend operator == in the declaration of the template class Vector. However, it is still recommended that you do so in order to document the existence of a specialized operator ==. For example

The definition of the specialized function must appear after the generic version. Therefore, you place it at the same header file, right after the generic version. Following is the specialized version:

```
//appended to vector.hpp
#include <cstring> //needed for strcmp
```

Here again, the empty angular brackets that follow the keyword template indicate a specialized version that overrides a previously defined generic version. The compiler now uses the specialized form of operator == to compare v1 and v2; as expected, the result is now true.

Specialized functions operate in a way that resembles the behavior of virtual member functions in a derived class. In both cases, the actual function that is being called depends on the type. However, the virtual dispatch mechanism relies on the dynamic type of the object, whereas template function specializations are resolved statically.

# **Function Templates**

Many algorithms perform a sequence of identical operations, regardless of the data type they manipulate. min and max, array sort, and swap are examples of such type-independent algorithms. In the pre-template era, programmers had to use alternative techniques to implement generic algorithms:-- macros, void pointers, and a common root base -- all of which incurred significant drawbacks. This section exemplifies the drawbacks of these techniques and then demonstrates how function templates are used in implementing generic algorithms.

### **Function-Like Macros**

Function-like macros were the predominant form of implementing generic algorithms in C. For example

```
#define min(x,y) ((x)<(y))?(x):(y)
void f()
{
  double dlower = min(5.5, 5.4);
  int ilower = min(sizeof(double), sizeof(int));
  char clower = min('a', 'b');
}</pre>
```

The C Standard library defines various function-like macros. To some extent, they can be used effectively because they avoid the overhead that is associated with a full-blown function call. However, macros have significant drawbacks as well. The preprocessor macro expansion is a simple text substitution, with very limited awareness of scope rules and type-checking. Furthermore, macros are notoriously hard to debug because the compiler scans a source file that might look very different from the original file. For this reason, compiler diagnostics can refer to code that the original source file does not contain. Macros can easily bloat the size of a program because every macro call is expanded inline. When large macros are called repeatedly, the result can be a dramatic increase in the size of the program. In spite of the syntactic similarity, macros are semantically very different from functions -- they have no

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates

linkage, address, or storage type. For these reasons, use macros sparingly -- if at all.

### void Pointers

An alternative approach to macros is the use of a generic pointer, void \*, which can hold the address of any data type. The C standard library defined two generic functions that rely on this feature: qsort and bsearch. qsort is declared in the header <stdlib.h> as follows:

The type-unawareness of these generic functions is achieved by using void pointers and an abstract, user-defined comparison function. Still, there are noticeable limitations to this technique. void pointers are not type-safe, and the repeated function callbacks impose runtime overhead that, in most cases, cannot be avoided by inlining.

### **A Common Root Base**

In some other object-oriented languages, every object is ultimately derived from a common base class (this design approach and its deficiencies in C++ are described in further detail in Chapter 5, "Object-Oriented Programming and Design"). Generic algorithms can rely on this feature. For example

```
// pseudo C++ code
class Object // a common root class
{
public:
    virtual bool operator < (const Object&) const; //polymorphic behavior
    //..other members
};
const Object& min(const Object &x, const Object& y)
{
    return x.operator<(y) ? x : y; //x and y can be objects of any class type
}</pre>
```

Imitating this approach in C++ is not as useful as it is in other languages, though. C++ does not force a common root class. Therefore, it is the programmer's -- not the implementation's -- responsibility to ensure that every class is derived from a common base. Worse yet, the common root class is not standardized. Thus, such algorithms are not portable. In addition, these algorithms cannot handle fundamental types because they are limited to class objects exclusively. Finally, the extensive use of runtime type checking imposes an unacceptable performance on general-purpose algorithms.

Function templates are free from all these drawbacks. They are type-safe, they can be inlined by the compiler to boost performance, and -- most importantly -- they are applicable to fundamental types and user-defined types alike.

A function template declaration contains the keyword template, followed by a list of template parameters and a function declaration. As opposed to ordinary functions, which are usually declared in one translation unit and defined in another, the definition of a function template follows its declaration. For example

```
template <class T> T max( T t1, T t2)
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates return (t1 > t2) ? t1 : t2;
```

Unlike class templates, function template parameters are implicitly deduced from the type of their arguments.

In the following example, the compiler instantiates three distinct specializations of swap, according to the type of arguments used in each invocation:

It is possible to define several function templates with the same name (that is, to overload it) or to combine ordinary functions with function templates that have the same name. For example

```
template <class T> T max( T t1, T t2)
{
  return (t1 > t2) ? t1 : t2;
}
int max (int i, int j)
{
  return (i > j) ? i : j;
}
```

The compiler does not generate an int version of max(). Instead, it invokes the function int max (int, int) when max() is called with arguments of type int.

# **Performance Considerations**

C++ provides several facilities for controlling the instantiation of templates, including explicit instantiation of templates and exported templates. The following sections demonstrate how to use these features, as well as other techniques to enhance performance.

# Type Equivalence

Two templates are equivalent (that is, they refer to the same template id) when all the following conditions hold:

- Name equivalence -- The names of the templates are identical and they refer to the same template.
- **Argument Equivalence** -- The type arguments of the templates are the same.
- **Identical non-Type Arguments** -- The non-type arguments of integral or enumeration type of both templates have identical values, and their non-type arguments of pointer or reference type refer to the same external object or function.

• **Template-template Arguments** -- The template-template arguments of both templates refer to the same template.

Following are some examples:

```
template<class T, long size> class Array
{ /* ... */ };
void func()
{
Array<char, 2*512> a;
Array<char, 1024> b;
}
```

The compiler evaluates constant expressions such as 2\*512, so templates a and b are of the same type. Following is another example:

```
template < class T, int(*error_code_fct)() > class Buffer
{    /* ... */ };
int error_handler();
int another_error_handler();
void func()
{
    Buffer < int, & error_handler > b1;
    Buffer < int, & another_error_handler > b2;
    Buffer < int, & another_error_handler > b3;
    Buffer < unsigned int, & another_error_handler > b4;
}
```

b2 and b3 are of the same type because they are instances of the same template and they take the same type and non-type arguments. Conversely, b1 and b4 are of distinct types.

The function func() instantiated three distinct specializations from the same class template: one for b1, a second for b2 and b3, and a third for b4. Unlike ordinary function overloading, the compiler generates a distinct class from the template for every unique type. On machines that have the same underlying representation for long and int types, the following code still results in the instantiation of two distinct templates:

```
void too_prolific()
{
   Buffer<int, &error_handler> buff1;
   Buffer<long, &error_handler> buff2;
}
```

Similarly, char and unsigned char are distinct types, even on machines that treat char as unsigned by default. Programmers who are accustomed to the lenient matching rules of ordinary function overloading are not always aware of the potential code bloat that can result from using templates with very similar yet distinct types.

### **Avoiding Unnecessary Instantiations**

In the following example, three distinct copies of the template min are generated -- one for each type that is used:

```
template < class T > T min(T f, T s)
```

On the other hand, an ordinary function avoids the automatic generation of redundant specializations:

```
int min(int f, int s)
{
  return f < s? f: s;
}

void use_min()
{
  // all three invocation of min
  // use int min (int, int);
  int n = 5, m= 10;
  int j = min(n,m);
  char c = 'a', d = 'b';
  char k = min(c,d);
  short int u = 5, v = 10;
  short int w = min(u,v);
}</pre>
```

Still, the template version of min has a clear advantage over the function: It can handle pointers and any other user-defined types. You want the benefits of a template while avoiding the unnecessary generation of specializations. How can these be avoided? A simple solution is to safely cast the arguments into one common type before invoking the function template. For example:

This technique can also be applied to pointers: First, they have to be cast to void \*, and then they must be cast back to their original type. When you are using pointers to polymorphic objects, pointers to derived objects are cast to pointers to a base class.

For very small templates such as min, casting the arguments into a common denominator type is not worth the trouble. Nonetheless, when nontrivial templates that contain hundreds of code lines are used, you might consider

doing so.

## **Explicit Template Instantiation**

//filename func1.cpp

As was previously noted, templates are instantiated only if they are used in the program. Generally, compilers generate the necessary code for a specialization when they encounter its use in the source file. When large applications that consist of hundreds of source files have to be compiled, this can cause a significant increase in compilation time because the compiler's processing is repeatedly interrupted when it has to generate code for sporadic specializations. The recurrent interruption can occur in almost every source file because they use -- almost without exception -- template classes of the Standard Library. Consider a simple project that consists of only three source files:

```
#include <string>
#include <iostream>
using namespace std;
void func1()
  string s; //generate default constructor and destructor
  s = "hello"; //generate assignment operator for const char *
  string s2;
  s2 = s; // generate operator = const string&, string&
  cout<<s2.size(); // generate string::size, ostream& operator <<(int)</pre>
//funcl.cpp
//filename func2.cpp
#include <string>
#include <iostream>
using namespace std;
void func2()
 string s; //generate default constructor and destructor
cout<<"enter a string: "<<endl; //generate ostream& operator<<(const char *)</pre>
 cin>>s //generate istream& operator>>(string&)
//func2.cpp
//filename main.cpp
int main()
 func1();
 func2();
 retrun 0;
// main.cpp
```

The compilation time can be reduced if all the necessary template code is instantiated all at once, thereby avoiding the repeated interruption of the compiler's processing. For this purpose, you can use an *explicit instantiation*. An explicit instantiation is indicated by the keyword template (without the <>), followed by a template declaration. Here are a few examples of explicit template instantiations:

```
template <class T> class A{/*..*/};
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates

template < class T > void func(T&) {
    //filename instantiations.hpp

template class Vector < short >;    //explicit instantiation of a class template

template A < int > :: A < int > ();    //explicit instantiation of a member function

template class
    std::basic_string < char > ;    //explicit instantiation of a namespace member

template void func < int > (int &);    //explicit instantiation of a function template
```

### **Examples of Explicit Instantiations in the Standard Library**

The Standard Library defines several specializations of class templates. One example is the class template basic\_string<>. Two specialized versions of this class are std::string and std::wstring, which are typedefs of the specializations basic\_string<char> and basic\_string<wchar\_t>, respectively. Usually, there is no need to instantiate any of these explicitly because the header <string> already instantiates these specializations:

## **Exported Templates**

**NOTE:** Exported templates are relatively new in C++; therefore, not all compilers support this feature yet. Please consult your user's manual to check whether your compiler supports it.

A template definition can be #included in several translation units; consequently, it can be compiled several times. As you have observed, this can considerably increase compilation and linkage time. Instead of #including a complete definition of the template, it is possible to compile the template definition only once, and use only the template's declaration in other translation units. This is very similar to the compilation of external functions and classes, in which the definition is compiled only once and then only the declarations are required.

To compile a template separately and then use its declaration, the template has to be *exported*. This is done by preceding the template's definition with the keyword export:

```
//filename min.cpp
export template < class T > T min (const T& a, const T& b)
{
  return a > b ? b : a;
}
```

Now only the declaration of the template is required when it is used in other translation units. For example

```
//file min.c
template < class T > T min (const T & a, const T & b); //declaration only
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 9 - Templates
```

```
int main()
{
  int j=0, k=1;
  in smaller = min(j,k);
  return 0;
}
```

Inline function templates cannot be exported. If an inline template function is declared both export and inline, the export declaration has no effect and the template is only inline. Declaring a class template exported is equivalent to declaring all its non-inline member functions, static data members, and member classes exported. Templates in an unnamed namespace are not to be exported.

# **Interaction with Other Language Features**

The interaction of templates with other language features can sometimes yield surprising results. The following sections discuss various aspects of interaction between templates and other language features, including ambiguous interpretation of qualified template names, inheritance, and virtual member functions.

## The typename Keyword

Using qualified names in a template can cause ambiguity between a type and a non-type. For example

```
int N;
template < class T > T func()
{
   T::A * N; // ambiguous: multiplication or a pointer declaration?
//
}
```

If T::A is a typename, the definition of func() N creates a pointer. If, on the other hand, T::A is a non-type (for example, if A is data member of type int), T::A \* N is an expression statement that consists of the multiplication of the qualified member T::A by a global int N. By default, the compiler assumes that an expression such as T::A refers to a non-type. The typename keyword instructs the compiler to supersede this default interpretation and resolve the ambiguity in favor of a type name rather than a non-type. In other words, the preceding (seemingly ambiguous) statement is actually resolved as a multiplication expression, the result of which is discarded. In order to declare a pointer, the typename keyword is required:

```
int N;
template < class T > T func()
{
   typename T::A * N; // N is a now pointer since T::A is a typename
//...
};
```

### Inheritance Relationship of Templates

A common mistake is to assume that a container of pointers or references to objects of a derived class is a container of pointers or references to a base class. For example

```
#include<vector>
```

```
using namespace std;
class Base
{
public: virtual void f() {}
};
class Derived : public Base
{
public: void f() {}
};
void func( vector<Base*>& vb);
int main()
{
   Derived d;
   vector<Derived*> vd;
   vd.push_back(&d);
   func(vd); //error, vector<Derived*>& is not a vector<Base*>}
```

Although the is-a relationship exists between the classes Derived and Base, there is no such relationship between specializations of the same class template that contain pointers or references to related objects.

### **Virtual Member Functions**

A member function template should not be virtual. However, ordinary member functions in a class template *can* be virtual. For example

A specialization of a member function template does not override a virtual function that is defined in a base class. For example

## **Pointers to Members of a Class Template**

Pointers to class members can take the address of a specialized member function of a class template. As with ordinary classes, pointers to members cannot take the address of a static member function. In the following example, the specialization std::vector<int> is used:

```
#include<vector>
using namespace std;
  // a typedef is used to hide the unwieldy syntax
typedef void (vector< int >::*pmv) (size_t);
void func()
{
  pmv reserve_ptr = &vector< int >::reserve;
  //...use reserve_ptr
}
```

# **Conclusions**

Templates simplify and streamline the implementation of generic containers and functions. The benefits of templates have allured software vendors, who are now migrating from plain object-oriented frameworks to object-oriented generic frameworks. However, parameterized types are not unique to C++. Back in 1983, Ada introduced generic packages, which were roughly equivalent to class templates. Other languages implemented similar mechanisms of automated code generation from a skeletal user-written code.

The two main template categories in C++ are class templates and function templates. A class template encapsulates parameterized data members and function members. Function templates are a means of implementing generic algorithms. The traditional methods of implementing generic algorithms in pre-template C++ were rather limited, unsafe, and inefficient compared to templates. An important aspect of templates is the support of object semantics.

C++ enables programmers to control the instantiation of templates by explicitly instantiating them. It is possible to instantiate an entire class, a certain member function of a class, or a particular specialization of a function template. An explicit instantiation of a template is indicated by the keyword template, without angular brackets that are followed by the template declaration. Explicit specializations of a class template are always required. For function templates, the compiler usually deduces the specialization from the type of the arguments. It is possible to define partial specialization of a class template that overrides the primary class template for a set of types. This feature is most useful for modifying the behavior of a class template that manipulates pointers. A partial specialization is indicated by a secondary list of parameters following the name of the template. An explicit specialization enables the programmer to override the automatic instantiation of a class template for a certain type. An explicit specialization is indicated by the keyword template, followed by empty angular brackets and a list of type arguments after the template's name.

Templates and operator overloading are the building blocks of generic programming. The Standard Template Library is an exemplary framework of generic programming, as you will see in the next chapter.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

# 10

# STL and Generic Programming

#### by Danny Kalev

- Introduction
- Generic Programming
- Organization of STL Header Files
  - o **Containers**
  - o Algorithms
  - o <u>Iterators</u>
  - o Numeric Library
  - Utilities
- Containers
  - Sequence Containers
  - Requirements for STL Containment
  - The vector Container Class
  - Container Reallocation
  - o capacity() and size()
  - o Specifying the Container's Capacity During Construction
  - Accessing a Single Element
  - Front and Back Operations
  - Container Assignment
  - Contiguity of Vectors
  - o A vector<Base> Should not Store Derived Objects
  - FIFO Data Models
- Iterators

- o begin() and end()
- o The Underlying Representation of Iterators
- o "const Correctness" of Iterators
- o Initializing a Vector with the Contents of a Built-in Array
- Iterator Invalidation
- Algorithms
  - Non-Modifying Sequence Operations
  - o Mutating Sequence Operations
  - Sort Operations
- Function Objects
  - o Implementation of Function Objects
  - Uses of Function Objects
  - Predicate Objects
- Adaptors
  - Sequence Adaptors
  - Iterator Adaptors
  - Function Adaptors
- Allocators
- Specialized Containers
- Associative Containers
- Class auto\_ptr
  - o STL Containers Should not Store auto\_ptr Elements
- Nearly Containers
- Class string
  - Constructors
  - Conversion to a C-string
  - Accessing a Single Element
  - o Clearing the Contents of A string
  - o Comparison
  - Additional Overloaded Operators
  - Performance Issues
- Conclusions

# Introduction

Object-oriented design offers a limited form of code reuse inheritance and polymorphism. The generic programming paradigm is designed to enable a higher level of reusability. Instead of data hiding, it relies on data independence. C++ has two features that support data independence: templates and operator overloading. A combination of these

features allows a generic algorithm to assume very little about the actual object to which it is applied, whether it is a fundamental type or a user-defined type. Consequently, such an algorithm is not confined to a specific data type, and it has a higher reusability potential than does a type-dependent algorithm.

The Standard Template Library (STL) is an exemplary framework that is built on the foundations of generic programming. STL is a collection of generic algorithms and containers that communicate through iterators. This chapter explores the principles of generic programming, focusing on STL. A complete account of every STL container and algorithm can fill a book of its own, so this chapter only discusses the basic concepts of generic programming. It starts with an overview of STL header files. STL components are discussed next: containers, iterators, algorithms, function objects, adaptors, and allocators. This discussion presents some of the most widely used containers and algorithms of STL. Finally, class string is described in detail.

# **Generic Programming**

Generic software is primarily reusable software. Reusability is characterized by two key features: adaptability and efficiency. It is not difficult to imagine highly adaptive software components that are too inefficient to become widely used (these are usually implemented by complex inheritance hierarchies, virtual functions, and extensive use of runtime type information). Conversely, efficient components are generally written in low-level, platform-dependent code that is both nonportable and hard to maintain. Templates overcome these difficulties because they are checked at compile time rather than at runtime, because they do not require any inheritance relation among objects, and because they are applicable to fundamental types. The most useful generic components are containers and algorithms. For years, programmers were implementing their own lists, queues, sets, and other container types to make up for the lack of language support; however, homemade containers suffer from significant drawbacks. They are not portable, they are sometimes less than 100% bug free, their interfaces vary from one implementation to another, and they can be less than optimal in terms of runtime performance and memory usage.

In the latest phases of the standardization of C++, Alex Stepanov suggested adding a generic library of containers and algorithms to C++. He based his proposal on a similar generic library that he had previously designed for Ada. At that time (November 1993), the committee was under pressure to complete the ongoing standardization process as fast as possible. Consequently, suggestions for language extensions were rejected one after another. However, Stepanov's proposal was too good to be forsaken the committee adopted it unanimously.

The proposed generic library was a collection of containers based on mathematical data models such as vector, queue, list, and stack. It also contained a set of generic algorithms such as sort, merge, find, replace, and so on. These library constituents were implemented with templates. Still, templates alone are insufficient because fundamental types, pointers, user-defined types, and single bits are manipulated by different language constructs and operators. Operator overloading provides the necessary uniform interface that abstracts the actual data type of a container or an algorithm. The following section examines these components in greater detail.

# **Organization of STL Header Files**

STL components are grouped under namespace std. They are defined in the following header files. Note that prestandardized implementations of STL might use different header names, as indicated below.

### **Containers**

Container classes are defined in the following header files (see Table 10.1). The associative containers multimap and multiset are defined in <map> and <set>, respectively. Similarly, priority\_queue and deque are defined in <queue>. (On some prestandardized implementations, the container adaptors stack, queue, and priority\_queue are in <stack.h>).

### **Table 10.1 STL Containers**

Header	Contents
<vector></vector>	An array of T
<li>st&gt;</li>	A doubly-linked list of T
<deque></deque>	A double-ended queue of T
<queue></queue>	A queue of T
<stack></stack>	A stack of T
<map></map>	An associative array of T
<set></set>	A set of T
 ditset>	A set of Boolean values

### **Algorithms**

STL generic algorithms can be applied to a sequence of elements. They are defined in the following header file (see Table 10.2). (On prestandardized implementations, generic algorithms are defined in <algo.h>).

### **Table 10.2 STL Algorithms**

Header	Contents
<algorithm></algorithm>	A collection of generic algorithms

### **Iterators**

Iterators are used to navigate sequences. They are defined in the following header file (see Table 10.3)

### **Table 10.3 STL Iterators**

Header	Contents
<iterator></iterator>	Various types of iterators and iterator support

## **Numeric Library**

STL provides several classes and algorithms that are specifically designed for numeric computations (see Table 10.4).

### **Table 10.4 Numeric Containers and Algorithms**

Header	Contents
<pre><complex></complex></pre>	Complex numbers and their associated operations
<valarray></valarray>	Mathematical vectors and their associated operations
<numerics></numerics>	Generalized numeric operations

### **Utilities**

The following headers define auxiliary components that are used in STL containers and algorithms (see Table 10.5). These include function adaptors, pairs, and class auto\_ptr (discussed later).

#### **Table 10.5 General Utilities**

Header	Contents
<utility></utility>	Operators and pairs
<functional></functional>	Function objects
<memory></memory>	Allocators and auto_ptr

# **Containers**

A container is an object that can hold other objects as its elements. A generic container is not confined to a specific type it can store objects of any kind. C supports one container type in the form of built-in arrays. Other languages support other data models. Pascal, for example, has a built-in set type, and Lisp supports lists (hence its name). C++ inherited from C its support for arrays. Arrays have several properties that more or less correspond to the mathematical notion of a vector: They can store any data type and they provide random access that is, the time needed to access any element is identical, regardless of the element's position.

Still, under some circumstances, arrays are less convenient than other data models; it is impossible to insert a new element in the middle of an array. Also, you cannot append new elements to the end of an array. With other data models, (a list, for example), it is possible to insert new elements in the middle of the container or to append elements to its end. A special type of list, a *heterogenic list*, can hold elements of different types at the same time.

### **Sequence Containers**

A sequence container organizes a collection of objects of the same type T into a strictly linear arrangement. Following are examples of sequence containers:

- $\mathbf{T}$   $\mathbf{v}[\mathbf{n}]$  A built-in array that stores a fixed number of n elements and provides random access to them.
- **std::vector**<**T**> An array-like container that stores a varying number of n elements and provides random access to them. Insertions and deletions at the end of a vector are constant time operations.
- **std::deque<T>** A double-ended queue that provides random access to a sequence of varying length, with constant time insertions and deletions at the beginning and the end.
- std::list<T> A list that provides linear time access to a sequence of varying length, with constant time insertions and deletions at any position.

Interestingly, built-in arrays are considered sequence containers because STL algorithms are designed to work with them as they work with other sequence types.

# **Requirements for STL Containment**

Elements of STL containers must be *copy-constructible* and *assignable*. Essentially, copy-constructible means that an object and a copy of that object must be identical (although the formal definition in the Standard is somewhat more complicated than that). Likewise, assignable means that assigning one object to another results in two identical objects. These definitions might sound trivial because objects in general are copy-constructible and assignable; later,

however (when class auto\_ptr is discussed), you will see an example of an object that does not meet these requirements and is, therefore, not to be stored in STL containers.

An additional requirement is that container elements must have their copy constructor, default constructor, assignment operator, and destructor publicly declared (either explicitly or implicitly).

### The vector Container Class

The standard containers share a common interface, but each container also defines particular operations. Following is the interface of class vector<T>:

```
namespace std {
       template <class T, class Allocator = allocator<T> >
       class vector {
       public:
         // implementation-defined types
         typedef implementation defined
                                                       iterator;
         typedef implementation defined
                                                       const_iterator;
         typedef implementation defined
                                                       size_type;
         typedef implementation defined
                                                       difference_type;
         // additional types
         typedef typename Allocator::reference
                                                       reference;
         typedef typename Allocator::const_reference
                                                       const_reference;
         typedef T value_type;
         typedef Allocator
                                                       allocator_type;
         typedef typename Allocator::pointer
                                                       pointer;
         typedef typename Allocator::const_pointer
                                                       const_pointer
         typedef std::reverse_iterator<iterator>
                                                       reverse_iterator;
         typedef std::reverse_iterator<const_iterator> const_reverse_iterator;
         // construction, copying destruction and assignment operations
         explicit vector(const Allocator& = Allocator());
         explicit vector(size_type n, const T& value = T(),
                              const Allocator& = Allocator());
         template <class InputIterator>
           vector(InputIterator first, InputIterator last,
             const Allocator& = Allocator());
        vector(const vector<T,Allocator>& x);
        ~vector();
        vector<T,Allocator>& operator=(const vector<T,Allocator>& x);
         template <class InputIterator>
           void assign(InputIterator first, InputIterator last);
        void assign(size_type n, const T& u);
         allocator_type get_allocator() const;
         //iterators
         iterator
                                begin();
         const_iterator
                                begin() const;
         iterator
                                end();
         const iterator
                                end() const;
                           rbegin();
         reverse_iterator
         const_reverse_iterator rbegin() const;
         reverse_iterator
                           rend();
```

```
const_reverse_iterator rend() const;
  //capacity operations
  size_type size() const;
  size_type max_size() const;
           resize(size_type sz, T c = T());
  size_type capacity() const;
 bool empty() const;
 void
        reserve(size_type n);
  //element access operations
  reference operator[](size_type n);
  const_reference operator[](size_type n) const;
  const_reference at(size_type n) const;
 reference at(size type n);
 reference front();
  const reference front() const;
 reference back();
  const_reference back() const;
  // modifiers
 void push_back(const T& x);
 void pop_back();
  iterator insert(iterator position, const T& x);
           insert(iterator position, size_type n, const T& x);
  template <class InputIterator>
      void insert(iterator position,
                  InputIterator first, InputIterator last);
  iterator erase(iterator position);
  iterator erase(iterator first, iterator last);
          swap(vector<T,Allocator>&);
 void
          clear();
}; //class vector
//non-member overloaded operators
template <class T, class Allocator>
 bool operator==(const vector<T,Allocator>& x,
                 const vector<T,Allocator>& y);
template <class T, class Allocator>
 bool operator< (const vector<T,Allocator>& x,
                 const vector<T,Allocator>& y);
template <class T, class Allocator>
 bool operator!=(const vector<T,Allocator>& x,
                  const vector<T,Allocator>& y);
template <class T, class Allocator>
 bool operator> (const vector<T,Allocator>& x,
                  const vector<T,Allocator>& y);
template <class T, class Allocator>
 bool operator>=(const vector<T,Allocator>& x,
                  const vector<T,Allocator>& y);
template <class T, class Allocator>
 bool operator <= (const vector < T, Allocator > & x,
                  const vector<T,Allocator>& y);
//specialized algorithms
template <class T, class Allocator>
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming

void swap(vector<T,Allocator>& x, vector<T,Allocator>& y);
}//namespace std
```

On most implementations, the parameterized types size\_type and difference\_type have the default values size\_t and ptrdiff\_t, respectively. However, they can be replaced by other types for particular specializations.

The storage of STL containers automatically grows as necessary, freeing the programmer from this tedious and error-prone task. For example, a vector can be used to read an unknown number of elements from the keyboard:

```
#include <vector>
#include <iostream>
using namespace std;
int main()
{
  vector <int> vi;
  for (;;) //read numbers from a user's console until 0 is input
  {
    int temp;
    cout<<"enter a number; press 0 to terminate" <<endl;
    cin>>temp;
    if (temp == 0 ) break; //exit from loop?
    vi.push_back(temp); //insert int into the buffer
  }
  cout<< "you entered "<< vi.size() <<" elements" <<endl;
  return 0;
}//end main</pre>
```

### **Container Reallocation**

The memory allocation scheme of STL containers must address two conflicting demands. On the one hand, a container should not preallocate large amounts of memory because it can impair the system's performance. On the other hand, it is inefficient to allow a container reallocate memory whenever it stores a few more elements. The allocation strategy has to walk a thin line. On many implementations, a container initially allocates a small memory buffer, which grows exponentially with every reallocation. Sometimes, however, it is possible to estimate in advance how many elements the container will have to store. In this case, the user can preallocate a sufficient amount of memory in advance so that the recurrent reallocation process can be avoided. Imagine a mail server of some Internet Service Provider: The server is almost idle at 4 a.m. At 9 a.m., however, it has to transfer thousands of emails every minute. The incoming emails are first stored in a vector before they are routed to other mail servers across the Web. Allowing the container to reallocate itself little by little with every few dozen emails can degrade performance.

### **What Happens During Reallocation?**

The reallocation process consists of four steps. First, a new memory buffer that is large enough to store the container is allocated. Second, the existing elements are copied to the new memory location. Third, the destructors of the elements in their previous location are successively invoked. Finally, the original memory buffer is released. Obviously, reallocation is a costly operation. You can avert reallocation by calling the member function reserve().reserve(n) ensures that the container reserves sufficient memory for at least n elements in advance, as in the following example:

```
class Message { /*...*/};
#include <vector>
using namespace std;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming

nt FillWithMessages(vector<Message>& msg gue); //severe time constrai
```

```
int FillWithMessages(vector<Message>& msg_que); //severe time constraints
int main()
{
   vector <Message> msgs;
   // before entering a time-critical section, make room for 1000 Messages
   msgs.reserve(1000);
//no re-allocation should occur before 1000 objects have been stored in vector
   FillWithMessages(msgs);
   return 0;
}
```

# capacity() and size()

capacity() returns the total number of elements that the container can hold without requiring reallocation.
size() returns the number of elements that are currently stored in the container. In other words, capacity() size() is the number of available "free slots" that can be filled with additional elements without reallocating. The
capacity of a container can be resized explicitly by calling either reserve() or resize(). These member
functions differ in two respects. resize(n) allocates memory for n objects and default-initializes them (you can
provide a different initializer value as the second optional argument).

reserve() allocates raw memory without initializing it. In addition, reserve() does not change the value that is returned from size() it only changes the value that is returned from capacity(). resize() changes both these values. For example

```
#include <iostream>
#include <vector>
#include <string>
using namespace std;
int main()
  vector <string> vs;
  vs.reserve(10);
                   //make room for at least 10 more strings
  vs.push_back(string()); //insert an element
  cout<<"size: "<< vs.size()<<endl; //output: 1</pre>
  cout<<"capacity: "<<vs.capacity()<<endl; //output: 10</pre>
  cout<<"there's room for "<<vs.capacity() - vs.size()</pre>
      <<" elements before reallocation"<<endl;</pre>
  //allocate 10 more elements, initialized each with string::string()
  vs.resize(20);
  cout<<"size: "<< vs.size()<<endl; //output 20</pre>
  cout<<"capacity: "<<vs.capacity()<<endl; //output 20;</pre>
  return 0;
```

# **Specifying the Container's Capacity During Construction**

Up until now, the examples in this chapter have used explicit operations to preallocate storage by calling either reserve() or resize(). However, it is possible to specify the requested storage size during construction. For example

```
#include <vector>
```

```
using namespace std;
int main()
{
  vector<int> vi(1000); //initial storage for 1000 int's
  //vi contains 1000 elements initialized by int::int()
  return 0;
}
```

Remember that reserve() allocates raw memory without initializing it. The constructor, on the other hand, initializes the allocated elements by invoking their default constructor. It is possible to specify a different initializer value, though:

```
vector<int> vi(1000, 4); //initial all 1000 int's with 4
```

## **Accessing a Single Element**

The overloaded operator [] and the member function at () enable direct access to a vector's element. Both have a const and a non-const version, so they can be used to access an element of a const and a non-const vector, respectively.

The overloaded [] operator was designed to be as efficient as its built-in counterpart. Therefore, [] does not check to see if its argument actually refers to a valid element. The lack of runtime checks ensures the fastest access time (an operator [] call is usually inlined). However, using operator [] with an illegal subscript yields undefined behavior. When performance is paramount, and when the code is written carefully so that only legal subscripts are accessed, use the [] operator. The [] notation is also more readable and intuitive. Nonetheless, runtime checks are unavoidable in some circumstances for instance, when the subscript value is received from an external source such as a function, a database record, or a human operator. In such cases you should use the member function at () instead of operator [].at() performs range checking and, in case of an attempt to access an out of range member, it throws an exception of type std::out\_of\_range. Here is an example:

```
#include <vector>
#include <iostream>
#include <stdexcept>
using namespace std;
int main()
{
   vector<string> vs; // vs has no elements currently
   vs.push_back("string"); //add first element
   vs[0] = "overriding string"; //override it using []
   try
   {
      cout<< vs.at(10) <<endl; //out of range element, exception thrown
   }
   catch(std::out_of_range & except)
   {
      // handle out-of-range subscript
   }
}//end main</pre>
```

### **Front and Back Operations**

Front and back operations refer to the beginning and the end of a container, respectively. The member function push\_back() appends a single element to the end of the container. When the container has exhausted its free storage, it reallocates additional storage, and then appends the element. The member function pop\_back() removes the last element from the container. The member functions front() and back() access a single element at the container's beginning and end, respectively. front() and back() both have a const and a non-const version. For example

```
#include <iostream>
#include <vector>
using namespace std;
int main()
{
   vector <short> v;
   v.push_back(5);
   v.push_back(10);
   cout<<"front: " << v.front() << endl; //5
   cout<<"back: " << v.back() << endl; //10
   v.pop_back(); //remove v[1]
   cout<<"back: " << v.back() << endl; //now 5
   return 0;
}</pre>
```

# **Container Assignment**

STL containers overload the assignment operator, thereby allowing containers of the same type to be assigned easily. For example

```
#include <iostream>
#include<vector>
using namespace std;
int main()
{
   vector <int> vi;
   vi.push_back(1);
   vi.push_back(2);
   vector <int> new_vector;
   //copy the contents of vi to new_vector, which automatically grows as needed new_vector = vi;
   cout << new_vector[0] << new_vector[1] << endl;   // display 1 and 2
   return 0;
}</pre>
```

## **Contiguity of Vectors**

Built-in arrays in C++ reside in contiguous chunks of memory. The Standard, however, does not require that vector elements occupy contiguous memory. When STL was added to the Standard, it seemed intuitive that vectors should store their elements contiguously, so contiguity never became an explicit requirement. Indeed, all current STL implementations follow this convention. The current specification, however, permits implementations that do not use

contiguous memory. This loophole will probably be fixed by the Standardization committee in the future, and vector contiguity will become a Standard requirement.

### A vector<Base> Should not Store Derived Objects

Each element in a vector must have the same size. Because a derived object can have additional members, its size might be larger than the size of its base class. Avoid storing a derived object in a vector<Base> because it can cause object slicing with undefined results. You can, however, achieve the desired polymorphic behavior by storing a pointer to a derived object in a vector<Base\*>.

### **FIFO Data Models**

In a queue data model (a queue is also called FIFO first in first out), the first element that is inserted is located at the topmost position, and any subsequent elements are located at lower positions. The two basic operations in a queue are pop() and push(). A push() operation inserts an element into the bottom of the queue. A pop() operation removes the element at the topmost position, which was the first to be inserted; consequently, the element that is located one position lower becomes the topmost element. The STL queue container can be used as follows:

STL also defines a double-ended queue, or *deque* (pronounced "deck") container. A deque is a queue that is optimized to support operations at both ends efficiently. Another type of queue is a priority\_queue. A priority\_queue has all its elements internally sorted according to their priority. The element with the highest priority is located at the top. To qualify as an element of priority\_queue, an object has to define the < operator (priority\_queue is discussed in detail later, in the section titled "Function Objects").

# **Iterators**

*Iterators* can be thought of as generic pointers. They are used to navigate a container without having to know the actual type of its elements. Several member functions such as begin() and end() return iterators that point to the ends of a container.

## begin() and end()

All STL containers provide the begin() and end() pair of member functions. begin() returns an iterator that points to the first element of the container. For example

The member function end(), on the other hand, returns an iterator that points one position *past* the last valid element of the container. This sounds surprising at first, but there's nothing really unusual about it if you consider how C-strings are represented: An additional null character is automatically appended one position past the final element of the char array. The additional element in STL has a similar role it indicates the end of the container. Having end() return an iterator that points one position past the container's elements is useful in for and while loops. For example

```
vector <int> v(10);
int n=0;
for (vector<int>::iterator p = v.begin(); p<v.end(); p++)
  *p = n++;</pre>
```

begin() and end() come in two versions: const and non-const. The non-const version returns a *non-const iterator*, which enables the user to modify the values of the container's element, as you just saw. The const version returns a *const iterator*, which cannot modify its container.

For example

```
const vector <char> v(10);
vector<char>::iterator p = v.begin(); //error, must use a const_iterator
vector<char>::const_iterator cp = v.begin(); //OK
*cp = 'a'; //error, attempt to modify a const object
cout << *cp; //OK</pre>
```

The member functions rbegin() and rend() (reverse begin() and reverse end()) are similar to begin() and end(), except that they return *reverse iterators*, which apply to reverse sequences. Essentially, reverse iterators are ordinary iterators, except that they invert the semantics of the overloaded ++ and -- operators. They are useful when the elements of a container are accessed in reverse order.

For example

```
#include <iostream>
#include <vector>
```

```
#include <string>
using namespace std;
void ascending_order()
{
   vector <double> v(10);
   double d = 0.1;
   for (vector<double>::iterator p = v.begin(); p<v.end(); p++) //initialize
   {
      *p = d;
      d+= 0.1;
   }
   //display elements of v in ascending order
   for (vector<double>::reverse_iterator rp = v.rbegin(); rp < v.rend(); rp++)
   {
      cout<< *rp<<endl;
   }
}</pre>
```

Like begin() and end(), rbegin() and rend() have a const and a non-const version.

## The Underlying Representation of Iterators

Most implementations of STL use pointers as the underlying representation of iterators. However, an iterator need not be a pointer, and there's a good reason for that. Consider a huge vector of scanned images that are stored on a 6GB disk; the built-in pointer on most machines has only 32 bits, which is not large enough to iterate through this large vector. Instead of a bare pointer, an implementation can use a 64-bit integer as the underlying iterator in this case. Likewise, a container that holds elements such as bits and nibbles (to which built-in pointers cannot refer) can be implemented with a different underlying type for iterators and still provide the same interface. However, bare pointers can sometimes be used to iterate through the elements of a container on certain implementations; for example

```
#include <vector>
#include <iostream>
using namespace std;

void hack()
{
   vector<int> vi;
   vi.push_back(5);
   int *p = vi.begin();//bad programming practice, although it may work
   *p = 6; //assign vi[0]
   cout<<vi[0]; //output 6 (maybe)
}</pre>
```

Using bare pointers instead of iterators is a bad programming practice avoid it.

#### "const Correctness" of Iterators

Use the const iterator of a container when the elements that are accessed through it are not to be modified. As with ordinary pointer types, using a non-const iterator implies that the contents of the container are to be changed. A const iterator enables the compiler to detect simple mistakes, and it is more readable.

#### Initializing a Vector with the Contents of a Built-in Array

As was previously noted, built-in arrays are valid sequence containers. Thus, the addresses of array ends can be used as iterators to initialize a vector with the contents of a built-in array. For example

#### **Iterator Invalidation**

Reallocation can occur when a member function modifies its container. Modifying member functions are reserve() and resize(), push\_back() and pop\_back(), erase(), clear(), insert(), and others. In addition, assignment operations and modifying algorithms can also cause reallocation. When a container reallocates its elements, their addresses change. Consequently, the values of existing iterators are invalidated.

For example

In the preceding example, payroll might have reallocated itself during the insertion of ten additional elements, thereby invalidating the value of p. Using an invalid iterator is similar to using a pointer with the address of a deleted object both result in undefined behavior. To be on the safe side, it is recommended that you reassign the iterator's value after calling a modifying member function. For example

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming
```

```
list<double>::const_iterator p = payroll.begin();//points to the first element
for (int i = 0 ; i < 10; i++)
{
    payroll.push_back(4500.00); // reallocation may occur here
}
    p = payroll.begin(); // reassign p
    cout <<"first element in payroll: "<<*p<<endl; // now safe
}</pre>
```

Alternatively, you can prevent reallocation by preallocating sufficient storage before the instantiation of an iterator. For example

```
int main()
{
    list <double> payroll;
    payroll.reserve(11);
    payroll.push_back(5000.00);
    list<double>::const_iterator p = payroll.begin();
    for (int i = 0 ; i < 10; i++)
    {
        payroll.push_back(4500.00); //no reallocation
    }
    cout << "first element in payroll: "<< *p <<endl; // OK return 0;
}</pre>
```

# **Algorithms**

STL defines a rich collection of generic algorithms that can be applied to containers and other sequences. There are three major categories of algorithms: non-modifying sequence operations, mutating sequence operations, and algorithms for sorting.

#### **Non-Modifying Sequence Operations**

Non-modifying sequence operations are algorithms that do not directly modify the sequence on which they operate. They include operations such as search, checking for equality, and counting.

#### The find() Algorithm

The generic algorithm find() locates an element within a sequence. find() takes three arguments. The first two are iterators that point to the beginning and the end of the sequence, respectively.

The third argument is the sought-after value. find() returns an iterator that points to the first element that is identical to the sought-after value. If find() cannot locate the requested value, it returns an iterator that points one element past the final element in the sequence (that is, it returns the same value as end() does). For example

```
#include <algorithm> // definition of find()
#include <list>
#include <iostream>
using namespace std;
int main()
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming
{
    list < char > lc;
    lc.push_back('A');
    lc.push_back('T');
    lc.push_back('L');
    list < char > :: iterator p = find(lc.begin(), lc.end(), 'A'); // find 'A'
    if (p != lc.end()) // was 'A' found?
        *p = 'S'; // then replace it with 'S'
    while (p != lc.end()) // display the modified list
        cout < < *p++;
    return 0;
}</pre>
```

#### **Mutating Sequence Operations**

Mutating sequence algorithms modify the sequence on which they operate. They include operations such as copy, fill, replace, and transform.

#### The copy() Algorithm

The Standard Library provides a generic copy function, which can be used to copy a sequence of objects to a specified target. The first and the second arguments of copy() are const iterators that mark the sequence's beginning and its end, respectively. The third argument points to a container into which the sequence is copied. The following example demonstrates how to copy the elements of a list into a vector:

```
#include <algorithm>
#include<list>
#include<vector>
using namespace std;
int main()
{
    list<int> li; vector <int> vi;
    li.push_back(1);
    li.push_back(2);
    vi.reserve( li.size() ); //must make room for copied elements in advance
    //copy list elements into vector, starting at vector's beginning
    copy (li.begin(), li.end(), vi.begin() );
    return 0;
}
```

#### **Sort Operations**

This category contains algorithms for sorting and merging sequences and set-like algorithms that operate on sorted sequences. These include sort(), partial\_sort(), binary\_search(), lower\_bound(), and many others.

#### The sort() Algorithm

sort() takes two arguments of type const iterator that point to the beginning and the end of the sequence, respectively. An optional third algorithm is a *predicate object*, which alters the computation of sort (predicate objects and adaptors are discussed shortly). For example

```
#include <iostream>
#include <algorithm> //definition of sort()
#include <vector>
using namespace std;
int main()
{
   vector <int> vi;
   vi.push_back(7);
   vi.push_back(1);
   vi.push_back(1);
   vi.push_back(19);
   sort(vi.begin(), vi.end() );   // sort vi; default is ascending order
   cout<< vi[0] <<", "<< vi[1] <<", "<< vi[2] <<endl;   // output: 1, 7, 19
   return 0;
}</pre>
```

One way to force a descending order is to use reverse iterators:

```
sort(vi.rbegin(), vi.rend() ); // now sort in descending order
cout<< vi[0] <<", "<<vi[1]<<", "<<vi[2]<<endl; // output: 19, 7, 1</pre>
```

#### **Requirements for Sorting Containers**

When sort () operates on a container, it uses the relational operators == and < of the container's elements. User-defined types that do not support these operators can still be stored in a container, but such a container cannot be sorted.

# **Function Objects**

It is customary to use a function pointer to invoke a callback routine. In an object-oriented environment, nonetheless, a function can be encapsulated in a *function object* (see also Chapter 3, "Operator Overloading"). There are several advantages to using a function object, or *functor*, instead of a pointer. Function objects are more resilient because the object that contains the function can be modified without affecting its users. In addition, compilers can inline a function object, which is nearly impossible when function pointers are used. But perhaps the most compelling argument in favor of function objects is their genericity a function object can embody a generic algorithm by means of a member template.

#### **Implementation of Function Objects**

A function object overloads the function call operator. A generic function object defines the overloaded function call operator as a member function template. Consequently, the object can be used like a function call. Remember that the overloaded operator () can have a varying number of arguments, and any return value. In the following example, a function object implements a generic negation operator:

```
#include <iostream>
#include <vector>
using namespace std;
class negate
{
public : //generic negation operator
  template < class T > T operator() (T t) const { return -t;}
```

#### **Uses of Function Objects**

Some container operations use function objects. For example, a priority\_queue uses the less function object to sort its elements internally. The following example demonstrates a scheduler that stores tasks with different priorities in a priority\_queue. Tasks that have higher priority are located at the top. Tasks with identical priority are located according to the order of their insertion, as in an ordinary queue:

```
#include <functional> // definition of less
#include <queue> // definition of priority_queue
#include <iostream>
using namespace std;
struct Task
  int priority;
 friend bool operator < (const Task& t1, const Task& t2);
 Task(int p=0) : priority(p) {}
};
bool operator < (const Task& t1, const Task& t2)
 return t1.priority < t2.priority;
int main()
 priority_queue<Task> scheduler;
 scheduler.push(Task(3));
 scheduler.push(Task(5));
  scheduler.push(Task(1));
  scheduler.push(Task(1));
  cout<< scheduler.top().priority <<endl; // output 5</pre>
 return 0;
```

#### **Predicate Objects**

A predicate is an expression that returns a Boolean value. Similarly, a function object that returns a Boolean value is a *predicate object*. STL defines several predicate objects that can be used to alter the computation of a generic algorithm. These predicate objects are defined in the header <functional>. In a previous example, you saw the operation of the algorithm sort(). The third argument of sort() is a predicate that alters the computation of this

algorithm. For example, the predicate greater<int> can be used to override the default ascending order. Likewise, the predicate less<int> restores the original ascending order:

```
#include <functional> //definitions of STL predicates
#include <algorithm> //definition of sort
#include <vector>
#include <iostream>
using namespace std;
int main()
 vector <int> vi;
 vi.push_back(9);
 vi.push_back(5);
 vi.push_back(10);
  sort(vi.begin(), vi.end(), greater<int> () ); // descending order
  cout << vi[0] << '\t' << vi[1] << '\t' << vi[2] << endl;
                                                            // output: 10
                                                                              5
  sort(vi.begin(), vi.end(), less<int> () ); // now in ascending order
  cout << vi[0] << '\t' << vi[1] << '\t' << vi[2] << endl; // output: 5
                                                                             10
  return 0;
```

# **Adaptors**

An adaptor is a component that modifies the interface of another component. STL uses several types of adaptors: sequence adaptors, iterator adaptors, and function adaptors.

#### **Sequence Adaptors**

A sequence adaptor is a container that is built upon another container and that modifies its interface. For example, the container stack is usually implemented as a deque, whose non-stack operations are hidden. In addition, stack uses the operations back(), push\_back(), and pop\_back() of a deque to implement the operations top(), push(), and pop(), respectively. For example

```
#include <stack>
#include <iostream>
using namespace std;
int main()
{
    stack <string> strstack;
    strstack.push("Bjarne");
    strstack.push("Stroustrup");
    string topmost = strstack.top();
    cout<< "topmost element is: "<< topmost << endl; // "Stroustrup"
    strstack.pop();
    cout<< "topmost element is: "<< strstack.top() << endl; // "Bjarne"
    return 0;
}</pre>
```

Calling the member function pop () on an empty stack is an error. If you are not sure whether a stack contains any

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming

elements, you can use the member function empty() to check it first. For example

```
stack<int> stk;
//...many lines of code
if (!stk.empty() ) //test stack before popping it
{
    stk.pop();
}
```

#### **Iterator Adaptors**

The interface of an iterator can be altered by an *iterator adaptor*. The member functions rend() and rbegin() return reverse iterators, which are iterators that have the meanings of operators ++ and -- exchanged. Using a reverse iterator is more convenient in some computations.

#### **Function Adaptors**

Earlier you saw the use of greater as a function adaptor for changing the computation of sort(). STL also provides *negators*, which are used to reverse the result of certain Boolean operations. *Binders* are another type of adaptors, which convert a binary function object into a unary function object by binding an argument to a specific value.

## **Allocators**

Every STL container uses an allocator that encapsulates the memory model that the program uses. Allocators hide the platform-dependent details such as the size of pointers, memory organization, reallocation model, and memory page size. Because a container can work with different allocator types, it can easily work in different environments simply by plugging a different allocator into it. An implementation provides a suitable allocator for every container. Normally, users should not override the default allocator.

# **Specialized Containers**

Chapter 9, "Templates," discussed the benefits of defining template specializations to optimize and rectify the behavior of a primary template for a particular type. vector has a specialized form that manipulates Boolean values optimally, namely vector<br/>bool>. This specialization is implemented in a way that squeezes each element into a single bit, rather than a bool variable, albeit with the familiar vector interface. For example

```
#include <vector>
#include <iostream>
using namespace std
void transmit(vector <bool> &binarystream)
{
   cout<<binarystream[0]; // subscript operator provided
   vector<bool>::const_iterator bit_iter = binarystream.begin(); //iterators
   if (binarystream[0] == true)
   {/* do something */ }
}
```

## **Associative Containers**

An associative array is one for which the index need not be an integer. An associative array is also called *map* or dictionary. STL defines several associative containers. A map, for instance, stores pairs of values; one serves as the key, and the other is the associated value. The template pair<class Key, class Value> serves as a map element. In the following example, a map is used to translate the string value of an enumerator into its corresponding integral value. The string is the key whose associated value is an int:

```
#include <map>
#include <iostream>
#include <iostream>
using namespace std;
enum directions {up, down};
int main()
{
   pair<string, int> Enumerator(string("down"), down); //create a pair map<string, int> mi; //create a map
   mi.insert(Enumerator); //insert the pair
   int n = mi["down"]; //n = 1 //string used as subscript
   return 0;
}
```

A map can store only unique keys. A multimap is a map that can store duplicate keys.

set is similar to a map except that the associated values are irrelevant in this case. A set is used when only the keys are important: to ensure that a database transaction does not attempt to insert a record with a unique key that already exists in a table, for example. multiset is a set that allows duplicate keys.

# Class auto\_ptr

The class template auto\_ptr implements the "resource acquisition is initialization" idiom (discussed in Chapter 5, "Object-Oriented Programming Design"). It is initialized by a pointer to an object allocated on the free store (auto\_ptr has a default constructor so you can instantiate an empty auto\_ptr and assign a pointer to it later). The destructor of auto\_ptr destroys the object that is bound to the pointer. This technique can avoid memory leakage in the case of exceptions (see also Chapter 6, "Exception Handling"), or it can simplify programming by sparing the hassle of explicitly deleting every object allocated on the free store. Class auto\_ptr is declared in the standard header <memory>. Following is an example of using auto\_ptr (points of possible object destruction are numbered):

```
#include <memory>
using namespace std;
void f() { if (condition) throw "err";}
int main()
{
   try
   {
    auto_ptr<double> dptr(new double(0.0));
    *dptr = 0.5; //overloaded * provides pointer-like syntax
   f();
   } // 1: no exception was thrown, dptr destroyed here
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming catch(...)
{ // 2: an exception was thrown, dptr destroyed here }
return 0;
```

It is guaranteed that the memory that was allocated from the free store is released: If f() throws an exception, the dptr object is destroyed during stack unwinding (2) and, as a result, the memory that was allocated from the free store is released. Otherwise, dptr is destroyed when the try block exits (1).

#### STL Containers Should not Store auto\_ptr Elements

Elements of STL containers must be copy-constructible and assignable, as was noted previously. During reallocation, a container copy-constructs its elements in a new memory location and destroys the original elements by invoking their destructor. However, an auto\_ptr is not copy-constructible. Rather, it provides *strict ownership* semantics, which means that it owns the object to which it holds a pointer (ownership is also discussed in Chapter 5). Copying an auto\_ptr object copies that pointer and transfers ownership to the destination. This stands in contrast to the copy-constructible and assignable requirements: One copy of auto\_ptr holds a pointer to the free store object, whereas the other copy doesn't. (If more than one auto\_ptr owns the same object at the same time, the results are undefined.) Therefore, auto\_ptr objects are not to be stored in STL containers.

# **Nearly Containers**

STL defines three additional components that behave, in many ways, like ordinary containers. They have automatic memory management, they have iterators, and they share a container-like interface with member functions such as begin() and end(). Still, they are not considered "first-class citizens" in the STL catalog because they are not generic. A string is similar to vector but is confined to char data type. valarray resembles vector, albeit with a strong bias toward numerical computations. The third class in this category is bitset, which is a set designed to store and manipulate bits in an efficient way. These *nearly containers* have a limited use for general purposes, except for string.

# **Class string**

std::string is a shorthand for std::basic\_string<char>, as you saw in Chapter 9. string provides many of the operations of ordinary STL containers; for example, it conforms to the requirements of a sequence and it defines iterators. However, string is optimized for the use of a character string exclusively.

The consideration in the design of string included utmost efficiency, support for C-strings, and generality (that is, string is not targeted for a particular application use).

#### **Constructors**

string has a default constructor and five more constructors:

In other words, a string can be initialized by a C-string, by another string object, by part of a C-string, by a sequence of characters, or by part of another string. Following are some examples:

It is important to note that when the initializer is a pointer to char, string does not check the pointer. It is the programmer's responsibility to ensure that the pointer is valid and that it is not NULL. Otherwise, the results are undefined. For example

```
#include<string>
using std::string;
const char * getDescription(int symbol); // may return a NULL pointer
string& writeToString (int symbol)
{
    // sloppy: initializer might be NULL; undefined behavior in this case
    string *p = new string(getDescription(symbol));
    return *p;
}
```

string does not check for a NULL pointer to avoid the incurred performance overhead. Remember that standard C functions such as strcpy() avoid this overhead too. Even if string did check the char pointer, it is unclear what it is to do in the case of a NULL value. Clearly, a NULL pointer is not a valid C-string, so creating an empty string is incorrect. Throwing an exception is perhaps a plausible approach, but it incurs additional runtime overhead and is not always desirable.

A safer implementation of the preceding example might check the initializing pointer to make sure that it is not

**}**;

```
NULL:
string& writeToString (int symbol)
{
  const char *p = getDescription(symbol);
  if (p) // now safe
  {
    string *pstr = new string(p);
    return *pstr;
  }
  return *new string;
}
```

#### **Conversion to a C-string**

Class string provides two member functions that return the const char \* representation of its object. The following sections discuss these member functions.

#### The c\_str() Member Function

string does not define a char \* conversion operator. There are two reasons for this. First, implicit conversions can cause undesirable surprises when you least expect it (refer to Chapter 3). Another reason is that C-strings must be null-terminated. The underlying representation of a string object is implementation-dependent and might not use a null-terminated sequence. Therefore, an implicit conversion of a string object in a context that requires a null-terminated array of characters can be disastrous. For these reasons, string does not provide such a conversion operator. Instead, an explicit call to string::c\_str() is required. c\_str() returns the const\_char \* representation of its object. For example

```
void f()
{
  string s = "Hello";
  if( strcmp( s.c_str(), "Hello")== 0)
   cout <<"identical"<<endl;
  else
   cout<<"different"<<endl;
}</pre>
```

The pointer that is returned from c\_str () is owned by the string object. The user should not attempt to delete it or to modify its associated char array. The returned pointer is not to be used after a non-const member function has been called.

#### The data() Member Function

The member function data() also returns a const char \* representation of its object (but the resultant array might not be null-terminated).

#### **Accessing a Single Element**

There are two ways to access a single character from a string object. One is to use the overloaded operator [], as in the following example:

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming
```

```
#include <string>
using namespace std;
void first()
{
  string s = "hello world";
  char c = s[0]; //assign 'h'
}
```

Another way is to use the member function at (). Similar to class vector, string::at() performs range-checking and throws an exception of type std::out\_of\_range when an attempt is made to access an out-of-range character.

## Clearing the Contents of A string

To explicitly erase the contents of a string, you can use the member function erase (). For example

```
#include <iostream>
#include <string>
using namespace std;
void f()
{
  char key;
  string msg = "press any key to continue";
  cout<<msg<<endl;
  cin<<key;
  msg.erase(); //clear msg
}</pre>
```

#### Comparison

string defines three versions of operator ==:

```
bool operator == (const string& left, const string right);
bool operator == (const char* left, const string right);
bool operator == (const string& left, const char* right);
```

This proliferation might seem redundant because string has a constructor that automatically converts a const char \* to a string object. Therefore, only the first version of operator == is necessary. However, the overhead of creating a temporary string can be unacceptable under some circumstances: The temporary string has to allocate memory on the free store, copy the C-string, and then release the allocated memory. The Standardization committee's intent was to make comparison of strings as efficient as possible. Therefore, the additional versions of operator == were added to enable efficient comparisons.

#### **Additional Overloaded Operators**

As was previously noted, a string can be assigned another string, a C-string, or a single character. Similarly, there are three versions of the overloaded operator += that support concatenation of another string, a C-string, or a single character to an existing string. For example

```
#include <string>
using namespace std;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming
```

```
void f()
{
   string s1 = "ab"
   string s2= "cd";
   s1+=s2;
   s1+= "ef";
   s1+='g';
}
```

string also defines an overloaded + that returns a string that concatenates its operands. Similarly, the operators < and > perform a lexicographical comparison between their operands.

#### **Performance Issues**

string is probably the most widely used class in C++ programs. The efficiency of its design and implementation were cardinal. For example, string provides optimized container operations such as find(), copy(), and replace() that are specifically designed to manipulate characters efficiently. In some respects, string objects are even more efficient than char \* in terms of speed and space. The following sections discuss two aspects of string's performance: size computation and reference counting.

#### Size

string has a data member that holds its size. Calculating the size of a string object is, therefore, a fast constant time operation. On the other hand, the performance of strlen() is proportional to the number of characters that are stored in a C-string. When large strings are used and size computations are frequent, std::string is more efficient than a C-string.

#### Reference Counting

In a nutshell, a reference counted model counts how many instances of a class have an identical state. When two or more instances share the same state, the implementation creates only a single copy and counts the number of existing references to this copy. For example, an array of strings can be represented as a single string object that holds the number of elements in the array (reference counting is not confined to arrays). Since initially the array elements share the same state (they all are empty strings), only a single object is needed. When one of the array elements changes its state (if it is assigned a different value, for instance), the existing object creates one more object this is called "copy on write". As you can see, the reference counting model can enhance performance in terms of both memory usage and speed. The Standard's specification of class string is formulated to allow but it does not require a reference counted implementation.

A reference counted implementation must have the same semantics as a non-reference counted implementation. For example

```
string str1("xyz");
string::iterator i = str1.begin();
string str2 = str1;
*i = 'w'; //must modify only str1
```

## **Conclusions**

STL was designed to allow maximal reusability without sacrificing efficiency. The Standard specifies performance requirements with which STL containers and algorithms must comply. These performance specifications are the

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 10 - STL and Generic Programming

minimum requirements; an implementation might offer better performance.

The plug compatibility of STL components, which enables the user to create other components or to modify the interface of existing components, is remarkable. Other frameworks and libraries impose severe constraints on the use of their components, considerably limiting their plug-compatibility.

STL is regarded by C++ creators as the most important addition to the language in recent years. Mastering STL is a worthwhile investment. It is estimated that other programming languages will follow the role model of STL and provide similar generic frameworks. Three major advantages of preferring STL to homemade containers are

- **Portability** All standard-compliant C++ implementations supply them.
- **Performance** STL components were designed and implemented to meet strict efficiency demands.
- Reliability STL containers and algorithms were already debugged and tested.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

## 11

# **Memory Management**

#### by Danny Kalev

- Introduction
- Types of Storage
  - Automatic Storage
  - o Static Storage
  - Free Store
- POD (Plain Old Data) and non-POD Objects
- The Lifetime of a POD Object
- The Lifetime of a non-POD Object
- Allocation and Deallocation Functions
  - Semantics of Allocation Functions
  - Semantics of Deallocation Functions
- malloc() and free() Versus new and delete
  - Support For Object Semantics
  - o <u>Safety</u>
  - o Extensibility
- new and delete
  - Allocating and Deallocating Arrays Using new[] and delete[]
  - Exceptions and Operator new
  - o Exception-Free Version of Operator new
  - o Placement new
- Exceptions During Object Construction
- Alignment Considerations

- Member Alignment
- The Size Of A Complete Object Can Never Be Zero
- User-Defined Versions of new and delete Cannot Be Declared in a Namespace
- Overloading new and delete in a Class
- Guidelines for Effective Memory Usage
  - Prefer Automatic Storage to Free Store Whenever Possible
  - Correct Syntax for Local Object Instantiation
  - o Zero As A Universal Initializer
  - Always Initialize Pointers
- Explicit Initializations of POD Object
  - o Initializing Local Automatic Structs and Arrays
  - Union Initialization
  - o Detecting a Machine's Endian
  - o The Lifetime Of A Bound Temporary Object
  - o Deleting A Pointer More Than Once
- Data Pointers Versus Function Pointers
- Pointer Equality
- Storage Reallocation
- Local Static Variables
- Global Anonymous Unions
- The const and volatile Properties of an Object
- Conclusions

## Introduction

C++ added the necessary language constructs to the memory model of C to support object semantics. In addition, it fixed some loopholes in the original model and enhanced it with higher levels of abstraction and automation. This chapter delves into the memory model of C++, starting with the three types of data storage. Next, the various versions of operators new and delete are discussed; finally, some techniques and guidelines for effective and bug-free usage of the memory management constructs are presented.

## **Types of Storage**

C++ has three fundamental types of data storage: automatic storage, static storage, and free store. Each of these memory types has different semantics of object initialization and lifetime.

#### **Automatic Storage**

Local objects that are not explicitly declared static or extern, local objects that are declared auto or register, and function arguments have *automatic storage*. This type of storage is also called *stack memory*. Automatic objects are created automatically upon entering a function or a block. They are destroyed when the

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management

function or block exits. Thus, on each entry into a function or a block, a new copy of its automatic objects is created. The default value of automatic variables and nonclass objects is indeterminate.

#### **Static Storage**

Global objects, static data members of a class, namespace variables, and static variables in functions reside in static memory.

The address of a static object remains the same throughout the program's execution.

Every static object is constructed only once during the lifetime of the program. By default, static data are initialized to binary zeros. Static objects with a *nontrivial constructor* (see Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, And Assignment Operator") are subsequently initialized by their constructors. Objects with static storage are included in the following examples:

```
int num; //global variables have static storage
int func()
{
   static int calls; //initialized to 0 by default
   return ++calls;
}
class C
{
   private:
    static bool b;
};
namespace NS
{
   std::string str; //str has static storage
}
```

#### **Free Store**

Free store memory, also called *heap memory* or *dynamic memory*, contains objects and variables that are created by operator new. Objects and variables that are allocated on the free store persist until they are explicitly released by a subsequent call to operator delete. The memory that is allocated from the free store is not returned to the operating system automatically after the program's termination.

Therefore, failing to release memory that was allocated using new generally yields memory leaks. The address of an object that is allocated on the free store is determined at runtime. The initial value of raw storage that is allocated by new is unspecified.

# POD (Plain Old Data) and non-POD Objects

A *POD* (*plain old data*) object has one of the following data types: a fundamental type, pointer, union, struct, array, or class with a trivial constructor. Conversely, a non-POD object is one for which a nontrivial constructor exists. The properties of an object are in effect only during its *lifetime*.

# The Lifetime of a POD Object

A POD object begins its lifetime when it obtains storage with the proper alignment and size for its type, and its lifetime ends when the storage for the object is either reused or deallocated.

## The Lifetime of a non-POD Object

A non-POD object begins its lifetime after the constructor call has completed; its lifetime ends when its destructor has started.

## **Allocation and Deallocation Functions**

C++ defines the global *allocation functions* new and new[] as well as the corresponding global *deallocation* functions delete and delete[]. These functions are accessible from each translation unit of a program without including the header <new>. Their implicit declarations are as follows:

```
void* operator new(std::size_t) throw(std::bad_alloc); // new
void* operator new[](std::size_t) throw(std::bad_alloc); // new []
void operator delete(void*) throw(); // delete
void operator delete[](void*) throw(); // delete[]
```

The implicit declarations introduce only the function names operator new, operator new[], operator delete, and operator delete[]. However, they do not introduce the names std, std::bad\_alloc, and std::size\_t. An explicit reference to any of these names requires that the appropriate header file be included. For example

```
#include <new> // declarations of std and size_t
using namespace std;
char * allocate (size_t bytes);
int main
{
   char * buff = allocate(sizeof (char) );
   return 0;
}
```

#### **Semantics of Allocation Functions**

The return type of an allocation function is void \*, and its first parameter is of type size\_t. The value of the first parameter is interpreted as the requested memory size. The allocation function attempts to allocate the requested size of memory from the free store. If the allocation request is successful, it returns the address of the start of a block of storage whose size, in bytes, is at least as large as the requested size.

#### **Semantics of Deallocation Functions**

The return type of a deallocation function is void; its first parameter is of type void \*. A deallocation function can have more than one parameter. The value of the first argument that is supplied to a deallocation function can be NULL (in this case, the deallocation function call has no effect). Otherwise, the value supplied to a deallocation function must be one of the values returned by a previous invocation of a corresponding allocation function. Allocation and deallocation functions perform the basic operations of allocating memory from the free store and releasing it. Note however, that in general, you do not invoke these functions directly. Rather, you use a *new expression* and a *delete* 

expression. A new expression implicitly invokes an allocation function and then constructs an object on the allocated memory; likewise, a delete expression destroys an object, and then it invokes a deallocation function to release the storage of the destroyed object.

**NOTE:** In the following sections, new and delete refer to a new expression and a delete expression, respectively, unless stated otherwise.

# malloc() and free() Versus new and delete

C++ still supports the standard C library functions malloc() and free(). The backward compatibility with C is useful in three cases: for combining legacy code that was originally written in C in C++ programs, for writing C++ code that is meant to be supported in C environment (more on this in Chapter 13, "C Language Compatibility Issues"), and for making new and delete implementable by calling malloc() and free().

Otherwise, malloc() and free() are not to be used in C++ code because -- unlike new and delete -- they do not support object semantics. new and delete are also significantly safer and more extensible.

#### **Support For Object Semantics**

new and delete automatically construct and destroy objects. malloc() and free(), on the other hand, merely allocate and deallocate raw memory from the heap. In particular, using malloc() to create a non-POD object yields undefined behavior. For example

```
#include <cstdlib>
#include <string>
using namespace std;
string* func() //very bad
{
   string *pstr = static_cast<string*> (malloc (sizeof(string))); //disaster!
   return pstr; //any attempt to use pstr as a pointer to a string is undefined
}
```

#### Safety

Operator new automatically calculates the size of the object that it constructs. Conversely, with malloc(), the programmer has to specify explicitly the number of bytes that have to be allocated. In addition, malloc() returns a pointer to void, which has to be explicitly cast to the desired type. This is both tedious and dangerous. Operator new returns a pointer to the desired type, so no explicit type cast is required. For example

```
#include <cstdlib>
using namespace std;
void func()
{
  int * p = static_cast<int *> malloc(sizeof(int));
  int * p2 = new int;
}
```

## **Extensibility**

Operator new can be overloaded by a class. This feature enables specific classes to use different memory management policies, as you will see next. On the other hand, malloc() cannot be overloaded for a specific class.

The results of calling free() to release a pointer that was allocated by new, or of using delete to release memory that was allocated by malloc(), are undefined. The Standard does not guarantee that the underlying implementation of operator new uses malloc(); furthermore, on some implementations malloc() and new use different heaps.

#### new and delete

## Allocating and Deallocating Arrays Using new[] and delete[]

new[] allocates an array of objects of the specified type. The value that is returned by new[] is the address of the first element in the allocated array. For example

```
int main()
{
  int *p = new int[10];
  bool equal = (p == &p[0]); //true
  delete[] p;
  return 0;
}
```

Objects that are allocated using new[] must be released by a call to delete[]. Using plain delete instead of delete[] in this case results in undefined behavior. This is because when new[] is executed, the runtime system stores the number of elements in the allocated array in an implementation-defined way. The corresponding delete[] expression retrieves the number of allocated elements to invoke the same number of destructors. How does new[] store the number of elements in the allocated array? The most widely used technique is to allocate an extra sizeof(std::size\_t) bytes; that is, for a class C, the expression

```
C * p = new C[n];
```

allocates a memory buffer that contains sizeof(std::size\_t) + n \* sizeof bytes. The value n is written to the allocated buffer just before the first C object. When delete[] is invoked, it looks for the value n in a fixed offset before p (which must point to the first element in the array). delete[] then invokes C's destructor n times and, finally, releases the memory block. Plain delete, on the other hand, does not perform such offset adjustments -- it simply invokes the destructor of the object to which p points.

An alternative technique is to store n in an associative array in which p serves as the key and n is its associated value. When the statement

```
delete[] p;
```

is executed, delete[] can lookup p in an associative array such as

```
std::map<void *, std::size_t>
```

and retrieve its associated value n. Other techniques for storing the number of array elements can be used as well, but in any one of them, using plain delete instead of delete[] to release an array of objects allocated by new[] results in undefined behavior and should never happen. Similarly, using delete[] to release a single object that

was allocated by plain new is also disastrous: It might cause memory leaks, heap corruption, or a program crash.

Contrary to popular belief, the same rules apply to arrays of fundamental types -- not just to arrays of objects. Although delete[] does not invoke destructors in the case of fundamental types, it still has to retrieve the number of elements in the array to calculate the complete size of the memory block. For example

#### **Exceptions and Operator new**

In pre-Standard C++, new returned a NULL pointer when it failed to allocate the requested amount of memory. In this respect, new behaved like malloc() in C. Programmers had to check the value that was returned from new before they used it to make sure that it was not NULL. For example

Returning a NULL pointer upon failure, however, was problematic. (Note that the NULL pointer policy was applicable to both plain new and new[]. Similarly, the modified behavior applies to new as well as new[].) It forced programmers to test the value that was returned by every invocation of operator new, which is a tedious and error-prone process. In addition, the recurrent testing of the returned pointer can increase the size of the programs and add a runtime performance overhead (you might recall that these are the drawbacks associated with the return value policy, discussed in Chapter 6, "Exception Handling"). Failures in dynamic memory allocation are rather rare and generally indicate an unstable system state. This is exactly the kind of runtime errors that exception handling was designed to cope with. For these reasons, the C++ standardization committee changed the specification of new a few years ago. The Standard now states that operator new throws an exception of type std::bad\_alloc when it fails, rather than returning a NULL pointer.

**CAUTION:** Although compiler vendors have been sluggish in adopting this change, most C++ compilers now conform to the standard in this respect, and throw an exception of type std::bad\_alloc when new fails. Please consult your compiler's documentation for more details.

A program that calls new either directly or indirectly (for example, if it uses STL containers, which allocate memory from the free store) must contain an appropriate handler that catches a std::bad\_alloc exception. Otherwise, whenever new fails, the program terminates due to an uncaught exception. The exception-throwing policy also implies that testing the pointer that is returned from new is completely useless. If new is successful, the redundant test wastes system resources. On the other hand, in the case of an allocation failure, the thrown exception aborts the current thread of execution from where it was thrown -- so the test is not executed anyway. The revised, standard-conforming form of the previously presented program looks similar to the following:

```
void f(int size) //standard-conforming usage of new
  char *p = new char [size];
  //...use p safely
 delete [] p;
 return;
#include <stdexcept>
#include <iostream>
using namespace std;
const int BUF_SIZE = 1048576L;
int main()
  try
    f(BUF_SIZE);
  catch(bad_alloc& ex) //handle exception thrown from f()
    cout<<ex.what()<<endl;</pre>
    //...other diagnostics and remedies
  return -1;
```

## **Exception-Free Version of Operator new**

Still, under some circumstances, throwing an exception is undesirable. For example, exception handling might have been turned off to enhance performance; on some platforms, it might not be supported at all.

The Standardization committee was aware of this and added an exception-free version of new to the Standard. The exception-free version of new returns a NULL pointer in the event of a failure, rather than throwing a std::bad\_alloc exception. This version of new takes an additional argument of type const std::nothrow\_t& (defined in the header <new>). It comes in two flavors, one for plain new and another for new[].

```
//exception-free versions of new and new[] defined in the header <new>
void* operator new(std::size_t size, const std::nothrow_t&) throw();
void* operator new[](std::size_t size, const std::nothrow_t&) throw();
```

The exception-free new is also called *nothrow new*. It is used as follows:

```
#include <new>
#include <string>
using namespace std;
void f(int size) // demonstrating nothrow new
  char *p = new (nothrow) char [size]; //array nothrow new
  if (p == 0)
    //...use p
    delete [] p;
  string *pstr = new (nothrow) string; //plain nothrow new
  if (pstr == 0)
    //...use pstr
    delete [] pstr;
 return;
const int BUF_SIZE = 1048576L;
int main()
 f(BUF_SIZE);
 return 0;
```

The argument nothrow is defined and created in header <new> as follows:

```
extern const nothrow_t nothrow;
Class nothrow_t is defined as follows:
struct nothrow_t {}; //an empty class
```

In other words, the type nothrow\_t is an empty class (the empty class idiom is discussed in Chapter 5, "Object-Oriented Program and Design") whose sole purpose is to overload global new.

#### Placement new

An additional version of operator new enables you to construct an object (or an array of objects) at a predetermined memory position. This version is called *placement new* and has many useful applications, including building a custom-made memory pool or a garbage collector. Additionally, it can be used in mission-critical applications because there is no danger of allocation failure (the memory that is used by placement new has already been allocated). Placement new is also faster because the construction of an object on a preallocated buffer takes less time. Following is an example of using placement new:

```
#include <new>
#include <iostream>
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management
```

#### Explicit Destructor Invocation Is Required for an Object Created by Placement new

Destructors of objects that were constructed using placement new have to be invoked explicitly. To see why, consider the following example:

```
#include <new>
#include <iostream>
using namespace std;
class C
{
public:
    C() { cout<< "constructed" <<endl; }
    ~C() { cout<< "destroyed" <<endl; }
};
int main()
{
    char * p = new char [sizeof ]; // pre-allocate a buffer
    C *pc = new (p) C; // placement new
    //... used pc
    pc->C::~C(); // 1:explicit destructor invocation is required delete [] p; //2
    return 0;
}
```

Without an explicit destructor invocation in (1), the object that is pointed to by p will never be destroyed, but the memory block on which it was created will be released by the delete[] statement in (2).

# **Exceptions During Object Construction**

As was previously noted, new performs two operations: It allocates memory from the free store by calling an allocation function, and it constructs an object on the allocated memory. The question is, does the allocated memory leak when an exception is thrown during the construction process? The answer is no, it doesn't. The allocated memory is returned to the free store by the system before the exception propagates to the program. Thus, an invocation of operator new can be construed as two consecutive operations. The first operation merely allocates a sufficient memory block from the free store with the appropriate alignment requirements. In the event of failure, the system throws an exception of type std::bad\_alloc. If the first operation was successful, the second one begins. The second operation consists of invoking the object's constructor with the pointer that is retained from the previous step.

Put differently, the statement

```
C* p = new C;
```

is transformed by the compiler into something similar to the following:

# **Alignment Considerations**

The pointer that is returned by new has the suitable alignment properties so that it can be converted to a pointer of any object type and then used to access that object or array. Consequently, you are permitted to allocate character arrays into which objects of other types will later be placed. For example

```
#include <new>
#include <iostream>
#include <string>
using namespace std;
class Employee
private:
  string name;
  int age;
public:
 Employee();
  ~Employee();
void func() //use a pre allocated char array to construct
            //an object of a different type
  char * pc = new char[sizeof(Employee)];
 Employee *pemp = new (pc) Employee; //construct on char array
  //...use pemp
 pemp->Employee::~Employee(); //explicit destruction
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management delete [] pc;
```

It might be tempting to use a buffer that is allocated on the stack to avoid the hassle of deleting it later:

```
char pbuff [sizeof(Employee)];
Employee *p = new (pbuff ) Employee; //undefined behavior
```

However, char arrays of automatic storage type are not guaranteed to meet the necessary alignment requirements of objects of other types. Therefore, constructing an object of a preallocated buffer of automatic storage type can result in undefined behavior. Furthermore, creating a new object at a storage location that was previously occupied by a const object with static or automatic storage type also results in undefined behavior. For example

#### **Member Alignment**

The size of a class or a struct might be larger than the result of adding the size of each data member in it. This is because the compiler is allowed to add additional *padding bytes* between members whose size does not fit exactly into a machine word (see also Chapter 13). For example

On a 32-bit architecture, three additional bytes can be inserted between the first and the second members of Person, increasing the size of Person from 17 bytes to 20.

On some implementations, the memset () call does not clear the last three bytes of the member lastName. Therefore, use the sizeof operator to calculate the correct size:

```
memset(&p, 0, sizeof(Person));
```

# The Size Of A Complete Object Can Never Be Zero

An empty class doesn't have any data members or member functions. Therefore, the size of an instance is seemingly zero. However, C++ guarantees that the size of a complete object is never zero. Consider the following example:

```
class Empty {};
Empty e; // e occupies at least 1 byte of memory
```

If an object is allowed to occupy zero bytes of storage, its address can overlap with the address of a different object. The most obvious case is an array of empty objects whose elements all have an identical address. To guarantee that a complete object always has a distinct memory address, a complete object occupies at least one byte of memory. Non-complete objects -- for example, base class subobjects in a derived class -- can occupy zero bytes of memory.

# User-Defined Versions of new and delete Cannot Be Declared in a Namespace

User-defined versions of new and delete can be declared in a class scope. However, it is illegal to declare them in a namespace. To see why, consider the following example:

```
char *pc;
namespace A
{
  void* operator new ( size_t );
  void operator delete ( void * );
  void func ()
  {
    pc = new char ( 'a');
  }
}
void f() { delete pc; } // A::delete or ::delete?
```

Declaring new and delete in namespace A is confusing for both compilers and human readers. Some programmers might expect the operator A::delete to be selected in the function f() because it matches the operator new that was used to allocate the storage. In contrast, others might expect delete to be called because A::delete is not visible in f(). For this reason, the Standardization committee decided to disallow declarations of new and delete in a namespace.

# Overloading new and delete in a Class

It is possible to override new and delete and define a specialized form for them for a given class. Thus, for a class C that defines these operators, the following statements

```
C* p = new C;
delete p;
```

invoke the class's versions of new and delete, respectively. Defining class-specific versions of new and delete is useful when the default memory management scheme is unsuitable. This technique is also used in applications that have a custom memory pool. In the following example, operator new for class C is redefined to alter the default behavior in case of an allocation failure; instead of throwing std::bad\_alloc, this specific version throws a

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management const char \*. A matching operator delete is redefined accordingly: #include <cstdlib> // malloc() and free() #include <iostream> using namespace std; class C private: int j; public: C(): j(0) { cout<< "constructed"<<endl; } ~C() { cout<<"destroyed";} void\* operator new (size\_t size); //implicitly declared static void operator delete (void \*p); //implicitly declared static void\* C::operator new (size\_t size) throw (const char \*) void \* p = malloc(size); if (p == 0)throw "allocation failure"; //instead of std::bad\_alloc return p; void C::operator delete (void \*p) free(p); int main() try C \*p = new C;delete p;

Remember that overloaded new and delete are implicitly declared as static members of their class if they are not explicitly declared static. Note also that a user-defined new implicitly invokes the objects's constructor; likewise, a user-defined delete implicitly invokes the object's destructor.

# **Guidelines for Effective Memory Usage**

Choosing the correct type of storage for an object is a critical implementation decision because each type of storage has different implications for the program's performance, reliability, and maintenance. This section tells you how to choose the correct type of storage for an object and thus avoid common pitfalls and performance penalties. This section also discusses general topics that are associated with the memory model of C++, and it compares C++ to other languages.

catch (const char \* err)

cout<<err<<endl;

return 0;

#### **Prefer Automatic Storage to Free Store Whenever Possible**

Creating objects on the free store, when compared to automatic storage, is more expensive in terms of performance for several reasons:

- Runtime overhead Allocating memory from the free store involves negotiations with the operating system. When the free store is fragmented, finding a contiguous block of memory can take even longer. In addition, the exception handling support in the case of allocation failures adds additional runtime overhead.
- Maintenance Dynamic allocation might fail; additional code is required to handle such exceptions.
- Safety An object might be accidentally deleted more than once, or it might not be deleted at all. Both of these are a fertile source of bugs and runtime crashes in many applications.

The following code sample demonstrates two common bugs that are associated with allocating objects on the free store:

Such bugs are quite common in large programs that frequently allocate objects on the free store. Often, it is possible to create objects on the stack, thereby simplifying the structure of the program and eliminating the potential for such bugs. Consider how the use of a local string object simplifies the preceding code sample:

```
#include <string>
using namespace std;
void f()
{
   string s;
   //...use s
   if (s.empty()!= false)
   {
      //...do something
      return;
   }
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management
```

```
else
{
    //..do other stuff
}
```

As a rule, automatic and static storage types are always preferable to free store.

#### **Correct Syntax for Local Object Instantiation**

The correct syntax for instantiating a local object by invoking its default constructor is

```
string str; //no parentheses
```

Although empty parentheses can be used after the class name, as in

```
string str(); //entirely different meaning
```

the statement has an entirely different meaning. It is parsed as a declaration of a function named str, which takes no arguments and returns a string by value.

#### Zero As A Universal Initializer

The literal 0 is an int. However, it can be used as a universal initializer for every fundamental data type. Zero is a special case in this respect because the compiler examines its context to determine its type. For example:

```
void *p = 0; //zero is implicitly converted to void *
float salary = 0; // 0 is cast to a float
  char name[10] = {0}; // 0 cast to a '\0'
  bool b = 0; // 0 cast to false
  void (*pf)(int) = 0; // pointer to a function
  int (C::*pm) () = 0; //pointer to a class member
```

#### **Always Initialize Pointers**

An uninitialized pointer has an indeterminate value. Such a pointer is often called a *wild pointer*. It is almost impossible to test whether a wild pointer is valid, especially if it is passed as an argument to a function (which in turn can only verify that it is not NULL). For example

Even if your compiler does initialize pointers automatically, it is best to initialize them explicitly to ensure code

readability and portability.

# **Explicit Initializations of POD Object**

As was previously noted, POD objects with automatic storage have an indeterminate value by default in order to avoid the performance penalty incurred by initialization. However, you can initialize automatic POD objects explicitly when necessary. The following sections explain how this is done.

#### **Initializing Local Automatic Structs and Arrays**

One way to initialize automatic POD objects is by calling memset () or a similar initialization function. However, there is a much simpler way to do it -- without calling a function, as you can see in the following example:

This technique is applicable to every POD struct. It relies on the fact that the first member is a fundamental data type. The initializer zero is automatically cast to the appropriate fundamental type. It is guaranteed that whenever the initialization list contains fewer initializers than the number of members, the rest of the members are initialized to binary zeros as well. Note that even if the definition of Person changes -- additional members are added to it or the members' ordering is swapped -- all its members are still initialized. The same initialization technique is also applicable to local automatic arrays of fundamental types as well as to arrays of POD objects:

```
void f()
{
  char name[100] = {0}; //all array elements are initialized to '\0'
  float farr[100] = {0}; //all array elements are initialized to 0.0
  int iarr[100] = {0}; //all array elements are initialized to 0
  void *pvarr[100] = {0}; //array of void * all elements are initialized to NULL
  //...use the arrays
}
```

This technique works for any combination of structs and arrays:

```
struct A
{
   char name[20];
   int age;
   long ID;
};
```

#### **Union Initialization**

You can initialize a union. However, unlike struct initialization, the initialization list of a union must contain only a single initializer, which must refer to the first member in the union. For example

## **Detecting a Machine's Endian**

The term *endian* refers to the way in which a computer architecture stores the bytes of a multibyte number in memory. When bytes at lower addresses have lower significance (as is the case with Intel microprocessors, for instance), it is called *little endian ordering*. Conversely, *big endian ordering* describes a computer architecture in which the most significant byte has the lowest memory address. The following program detects the endian of the machine on which it is executed:

#### The Lifetime Of A Bound Temporary Object

You can safely bind a reference to a temporary object. The temporary object to which the reference is bound persists for the lifetime of the reference. For example

```
class C
```

}//temporary destroyed here along with its bound reference

#### **Deleting A Pointer More Than Once**

return 0;

The result of applying delete to the same pointer after it has been deleted is undefined. Clearly, this bug should never happen. However, it can be prevented by assigning a NULL value to a pointer right after it has been deleted. It is guaranteed that a NULL pointer deletion is harmless. For example

```
#include <string>
using namespace std;
void func
{
   string * ps = new string;
   //...use ps
   if ( ps->empty() )
   {
      delete ps;
      ps = NULL; //safety-guard: further deletions of ps will be harmless
   }
   //...many lines of code
   delete ps; // ps is deleted for the second time. Harmless however
}
```

## **Data Pointers Versus Function Pointers**

Both C and C++ make a clear-cut distinction between two types of pointers -- data pointers and function pointers. A function pointer embodies several constituents, such as the function's signature and return value. A data pointer, on the other hand, merely holds the address of the first memory byte of a variable. The substantial difference between the two led the C standardization committee to prohibit the use of void\* to represent function pointers, and vice versa. In C++, this restriction was relaxed, but the results of coercing a function pointer to a void\* are implementation-defined. The opposite -- that is, converting data pointers to function pointers -- is illegal.

# **Pointer Equality**

Pointers to objects or functions of the same type are considered equal in three cases:

• If both pointers are NULL. For example

```
int *p1 = NULL, p2 = NULL;
bool equal = (p1==p2); //true
```

• If they point to the same object. For example

```
char c;
char * pc1 = &c;
char * pc2 = &c;
bool equal = (pc1 == pc2); // true
```

• If they point one position past the end of the same array. For example

```
int num[2];
int * p1 = num+2, *p2 = num+2;
bool equal = ( p1 == p2); //true
```

# **Storage Reallocation**

In addition to malloc() and free(), C also provides the function realloc() for changing the size of an existing buffer. C++ does not have a corresponding reallocation operator. Adding operator renew to C++ was one of the suggestions for language extension that was most frequently sent to the standardization committee. Instead, there are two ways to readjust the size of memory that is allocated on the free store. The first is very inelegant and error prone. It consists of allocating a new buffer with an appropriate size, copying the contents of the original buffer to it and, finally, deleting the original buffer. For example

```
void reallocate
{
  char * p new char [100];
  //...fill p
  char p2 = new char [200]; //allocate a larger buffer
  for (int i = 0; i<100; i++) p2[i] = p[i]; //copy
  delete [] p; //release original buffer
}</pre>
```

Obviously, this technique is inefficient and tedious. For objects that change their size frequently, this is unacceptable. The preferable method is to use the container classes of the Standard Template Library (STL). STL containers are discussed in Chapter 10, "STL and Generic Programming."

## **Local Static Variables**

By default, local static variables (not to be confused with static class members) are initialized to binary zeros. Conceptually, they are created before the program's outset and destroyed after the program's termination. However, like local variables, they are accessible only from within the scope in which they are declared. These properties make static variables useful for storing a function's state on recurrent invocations because they retain their values from the previous call. For example

```
void MoveTo(int OffsetFromCurrentX, int OffsetFromCurrentY)
{
  static int currX, currY; //zero initialized
```

```
currX += OffsetFromCurrentX;
currY += OffsetFromCurrentY;
PutPixel(currX, currY);
}
void DrawLine(int x, int y, int length)
{
  for (int i=0; i<length; i++)
     MoveTo(x++, y--);
}</pre>
```

However, when the need arises for storing a function's state, a better design choice is to use a class. Class data members replace the static variables and a member function replaces the global function. Local static variables in a member function are of special concern: Every derived object that inherits such a member function also refers to the same instance of the local static variables of its base class. For example

```
class Base
{
public:
    int countCalls()
    {
        static int cnt = 0;
        return ++cnt;
    }
};
class Derived1 : public Base { /*..*/};
class Derived2 : public Base { /*..*/};
// Base::countCalls(), Derived1::countCalls() and Derived2::countCalls
// hold a shared copy of cnt
int main()
{
    Derived1 d1;
    int d1Calls = d1.countCalls(); //d1Calls = 1
    Derived2 d2;
    int d2Calls = d2.countCalls(); //d2Calls = 2, not 1
    return 0;
}
```

Static local variables in the member function countCalls can be used to measure load balancing by counting the total number of invocations of that member function, regardless of the actual object from which it was called. However, it is obvious that the programmer's intention was to count the number of invocations through Derived2 exclusively. In order to achieve that, a static class member can be used instead:

```
class Base
{
private:
    static int i;
public:
    virtual int countCalls() {    return ++i; }
};
int Base::i;
class Derived1 : public Base
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 11 - Memmory Management
private:
  static int i; //hides Base::i
public:
  int countCalls() { return ++i; } //overrides Base:: countCalls()
int Derived1::i;
class Derived2 : public Base
private:
  static int i; //hides Base::i and distinct from Derived1::i
public:
  virtual int countCalls() { return ++i; }
int Derived2::i;
int main()
  Derived1 d1;
  Derived2 d2;
  int d1Calls = d1.countCalls(); //d1Calls = 1
  int d2Calls = d2.countCalls(); //d2Calls also = 1
  return 0;
```

Static variables are problematic in a multithreaded environment because they are shared and have to be accessed by means of a lock.

# **Global Anonymous Unions**

An *anonymous union* (anonymous unions are discussed in Chapter 12, "Optimizing Your Code") that is declared in a named namespace or in the global namespace has to be explicitly declared static. For example

```
static union //anonymous union in global namespace
{
  int num;
  char *pc;
};
namespace NS
{
  static union { double d; bool b;}; //anonymous union in a named namespace
}
int main()
{
  NS::d = 0.0;
  num = 5;
  pc = "str";
  return 0;
}
```

# The const and volatile Properties of an Object

There are several phases that comprise the construction of an object, including the construction of its base and embedded objects, the assignment of a this pointer, the creation of the virtual table, and the invocation of the constructor's body. The construction of a cv-qualified (const or volatile) object has an additional phase, which turns it into a const/volatile object. The cv qualities are effected after the object has been fully constructed.

# **Conclusions**

The complex memory model of C++ enables maximal flexibility. The three types of data storage -- automatic, static, and free store -- offer a level of control that normally exist only in assembly languages.

The fundamental constructs of dynamic memory allocation are operators new and delete. Each of these has no fewer than six different versions; there are plain and array variants, each of which comes in three flavors: exception throwing, exception free, and placement.

Many object-oriented programming languages have a built-in *garbage collector*, which is an automatic memory manager that detects unreferenced objects and reclaims their storage (see also Chapter 14, "Concluding Remarks and Future Directions," for a discussion on garbage collection). The reclaimed storage can then be used to create new objects, thereby freeing the programmer from having to explicitly release dynamically-allocated memory. Having an automatic garbage collector is handy because it eliminates a large source of bugs, runtime crashes, and memory leaks. However, garbage collection is not a panacea. It incurs additional runtime overhead due to repeated compaction, reference counting, and memory initialization operations, which are unacceptable in time-critical applications. Furthermore, when garbage collection is used, destructors are not necessarily invoked immediately when the lifetime of an object ends, but at an indeterminate time afterward (when the garbage collector is sporadically invoked). For these reasons, C++ does not provide a garbage collector. Nonetheless, there are techniques to minimize -- and even eliminate -- the perils and drudgery of manual memory management without the associated disadvantages of garbage collection. The easiest way to ensure automatic memory allocation and deallocation is to use automatic storage. For objects that have to grow and shrink dynamically, you can use STL containers that automatically and optimally adjust their size. Finally, in order to create an object that exists throughout the execution of a program, you can declare it static. Nonetheless, dynamic memory allocation is sometimes unavoidable. In such cases, auto\_ptr(discussed in Chapters 6 and 11, "Memory Management") simplifies the usage of dynamic memory.

Effective and bug-free usage of the diversity of C++ memory handling constructs and concepts requires a high level of expertise and experience. It isn't an exaggeration to say that most of the bugs in C/C++ programs are related to memory management. However, this diversity also renders C++ a multipurpose, no compromise programming language.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

# **12**

# **Optimizing Your Code**

#### by Danny Kalev

- Introduction
  - Scope of This Chapter
- Before Optimizing Your Software
- Declaration Placement
  - Prefer Initialization to Assignment
  - Relocating Declarations
  - Member-Initialization Lists
  - o Prefix Versus Postfix Operators
- Inline Functions
  - Function Call Overhead
  - Benefits of Inline Functions
  - What Happens When a Function that Is Declared inline Cannot Be Inlined?
  - Additional Issues of Concern
  - o The Do's and Don'ts of inline
- Optimizing Memory Usage
  - o Bit Fields
  - Unions
- Speed Optimizations
  - o Using a Class To Pack a Long Argument List
  - Register Variables
  - o Declaring Constant Objects as const
  - o Runtime Overhead of Virtual Functions

- o Function Objects Versus Function Pointers
- A Last Resort
  - o Disabling RTTI and Exception Handling Support
  - o Inline Assembly
  - o Interacting with the Operating System Directly
- Conclusions

# Introduction

One often-heard claim during the past 30 years is that performance doesn't matter because the computational power of hardware is constantly dropping. Therefore, buying a stronger machine or extending the RAM of an existing one can make up for the sluggish performance of software written in a high-level programming language. In other words, a hardware upgrade is more cost-effective than the laborious task of hand-tuning code. That might be correct for client applications that execute on a standard personal computer. A modestly priced personal computer these days offers higher computational power than a mainframe did two decades ago, and the computational power still grows exponentially every 18 months or so. However, in many other application domains, a hardware upgrade is less favorable because it is too expensive or because it simply is not an option. In proprietary embedded systems with 128K of RAM or less, extending the RAM requires redesigning the entire system from scratch, as well as investing several years in the development and testing of the new chips. In this case, code optimization is the only viable choice for satisfactory performance.

But optimization is not confined to esoteric application domains such as embedded systems or hard core real-time applications. Even in mainstream application domains such as financial and billing systems, code optimization is sometimes necessary. For a bank that owns a \$1,500,000 mainframe computer, buying a faster machine is less preferable than rewriting a few thousand lines of critical code. Code optimization is also the primary tool for achieving satisfactory performance from server applications that support numerous users, such as Relational Database Management Systems and Web servers.

Another common belief is that code optimization implies less readable and harder to maintain software. This is not necessarily true. Sometimes, simple code modifications such as relocating the declarations in a source file or choosing a different container type can make all the difference in the world. Yet none of these changes entails unreadable code, nor do they incur any additional maintenance overhead. In fact, some of the optimization techniques can even improve the software's extensibility and readability. More aggressive optimizations can range from using a simplified class hierarchy, through the combination of inline assembly code. The result in this case is less readable, harder to maintain, and less portable code. Optimization can be viewed as a continuum; the extent to which it is applied depends on a variety of considerations.

#### **Scope of This Chapter**

Optimization is a vast subject that can easily fill a few thick volumes. This chapter discusses various optimization techniques, most of which can be easily applied in C++ code without requiring a deep understanding of the underlying hardware architecture of a particular platform. The intent is to give you a rough estimate of the performance cost of choosing one programming strategy over another (you can experiment with the programs that are discussed in the following sections on your computer). The purpose is to provide you with practical guidelines and notions, rather than delve into theoretical aspects of performance analysis, efficiency of algorithms, or the Big Oh notation.

# **Before Optimizing Your Software**

Detecting the bottlenecks of a program is the first step in optimizing it. It is important, however, to profile the release version rather than the debug version of the program because the debug version of the executable contains additional code. A debug-enabled executable can be about 40% larger than the equivalent release executable. The extra code is required for symbol lookup and other debug "scaffolding". Most implementations provide distinct debug and release versions of operator new and other library functions. Usually, the debug version of new initializes the allocated memory with a unique value and adds a header at block start; the release version of new doesn't perform either of these tasks. Furthermore, a release version of an executable might have been optimized already in several ways, including the elimination of unnecessary temporary objects, loop unrolling (see the sidebar "A Few Compiler Tricks"), moving objects to the registers, and inlining. For these reasons, you cannot assuredly deduce from a debug version where the performance bottlenecks are actually located.

#### **A Few Compiler Tricks**

A compiler can automatically optimize the code in several ways. The *named return value* and *loop unrolling* are two instances of such automatic optimizations.

Consider the following code:

```
int *buff = new int[3];
for (int i =0; i<3; i++)
  buff[i] = 0;</pre>
```

This loop is inefficient: On every iteration, it assigns a value to the next array element. However, precious CPU time is also wasted on testing and incrementing the counter's value and performing a jump statement. To avoid this overhead, the compiler can unroll the loop into a sequence of three assignment statements, as follows:

```
buff[0] = 0;
buff[1] = 0;
buff[2] = 0;
```

The named return value is a C++-specific optimization that eliminates the construction and destruction of a temporary object. When a temporary object is copied to another object using a copy constructor, and when both these objects are cv-unqualified, the Standard allows the implementation to treat the two objects as one, and not perform a copy at all. For example

```
class A
{
public:
    A();
    ~A();
    A(const A&);
    A operator=(const A&);
};
A f()
{
    A a;
    return a;
}
```

```
A \ a2 = f();
```

The object a does not need to be copied when f() returns. Instead, the return value of f() can be constructed directly into the object a 2, thereby avoiding both the construction and destruction of a temporary object on the stack.

Remember also that debugging and optimization are two distinct operations. The debug version needs to be used to trap bugs and to verify that the program is free from logical errors. The tested release version needs to be used in performance tuning and optimizations. Of course, applying the code optimization techniques that are presented in this chapter can enhance the performance of the debug version as well, but the release version is the one that needs to be used for performance evaluation.

**NOTE:** It is not uncommon to find a "phantom bottleneck" in the debug version, which the programmer strains hard to fix, only to discover later that it has disappeared anyway in the release version. Andrew Koenig wrote an excellent article that tells the story of an evasive bottleneck that automatically dissolved in the release version ("An Example of Hidden Library Overhead", *C++ Report* vol. 10:2, February 1998, page 11). The lesson that can be learned from this article is applicable to everyone who practices code optimization.

# **Declaration Placement**

The placing of declarations of variables and objects in the program can have significant performance effects. Likewise, choosing between the postfix and prefix operators can also affect performance. This section concentrates on four issues: initialization versus assignment, relocation of declarations to the part of the program that actually uses them, a constructor's member initialization list, and prefix versus postfix operators.

#### **Prefer Initialization to Assignment**

C allows declarations only at a block's beginning, before any program statements. For example

```
void f();
void g()
{
   int i;
   double d;
   char * p;
   f();
}
```

In C++, a declaration is a statement; as such, it can appear almost anywhere within the program. For example

```
void f();
void g()
{
  int i;
  f();
  double d;
  char * p;
}
```

The motivation for this change in C++ was to allow for declarations of objects right before they are used. There are two benefits to this practice. First, this practice guarantees that an object cannot be tampered with by other parts of the program before it has been used. When objects are declared at the block's beginning and are used only 20 or 50 lines later, there is no such guarantee. For instance, a pointer to an object that was allocated on the free store might be accidentally deleted somewhere before it is actually used. Declaring the pointer right before it is used, however, reduces the likelihood of such mishaps.

The second benefit in declaring objects right before their usage is the capability to initialize them immediately with the desired value. For example

```
#include <string>
using namespace std;
void func(const string& s)
{
  bool emp = s.empty(); //local declarations enables immediate initialization
}
```

For fundamental types, initialization is only marginally more efficient than assignment; or it can be identical to late assignment in terms of performance. Consider the following version of func(), which applies assignment rather than initialization:

```
void func2() //less efficient than func()? Not necessarily
{
  string s;
  bool emp;
  emp = s.empty(); //late assignment
}
```

My compiler produces the same assembly code as it did with the initialization version. However, as far as user-defined types are concerned, the difference between initialization and assignment can be quite noticeable. The following example demonstrates the performance gain in this case (by modifying the preceding example). Instead of a bool variable, a full-blown class object is used, which has all the four special member functions defined:

```
int constructor, assignment_op, copy, destr; //global counters
class C
{
  public:
    C();
    C& operator = (const C&);
    C(const C&);
    ~C();
};
C::C()
{
    ++constructor;
}
C& C::operator = (const C& other)
{
    ++assignment_op;
    return *this;
}
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 12 - Optimizing Your Code
```

```
C::C(const C& other)
{
    ++copy;
}
C::~C()
{
    ++destr;
}
```

As in the previous example, two different versions of the same function are compared; the first uses object initialization and the second uses assignment:

```
void assign(const C& c1)
{
  C c2;
  c2 = c1;
}
void initialize(const C& c1)
{
  C c2 = c1;
}
```

Calling assign() causes three member function invocations: one for the constructor, one for the assignment operator, and one for the destructor. initialize() causes only two member function invocations: the copy constructor and the destructor. Initialization saves one function call. For a nonsensical class such as C, the additional runtime penalty that results from a superfluous constructor call might not be crucial. However, bear in mind that constructors of real-world objects also invoke constructors of their base classes and embedded objects. When there is a choice between initialization and assignment, therefore, initialization is always preferable.

#### **Relocating Declarations**

Preferring initialization of objects over assignment is one aspect of localizing declarations. On some occasions, the performance boost that can result from moving declarations is even more appreciable. Consider the following example:

```
bool is_C_Needed();
void use()
{
   C c1;
   if (is_C_Needed() == false)
   {
     return; //c1 was not needed
   }
   //use c1 here
   return;
}
```

The local object c1 is unconditionally constructed and destroyed in use(), even if it is not used at all. The compiler transforms the body of use() into something that looks like this:

```
void use()
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 12 - Optimizing Your Code

{
    C c1;
    c1.C::C(); //1. compiler-added constructor call
    if (is_C_Needed() == false)
    {
        c1.C::~C(); //2. compiler-added destructor call
        return; //c1 was not needed but was constructed and destroyed still
    }
    //use c1 here
    c1.C::~C(); //3. compiler-added destructor call
    return;
}
```

As you can see, when <code>is\_C\_Needed()</code> returns <code>false</code>, the unnecessary construction and destruction of <code>c1</code> are still unavoidable. Can a clever compiler optimize away the unnecessary construction and destruction in this case? The Standard allows the compiler to suppress the creation (and consequently, the destruction) of an object if it is not needed, and if neither its constructor nor its destructor has any side effects. In this example, however, the compiler cannot perform this feat for two reasons. First, both the constructor and the destructor of <code>c1</code> have side effects -- they increment counters. Second, the result of <code>is\_C\_Needed()</code> is unknown at compile time; therefore, there is no guarantee that <code>c1</code> is actually unnecessary at runtime. Nevertheless, with a little help from the programmer, the unnecessary construction and destruction can be eliminated. All that is required is the relocation of the declaration of <code>c1</code> to the point where it is actually used:

```
void use()
{
  if (is_C_Needed() == false)
  {
    return; //c1 was not needed
  }
  C c1; //moved from the block's beginning
  //use c1 here
  return;
}
```

Consequently, the object c1 is constructed only when it is really needed -- that is, when is\_C\_Needed() returns true. On the other hand, if is\_C\_Needed() returns false, c1 is neither constructed nor destroyed. Thus, simply by moving the declaration of c1, you managed to eliminate two unnecessary member function calls! How does it work? The compiler transforms the body of use() into something such as the following:

```
void use()
{
   if (is_C_Needed() == false)
   {
      return; //cl was not needed
   }
   C cl; //moved from the block's beginning
   cl.C::C(); //l compiler-added constructor call
   //use cl here
   cl.C::~C(); //2 compiler-added destructor call
   return;
}
```

To realize the effect of this optimization, change the body of use (). Instead of constructing a single object, you now use an array of 1000 C objects:

```
void use()
{
   if (is_C_Needed() == false)
   {
      return; //cl was not needed
   }
   C cl[1000];
   //use cl here
   return;
}
In addition, you define is_C_Needed() to return false:
bool is_C_Needed()
{
   return false;
}
Finally, the main() driver looks similar to the following:
int main()
{
   for (int j = 0; j<100000; j++)
      use();
   return 0;
}</pre>
```

The two versions of use() differ dramatically in their performance. They were compared on a Pentium II, 233MHz machine. To corroborate the results, the test was repeated five times. When the optimized version was used, the for loop in main() took less than 0.02 of a second, on average. However, when the same for loop was executed with the original, the nonoptimized version of use() took 16 seconds. The dramatic variation in these results isn't too surprising; after all, the nonoptimized version incurs 100,000,000 constructor calls as well as 100,000,000 destructor calls, whereas the optimized version calls none. These results might also hint at the performance gain that can be achieved simply by preallocating sufficient storage for container objects, rather than allowing them to reallocate repeatedly (see also Chapter 10, "STL and Generic Programming").

## **Member-Initialization Lists**

As you read in Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator," a member initialization list is needed for the initialization of const and reference data members, and for passing arguments to a constructor of a base or embedded subobject. Otherwise, data members can either be assigned inside the constructor body or initialized in a member initialization list. For example

```
class Date //mem-initialization version
{
private:
  int day;
  int month;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 12 - Optimizing Your Code
  int year;
  //constructor and destructor
public:
  Date(int d = 0, int m = 0, int y = 0) : day , month(m), year(y) {}
};
Alternatively, you can define the constructor as follows:
Date::Date(int d, int m, int y) //assignment within the constructor body
  day = di
  month = m;
  year = y;
Is there a difference in terms of performance between the two constructors? Not in this example. All the data
members in Date are of a fundamental type. Therefore, initializing them by a mem-initialization list is identical in
terms of performance to assignment within the constructor body. However, with user-defined types, the difference
between the two forms is significant. To demonstrate that, return to the member function counting class, C, and define
another class that contains two instances thereof:
class Person
private:
  C c_1;
  C c_2;
public:
  Person(const C\& c1, const C\& c2): c_1(c1), c_2(c2) {}
An alternative version of Person's constructor looks similar to the following:
Person::Person(const C& c1, const C& c2)
c 1 = c1;
 c 2 = c2;
Finally, the main() driver is defined as follows:
int main()
  C c; //created only once, used as dummy arguments in Person's constructor
  for (int j = 0; j < 30000000; j++)
     Person p(c, c);
  return 0;
```

The two versions were compared on a Pentium II, 233MHz machine. To corroborate the results, the test was repeated five times. When a member initialization list was used, the for loop in main() took 12 seconds, on average. The

nonoptimized version took 15 seconds, on average. In other words, the assignment inside the constructor body is slower by a factor of 25% compared to the member-initialized constructor. The member function counters can give you a clue as to the reasons for the difference. Table 12.1 presents the number of member function calls of class C for the member initialized constructor and for the assignment inside the constructor's body.

Table 12.1 Comparison Between Member Initialization and Assignment Within the Constructor's Body for Class Person

Initialization Method	Default Constructor Calls	Assignment Operator Calls	Copy Constructor Calls	<b>Destructor Calls</b>
Member initialization list	0	0	60,000,000	60,000,000
Assignment within Constructor	60,000,000	60,000,000	0	60,000,000

When a member initialization list is used, only the copy constructor and the destructor of the embedded object are called (note that Person has two embedded members), whereas the assignment within the constructor body also adds a default constructor call per embedded object. In Chapter 4, you learned how the compiler inserts additional code into the constructor's body before any user-written code. The additional code invokes the constructors of the base classes and embedded objects of the class. In the case of polymorphic classes, this code also initializes the vptr. The assigning constructor of class Person is transformed into something such as the following:

```
Person::Person(const C& c1, const C& c2) //assignment within constructor body
{
   //pseudo C++ code inserted by the compiler before user-written code
   c_1.C::C(); //invoke default constructor of embedded object c_1
   c_2.C::C(); //invoke default constructor of embedded object c_2
//user-written code comes here:
   c_1 = c1;
   c_2 = c2;
}
```

The default construction of the embedded objects is unnecessary because they are reassigned new values immediately afterward. The member initialization list, on the other hand, appears before any user-written code in the constructor. Because the constructor body does not contain any user-written code in this case, the transformed constructor looks similar to the following:

```
Person::Person(const C& c1, const C& c2) // member initialization list ctor
{
   //pseudo C++ code inserted by the compiler before user-written code
   c_1.C::C(c1); //invoke copy constructor of embedded object c_1
   c_2.C::C(c2); //invoke copy constructor of embedded object c_2
//user-written code comes here (note: there's no user code)
}
```

You can conclude from this example that for a class that has subobjects, a member initialization list is preferable to an assignment within the constructor's body. For this reason, many programmers use member initialization lists across the board, even for data members of fundamental types.

## **Prefix Versus Postfix Operators**

The prefix operators ++ and -- tend to be more efficient than their postfix versions because when postfix operators are used, a temporary copy is needed to retain the value of the operand before it is changed. For fundamental types, the compiler can eliminate the extra copy. However, for user-defined types, this is nearly impossible. A typical implementation of the overloaded prefix and postfix operators demonstrates the difference between the two:

```
class Date
{
private:
    //...
    int AddDays(int d);
public:
    Date operator++(int unused);
    Date& operator++();
};
Date Date::operator++(int unused) //postfix
{
    Date temp(*this); //create a copy of the current object
    this->AddDays(1); //increment current object
    return temp; //return by value a copy of the object before it was incremented
}
Date& Date::operator++() //prefix
{
    this->AddDays(1); //increment current object
    return *this; //return by reference the current object
```

The overloaded postfix ++ is significantly less efficient than the prefix for two reasons: It requires the creation of a temporary copy, and it returns that copy by value. Therefore, whenever you are free to choose between postfix and prefix operators of an object, choose the prefix version.

## **Inline Functions**

Inline functions can eliminate the overhead incurred by a function call and still provide the advantages of ordinary functions. However, inlining is not a panacea. In some situations, it can even degrade the program's performance. It is important to use this feature judiciously.

#### **Function Call Overhead**

The exact cost of an ordinary function call is implementation-dependent. It usually involves storing the current stack state, pushing the arguments of the function onto the stack and initializing them, and jumping to the memory address that contains the function's instructions -- only then does the function begin to execute. When the function returns, a sequence of reverse operations also takes place. In other languages (such as Pascal and COBOL), the overhead of a function call is even more noticeable because there are additional operations that the implementation performs before and after a function call. For a member function that merely returns the value of a data member, this overhead can be unacceptable. Inline functions were added to C++ to allow efficient implementation of such accessor and mutator member functions (*getters* and *setters*, respectively). Nonmember functions can also be declared inline.

#### **Benefits of Inline Functions**

The benefits of inlining a function are significant: From a user's point of view, the inlined function looks like an ordinary function. It can have arguments and a return value; furthermore, it has its own scope, yet it does not incur the overhead of a full-blown function call. In addition, it is remarkably safer and easier to debug than using a macro. But there are even more benefits. When the body of a function is inlined, the compiler can optimize the resultant code even further by applying context-specific optimizations that it cannot perform on the function's code alone.

All member functions that are implemented inside the class body are implicitly declared inline. In addition, compiler synthesized constructors, copy constructors, assignment operators, and destructors are implicitly declared inline. For example

```
class A
{
private:
   int a;
public:
   int Get_a() { return a; } // implicitly inline
   virtual void Set_a(int aa) { a = aa; } //implicitly inline
   //compiler synthesized canonical member functions also declared inline
};
```

It is important to realize, however, that the inline specifier is merely a recommendation to the compiler. The compiler is free to ignore this recommendation and *outline* the function; it can also inline a function that was not explicitly declared inline. Fortunately, C++ guarantees that the function's semantics cannot be altered by the compiler just because it is or is not inlined. For example, it is possible to take the address of a function that was not declared inline, regardless of whether it was inlined by the compiler (the result, however, is the creation of an outline copy of the function). How do compilers determine which functions are to be inlined and which are not? They have proprietary heuristics that are designed to pick the best candidates for inlining, depending on various criteria. These criteria include the size of the function body, whether it declares local variables, its complexity (for example, recursion and loops usually disqualify a function from inlining), and additional implementation- and context-dependent factors.

## What Happens When a Function that Is Declared inline Cannot Be Inlined?

Theoretically, when the compiler refuses to inline a function, that function is then treated like an ordinary function: The compiler generates the object code for it, and invocations of the function are transformed into a jump to its memory address. Unfortunately, the implications of outlining a function are more complicated than that. It is a common practice to define inline functions in the class declaration. For example

```
// filename Time.h
#include<ctime>
#include<iostream>
using namespace std;
class Time
{
public:
   inline void Show() { for (int i = 0; i<10; i++) cout<<time(0)<<endl;}
};
   // filename Time.h</pre>
```

Because the member function Time::Show() contains a local variable and a for loop, the compiler is likely to

ignore the inline request and treat it as an ordinary member function. However, the class declaration itself can be #included in separately compiled translation units:

```
// filename f1.cpp
#include "Time.hj"
void f1()
{
   Time t1;
   t1.Show();
}
   // f1.cpp
// filename f2.cpp
#include "Time.h"
void f2()
{
   Time t2;
   t2.Show();
}
   // f2.cpp
```

As a result, the compiler generates two identical copies of the same member function for the same program:

```
void f1();
void f2();
int main()
{
  f1();
  f2();
  return 0;
}
```

When the program is linked, the linker is faced with two identical copies of Time::Show(). Normally, function redefinition causes a link-time error. Un-inlined functions are a special case, however. Older implementations of C++ coped with this situation by treating an un-inlined function as if it had been declared static. Consequently, each copy of the compiled function was only visible within the translation unit in which it was declared. This solved the name clashing problem at the cost of multiple local copies of the same function. In this case, the inline declaration did not boost performance; on the contrary, every call of the un-inlined function was resolved as an ordinary function call with the regular overhead. Even worse, the multiple copies of the function code increased compilation and linkage time and bloated the size of the executable. Ironically, not declaring Time::Show() inline might have yielded better performance! Remember that the programmer is generally not aware of all the actual costs of this -- the compiler strains quietly, the linker sighs silently, and the resultant executable is more bloated and sluggish than ever. But it still works, and the users scratch their heads, saying, "This object-oriented programming is really awful! I'm sure this app would run much faster if I'd written it in C!".

Fortunately, the Standard's specification regarding un-inlined functions was recently changed. A Standard compliant implementation generates only a single copy of such a function, regardless of the number of translation units that define it. In other words, an un-inlined function is treated similarly to an ordinary function. However, it might take some time for all compiler vendors to adopt the new specifications.

#### **Additional Issues of Concern**

There are two more conundrums that are associated with inline functions. The first has to do with maintenance. A function can begin its life as a slim inline function, offering the benefits that were previously described. At a later phase in the lifetime of the system, the function body can be extended to include additional functionality, resulting from changes in the implementation of its class. Suddenly, the inline substitution can become inefficient or even impossible. It is therefore important to reconsider the removal of the inline specifier from such functions. For member functions that are defined in the class body, the change is more complicated because the function definition has to be moved to a separate source file.

Another problem might arise when inline functions are used in code libraries. It is impossible to maintain binary compatibility if the definition of an inline function changes. In this case, the users must recompile their code to reflect the change. For a non-inline function, the users only need to relink their code, which is considerably less of a burden than a massive recompilation and relink.

#### The Do's and Don'ts of inline

The lesson here is that inline is not a magical potion for enhancing performance. For very short functions -- for example, accessors, mutators, and function wrappers (see Chapter 13, "C Language Compatibility Issues") -- the inline specifier can be profitable in terms of both execution speed and program size. If the inlined function is not very short and it is called extensively, however, the result can be an increase in the size of the executable. Furthermore, many processors cache the machine instructions of frequently used parts of the program; excessive inlining can cause a reduced instruction cache hit and, consequently, poorer overall performance. The real annoyance occurs when the compiler refuses to inline a function even though it was declared inline. On older implementations, the result was quite painful. On Standard compliant implementations, the consequences of un-inlining are less detrimental, but they are still undesirable. Some compilers are clever enough to figure out on their own which functions are to be inlined. However, most compilers are less inline-savvy so it is best to examine the effect of an inline declaration empirically. If the inline declaration does not enhance performance, avoid it.

# **Optimizing Memory Usage**

Optimization has several aspects: faster execution speed, efficient usage of system resources, and minimal usage of memory. In general, code optimization attempts to improve all these aspects. The declaration relocation technique that was demonstrated earlier eliminates the unnecessary creation and destruction of objects, thereby reducing the program's size and accelerating its runtime speed. However, other optimization techniques are heavily biased toward one direction -- speedier code or a smaller memory footprint. Sometimes, though, these goals are mutually exclusive; that is, compacting the memory footprint engenders slower code, whereas a faster code implies a larger memory footprint. This section presents various techniques for optimizing, or compacting, the memory requirements of a program.

#### **Bit Fields**

In both C and C++ it is possible to store and access data directly in the tiniest possible unit: a single bit. Because a bit is not the natural storage unit for C/C++ implementations, the use of bit fields can increase the size of the executable due to the additional maneuvers that are exercised by the processor in accessing a sequence of one or more bits. This is a clear-cut case of sacrificing runtime speed for the sake of minimizing memory usage.

**NOTE:** Note, however, that some hardware architectures provide special processor instructions for accessing bits. Therefore, whether bit fields affect the program's speed or not is very much platform-dependent.

Normally, you don't use bit fields just to save a few more bytes. For some applications, however, the tradeoff between execution speed and storage compaction is definitely worth its while. For example, the billing system of an average international telephone company stores every phone call as a record in a relational database. These records are processed in batch periodically to calculate the customer's monthly bill. The database stores millions of new records every day, and it has to keep the customer's billing information for at least one year. The complete database contains around one billion records at any given time. Because the database is also backed up periodically, and because it might also be a distributed database, every record is stored in more than one physical location. In fact, there might be 20 billion records stored in different backup generations and distributed portions of the database at any given time. A minimal billing record contains the customer's ID, a timestamp, codes that indicate the type of the call (for example, local or long distance) and the tariff (off peak, peak time). Literally, every bit counts here -- one redundant bit implies 2.5GB of wasted storage!

A non-space-optimizing definition of the billing record might look like this:

```
struct BillingRec
  long cust_id;
  long timestamp;
  enum CallType
    toll_free,
    local,
    regional,
    long_distance,
    international,
    cellular
   type;
  enum CallTariff
    off_peak,
    medium_rate,
    peak_time
  } tariff;
```

A BillingRec occupies no fewer than 16 bytes of memory on my 32-bit machine. Clearly, space is wasted here. The first two fields occupy four bytes each, as expected. However, the two enum variables occupy an additional eight bytes, even though they both can be safely represented in less than a single byte. A tweaked version of BillingRec can squeeze the enum values into two bit fields:

```
struct BillingRec
{
  long cust_id;
  long timestamp;
  enum CallType
  {
    toll_free,
    local,
    regional,
    long_distance,
    international,
```

```
cellular
};
enum CallTariff
{
   off_peak,
   medium_rate,
   peak_time
};
unsigned call: 3; //three bits
unsigned tariff: 2; //two bits
};
```

The size of BillingRec is now 12 bytes. The four bytes that are saved are equal to megabytes of data storage per day. Still, the size can be reduced even more. The two bit fields occupy five bits in total, which is less than a byte. One might therefore expect BillingRec to occupy 9 bytes rather than 12. The problem is that the compiler inserts three additional padding bytes after the bit fields to align the size of BillingRec on a word boundary (more on member alignment in Chapter 11, "Memory Management"). The additional padding bytes ensure faster access time -- at the cost of three wasted bytes. There are two ways to overcome this problem: You can change the compiler's setting to allow alignment on a byte boundary, or you can change the size of the other members so that -- in total -- it reaches exactly eight bytes.

**NOTE:** Note that both solutions might not be portable, and on some hardware architectures, the compiler will nonetheless insist on word boundary alignment. Check your compiler's specifications regarding member alignment settings.

Changing the size of the members is somewhat tricky because the first two members have to become bit fields as well:

```
struct BillingRec
{
  int cust_id: 24; // 23 bits + 1 sign bit
  int timestamp: 24;
  enum CallType
  {//...
  };
  enum CallTariff
  {//...
  };
  unsigned call: 3;
  unsigned tariff: 2;
};
```

This time, BillingRec occupies eight bytes in total, which is half of its original size. The storage that is saved in this example can amount to 10GB annually. Considering the cheap prices of magnetic storage media these days, saving a few thousand dollars might not seem to be a compelling argument -- but there is another reason for favoring smaller data storage: the costs of digital communication. A distributed database has synchronized copies in multiple sites. The synchronization process is usually done by means of digital data transfer from the central database to its synchronized copies, and vice versa. The transmission of millions of records on leased lines is pretty expensive. But for a phone company that owns these lines, this is not an issue of special concern; suppose, however, that the company is an international bank that pays hundreds of dollars for every hour of data transfer. In this case, halving the data volume is unquestionably profitable. Another point to remember is the Web; if the telephone company has a Web site that enables its customers to view their billing information online, the download time of hundreds of records

through analog dialup lines can be cut in half by this tweak.

#### **Unions**

Unions can also be used to minimize memory waste by locating two or more data members at the same memory address, where the value of (at most) one of the data members is active at any time. The size of a union is sufficient to hold the largest of its data members. A union can have member functions, including a constructor and destructor, but it cannot have virtual member functions. A union cannot serve as a base class of, nor can it inherit from, another class. In addition, a union cannot store objects that have nontrivial special member functions. C++ also supports *anonymous unions*. An anonymous union is an unnamed object of an unnamed type (anonymous unions are also discussed in Chapter 11). For example

```
union { long n; void * p}; // anonymous
n = 1000L; // members are directly accessed
p = 0; // n is now also 0
```

Unlike a named union, an anonymous one cannot have member functions or nonpublic data members.

When are unions useful? The following class retrieves a person's data from a database. The key can be either a unique ID number or a person's last name, but never both at once:

```
class PersonalDetails
{
private:
   char * name;
   long ID;
   //...
public:
   PersonalDetails(const char *nm);   //key is of type char * used
   PersonalDetails(long id) : ID(id) {}  //numeric key used
};
```

Memory is wasted here because only one of the keys can be used at a time. An anonymous union can be used in this case to minimize memory usage. For example

```
class PersonalDetails
{
  private:
    union //anonymous
    {
       char * name;
       long ID;
    };
  public:
    PersonalDetails(const char *nm);
    PersonalDetails(long id) : ID(id) {/**/} // direct access to a member //...
};
```

By using a union, the size of class PersonalDetails is halved. Again, saving four bytes of memory is not worth the trouble unless this class serves as a mold for millions of database records or if the records are transmitted on slow communication lines. Note that unions do not incur any runtime overhead, so there is no speed tradeoff in this case.

The advantage of an anonymous union over a named one is that its members can be accessed directly.

# **Speed Optimizations**

In time-critical applications, every CPU cycle counts. This section presents a few simple guidelines for speed optimization. Some of them have been around since the early days of C; others are C++ specific.

## **Using a Class To Pack a Long Argument List**

The overhead of a function call is increased when the function has a long list of arguments. The runtime system has to initialize the stack with the values of the arguments; naturally, this operation takes longer when there are more arguments. For example, executing the following function 100,000,000 times takes 8.5 seconds on average on my machine:

Packing the argument list into a single class and passing it by reference as the only argument reduces the result to five seconds, on average. Of course, for functions that take a long time to execute, the stack initialization overhead is negligible. However, for short and fast functions that are called very often, packing a long parameter list within a single object and passing it by reference can improve performance.

## Register Variables

The storage specifier register can be used as a hint to the compiler that an object will be heavily used in the program. For example

```
void f()
{
  int *p = new int[3000000];
  register int *p2 = p; //store the address in a register
  for (register int j = 0; j<3000000; j++)
  {
     *p2++ = 0;
  }
  //...use p
  delete [] p;
}</pre>
```

Loop counters are good candidates for being declared as register variables. When they are not stored in a register, a substantial amount of the loop's execution time is wasted in fetching the variable from memory, assigning a new value to it, and storing it back in memory repeatedly. Storing it in a machine register reduces this overhead. Note, however, that register is only a recommendation to the compiler. As with function inlining, the compiler can refuse to store the object in a machine register. Furthermore, modern compilers optimize loop counters and move them to the machine's registers anyway. The register storage specification is not confined to fundamental types. Rather, it can be used for any type of object. If the object is too large to fit into a register, the compiler can still store the object in a faster memory region, such as the cache memory (cache memory is about ten times faster than the main memory).

**NOTE:** Some compilers ignore the register specification altogether and automatically store the program's variables according to a set of built-in optimization rules. Please consult your vendor's specifications for more details on the compiler's handling of register declarations.

Declaring function parameters with the register storage specifier is a recommendation to pass the arguments on the machine's registers rather than passing them on the stack. For example

```
void f(register int j, register Date d);
```

## **Declaring Constant Objects as const**

In addition to the other boons of declaring constant objects as const, an optimizing compiler can take advantage of this declaration, too, and store such an object in a machine register instead of in ordinary memory. Note that the same optimization can be applied to function parameters that are declared const. On the other hand, the volatile qualifier disables such an optimization (see Appendix A, "Manual of Programming Style"), so use it only when it is unavoidable.

#### **Runtime Overhead of Virtual Functions**

When a virtual function is called through a pointer or a reference of an object, the call doesn't necessarily impose additional runtime penalties. If the compiler can resolve the call statically, no extra overhead is incurred. Furthermore, a very short virtual function can be inlined in this case. In the following example, a clever compiler can resolve the calls of the virtual member functions statically:

```
#include <iostream>
using namespace std;
class V
public:
  virtual void show() const { cout<<"I'm V"<<endl; }</pre>
class W : public V
public:
  void show() const { cout<<"I'm W"<<endl; }</pre>
void f(V \& v, V *pV)
  v.show();
  pV->show();
void g()
  V v;
  f(v, &v);
int main()
  g();
  return 0;
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 12 - Optimizing Your Code
```

If the entire program appears in a single translation unit, the compiler can perform an inline substitution of the call of the function g() in main(). The invocation of f() within g() can also be inlined, and because the dynamic type of the arguments that are passed to f() is known at compile time, the compiler can resolve the virtual function calls inside f() statically. There is no guarantee that every compiler actually inlines all the function calls; however, some compilers certainly take advantage of the fact that the dynamic type of the arguments of f() can be determined at compile time, and avoid the overhead of dynamic binding in this case.

## **Function Objects Versus Function Pointers**

The benefits of using function objects instead of function pointers (function objects are discussed in Chapter 10 and in Chapter 3, "Operator Overloading") are not limited to genericity and easier maintenance. Furthermore, compilers can inline the call of a function object, thereby enhancing performance even further (inlining a function pointer call is rarely possible).

## A Last Resort

The optimization techniques that have been presented thus far do not dictate design compromises or less readable code. In fact, some of them *improve* the software's robustness and the ease of maintenance. Packing a long argument list within a class object, const declarations, and using function objects rather than function pointers provide additional benefits on top of the performance boost. Under strict time and memory constraints, however, these techniques might not suffice; additional tweaks are sometimes required, which affect the portability and extensibility of the software. The techniques that are presented in this section are to be used only as a last resort, and only after all the other optimizations have been applied.

## **Disabling RTTI and Exception Handling Support**

When you port pure C code to a C++ compiler, you might discover a slight performance degradation. This is not a fault in the programming language or the compiler, but a matter of compiler tuning. All you have to do to gain the same (or better) performance that you might get from a C compiler is switch off the compiler's RTTI and exception handling support. Why is this? In order to support RTTI or exception handling, a C++ compiler inserts additional "scaffolding" code to the original source file. This increases the executable size a little, and imposes slight runtime overhead (the overhead of exception handling and RTTI are discussed in Chapter 6, "Exception Handling," and Chapter 7, "Runtime Type Identification", respectively). When pure C is used, this additional code is unnecessary. Please note, however, that you should not attempt to apply this tweak with C++ code or C code that uses any C++ constructs such as operator new and virtual functions.

## Inline Assembly

Time-critical sections of C++ code can be rewritten in native assembly code. The result can be a significant increase in speed. Note, however, that this measure is not to be taken lightly because it makes future modifications much more difficult. Programmers who maintain the code might not be familiar with the particular assembly language that is used, or they might have no prior experience in assembly language at all. Furthermore, porting the software to other platforms requires rewriting of the assembly code parts (in some instances, upgrading the processor can also necessitate rewriting). In addition, developing and testing assembly code is an arduous task that can take much more time than developing and testing code that is written in a high-level language.

Generally, operations that are coded in assembly are low-level library functions. On most implementations, for example, the standard library functions memset() and strcpy() are written in native assembly code. C and C++ enable the programmer to embed inline assembly code within an asm block. For example

```
asm
{
   mov a, ecx
   //...
}
```

## Interacting with the Operating System Directly

API functions and classes enable you to interact with the operating system. Sometimes, however, executing a system command directly can be much faster. For this purpose, you can use the standard function <code>system()</code> that takes a shell command as a <code>const char \*</code>. For example, on a DOS/Windows system, you can display the files in the current directory as follows:

```
#include <cstdlib>
using namespace std;
int main()
{
   system("dir"); //execute the "dir" command
}
```

Here again, the tradeoff is between speed on the one hand and portability and future extensibility on the other hand.

## **Conclusions**

In an ideal world, software designers and developers might focus their efforts on robust, extensible, and readable code. Fortunately, the current state of affairs in the software world is much closer to that ideal than it was 15, 30, or 50 years ago. Notwithstanding that, performance tuning and optimizations will probably remain a necessity for a long time. The faster hardware becomes, the more the software that runs on it is required to meet higher demands. Speech recognition, online translation of natural languages, neural networks, and complex mathematical computations are only a few examples of resource-hungry applications that will evolve in the future and require careful optimizations.

Textbooks often recommend that you put off optimization consideration to the final stages of testing. Indeed, the primary goal is to get the system to work correctly. Nonetheless, some of the techniques presented here -- such as declaring objects locally, preferring prefix to postfix operators, and using initialization instead of assignment -- need to become a natural habit. It is a well-known fact that programs usually spend 90% of their time executing only 10% of their code (the numbers might vary, but they range between 80% and 20% to 95% and 5%). The first step in optimization is, therefore, identifying that 10% of your programs and optimizing them. Many automated profiling and optimization tools can assist you in identifying these critical code parts. Some of these tools can also suggest solutions to enhance performance. Still, many of the optimization techniques are implementation-specific and always require human expertise. It is important to empirically verify your suspicions and to test the effect of suggested code modifications to ensure that they indeed improve the system's performance. Programmers' intuitions regarding the cost of certain operations are often misleading. For example, shorter code is not necessarily faster code. Similarly, writing convoluted code to avoid the cost of a simple if statement is not worth the trouble because it saves only one or two CPU cycles.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

# 13

# C Language Compatibility Issues

#### by Danny Kalev

- Introduction
- Differences Between ISO C and the C Subset of ANSI/ISO C++
  - Function Parameter List
  - Function Declaration
  - Empty Parameter List
  - Implicit int Declarations
  - o ISO C is currently being revised to disallow implicit int declarations. Repeated Declarations of Global Variables
  - o <u>Implicit Casting of void Pointers</u>
  - The Underlying Representation of NULL Pointers
  - o Default Linkage Type of Global const Variables
  - Null-Terminated Character Arrays
  - Assignment of Integers to an enum Type
  - o Definition of Structs in a Function Parameter List and Return Type
  - Bypassing an Initialization
- Quiet Differences Between C and C++
  - The Size of an enum Type
  - The Size of A Character Constant
  - Predefined Macros
  - o Default Value Returned from main()
- Migrating From C to C++
  - o Function Wrappers
- Designing Legacy Code Wrapper Classes
- Multilingual Environments
- C and C++ Linkage Conventions
  - o Forcing C Linkage on A C++ Function

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues

- O Calling C++ Code from C Code
- Compiling main()
- Minimize the Interface Between C and C++ Code
- Mixing <iostream> Classes with <stdio.h> Functions
- Accessing a C++ Object in C Code
  - The Underlying Representation of an Object in Memory
  - The C++ Object Model is Efficient
  - o Memory Layout of Derived Objects
  - Support for Virtual Member Functions
  - Virtual Inheritance
  - o Different Access Specifiers
- Conclusions

# Introduction

C is a subset of C++. Theoretically, every valid C program is also a valid C++ program. In practice, however, there are some subtle incompatibilities and silent differences between the seemingly common portion of both languages. Most of these differences can be diagnosed by the compiler. Others are more evasive and, in rare conditions, they can have surprising effects.

Although it seems that most of the time legacy C code is combined with newer C++ code, the opposite is also true: C++ code is used in C-based applications. For example, transaction-processing monitors of relational databases that are written in C interact with code modules that are written in C++. This chapter first discusses the differences between ISO C and the C subset of ANSI/ISO C++, and it demonstrates how to migrate legacy C code to a C++ environment. Next, you will explore the underlying object model of C++, including the memory layout of objects, member functions, virtual member functions, virtual base classes, and access specifiers, and you will learn how C code can access C++ objects.

## Differences Between ISO C and the C Subset of ANSI/ISO C++

With a few minor differences, C++ is a superset of C. The following sections outline the differences between the C subset of C++ and ISO C.

#### **Function Parameter List**

In pre-Standard C, the parameter list of a function was declared as follows:

```
/* pre-standard C, still valid in ISO C, invalid in C++*/
int negate (n)
int n; /* parameter declaration appears here*/
{
   return -n;
}
```

In other words, only the parameters' names appeared in the parentheses, whereas their types were declared before the opening brace. Undeclared parameters defaulted to int. In ISO C, as in C++, both the names and types of the parameters must appear in the parentheses:

```
/* ISO C and C++ */
int negate (int n)
{
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues return -n;
```

The old-style parameter list is still legal in ISO C, but it is deprecated. In C++, it is illegal. Legacy C code that contains an old-style parameter list has to be changed to become valid in C++.

#### **Function Declaration**

In C, functions can be called without having to be declared first. In C++, a function cannot be called without a previous declaration or definition. For example

```
/* valid in C but not in C++ */
int main()
{
   int n;
   n = negate(5); /* undeclared function; valid in C but not in C++ */
   return 0;
}
Functions can be declared in C, just as in C++:

/* C/C++ */
int negate(int n);
int main()
{
   int n;
   n= negate(5);
   return 0;
}
```

The use of a function declaration (also called a *function prototype*) in C is recommended because it enables the compiler to detect mismatches in type and argument number. However, it is not a requirement.

#### **Empty Parameter List**

In C, a function that is declared with an empty list of parameters such as

```
int f();
void g( int i)
{
   f(i) /* valid in C but not in C++ */
}
```

can take any number of arguments of any type. In C++, such a function does not take any arguments.

#### Implicit int Declarations

In C and in pre-Standard C++, the default type for missing declarations is int. For example

```
/* valid in C but not in C++ */
void func()
{
  const k =0; /*int type assumed in C; invalid in C++*/
}
```

# ISO C is currently being revised to disallow implicit int declarations. Repeated Declarations of Global Variables

In C, global variables can be declared more than once without the extern specifier. As long as a single initialization (at most) for the same variable is used, the linker resolves all the repeated declarations into a single entity:

```
/* valid in C but not in C++ */
int flag;
int num;
int flag; /* repeated declaration of a global variable */
void func()
{
   flag = 1;
}
```

In C++, an entity must be defined exactly once. Repeated definitions of the same entity in separate translation units result in a link-time error.

#### **Implicit Casting of void Pointers**

/\* valid in C but not C++\*/

In C, a void pointer is implicitly cast to any other pointer type in assignments and initializations. For example

```
/* valid in C but not C++*/
#include <stdlib.h>
long * p_to_int()
{
   long * pl = malloc(sizeof(long)); /* implicit conversion of void* to long* */
   return pl;
}
```

In general, implicit conversion of void \* is undesirable because it can result in bugs that can otherwise be detected by the compiler. Consider the following example:

```
#include <stdlib.h>
long * p_to_int()
{
    long * pl = malloc(sizeof(short)); /* oops! */
    return pl;
}
In C++, void pointers have to be cast explicitly to the desired type. The explicit cast makes the programmer's intention clearer and reduces the likelihood of unpleasant surprises.
```

#### The Underlying Representation of NULL Pointers

NULL is an implementation-defined const null pointer. C implementations usually define NULL as follows:

```
#define NULL ((void*)0)
However, In C++, NULL is usually defined as the literal 0 (or 0L), but never as void *:
const int NULL = 0; //some C++ implementations use this convention
#define NULL 0; //others might use this convention
```

The difference in the underlying representations of NULL pointers between C and C++ derives from the fact that C++ pointers are strongly typed, whereas in C they are not. If C++ retained C's convention, a C++ statement such as

```
char * p = NULL;
```

would be expanded into something similar to

```
char * p = (void*) 0;  // compile time error: incompatible pointer types
```

Because 0 is the universal initializer for all pointer types in C++, it is used instead the traditional C convention; in fact, many programmers simply use the literal 0 or 0L instead of NULL.

#### **Default Linkage Type of Global const Variables**

In C, the default linkage of global const variables is extern. An uninitialized const variable is implicitly zero initialized. For example

```
/*** valid in C but not C++ ***/
/* file error_flag.h */
const int error; /*default extern linkage */
/*** end file ***/
#include"error_flag.h"
int func();
int main()
{
   int status = func();
   if( status == error)
   {
      /*do something */
   }
   return 0;
}
```

In C++, a global const variable that is not explicitly declared extern has static linkage. In addition, a const variable must be initialized.

#### **Null-Terminated Character Arrays**

In C, character arrays can be initialized with a string literal without the null-terminating character. For example

```
/*** valid in C but not C++ ***/
const char message[5] = "hello"; /* does not contain a null terminator */
```

In C++, character arrays that are initialized by a string literal must be large enough to contain a null terminator.

#### Assignment of Integers to an enum Type

In C, the assignment of integers to an enumerated type is valid. For example

```
/*** valid in C but not C++ ***/
enum Status {good, bad};
void func()
{
   Status stat = 1; /* integer assignment */
}
```

In C++, enums are strongly typed. Only enumerators of the same enum type can be assigned to an enum variable. Explicit type casting is required otherwise. For example

```
//C++
enum Status {good, bad};
void func()
{
   Status stat = static_cast<Status> (1); // stat = bad
}
```

#### **Definition of Structs in a Function Parameter List and Return Type**

In C, a struct can be defined in a function parameter list as well as in its return type. For example

```
/*** valid in C but not C++ ***/
/* struct definition in return type and parameter list of a function */
struct Stat { int code; char msg[10];}
    logon (struct User { char username[8]; char pwd[8];} u );
In C++, this is illegal.
```

#### **Bypassing an Initialization**

A *jump statement* unconditionally transfers control. A jump statement is one of the following: a goto statement, a transfer from the condition of a switch statement to a case label, a break statement, a continue statement, or a return statement. In C, the initialization of a variable can be skipped by a jump statement, as in the following example:

```
/*** valid in C but not C++ ***/
int main()
{
  int n=1;
  switch(n)
  {
  case 0:
    int j=0;
    break;
  case 1: /* skip initialization of j */
    j++; /* undefined */
    break;
  default:
    break;
}
  return 0;
}
```

In C++, bypassing an initialization is illegal.

# Quiet Differences Between C and C++

The differences that have been presented thus far are easily diagnosed by a C++ compiler. There are, however, semantic differences between C and C++ in the interpretation of certain constructs. These differences might not result in a compiler diagnostic; therefore, it is important to pay attention to them.

#### The Size of an enum Type

In C, the size of an enumeration equals the sizeof(int). In C++, the underlying type for an enumeration is not necessarily an int -- it can be smaller. Furthermore, if an enumerator's value is too large to be represented as an unsigned int, the implementation is allowed to use a larger unit. For example enum { SIZE = 500000000UL };

#### The Size of A Character Constant

In C, the result of applying the operator sizeof to a character constant -- for example, sizeof('c'); -- equals sizeof(int). In C++, on the other hand, the expression sizeof('c'); equals sizeof(char).

#### **Predefined Macros**

C and C++ compilers define the following macros:

```
__DATE__ /*a literal containing compilation date in the form "Apr 13 1998" */
__TIME__ /*a literal containing the compilation time in the form "10:01:07" */
__FILE__ /*a literal containing the name of the source file being compiled */
__LINE__ /* current line number in the source file */
```

C++ compilers exclusively define the following macro:

```
__cpluplus
```

Standard-compliant C compilers define the following macro symbol:

```
__STDC__
```

Whether a C++ compiler also defines the macro symbol \_\_\_STDC\_\_ is implementation-dependent.

#### **Default Value Returned from main()**

In C, when control reaches the end of main() without encountering a return statement, the effect is that of returning an undefined value to the environment. In C++, however, main() implicitly executes a

```
return 0;
```

statement in this case.

**NOTE:** You might have noticed that the code listings throughout the book contain an explicit return statement at the end of main(), even though this is not necessary. There are two reasons for this: First, many compilers that do not comply with the Standard issue a warning message when a return statement is omitted. Secondly, the explicit return statement is used to return a nonzero value in the event of an error.

# Migrating From C to C++

Resolving the syntactic and semantic differences between C and C++ is the first step in migrating from C to C++. This process ensures that C code can compile under a C++ compiler, and that the program behaves as expected. There is another clear advantage of compiling C code under a C++ compiler: The tighter type checking that is applied by a C++ compiler can detect potential bugs that a C compiler does not detect. The list of discrepancies between C and C++ that was previously presented is mostly a result of loopholes and potential traps in C that were fixed in C++. An issue that is of concern, however, is

performance -- does a C++ compiler produce object code that is less efficient than the code produced by a C compiler? This topic is discussed in more detail in Chapter 12, "Optimizing Your Code." However, it is important to note that a good C++ compiler can *outperform* a good C compiler because it can exercise optimization techniques that C compilers normally do not support, such as function inlining and the *named return value* (also discussed in Chapter 12).

Nonetheless, in order to benefit from the robustness of object-oriented programming, more substantial code modifications are required. Fortunately, the transition from procedural to object-oriented programming can be performed gradually. The following section demonstrates a technique of wrapping bare functions with an additional code layer to minimize the dependency on implementation details. Following that is a discussion of how to use full-fledged classes that wrap legacy code in order to gain more of the benefits of object-orientation.

#### **Function Wrappers**

Low-level code such as infrastructure routines and API functions can be used by different teams for the same project. Normally, this code is developed and maintained by a third party vendor or a specific team in the project. For example

```
int retrievePerson (int key, Person* recordToBefilled); /* C function */
```

A problem can arise when the interface of () changes: Every occurrence of a function call has to be tracked down and modified accordingly. Consider how such a small change can affect existing programs:

```
/*
  function modification: key is now a char * instead of an int
  every call to this function has to modified accordingly
*/
int retrievePerson (const char * key, Person* recordToBefilled);
```

As you saw in Chapter 5, "Object-Oriented Programming and Design," one of the most noticeable weaknesses of procedural programming is its vulnerability to such changes; however, even in strict procedural programming you can localize their impact by using a *wrapper function*. A wrapper function calls the vulnerable function and returns its result. Following is an example:

```
/* A wrapper function */
int WrapRetrievePerson(int key, Person* recordToBefilled)
{
   return retrievePerson (key, recordToBefilled);
}
```

A wrapper provides a stable interface to a code fragment that is used extensively and that is vulnerable to changes. When using a wrapper function, a change in the interface of an API function is reflected only in the definition of its corresponding wrapper function. Other parts of the program are not affected by the change. This is very similar to the way in which a class's accessors and mutators provide indirect access to its nonpublic members. In the following example, the function wrapper's body has been modified due to the change in the type of key from int to char \*. Note, however, that its interface remains intact:

```
/*** file DB_API.h ***/
int retrievePerson (const char *strkey, Person* precordToBefilled);
typedef struct
{
    char first_name[20];
    char last_name[20];
    char address [50];
} Person;
/*** file DB_API.h ***/
#include <stdio.h>
#include " DB_API.h "
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues

int WrapRetrievePerson(int key, Person* precordToBefilled) //remains intact

{
    /* wrapper's implementation modified according to API's modification */
    char strkey[100];
    sprintf (strkey, "%d", key); /* convert int to a string */
    return retrievePerson (strkey, precordToBefilled);

}
```

By systematically applying this technique to every function that is maintained by other teams or vendors, you can ensure a reasonable level of interface stability even when the underlying implementation changes.

Although the function wrapper technique offers protection from changes in implementation details, it does not provide other advantages of object-oriented programming, including encapsulation of related operations in a single class, constructors and destructors, and inheritance. The next phase in the migration process is to encapsulate a collection of related functions into a single wrapper class. This technique, however, requires familiarity with object-oriented concepts and principles.

# **Designing Legacy Code Wrapper Classes**

In many frameworks that were originally written in C and then ported to C++, a common -- but wrong -- practice was to wrap C functions in a single *wrapper class*. Such a wrapper class provides as its interface a series of operations mapped directly to the legacy functions. The following networking functions provide an example:

```
/*** file: network.h ***/
#ifndef NETWORK H
#define NETWORK H
   /* functions related to UDP protocol */
int UDP init();
int UDP_bind(int port);
int UDP_listen(int timeout);
int UDP_send(char * buffer);
    /* functions related to X.25 protocol */
int X25_create_virtual_line();
int X25_read_msg_from_queue(char * buffer);
    /* general utility functions */
int hton(unsigned int); //reverse bytes from host to network order
int ntoh(unsigned int); //reverse bytes from network to host order
#endif
/*** network.h ***/
```

A na[um]ive implementation of a class wrapper might simply embed all these functions in a single class as follows:

```
#include "network.h"
class Networking
{
private:
//...stuff
public:
    //constructor and destructor
    Networking();
    ~Networking();
    //members
    int UDP_init();
    int UDP_bind(int port);
    int UDP_listen(int timeout);
    int UDP_send(char * buffer);
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues
```

```
int X25_create_virtual_line();
int X25_read_msg_from_queue(char * buffer);
int hton(unsigned int); //reverse bytes from host to network order
int ntoh(unsigned int); //reverse bytes from network to host order
};
```

However, this method of implementing a wrapper class is not recommended. X.25 and UDP protocols are used for different purposes and have almost nothing in common. Bundling the interfaces of these two protocols together can cause maintenance problems in the long term -- and it undermines the very reason for moving to an object-oriented design in the first place. Furthermore, due to its amorphous interface, Networking is not an ideal base for other derived classes. The problem with Networking and similar classes is that they do not genuinely embody an object-oriented policy. They are merely a collection of unrelated operations. A better design approach is to divide the legacy functions into meaningful, self-contained units and wrap each unit by a dedicated class. For example

```
#include "network.h"
class UDP_API
private:
//...stuff
public:
  //constructor and destructor
  UDP API();
  ~UDP_API();
  //members
  int UDP_init();
  int UDP_bind(int port);
  int UDP_listen(int timeout);
  int UDP_send(char * buffer);
};
class X25_API
private:
//...stuff
public:
  //constructor and destructor
  X25_API();
  ~X25_API();
  //members
  int X25_create_virtual_line();
  int X25 read msq from queue(char * buffer);
class Net_utility
    private:
//...stuff
public:
  //constructor and destructor
  Net_utility();
  ~Net_utility();
  //members
  int hton(unsigned int); //reverse bytes from host to network order
  int ntoh(unsigned int); //reverse bytes from network to host order
};
```

Now each class offers a coherent interface. Another advantage is a simpler usage protocol; users of class X25\_API, for

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues

instance, are not forced to accept the interface of UDP protocol, and vice versa.

# **Multilingual Environments**

**NOTE:** In this section, the distinction between C code and C++ is indicated explicitly by file extensions. The .h extension is used for C header files, whereas C++ header files are indicated by the .hpp extension. Similarly, .c and .cpp extensions are used for C and C++ source files, respectively. In addition, only C-style comments are used in C files.

Thus far, this chapter has concentrated on a unidirectional migration process: from C to C++. Nevertheless, many systems are not confined to a single programming language. A typical information system can simultaneously use one programming language for the graphical interface, another language for accessing data from a database, and a third language for server applications. Often, these languages have to share data and code with one another. This section focuses on how to combine C and C++ code in a bilingual system that uses both these languages simultaneously.

The easiest way to ensure compatibility between code modules that are written in C and C++ is to adhere to the common denominator of these languages. Then again, using C++ as a procedural language ("better C") isn't worth the bother -- you can simply stick to C. Combining object-oriented C++ code with procedural C code into a seamless executable is more challenging -- but it offers many advantages.

# C and C++ Linkage Conventions

By default, C++ functions have C++ linkage, which is incompatible with C linkage. Consequently, global C++ functions cannot be called from C code unless they are explicitly declared as having a C linkage.

#### Forcing C Linkage on A C++ Function

To override the default C++ linkage, a C++ function has to be declared extern "C". For example

The extern "C" prefix instructs a C++ compiler to apply C linkage to the function f() rather than the default C++ linkage. This means that a C++ compiler does not apply name mangling to f(), either (see the following sidebar, "What's in Name Mangling?"). Consequently, a call to f() from C code is properly resolved by a C linker. A C++ linker can also locate the compiled version of f() even though it has a C linkage type. In other words, declaring C++ functions as extern "C" guarantees interoperability between C++ and C (as well as other procedural languages that use the C calling convention). However, forcing C linkage has a price: It is impossible to overload another version of f() that is also declared as extern "C". For example

```
// filename decl.hpp
extern "C" void f(int n);
extern "C" void f(float f); //error, second C linkage of f is illegal
// decl.hpp
```

Note that you can declare additional overloaded versions of f() as long as they are not declared extern "C":

```
// filename decl.hpp extern "C" void f(int n); //OK, can be called from C and C++ code void f(float f); //OK, no C linkage used. Can be called only from C++ code void f(char c); //OK, no C linkage used. Can be called only from C++ code
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues
```

```
// decl.hpp
```

How does it work? A call to the function from C code is translated to a CALL assembly directive, followed by the function name. Declaring a C++ function as extern "C" ensures that the name that is generated for it by a C++ compiler is identical to the name that a C compiler expects. On the other hand, if the called function is compiled by a C++ compiler without the extern "C" specifier, it has a mangled name but a C compiler still places the nonmangled name after the CALL directive, resulting in a link-time error.

#### What's in Name Mangling?

Name mangling (the more politically correct term, although rarely used, is *name decoration*) is a method used by a C++ compiler to generate unique names for identifiers in a program. The exact details of the algorithm are compiler-dependent, and they might vary from one version to another. Name mangling ensures that entities with seemingly identical names get unique identifications. The resultant mangled name contains all the information that might be needed by the linker, including linkage type, scope, calling convention, and so on. For instance, when a global function is overloaded, the generated mangled name for each overloaded version is unique. Name mangling is also applied to variables. Thus, a local variable and a global variable with the same user-given name still get distinct mangled names. How is the mangled name synthesized? The compiler picks the user-given name of an identifier and decorates it with additional affixes to indicate a variable of a fundamental type, a class, or a function. For a function, the mangled name embeds its scope and linkage type, the namespace in which it is declared, the list of parameters, the parameters' passing mechanism, and the parameters' cv-qualifications. A mangled name of a member function incorporates additional information such as the class name, whether it is a const member function, and other implementation-dependent details that the linker and the runtime environment might need. Following is an example: For a global function void func(int);, a given compiler can generate the corresponding mangled name \_\_x\_func@i@, where the affix x indicates a function, func is the function's user-given name, @ indicates the beginning of the parameter list, i indicates the type of the parameter, and the closing @ sign signals the end of the parameter list. An overloaded version of £() has a different mangled name because it has a different parameter list. The original user-given name can be reproduced from the mangled name, so linkers in general can issue error messages in a human-readable format.

As was previously stated, the name mangling scheme of a given compiler can change from one version to another (for example, if the new version supports namespaces, whereas the previous one did not). This is one of the reasons you often have to recompile your code with every compiler upgrade. Another important implication is that, usually, the linker and the compiler need to come from the same vendor and have compatible versions. This ensures that they share the same naming conventions and that they produce compatible binary code.

#### Calling C++ Code from C Code

Up until now, you have observed the C++ side of the story. A C program cannot #include the header file decl.hpp because the extern "C" specifier is not recognized by a C compiler. To ensure that the declaration can be parsed by a C compiler, extern "C" needs to be visible to a C++ compiler -- but not to a C compiler. A C++ function with C linkage has to be declared in two distinct forms, one for C++ and another for C. This can be achieved by using separate C and C++ header files. The C header file looks similar to the following:

```
/*** filename decl.h ***/
void f(int n); /* identical to the C++ header but no extern "C" here */
/*** decl.h ***/
```

The header file can be #included in the C source file that calls the function f(). For example

```
/*** filename do_something.c ***/
#include "decl.h"
void do_something()
{
  f(5);
}
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues
```

```
/*** do_something.c ***/
```

Keeping separate header files for C and C++ is not an elegant solution, however. The header files have to remain in sync all the time, and when many header files are used, this can turn into a serious maintenance problem. A better alternative is to use one or more C header files for the declarations. For example

```
/*** filename f.h ***/
void f(int n); /* identical to the C++ header but no extern "C" here */
   /*** f.h ***/
/*** filename g.h ***/
void g(const char * pc, int n);
   /*** g.h ***/
```

Next, the C header files are #included in a C++ header file that contains an extern "C" block:

```
// filename decl.hpp
extern "C"
{
#include "f.h"
#include "g.h"
}
// filename decl.hpp
```

The effect of an extern "C" block is as if every declaration in the #included header files had a preceding extern "C" specifier. Another alternative is to modify the C header file directly by adding an #ifdef directive to make the extern "C" declaration visible only to a C++ compiler. For example

```
/*** filename decl.h ***/
#ifdef __cplusplus
extern "C" { //visible only to a C++ compiler
#endif
void g(const char * pc, int n);
void f(int n);
#ifdef __cplusplus
} //visible only to a C++ compiler
#endif
/*** g.h ***/
```

This way, only one header file is needed. However, it is not always possible to modify the C header files directly. In such cases, the preceding technique needs to be used. Please note that a C++ function called from C code is an ordinary C++ function. It can instantiate objects, invoke their member functions, or use any other C++ feature. However, some implementations might require special configuration settings to ensure that the linker has access to the C++ libraries and template codes.

#### Compiling main()

Functions can be compiled by either a C compiler or a C++ compiler. However, a C++ compiler should compile main(). This enables a C++ compiler to take care of templates, static initialization, and additional implementation-dependent operations for which main() is responsible. Compiling main() under a C compiler will most likely result in link-time errors due to the different semantics of main() in C and C++.

#### Minimize the Interface Between C and C++ Code

In general, you can call a C function from C++ code without special adjustments. The opposite, as you have seen, is also possible -- but it requires additional adjustments. It is therefore recommended that you keep the interface between the two languages at a minimum. Declaring every C++ function as extern "C", for example, is not recommended. Not only does this convention imply additional modifications to the header files, it also disables overloading. Remember also that you cannot declare a member function extern "C". For C++ functions that have to be called from C code, it might be advantageous to use a function wrapper that has an extern "C" specifier. In this case, the wrapped C++ functions can have the C++ linkage. For example

```
void g(const char * pc, int n); //extern "C" is unnecessary
void f(int n);
extern "C" void f_Wrapper(int n) //only the wrapper function is called from C
{
    f(n);
}
extern "C" void g_Wrapper(const char *pc, int n)
{
    g(pc, n);
}
```

# Mixing <iostream> Classes with <stdio.h> Functions

It is possible to use both <iostream> classes and <stdio.h> library functions in the same program, as long as they do not access the same file. For example, you can use the <iostream> object cin to read data from the keyboard, and then use <stdio.h> functions to write the data to a disk file, as in the following program:

```
#include <iostream>
#include <cstdio>
using namespace std;
int main()
{
   int num;
   cin>num;
   cout<<"you enetred: "<< num <<endl;
   FILE *fout = fopen("data.dat", "w");
   if (fout) //write num to a disk file
   {
     fprintf(fout, "%d\n", num);
   }
   fclose(fout);
   return 0;
}</pre>
```

It is even possible to use <iostream> and <stdio.h> to manipulate the same file; for instance, a program can send output to both stdout and cout, although this is not recommended. To enable simultaneous access to the same file, you first have to call ios::sync\_with\_stdio(true); to synchronize the I/O operations. Note, however, that this synchronization degrades performance. Therefore, only use it when <iostream> and <stdio.h> access the same file. For example

```
#include <iostream>
#include <cstdio>
using namespace std;
int main()
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues

ios::sync_with_stdio(true);//enable mixed I/O
int num;
printf("please enter a number\n");
cin>>num;
cout<<"you enetred: "<< num << "please enter another one " << endl;
scanf("%d", &num);
return 0;
}</pre>
```

Normally, you won't write such code. However, when a large application combines legacy C functions that use <stdio.h> and C++ objects that use <iostream>, I/O synchronization is unavoidable because, ultimately, the same low-level system resources are used by both <stdio.h> and <iostream>.

The fact that <iostream> and <stdio.h> can be combined is a major advantage. Otherwise, the migration process from C to C++ might be much fussier, and making C and C++ code work together might prove to be very difficult.

## Accessing a C++ Object in C Code

Can C code, which of course is unaware of object semantics, access the data members of a C++ object directly? The short answer is, "Yes, but". There are some guarantees about the underlying memory layout of an object; C code can take advantage of these guarantees and treat a C++ object as an ordinary data struct, provided that all the following restrictions apply to the class of the object in question:

- The class has no virtual member functions (including inherited virtual functions of a base class).
- The class has no virtual base classes in the entire inheritance chain.
- The class has no member objects that have either a virtual base class or virtual member functions.
- All the data members of the class are declared without an intervening access specifier.

#### The Underlying Representation of an Object in Memory

Examine these restrictions in more detail, given the following declaration of the class Date:

```
class Date
{
public:
    int day;
    int month;
    int year;
    //constructor and destructor
    Date(); //current date
    ~Date();
    //a non-virtual member function
    bool isLeap() const;
    bool operator == (const Date& other);
};
```

The Standard guarantees that within every instance of class Date, data members are set down in the order of their declarations (static data members are stored outside the object and are therefore ignored). There is no requirement that members be set down in contiguous memory regions; the compiler can insert additional padding bytes (more on this in Chapter 11, "Memory Management") between data members to ensure proper alignment. However, this is also the practice in C, so you can safely assume that a Date object has a memory layout that is identical to that of the following C struct:

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues
```

```
/*** filename POD_Date.h***/
struct POD_Date
/* the following struct has memory layout that is identical
to a Date object */
{
   int day;
   int month;
   int year;
};
/*** POD_Date.h***/
```

Consequently, a Date object can be passed to C code and treated as if it were an instance of POD\_Date. That the memory layout in C and C++ is identical in this case might seem surprising; class Date defines member functions in addition to data members, yet there is no trace of these member functions in the object's memory layout. Where are these member functions stored? C++ treats nonstatic member functions as static functions. In other words, member functions are ordinary functions. They are no different from global functions, except that they take an implicit this argument, which ensures that they are called on an object and that they can access its data members. An invocation of a member function is transformed to a function call, whereby the compiler inserts an additional argument that holds the address of the object. Consider the following example:

```
void func()
{
   Date d;
   bool leap = d.isLeap(); //1
}
```

The invocation of the member function isLeap() in (1) is transformed by a C++ compiler into something such as

```
_x_isLeap?Date@KPK_Date@(&d); //pseudo C++ code
```

What was that again? Parse it carefully. The parentheses contain the this argument, which is inserted by the compiler in every nonstatic member function call. As you already know, function names are mangled. \_x\_isleap?Date@KPK\_Date@ is a hypothetical mangled name of the member function bool Date::isleap() const;. In the hypothetical C++ compiler, every mangled name begins with an underscore to minimize the potential for conflicts with user-given names. Next, the x indicates a function, as opposed to a data variable. isleap is the user-given name of the function. The ? is a delimiter that precedes the name of the class. The @ that follows the class name indicates the parameter list, which begins with a KPK and Date to indicate a const pointer to a const Date (the this argument of a const member function is a const pointer to a const object). Finally, a closing @ indicates the end of the parameter list. \_x\_isleap?Date@KPK\_Date@ is, therefore, the underlying name of the member function bool Date::isleap() const;. Other compilers are likely to use different name mangling schemes, but the details are quite similar to the example presented here. You must be thinking: "This is very similar to the way procedural programming manipulates data." It is. The crucial difference is that the compiler, rather than the human programmer, takes care of these low-level details.

#### The C++ Object Model is Efficient

The object model of C++ is the underlying mechanism that supports object-oriented concepts such as constructors and destructors, encapsulation, inheritance, and polymorphism. The underlying representation of class member functions has several advantages. It is very efficient in terms of execution speed and memory usage because an object does not store pointers to its member functions. In addition, the invocation of a nonvirtual member function does not involve additional lookup and pointer dereferencing. A third advantage is backward compatibility with C; an object of type Date can be passed to C code safely because the binary representation of such an object complies with the binary representation of a corresponding C struct. Other object-oriented languages use a radically different object model, which might not be compatible with either C or C++. Most of them use *reference semantics*. In a reference-based object model, an object is represented as a reference (a pointer or a handle) that refers to a memory block in which data members and pointers to functions are stored. There are some advantages to reference semantics; for example, reference counting and garbage collection are easier to implement in such languages, and indeed such languages usually provide automatic reference counting and garbage collection. However, garbage collection also

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 13 - C Language Compatibility Issues

incurs additional runtime overhead, and a reference-based model breaks down backward compatibility with C. The C++ object model, on the other hand, enables C++ compilers to be written in C, and (as you read in Chapter 6, "Exception Handling,") early C++ compilers were essentially C++-to-C translators.

#### **Memory Layout of Derived Objects**

The Standard does not specify the memory layout of base class subobjects in a derived class. In practice, however, all C++ compilers use the same convention: The base class subobject appears first (in left-to-right order in the event of multiple inheritance), and data members of the derived class follow. C code can access derived objects, as long as the derived class abides by the same restrictions that were specified previously. For example, consider a nonpolymorphic class that inherits from Date and has additional data members:

```
class DateTime: public Date
{
public: //additional members
long time;
bool PM; //display time in AM or PM?
DateTime();
~DateTime();
long getTime() const;
};
```

The two additional data members of DateTime are appended after the three members of the base class Time, so the memory layout of a DateTime object is equivalent to the following C struct:

```
/*** filename POD_Date.h***/
struct POD_DateTime
{
  int day;
  int month;
  int year;
  long time
  bool PM;
};
/*** POD_Date.h***/
```

In a similar vein, the nonpolymorphic member functions of DateTime have no effect on the size or memory layout of the object.

The compatible memory layout of nonpolymorphic C++ objects and C structs has many useful applications. For example, it enables relational databases to retrieve and insert objects into a database table. Data Manipulation Languages, such as SQL, that do not support object semantics, can still treat a "live" object as a raw chunk of memory. In fact, several commercial databases rely on this compatibility to provide an object-oriented interface with an underlying relational data model. Another application is the capability to transmit objects as a stream of bytes from one machine to another.

#### **Support for Virtual Member Functions**

What happens when an object becomes polymorphic? In this case, backward compatibility with C is trickier. As was noted previously, the compiler is allowed to insert additional data members to a class in addition to user-declared data members. These members can be padding bytes that ensure proper alignment. In the case of virtual functions, an additional member is inserted into the class: a pointer to the virtual table, or \_vptr. The \_vptr holds the address of a static table of function pointers (as well as the runtime type information of a polymorphic class; see Chapter 7, "Runtime Type Identification"). The exact position of the \_vptr is implementation-dependent. Traditionally, it was placed after the class's user-declared data members. However, some compilers have moved it to the beginning of the class for performance reasons. Theoretically, the \_vptr can be located anywhere inside the class -- even among user-declared members.

A virtual member function, like a nonvirtual member function, is an ordinary function. When a derived class overrides it, however, multiple distinct versions of the function exist. It is not always possible to determine at compile time which of these functions needs to be invoked. For example

```
#include <iostream>
using namespace std;
class PolyDate
public:
//PolyDate has the same members as Date but it's polymorphic
virtual void name() const { cout<<"PolyDate"<<endl;}</pre>
class PolyDateTime: public PolyDate
public:
// the same members as DateTime but it's polymorphic
void name() const { cout<<"PolyDateTime"<<endl;} //override PolyDate::name()</pre>
};
When these classes are compiled, the hypothetical compiler generates two underlying functions that correspond to
PolyDate::name() and PolyDateTime()::name():
      // mangled name of void PolyDate::name() const
_x_name?PolyDate@KPK_PolyDate@
      // mangled name of void PolyDateTime::name() const;
_x_name?PolyDateTime@KPK_PolyDateTime@
```

So far, there's nothing unusual about this. You already know that a member function is an ordinary function that takes an implicit this argument. Because you have defined two versions of the same virtual function, you also expect to find two corresponding functions, each of which has a distinct mangled name. However, unlike nonvirtual functions, the compiler cannot always transform an invocation of a virtual member function into a direct function call. For example

```
void func(const PolyDate* pd)
{
   pd->name();
}
```

func() can be located in a separate source file, which might have been compiled before class PolyDateTime was defined. Therefore, the invocation of the virtual function name() has to be deferred until runtime. The compiler transforms the function call into something such as

```
(* pd->_vptr[2]) (pd);
```

Analyze it; the member \_vptr points to the internally-generated virtual table. The first member of the virtual table is usually saved for the address of the destructor, and the second might store the address of the class's type\_info. Any other user-defined virtual member functions are located in higher positions. In this example, the address of name() is stored at the third position in the virtual table (in practice, the name of the \_vptr is also mangled). Thus, the expression pd->\_vptr[2] returns the address of the function name() associated with the current object. pd, in the second occurrence, represents the this argument.

Clearly, defining a corresponding C struct is more precarious in this case and requires intimate acquaintance with the compiler's preferred position of the \_vptr as well as with its size. There is another hazard here: The value of the \_vptr is transient, which means that it might have a different value, according to the address space of the process that executes the program. Consequently, when an entire polymorphic object is stored in a file and retrieved later, the retrieved data cannot be used as a valid object. For all these reasons, accessing polymorphic objects from C code is dangerous and generally needs to be avoided.

#### Virtual Inheritance

C code does not access objects that have a virtual base class either. The reason is that a virtual base is usually represented in the form of a pointer to a shared instance of the virtual subobject. Here again, the position of this pointer among user-defined data members is implementation-dependent. Likewise, the pointer holds a transient value, which can change from one execution of the program to another.

#### **Different Access Specifiers**

The fourth restriction on the legality of accessing C++ objects from C code states that all the data members of the class are declared without an intervening access specifier. This means, theoretically, that the memory layout of a class that looks similar to the following

```
class AnotherDate
{
  private:
    int day;
  private:
    int month;
  private:
    int year;
  public:
    //constructor and destructor
    AnotherDate(); //current date
    ~AnotherDate();
    //a non-virtual member function
    bool isLeap() const;
    bool operator == (const Date& other);
};
```

might differ from a class that has the same data members declared in the same order, albeit without any intervening access specifiers. In other words, for class AnotherDate, an implementation is allowed to place the member month before the member day, year before month, or whatever. Of course, this nullifies any compatibility with C code. However, in practice, all current C++ compilers ignore the access specifiers and store the data members in the order of declaration. So C code that accesses a class object that has multiple access specifiers might work -- but there is no guarantee that the compatibility will remain in the future.

#### **Conclusions**

The creators of C++ have attempted to preserve, as closely as possible, backward compatibility with C. Indeed, almost without exception, every C program is also a valid C++ program. Still, there are some subtle differences between the seemingly common denominator of the two languages. Most of them, as you might have noted, derive from the improved type-safety of C++. -- for example, the obligatory declaration of a function prior to its usage, the need to use explicit cast of void pointers to the target pointer, the deprecation of implicit int declarations, and the enforcement of a null terminator in a string literal. Other discrepancies between the two languages derive from the different rules of type definition.

C code can be called directly from C++ code. Calling C++ code from C is also possible under certain conditions, but it requires additional adjustments regarding the linkage type and it is confined to global functions exclusively. C++ objects can be accessed from C code, as you have seen, but here again, there are stringent constraints to which you must adhere.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.

# ANSI/ISO C++ Professional Programmer's Handbook

Contents

## 14

# **Concluding Remarks and Future Directions**

by Danny Kalev

- Some of the Features that Almost Made It into the Standard
  - Hashed Associative Containers
  - O Default Type Arguments of Function Templates
- The Evolution of C++ Compared to Other Languages
  - Users' Convenience
  - o "Pay as You Go"
- Possible Future Additions to C++
  - Automatic Garbage Collection
  - Object Persistence
  - Support for Concurrency
  - Extensible Member Functions
  - Dynamically Linked Libraries
  - o Rule-Based Programming
- Conclusions

"Hey, we're done!"

(Josee Lajoie's words right after the approval of the C++ Final Draft International Standard in the November 1997 meeting of the ANSI/ISO C++ standardization committee in Morristown, New Jersey)Introduction

The previous chapters have told the past and the present of C++. In nearly 20 years, C++ has evolved from an experimental language into the most widely used object-oriented programming language worldwide. The importance of standardizing C++ cannot be overemphasized. Having the ANSI/ISO endorsement has several advantages:

• Language stability -- C++ is probably the largest programming language in commercial use today. Learning

it from scratch is a demanding and time-consuming process. It is guaranteed that, henceforth, learning C++ is a one-time investment rather than an iterative process.

- Code stability -- The Standard specifies a set of deprecated features that might become obsolete in the future. Other than that, Fully ANSI-compliant code is guaranteed to work in the future.
- **Manpower portability** -- C++ programmers can switch more easily to different environments, projects, compilers, and companies.
- Easier Portability -- The standard defines a common denominator for all platforms and compiler vendors, enabling easier porting of software across various operating systems and hardware architectures.

The following code sample is Standard-compliant; however, some compilers will reject it, whereas others will compile it without complaints:

```
#include <iostream>
using namespace std;
void detect_int(size_t size)
 switch(size)
   case sizeof(char):
     cout<<"char detected"<<endl;</pre>
   break;
   case sizeof(short):
     cout<<"short detected"<<endl;</pre>
   break;
   case sizeof(int):
     cout << "int detected" << endl;
   break;
   case sizeof(long):
     cout << "int detected " << endl;
   break;
```

On platforms that have distinct sizes for all four integral types (for example, architectures that use 16 bits for short, 32 bits for int, and 64 for long) this code will compile and work as expected. On other platforms, where the size of int overlaps with the size of another integral type, the compiler will complain on identical case labels.

The point to take home from this example is that the Standard does not guarantee absolute code portability, nor does it ensure binary compatibility. However, it facilitates software porting from one platform to another by defining a common ground for the language, which an implementation is allowed to extend. This practice is almost universal: Platform-specific libraries and keywords are added to almost every C++ implementation. However, an implementation cannot alter the specifications of the Standard (otherwise, such an implementation is not Standard-compliant). As you will read in the following sections, allowing platform-specific extensions is an important factor in the success of programming languages in general; languages that have attempted to prohibit platform-specific extensions have failed to obtain a critical mass of users due to a lack of vendor support.

#### Scope of this Chapter

The previous chapters mostly focus on the hows of C++; this chapter explores the whys. It elucidates the philosophy behind the design and evolution of C++ and compares it to the evolution of other programming languages. Some features that almost made it into the Standard are then presented. Possible future additions to C++, including automatic garbage collection, object persistence, and concurrency, are discussed next. Finally, theoretical and experimental issues are discussed. The intent is not to predict the future of C++ (there is no guarantee that any of the features discussed here will ever become an integral part of the Standard), but rather to give you a broader view of the challenges of language design.

# Some of the Features that Almost Made It into the Standard

The standardization of C++ lasted nine years. STL alone added at least one more year to the original agenda. However, STL was an exception. Other features that were proposed too late were not included in the Standard. The following section lists two such features: hashed associative containers and default type arguments of function templates.

#### **Hashed Associative Containers**

The STL sorted associated containers are map, multimap, set, and multiset (see Chapter 10, "STL and Generic Programming"). However, there is another type of associated container, the *hashed associative container*, that should really be in the Standard Library but isn't there because it was proposed too late. The difference between a sorted associative container and a hashed associative container is that the former keeps the keys sorted according to some total order. For example, in a map<string, int>, the elements are sorted according to the lexicographical order of the strings. A hashed associative container, on the other hand, divides the keys into a number of subsets, and the association of each key to its subset is done by a hash function. Consequently, searching a key is confined to its subset rather than the entire key space. Searching a hashed associative container can therefore be faster than searching a sorted associative container under some circumstances; but unlike sorted associated containers, the performance is less predictable. There are already vendors that include hashed associated containers as an extension, and it is likely that these containers will be added to the Standard in the next revision phase.

#### **Default Type Arguments of Function Templates**

As you read in Chapter 9, "Templates," class templates can take default type arguments. However, the Standard disallows default type arguments in function templates. This asymmetry between class templates and function templates is simply an unfortunate oversight that was discovered too late to be fixed. Default type arguments of function templates will most likely be added to C++ in the next revision of the Standard.

# The Evolution of C++ Compared to Other Languages

Unlike other newer languages, C++ is not an artifact of a commercial company. C++ does not bear the trademark sign, nor do any of its creators receive royalties for every compiler that is sold. Thus, C++ is not subjected to the marketing ploys and dominance battles that rage among software companies these days. Another crucial factor that distinguishes C++ from some other "would-be perfect" programming languages is the way in which it has been designed and extended through the years.

Some of you might recall the tremendous hype that surrounded Ada in its early days. Ada was perhaps the most presumptuous endeavor to create a language that was free from the deficiencies of the other programming languages that existed at that time. Ada promised to be a 100% portable language, free of subsets and dialects. It also provided built-in support for multitasking and parameterized types. The design of Ada lasted more than a decade, but it was a *design by committee* process rather than the *design by community* process that characterizes C++. The facts are known: Ada never really became the general purpose, widely used programming language it intended to be. It is amusing to recall today that back in 1983, when Ada was released, many believed that it was the last third generation programming language to be created. Ironically, C++ was making its first steps at exactly that same time. Needless to say, the design and evolution of C++ have taken a radically different path. Other third generation languages have appeared since 1983 and -- surely -- new third generation languages will appear in the future. The factors that led to the failure of Ada as a universal and general purpose programming language can serve as a lesson in language design.

#### **Users' Convenience**

The failure of Ada can be attributed mostly to the design by committee approach. In addition, the prohibition of platform-specific extensions deterred vendors from developing libraries and tools that supported the new language. It is always surprising to learn how computer scientists and language users differ in their views about the important features of the language. C, which was created by programmers rather than by academia, offered convenience and efficiency at the expense of readability and safety. For example, the capability to write statements such as this one

```
if (n = v) //did the programmer mistook assignment for equality? 
 \{ //...do something \}
```

has been a source of criticism. Still, it is this very feature that enables programmers to write a complete function that consists of a single statement such as the following:

```
void strcpy (char * dst, const char * src)
{
  while( *dst++ = *src++ );
}
```

The tedium of typing long keywords is also an issue of debate. "Academic languages" usually advocate the use of verbose statements that consist of complete keywords -- for example, integer rather than int, character rather than char (as in Eiffel and other similar languages), and call func(); rather than func();. Programmers, on the other hand, feel more comfortable with truncated keywords and symbols. Look at the following:

```
class Derived : Base {}; //inheritance indicated by :
```

In other languages, inheritance is expressed by explicit keywords:

```
class Derived extends Base {}; //Java; full keyword indicates inheritance
```

C++ adopts the policy of C in this respect. Furthermore, according to Bjarne Stroustrup, one of the principles in the design of C++ says that where there is a choice between inconveniencing the compiler writer and annoying the programmer, choose to inconvenience the compiler writer (*The Evolution of C++: Language Design in the Marketplace of Ideas*, p.50). The implementations of operator overloading, enum types, templates, default arguments, and Koenig lookup are instances of this approach. Programmers can get along without direct language

support for these features, at the cost of inconvenience: Ordinary functions can be used instead of overloaded operators, constants can replace enum types, and fully qualified names can make up for the lack of Koenig lookup. Fortunately, this is not the case in C++. Other languages, however, have adopted the opposite approach, namely simple compiler writing at the cost of inconveniencing the programmers. Java, for instance, does not have enum types, operator overloading, and default arguments by design. Although these features do not incur overhead of any kind, and no one doubts their importance and usefulness, they make a compiler writer's work more difficult (originally, Java designers claimed that operator overloading was an unnecessary complexity).

#### "Pay as You Go"

The benefits of object-oriented programming are not free. The automatic invocation of constructors and destructors is very handy, but it incurs additional overhead in the speed and the size of the program. Likewise, dynamic binding and virtual inheritance also impose performance penalties. But none of these features is forced on the programmer. Pure procedural C++ code (legacy C code that is ported to a C++ compiler, for example) does not pay for these features. In other words, users -- almost without exception -- have a choice between higher-level features, which impose a performance penalty, and lower-level features, which are free from these performance penalties but are more susceptible to design modifications and are harder to maintain. The "pay as you go" principle enables programmers to use C++ in diverse application domains and apply different programming paradigms according to their needs and priorities.

#### Possible Future Additions to C++

It's hard to predict which new features will be added to C++ in the future, mostly because it's hard to predict what programming in general will be like five or ten years from now. However, automatic garbage collection, concurrency, and object persistence are already implemented in many other object-oriented programming languages; in the future, they might be added to C++ as well. Rule-based programming and better support for dynamically linked libraries are other such possible extensions that C++ might or might not have in the future. The following sections discuss these features, and their incurred complications, in greater detail.

#### **Automatic Garbage Collection**

"If the programmer's convenience is that important, why doesn't C++ have a garbage collector?" is an often-heard question (garbage collection is also discussed in Chapter 11, "Memory Management"). Clearly, an automated garbage collector can make the life of a programmer easier. However, unlike objects, virtual member functions, and dynamic casts, the programmer does not have the freedom of choice with garbage collection. If garbage collection is an automatic process that is hidden from the programmer, it violates the "pay as you go" principle. The cost of automatic garbage collection is forced on users, even if they prefer to manage dynamic memory manually.

Is it possible to add automated garbage collection as a switch (very much like the capability to turn off RTTI support in some compilers)? This is an interesting question. Surely, in programs that do not use dynamic memory allocation, the programmer might want to turn the garbage collector off. The real crux is with programs that allocate memory dynamically. Consider the following example:

```
void f()
{
  int * p = new int;
  //...use p
}
```

When the garbage collector is switched on, the implementation will mark the pointer p as unreferenced when f ()

exits. Consequently, in the next invocation of the garbage collector, the memory pointed to by p will be released. Adding a garbage collector for such simple cases is overkill, though. The programmer can use an auto\_ptr (auto\_ptr is discussed in Chapter 6, "Exception handling," and in Chapter 11) to achieve the same effect. For example

```
void f()
{
  auto_ptr<int> p (new int);
  //...use p
} //auto_ptr's destructor releases p
```

Garbage collection is more useful when dynamic memory has to be released at a different scope from where it was allocated. For example, virtual constructors (which are discussed in Chapter 4, "Special Member Functions: Default Constructor, Copy Constructor, Destructor, and Assignment Operator") enable the user to instantiate a new object of the right type, without having to know the exact type of the source object (the example is repeated here for convenience):

```
class Browser
public:
 Browser();
 Browser( const Browser&);
 virtual Browser* construct()
    { return new Browser; } //virtual default constructor
 virtual Browser* clone()
    { return new Browser(*this); } //virtual copy constructor
 virtual ~Browser();
//...
};
class HTMLEditor: public Browser
public:
 HTMLEditor ();
 HTMLEditor (const HTMLEditor &);
 HTMLEditor * construct()
    { return new HTMLEditor; }//virtual default constructor
 HTMLEditor * clone()
    { return new HTMLEditor (*this); } //virtual copy constructor
  virtual ~HTMLEditor();
  //...
};
```

In a garbage collected environment, it is possible to use a virtual constructor in the following way:

```
void instantiate (Browser& br)
{
  br.construct()->view();
}
```

Here again, the system automatically registers the unnamed pointer that is returned from br.construct() and marks it as unreferenced so that the garbage collector can later destroy its associated object and recycle its storage.

In a non-garbage collected environment, instantiate() causes a memory leak because the allocated object is never deleted (it might cause undefined behavior as well because the allocated object is never destroyed). To enable this programming practice, a garbage collector is mandatory rather than optional. You might suggest that instantiate() is to be written as follows:

```
void instantiate (Browser& br)
{
   Browser *pbr = br.construct();
   pbr->view();
   delete pbr;
}
```

This way, instantiate() can be used in a non-garbage collected environment as well as in a garbage collected one: When the garbage collector is active, the delete statement is ignored (perhaps by some macro magic) and the dynamically allocated object is automatically released some time after instantiate() has exited. The delete statement is executed only when the garbage collector is inactive. However, there is another subtle problem here.

#### The Problem with Late Destructor Invocation

In a non-garbage collected environment, pbr is deleted right before instantiate() exits, which means that the destructor of the dynamically allocated object is also invoked at that point. Conversely, in a garbage collected environment, the destructor will be activated at an unspecified time after instantiate() exits. The programmer cannot predict when this will happen. It might take a few seconds, but it can also take hours or even days before the garbage collector is invoked the next time. Now suppose that the destructor of Browser releases a locked resourcesuch as a database connection, a lock, or a modem. The program's behavior in a garbage collected environment is unpredictable -- the locked resource can cause a deadlock because other objects might be waiting for it, too. In order to avert such a potential deadlock, destructors can perform only operations that do not affect other objects, and locked resources have to be released explicitly by calling another member function. For example

```
void instantiate (Browser& br)
{
   Browser *pbr = br.construct();
   pbr->view();
   pbr->release(); //release all locked resources delete pbr;
}
```

This is, in fact, the predominant technique in garbage collected languages. Then again, to ensure interoperability between a garbage collected environment and a non-garbage collected one, programmers will have to write a dedicated member function that releases locked resources that the class acquires -- even if that class is used in a non-garbage collected environment. This is an unacceptable burden and a violation of the "pay as you go" principle. The conclusion that can be drawn from this discussion is that garbage collection cannot be optional. It is nearly impossible to write efficient and reliable programs that work in both environments. Either automatic garbage collection needs to be an integral part of the language, or it is totally out (as is the case in C++ at present).

#### **Time-Critical Applications**

Garbage collection cannot be optional, as you have observed. Why not make it an integral part of the language? Real-time systems are based on deterministic time calculations. For example, a function that has to execute within a time slot of 500 microseconds should never exceed its allotted time slice. However, the garbage collection process is non-deterministic -- it is impossible to predict when it will be invoked, and how long it will take. Therefore,

languages that offer automatic garbage collection are usually disqualified for use in time-critical applications. Note that real-time programming is not confined to missile launching and low-level hardware manipulation; most modern operating systems include time-critical components that control the allocation of system resources among processes and threads. Many communication systems are also deterministic by nature. Adding an automated garbage collector to C++ would disqualify it from being used in such application domains. Because a toggled garbage collector is also impractical, C++, by design, is not a garbage collected language at present. Notwithstanding the difficulties involved in garbage collection, there are some serious discussions of adding garbage collection to C++. It is too early to determine if and when this will happen.

#### **Object Persistence**

Persistent objects can be stored in nonvolatile storage and used later in other runs of the same program or in other programs. Storing the contents of an object in persistent storage is called *serialization*. The process of reconstituting a serialized object from a persistent repository is called *deserialization*, or *reconstitution*. Other object-oriented languages support object persistence directly by means of a library or built-in keywords and operators. C++ does not support object persistence directly. Designing an efficient, general purpose, platform-independent model of object persistence is quite a challenge. This section exemplifies handmade solutions that make up for the lack of language support for persistence. The difficulties and complications that are associated with a handmade object persistence model demonstrate the importance of language support.

#### Serialization and Deserialization of Concrete Objects

Consider the following class:

```
class Date
{
private:
   int day;
   int month;
   int year;
   //constructor and destructor
public:
   Date(); //current date
   ~Date();
   //...
};
```

Storing a Date object is a rather straightforward operation: Every data member is written to a persistent stream (usually this is a local disk file, but it can also be a file on a remote computer). The data members can be read from the stream at a later stage. For that purpose, two additional member functions are required, one for storing the object and the other for reading the stored object:

```
#include<fstream>
using namespace std;
class Date
{
//...
  virtual ofstream& Write(ofstream& archive);
  virtual ifstream& Read(ifstream& archive);
};
ofstream& Date::Write(ofstream& archive)
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 14 - Concluding Remarks and Future Directions
{
    archive.write( reinterpret_cast<char*> (&day), sizeof(day));
    archive.write( reinterpret_cast<char*> (&month), sizeof(month));
    archive.write( reinterpret_cast<char*> (&month), sizeof(year));
    return archive;
}
ifstream& Date::Read(ifstream& archive)
{
    archive.read( reinterpret_cast<char*> (&day), sizeof(day));
    archive.read( reinterpret_cast<char*> (&month), sizeof(month));
    archive.read( reinterpret_cast<char*> (&month), sizeof(year));
    return archive;
}
```

In addition to the member functions Read() and Write(), it is necessary to define a *reconstituting constructor*, which reads a serialized object from a stream:

```
Date::Date(ifstream& archive) //reconstituting constructor
{
   Read(arcive);
}
```

#### **Class Hierarchies**

For concrete classes such as Date, whose members are fundamental types, making up for the lack of standardized persistence facilities is rather straightforward. The serialization and deserialization operations merely store and read data members, respectively. Note that the class's member functions are not serialized. This is not a major issue of concern because the serialized object should be a close approximation of the binary representation of the object in memory.

Handling derived classes and classes that contain member objects is more complicated: The member functions Read() and Write() need to be redefined in every class in the hierarchy. Likewise, a reconstituting constructor is required for every class, as in the following example:

```
class DateTime: public Date
{
  private:
    int secs;
    int minutes;
    int hours;
public:
    //...
    DateTime::DateTime(ifstream& archive); //reconstituting constructor
    ofstream& Write(ofstream& archive);
    ifstream& Read(ifstream& archive);
};

ofstream& DateTime::Write(ofstream& archive)
{
    Date::Write(archive); //must invoke base class Write() first
    archive.write( reinterpret_cast<char*> (&), sizeof(day));
    archive.write( reinterpret_cast<char*> (&month), sizeof(month));
```

```
ANSI/ISO C++ Professional Programmer's Handbook - Chapter 14 - Concluding Remarks and Future Directions
    archive.write( reinterpret_cast<char*> (&month), sizeof(year));
    return archive;
}
ifstream& DateTime::Read(ifstream& archive)
{
    Date::Read(archive);
    archive.read( reinterpret_cast<char*> (&day), sizeof(day));
    archive.read( reinterpret_cast<char*> (&month), sizeof(month));
    archive.read( reinterpret_cast<char*> (&month), sizeof(year));
    return archive;
}
DateTime::DateTime(ifstream& archive) //reconstituting constructor
{
        Read(arcive);
}
```

#### **Third Party Classes**

Overriding the member functions Read() and Write() and serializing data members to and from a stream are error prone and can cause maintenance difficulties. Whenever data members are added or removed, or when their types are changed, the implementer has to modify these member functions accordingly -- but this is still managable. However, deriving from classes that do not define a reconstituting constructor and the member functions Read() and Write() is more difficult to handle because a derived class can only serialize its own members -- not members of its base classes. The same difficulties exist with embedded objects. How are such subobjects serialized? It might be possible to overcome these difficulties in some cases, albeit with considerable efforts. For example, a class that contains a vector can iterate through the vector's members and serialize them one by one. This is only half the story, though. A vector's state depends on other parameters, such as its capacity. Where can this information be stored if the vector object itself cannot be serialized? Serializing arrays is another conundrum. One solution is to write a header in the beginning of every serialized object that contains the number of elements. However, this won't work with reference counted objects. Most implementations of std::string are reference counted, which means that in the following code snippet, the five string objects share some of their data members:

```
#include <string>
using namespace std;
void single_string()
{
   string sarr[4];
   string s = sarr[0];
   for (int i = 1; i < 4; i++)
   {
      sarr[i] = s;
   }
}</pre>
```

Reference counting is an implementation detail that is hidden from the users of the class; it is impossible to query the string object about how many strings it represents and to serialize this datum.

Handmade object persistence is becoming much more complicated than it seemed at first, isn't it? But that's not all yet. How might such a handmade persistence model represent templates? By simply storing specializations as ordinary objects, the model fails to represent the relationship that exists among the specializations. Worse yet, multiple inheritance and virtual inheritance are even more challenging. How can a handmade persistence model

ensure that a virtual subobject is serialized only once, regardless of the number of its occurrences in the inheritance graph?

#### A Proposal for a Standardized Persistence Model

Most programmers probably give in at this point, and rightfully so. It is possible to come up with a solution even to the virtual base class problem, but as soon as this problem is solved, other special cases such as function objects, static data members, reference variables, and unions present more complexities. There is another drawback in the handmade persistence model: It is not standardized, and as such, programmers have to implement it on their own. The result is a lack of uniformity and varying levels of reliability and performance. Without standardized support for object persistence, a homemade persistence model is, at best, brittle and error prone. Obviously, without standardized object persistence it is impossible to ensure simple, portable, and efficient serialization and deserialization of objects.

#### **Library-Based Extensions**

What might such a standardized persistence model look like? There are two basic strategies. One is library-based, whereas the other relies on core language extensions (keywords and syntax). A library-based solution is advantageous in many respects. For example, it does not extend the core language, thus avoiding additional burden for programmers who do not intend to use persistent objects. In addition, a library can be replaced by a better implementation from another vendor without having to switch to a different compiler. This practice can be seen today with people who uninstall the original STL implementation -- provided by the compiler vendor -- and replace it with another one. Still, a library-based solution has to deal with the lack of language support for persistence, and it must face the same difficulties and complications that were demonstrated previously (the intricacies and vagaries of the most widely used object distribution frameworks, namely the Distributed Component Object Model (DCOM) and the Common Object Request Broker Architecture (CORBA), prove this point). STL might have never become what it is today without built-in support for templates and operator overloading. Furthermore, the language support for templates was extended in various ways to provide the necessary constructs for STL (see Chapter 2, "Standard Briefing: The Latest Addenda to ANSI/ISO C+++," and Chapter 9). Similarly, the support for persistence requires core language extensions.

#### **A New Constructor Type**

The special member functions are automatically synthesized by the implementation if the programmer does not declare them explicitly and if the implementation needs them (see Chapter 4). Similarly, a language extension can be made so that another type of constructor, a *reconstituting constructor*, is either implicitly synthesized by the implementation when needed, or so that it can be declared by the programmer. As is the case with other constructor types, the programmers need to be allowed to override the default reconstituting constructor by defining it explicitly. The syntactic form of such a constructor must be distinct from all other constructor forms. In particular, a reconstituting constructor is not to be identified solely by its signature. In other words, the following

```
class A
{
//...
public:
   A(istream& repository ); //reconstituting ctor or an ordinary constructor
};
```

is not recommended. It might well be the case that the programmer's intention was to define an ordinary constructor that takes an istream object by reference and not a reconstituting constructor. Furthermore, such a convention might break existing code. A better approach is to add a syntactic clue that signifies a reconstituting constructor

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 14 - Concluding Remarks and Future Directions

exclusively. For example, by preceding the symbol >< to the constructor's name

the reconstituting constructor can take a single parameter of some stream type. This parameter is optional. When the reconstituting constructor is invoked without an argument, the implementation deserializes the object from a default input stream that can be specified in the compiler's setting (similar to the default location of the standard header files). To automate the serialization process, a serializing destructor is also necessary. How might such a destructor be declared? One solution is to add another type of destructor so that classes can have two destructor types. This is, however, troublesome because the object model of C++ is based on a single destructor per class. Adding another type of destructor is ruled out then. Perhaps there is no need to define a distinct destructor type. Instead, the existing destructor can do the serialization automatically: The compiler can insert into the destructor additional code that performs the necessary serialization operations. (As you know, compilers already insert code into user-defined destructors to invoke the destructors of base classes and embedded objects.)

Automating the serialization process has drawbacks, too. Not every class has to be serialized. The overhead of serializing an object should be imposed only when the user really needs it. Furthermore, the possibility of encountering runtime exceptions during serialization is rather high. A full hard disk, a broken network connection, and a corrupted repository are only a handful of the possible runtime exceptions that can occur during the process of writing the contents of an object to a permanent storage medium. However, throwing an exception from a destructor is highly undesirable (see Chapter 6), so perhaps automatic serialization during object destruction is too risky. Apparently, there is no escape from explicitly calling a member function to do the job. There are other obstacles here: How to handle the creation and serialization of an array of objects? How to synchronize changes in the definition of a class and the contents of an object that was serialized before the change took place? Every language that supports object persistence deals with these difficulties in its own way. C++ can borrow some of these ideas, too, or it can initiate innovative ideas.

This discussion gives you some feel of why language extensions are necessary, and what kind of obstacles they overcome. However hypothetical this discussion might seem, the evolution of C++ has been a democratic process. Many of the changes and extensions were initiated by users of the language rather than Standardization committee members. STL is probably the best example of this. If you have a comprehensive proposal for such an extension, you can present it to the Standardization committee.

#### **Support for Concurrency**

Concurrency is a generic term for multithreading and multiprocessing. Concurrent programming can effectively improve performance and responsiveness of an application, be it a word processor or a satellite homing system. C++ does not directly address the issues of multiprocessing, threads, and thread safety. It is important to note, however, that nothing in the Standard Library or the language itself *disallows* concurrency. Look at the example of exception handling: In a multithreaded environment, exception handling should be thread-safe, but a single-threaded environment can implement exception handling in a non-thread-safe manner; this is an implementation-dependent issue. Implementations are allowed to provide the necessary facilities for concurrency, and indeed many of them do so. Again, without direct support from the programming language, either by standardized libraries or by core extensions, the implementation of thread safety is more complicated and highly nonportable. There have been several proposals in the past for adding concurrency to C and C++. At present, however, none of these languages supports concurrency directly.

#### Multithreading

*Multithreading*, as opposed to multiprocessing, refers to the use of several control threads in a single process. Multithreading is therefore simpler to design and implement, and it enables the application to use system resources more effectively.

Because all threads in a process share the process's data, it is essential to synchronize their operation properly so that one thread does not interfere with another. For that purpose, *synchronization objects* are used. Various types of synchronization objects, such as mutex, critical section, lock, and semaphore offer different levels of resource allocation and protection. Unfortunately, the details and the characterizations of synchronization objects vary from platform to platform. A standard library of synchronization objects has to be flexible enough to enable users to combine platform-specific synchronization objects with standard objects. This is similar to the use of std::string and nonstandard string objects in the same program. Alternatively, the standard thread library could provide the basic interfaces of the synchronization objects, and the implementation would be platform-dependent. There is a problem with introducing multithreading support into the Standard, however: single-threaded operating systems such as DOS. Although these platforms are not very popular these days, they are still in use, and implementing a thread library on these platforms is nearly impossible.

#### Thread safety

Perhaps the Standard can provide only the necessary features for thread safety and leave the other issues -- such as synchronization objects, event objects, instantiation, destruction of threads, and so on -- implementation-defined, as they are today. Thread safety ensures that an object can be used safely in a multithreaded environment. For example, the following thread-unsafe class

```
class Date
private:
  int day;
  int month;
  int year;
public:
 Date(); //current date
  ~Date();
     //accessors
   int getDay() const { return day; }
   int getMonth() const { return month; }
   int getYear() const { return year; }
    //mutators
   void setDay(int d) { day = d; }
   void setMonth(int m) { month = m; }
  void setYear(int y) { year = y; }
};
```

can become thread-safe by applying the following changes to it: At the beginning of each member function, a lock has to be acquired; in every return point of each member function, the lock has to be released.

The modified member functions now look like this:

```
void Date::setDay(int d)
{
```

```
get_lock();
  day = d;
  release_lock();
}
void Date::setMonth(int m)
{
  get_lock();
  month = m;
  release_lock();
}
//etc.
```

This is tedious, and yet very simple to automate. The recurrent pattern is very reminiscent of the "resource acquisition is initialization" idiom (discussed in Chapter 5, "Object-Oriented Programming and Design"). You can define a class whose constructor acquires a lock, and whose destructor releases it. For example

```
class LockDate
{
private:
   Date& date;
public:
   LockDate(const Date& d) : date { lock(&d); }
   ~LockDate() { release(&d); }
};
```

A real-world lock class would probably be templatized. It would also provide timeouts and handle exceptions; however, the definition of LockDate suffices for this discussion. The member functions of Date can now be defined as follows:

```
int Date::getDay() const
{
   LockDate ld(this);
   return day;
}
/...and so on
void Date::getDay(int d)
{
   LockDate ld(this);
   day = d;
  }
//etc.
```

This looks better than the original thread-safe version, but it's still tedious. Standard C++, however, goes only that far. A fully automated thread safety requires core language extensions.

It might not seem obvious from the example why language support for thread safety is necessary. After all, instantiating a local object in every member function is not unacceptably complicated or inefficient. The troubles begin with inheritance. Invoking a non-thread-safe inherited member function might have undefined results in this case. To ensure thread safety in inherited member functions as well, the implementer of Date has to override every inherited member function. In each override, a lock has to be acquired. Then, the parent member function is invoked, and finally, the lock is released. With a little help from the programming language, these operations can be

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 14 - Concluding Remarks and Future Directions

made much easier.

#### **Before Method and After Method**

The CLOS programming language defines the concepts *before method* and *after method*. A before method is a sequence of operations that precedes the action of a method. An after method is a sequence of operations that succeeds the action of a method. Thus, each method (member function) in CLOS can be thought of as an object with a corresponding constructor and destructor. CLOS provides default before method and after method for each user-defined method. By default, the before method and after method do nothing. However, the user can override them to perform initialization and cleanup operations. Adopting this concept in C++ with slight modifications might simplify the implementation of thread-safe classes. One direction is to provide identical before method and after method for every member function of a class. That is, the before method and after method are defined only once, but they are automatically invoked by every member function of the class (except for the constructor and destructor). One of the benefits of this approach is that new member functions that are added to the class automatically become thread-safe, as do inherited member functions.

#### **Extensible Member Functions**

Several programming languages enable the user to compose inherited member functions in a derived class almost automatically. In C++, a member function of a derived class overrides rather than extends the corresponding member of the base class. It is possible to extend the inherited function by calling it explicitly before performing any other operations in the overriding member function (see Chapter 5). The following example (repeated here for convenience) shows how it is done:

There are two problems with this approach. First, if the base class name changes, the implementer of the derived class has to find every occurrence of the old qualified name and change it accordingly.

Another problem is that some member functions are meant to be extended rather than overridden. The best examples are constructors and destructors (which, luckily, the compiler takes care of), but there are other such examples. The serialization and deserialization operations that were discussed previously also need to be extended rather than overridden in a derived class.

It is very tempting to solve the first problem by adding the keyword super to the language. Smalltalk and other object-oriented languages already have it. Why not let C++ programmers enjoy it as well? super refers to the direct base class. It can be used in the following manner:

```
class rectangle: public shape
{
   //...
   void resize (int x, int y) //extends base's resize()
   {
```

```
super.resize(x, y); //the name of the base class is not necessary anymore
    //add functionality
    int size = x*y;
}
};
class specialRect: public rectangle
{
    void resize (int x, int y) //extends base's resize()
    {
        super.resize(x, y); //calls recatngle::resize()
        //add more functionality
    }
};
```

However, super is ambiguous in objects that have multiple base classes. An alternative solution is to add a different keyword to the language, extensible, that instructs the compiler to insert a call of the base member function in an overriding member function automatically. For example

extensible is a specialized form of virtual, so the latter is unnecessary. Surely, extensible solves the first problem: If the base class name changes, the implementer of the derived class does not have to change the definition of the member functions. The second problem is also solved here: After a member function is declared extensible, the compiler automatically sees that the corresponding member function of a derived class first invokes the member function of the base class.

#### **Dynamically Linked Libraries**

A typical C++ application consists of a statically linked executable that contains all the code and data of the program. Although static linking is efficient in terms of speed, it's inflexible: Every change in the code requires a complete rebuild of the executable. When a dynamically linked library is used, the executable does not need to be

rebuilt; the next time the application is run, it automatically picks up the new library version. The advantage of dynamically linked libraries is a transparent upgrade of new releases of the dynamically linked library. However, this transparent "drop in" model breaks under the object model of C++ if the data layout of an object changes in the new release of the library; this is because the size of an object and the offset of its data members are fixed at compile time. There have been suggestions to extend the object model of C++ so that it can support dynamic shared libraries better. However, the costs are slower execution speed and size.

#### **Rule-Based Programming**

Many commercial databases support *triggers*. A trigger is a user-defined rule that instructs the system to perform specific actions automatically whenever a certain data value changes. For example, imagine a database that contains two tables, Person and Bank Account. Every row in Bank Account is associated with a record in Person. Deleting a Person record automatically triggers the deletion of all its associated Bank Account records. Rules are the equivalent of triggers in software systems. William Tepfenhart and other researchers at AT&T Bell Laboratories have extended C++ to support rules (*UML and C++: A Practical Guide to Object-Oriented Development*, p. 137). The extended language is called R++ (the *R* stands for "rules"). In addition to member functions and data members, R++ defines a third kind of class member: a rule. A rule consists of a condition and an associated action that is automatically executed when the condition evaluates to true. In C++, the programmer has to test the condition manually in order to decide whether the associated action is to be executed, usually by a switch statement or an if statement. In R++, this testing is automated -- the system monitors the data members listed in the rule's condition, and whenever the condition is satisfied, the rule "fires" (that is, the associated action is executed). Rule-based programming is widely used in artificial intelligence, debugging systems, and event-driven systems. Adding this feature to C++ could considerably simplify the design and implementation of such systems.

### **Conclusions**

Language extensions are needed to facilitate the implementation of operations that otherwise might be more difficult or even impossible. However, there is always a tradeoff involved. To use an analogy, adding an air conditioner to a car decreases its fuel efficiency and degrades its performance (*Principles of Programming Languages: Design, Evaluation and Implementation*, p. 327). Whether it is a beneficial tradeoff depends on various factors, such as the climate in the region where the car is used, the cost of fuel, the engine's power, and the personal preferences of its users. Note that the air conditioner can always be turned off to gain more power and increase the fuel efficiency. Ideally, new language features will not impose a performance penalty of any kind when they are not used. When the programmer deliberately uses them, they should impose as little overhead as possible or no overhead at all. There is, however, a notable difference between an air conditioner and language extensions: Extensions interact with one another. For example, the imaginary keyword super has an undesirable interaction with another language feature, namely multiple inheritance. A more realistic example is template's template arguments. The space between the left two angular brackets is mandatory:

```
Vector <Vector<char*> > msq que(10);
```

Otherwise, the >> sequence is parsed as the right shift operator. In other situations, the interaction is much more complex: Koenig lookup, for instance, can have surprising results under some circumstances (as you read in Chapter 8, "Namespaces").

This chapter has presented three major proposals for language extensions: garbage collection, persistence, and concurrency. Suggestions for less radical extensions are extensible members and rules. None of these is to be taken lightly. The complexity involved in standardizing each of these is intensified even further when they interact with each other. For example, a persistence model becomes even more complicated in a thread-safe environment.

Considering the challenges that the designers of C++ have faced during the past two decades, you can remain

ANSI/ISO C++ Professional Programmer's Handbook - Chapter 14 - Concluding Remarks and Future Directions

optimistic. If you are familiar with the prestandardized implementations of container classes, RTTI, and exception handling of several well known frameworks, you are probably aware of how the standardized container classes, RTTI, and exception handling are much better in every way. This will also be the case if any of the features that are discussed here become part of the C++ Standard.

Contents

© Copyright 1999, Macmillan Computer Publishing. All rights reserved.



# ANSI/ISO C++ Professional Programmer's Handbook



# **Printed Book Copyright**

©Copyright 1999, by Que

All rights reserved. No part of this book shall be reproduced, stored in a retrieval system, or transmitted by any means, electronic, mechanical, photocopying, recording, or otherwise, without written permission from the publisher. No patent liability is assumed with respect to the use of the information contained herein. Although every precaution has been taken in the preparation of this book, the publisher and author assume no responsibility for errors or omissions. Neither is any liability assumed for damages resulting from the use of the information contained herein.

International Standard Book Number: 0-7897-2022-1

Library of Congress Catalog Card Number: 99-62146

Printed in the United States of America

First Printing: June 1999

00 99 98 4 3 2 1

### **Trademarks**

All terms mentioned in this book that are known to be trademarks or service marks have been appropriately capitalized. *Que* cannot attest to the accuracy of this information. Use of a term in this book should not be regarded as affecting the validity of any trademark or service mark.

# Warning and Disclaimer

Every effort has been made to make this book as complete and as accurate as possible, but no warranty or fitness is implied. The information provided is on an "as is" basis. The authors and the publisher shall have neither liability or responsibility to any person or entity with respect to any loss or damages arising from the information contained in this book.

# **Online Copyright**

# ©Copyright 1999, Macmillan Computer Publishing. All rights reserved.

No part of this book may be used or reproduced in any form or by any means, or stored in a database or retrieval system without prior written permission of the publisher except in the case of brief quotations embodied in critical articles and reviews.

For information, address Macmillan Publishing, 201 West 103rd Street, Indianapolis, IN 46290.

This material is provided "as is" without any warranty of any kind.