

Workday Studio
Product Summary

February 20, 2025

Contents

Setup Considerations: Workday Studio	10
Otradia Francisco de la	40
Studio Fundamentals	
Download and Install Workday Studio for Windows	
Download and Install Workday Studio for macOS	
Concept: Workday Studio	
Concept: Integration Development Lifecycle	
Concept: MediationContext Object	
Concept: Integration Systems and Events	
Integration Design	21
Assemblies	
Create an Assembly Project	
Add Child Elements	
Connect Assembly Elements	
Configure Assembly Element Properties	
Manage Collections and Projects	
Declare Namespace Prefixes	
Create Path Variables	
Concept: Assembly Palette	
Concept: Components and Steps	
Concept: Assembly Annotations	
Concept: Linked Resource Files for Assembly Projects	
Concept: Quick Outline View	
Reference: Assembly Properties	
Reference: Swimlane Properties	
Reference: Connection Line Properties	
Assembly Transports	31
Use Enumerations as Launch Parameters in Studio	31
Concept: Assembly Transports	32
Concept: Enumerations	34
Reference: Workday-In Transport Properties	35
Reference: Local-In Transport Properties	
Reference: Workday-Out-Rest Transport Properties	
Reference: Workday-Out-Soap Transport Properties	
Reference: Local-Out Transport Properties	
Reference: HTTP-Out Transport Properties	
Reference: FTP-Out Transport Properties	
Reference: FTPS-Out Transport Properties	
Reference: SFTP-Out Transport Properties	
Reference: XMPP-Out Transport Properties	
Reference: Custom-Out Transport Properties	
Reference: Email-Out Transport Properties	
HTTP-Out Transport Child Elements	
Concent: HTTP-Out Transport Child Flements	68

Reference: HTTP-Basic-Auth Properties	60
Reference: HTTP-Custom-Auth Properties	
Reference: HTTPS Properties	
FTPS-Out Transport Child Elements	
Concept: FTPS-Out Transport Child Elements	
Reference: Proxy-Properties Properties	
Reference: Firewall-Properties Properties	
Reference: Client-Key Properties	
Reference: Server-Key Properties	
SFTP-Out Child Elements	
Concept: SFTP-Out Child Elements	
Reference: Proxy-Properties Properties	
Reference: Private-Key Properties	
Components	
Concept: Components	
Reference: Async-Mediation Component Properties	74
Reference: Sync-Mediation Component Properties	
Reference: Custom-Mediation Component Properties	76
Reference: Route Component Properties	77
Reference: Splitter Component Properties	77
Reference: Aggregator Component Properties	77
Route Component Child Elements	78
Concept: Route Component Child Elements	78
Reference: Custom-Strategy Properties	
Reference: Regex-Strategy Properties	79
Reference: MVEL-Strategy Properties	
Reference: Round-Robin-Strategy Properties	
Reference: XPath-Strategy Properties	
Reference: Failover-Strategy Properties	
Reference: All-Strategy Properties	
Reference: Doc-Iterator Properties	
Reference: Loop Strategy Properties	
Reference: Choose-Route Properties	
Reference: Sub-Route Properties	
Splitter Component Child Elements	
Concept: Splitter Component Child Elements	
Reference: Custom-Splitter Properties	
Reference: Standard-Splitter Properties	
Reference: XPath-Splitter Properties	
Reference: XML-Stream-Splitter Properties	
Reference: JSON-Splitter Properties	
Reference: Unzip-Splitter Properties	
Reference: Mtable-Splitter Properties	
Standard-Splitter Child Elements	
Concept: Standard-Splitter Child Elements	
Reference: Header-Ends-With Properties	
Reference: Header-Fixed-Lines Properties	
Reference: Content-Fixed-Lines Properties	
Reference: Content-Starts-Ends Properties	
Reference: Content-Starts-With Properties	
Reference: Footer-Fixed-Lines Properties	
Reference: Footer-Starts-With Properties	
Aggregator Component Child Elements Concept: Aggregator Component Child Elements	
Reference: Custom-Batch-Strategy Properties	
Reference: Size-Batch-Strategy Properties	გგ

Reference: Time-Batch-Strategy Properties	
Reference: Custom-Collater Properties	
Reference: Message-Content-Collater Properties	
Reference: XML-Message-Content-Collater Properties	
Reference: JSON-Aggregator Properties	
Reference: Zip-File-Collater Properties	
Reference: Mtable-Collater Properties	
Common Components	
Concept: Common Components	
Reference: FTP Subassembly Properties	
Reference: GetEventConfigurations Subassembly Properties	
Reference: GetEventDocuments Subassembly Properties1	
Reference: GetIntegrationEvent Subassembly Properties1	
Reference: GetIntegrationSystems Subassembly Properties	
Reference: PagedGet Subassembly Properties1	
Reference: PagedGetLocalPaging Subassembly Properties1	
Reference: PdfPrintStep Subassembly Properties1	
Reference: PutIntegrationEvent Subassembly Properties1	
Reference: PutIntegrationMessage Subassembly Properties	
Reference: SalesforceConnector Subassembly Properties1	
The PrismAnalytics Subassembly1	
Error Handler Components	
Concept: Error Handler Components1	
Reference: Custom-Error-Handler Component Properties1	
Reference: Log-Error Component Properties1	
Reference: Send-Error Component Properties1	
Transform Steps1	
Convert Text to XML with a Text Schema File1	
Concept: Transform Steps1	
Reference: XSLT Step Properties1	
Reference: XSLT+ Step Properties1	
Reference: FOP Step Properties1	
Reference: Text-Excel Step Properties1	
Reference: TextSchema Step Properties1	153
Reference: Wrap-Soap Step Properties1	155
Reference: XML-to-Java Step Properties1	
Reference: JSON Transformer Properties1	
Reference: XML-to-JSON Step Properties1	160
Reference: JSON-to-XML Step Properties1	162
Reference: Java-to-XML Step Properties1	163
Reference: XML-to-CSV Step Properties1	
Reference: CSV-to-XML Step Properties1	
Reference: Character-Conversion Step Properties1	
Reference: Mtable-Builder Step Properties1	171
Reference: Mtable-Writer Step Properties1	172
Reference: ETV Step Properties1	174
Reference: XTT Step Properties1	175
Mtable-Builder Child Elements	
Concept: Mtable-Builder Child Elements1	
Reference: CSV-Mtable-Reader Properties1	
Reference: JSON-Mtable-Reader Properties1	177
Mtable-Writer Child Elements	
Concept: Mtable-Writer Child Elements1	178
Reference: CSV-Mtable-Writer Properties1	
Reference: JSON-Mtable-Writer Properties1	
Logging and Eventing Steps	179

Concept: Logging and Eventing Steps	
Reference: Log Step Properties	
Reference: Cloud-Log Step Properties	
Message Manipulation Steps	
Concept: Message Manipulation Steps	
Reference: Copy Step Properties	
Reference: JavaScript Step Properties	
Reference: Set-Headers Step Properties	
Reference: Write Step Properties	
Validation Steps	
Concept: Validation Steps	
Reference: Eval Step Properties	
Reference: Validate Step Properties	
Reference: Validate-Exp Step Properties	
Reference: Validate-Xpath Step Properties	
Encoding Steps	
Concept: Encoding Steps	
Concept: PGP Filenames	
Reference: PGP-Encrypt Step Properties	
Reference: PGP-Decrypt Step Properties	
Reference: Base64-Decode Step Properties	
Reference: Base64-Encode Step Properties	
Reference: Zip Step Properties	
Reference: Unzip Step Properties	208
Reference: Compress Step Properties	
Reference: Decompress Step Properties	
Other Steps	
Concept: Other Steps	213
Reference: Custom Step Properties	
Reference: Set-Dynamic-Endpoint Step Properties	215
Reference: Store Step Properties	216
Reference: Retrieve Step Properties	219
Reference: Xmldiff Step Properties	221
Reference: Enqueue-Message Step Properties	224
Assembly Modules	
Create Assembly Modules	226
Add Assembly Modules to a Project	227
Concept: Assembly Modules	228
Subassemblies	
Create Subassemblies	228
Concept: Subassemblies	229
Custom Assembly Components	
Create Custom Java Classes and Spring Beans	
Concept: Custom Assembly Elements	
Concept: Custom Element Packaging	232
Spring Bean Configuration	
Concept: Spring Bean Configuration	
Reference: Global Bean Properties	234
Reference: Individual Bean Properties	
Reference: Alias Properties	
Reference: Property Properties	236
Reference: Constructor-Arg Properties	237
Reference: Ref Properties	
Reference: List Properties	
Reference: Map Properties	
Managara Dullalan	000

	Create XML Literals Based on Schema or WSDLs	238
	Create XPath Expressions Based on Schema or WSDLs	239
	Concept: Workday Studio Message Builder	239
	Reference: Message Element Properties	241
Transp	port Bindings	244
	Concept: Transport Bindings	244
	Reference: WSDL-HTTP-Binding Properties	245
	Reference: WSDL-SOAP-Binding Properties	246
WSDL	-SOAP-Binding Child Elements	246
	Concept: WSDL-SOAP-Binding Child Elements	246
	Reference: Custom-Policy Properties	247
	Reference: WS-Rm Properties	247
	Reference: WS-Security Properties	247
	Reference: WS-Ut Properties	247
Schen	na Explorer	248
	Display WSDL and XSD Files	248
	Display Workday Web Service WSDLs	248
	Display Custom RaaS Report Schemas	249
	Concept: Schema Explorer	249
MVEL		
	Concept: MVEL Fundamentals	250
	Concept: MVEL and Studio	253
	Reference: Studio Helper Objects	253
	Reference: Document Accessor Helper Object	
	Reference: Launch Parameters Helper Object	262
	Reference: Util Helper Object	
	Reference: Sample Studio MVEL Expressions	
	Reference: Studio MVEL Auto-Conversion Syntax Samples	
	Reference: MVEL Methods	
Studio	Integration Services	273
	Create Attribute Map Services	273
	Create Delivery Services	275
	Create Listener Services	275
	Create Retrieval Services	276
	Create Sequence Generator Services	277
	Create Transaction Log Services	
	Create Report Services	278
	Create Custom Object Services	279
	Create Data Initialization Services	280
	Create Service References	
	Add References to Custom Reports on Workday-Out-Rest Transports	281
	Add References to Custom Objects on Workday-Out-Rest Transports	
CLAR	Files	
	Generate Manifest Files	283
	Import CLAR Files	
	Export CLAR Files	
	Concept: CLAR Files	
JAXB	Projects	
	Create JAXB Projects	
	Add JAXB Projects as Dependencies in Assembly Projects	
	Concept: JAXB Support in Studio	
Studio	Ivy Plugin	
	Configure the Ivy Plugin	
	Add Workday Ivy Natures on Workday Studio Projects	
	Resolve Dependencies for Projects with Ivy Definitions	
	Add Dependent JARs to Projects with Ivy Natures	

Remove Workday Ivy Natures from Studio Projects	290
Integration Deployment	290
Add a Connection	
Add a Group of Connections	
Edit a Connection	
Edit a Group of Connections	
Remove Connections.	
Import Connections	
Export Connections	
Connect to Workday	
Deploy Integrations to Workday	
View Deployed Integrations in Workday	
Configure Studio to Use a HTTPS Proxy Server	
Concept: Studio Connections	
Concept: Cloud Explorer	
Reference: Connection Errors	
Multifactor Authentication in Workday Studio	
Enable Multifactor Authentication in Workday Studio	
Enable Multifactor Authentication in Workday Studio	290
Integration Configuration	300
Assign an Integration System User Account to an Integration	
Concept: Integration System Security	
Integration Launching	301
Launch Integrations from Studio	
Copy Launch URLs	
Create Launch Configurations	
Edit Launch Configurations	
Integration Monitoring and Troubleshooting	303
Process Monitor	
Concept: Integration Event IDsReference: Process Monitor Toolbar Buttons	
Consolidated Report Viewer	
Load Consolidated Reports for Integrations	
Save Consolidated Reports to Your Workspace	
View Workday Integration Event Details Using Consolidated Reports	
View Request Messages for Integration Events Using Consolidated Reports	
Monitor Integrations with the Consolidated Report Viewer Events Log	
Monitor Integrations with the Consolidated Report Viewer Profile Log	
Replay Assembly Executions for Consolidated Reports	
Link Consolidated Report Audit Events to Assembly Elements	
Display Consolidated Report Annotations on Assembly Diagrams	
Concept: Consolidated Report Viewer	
Reference: Consolidated Report Error Messages	
AUnit Assembly Testing	
Create an AUnit Test Skeleton for an Assembly Project	
Concept: AUnit Tests	
Reference: AUnit Test Annotations	
Reference: AUnit Test Actions	
Web Service Testing	318

Test Web Services Using a WSDL File	
Test Web Services Using an XSD File	319
Test Individual Web Services from the Schema Explorer	320
Test Get Operations and Request Messages Using the Request Builder Wizard	320
Configure Web Service Tester Authentication	
Configure Web Service Tester X.509 Authentication	
Configure Web Service Tester Advanced WS-Security	
Concept: Web Service Testing	
Reference: Web Service Tester Toolbar Buttons	
Assembly Debugging	
Debug an Assembly	
Concept: Assembly Debugger	
Studio Management	
Studio Preferences	
Concept: Assembly Editor Preferences	
Concept: Connections Preferences	
Concept: Deployment Preferences	
Concept: HTTPS Preferences	328
Concept: Ivy Preferences	328
Concept: Linking Preferences	329
Concept: MVEL Validation Preferences	329
Concept: Packaged Integrations Preferences	329
Concept: Runtime Preferences	329
Concept: Server Preferences	
Concept: Splash Screen Login Preferences	
Concept: Status Bar Preferences	
Concept: Update Preferences	
Concept: XPath Explorer Preferences	
Reference: Assembly Debug Runtime Preferences	
Reference: Assembly Debug View Preferences	
Reference: Cloud Explorer Preferences	
Reference: Consolidated Report Viewer Preferences	
Reference: Java Project Settings Preferences	
Reference: Notification Preferences	
Reference: Process Monitor Preferences	
Reference: Web Service Tester Preferences	
Studio Updates	
Update Studio	
Workday Assembly Runtime Changes	
Concept: Assembly Versions	
Reference: Version Changes at the Schema Level	
Reference: Version Changes at the XML Level	
Reference: Saxon XSLT Processor Changes	
Sample Assemblies	341
Example: Run the Hello Cloud Sample Assembly	341
Example: Run the Hello Workday Web Services Sample Assembly	
Example: Run the Common Usage Patterns Sample Assembly	
Example: Run the Debugging Sample Assembly	
Example: Run the Workday-In Features Sample Assembly	
Example: Run the Error Handling Sample Assembly	
Example: Run the AUnit Sample Tests	
Example: Run the FOPStep Sample Assembly	

Example: Run the Extract Organization Data for a Worker Sample Assembly	350
Example: Run the PrismAnalytics Sample Assembly	
Third-Party Payroll Interface Sample	352
Steps: Run the Payroll Interface Sample	352
Create the Payroll Interface Security Group	353
Create the PayData Extract Integration System	354
Test the PayData Extract Integration System	355
Deploy the Studio PayData Integration	356
Assign an Integration System User to the PayData Integration	
Link the PayData Extract and PayData Integrations	
Launch the Linked Integrations	358

Note: The solutions described in this section are not part of the Workday Service. See Legal Notice for details.

You can use this topic to help make decisions when planning your configuration and use of Workday Studio. It explains:

- Why to set it up.
- How it fits into the rest of Workday.
- · Downstream impacts and cross-product interactions.
- Security requirements and business process configurations.
- Questions and limitations to consider before implementation.

Refer to detailed task instructions for full configuration details.

What It Is

Studio is an Eclipse[™]-based integrated development environment (IDE) that enables you to:

- Build custom integrations.
- Exchange bulk data with external endpoints.
- Upload integrations to Workday.

Studio is an external software application that you install separately from the rest of Workday.

Business Benefits

Studio improves productivity by enabling you to:

- Create integrations that support greater design flexibility than Enterprise Interface Builder (EIB) or connector templates.
- Debug the XML source code of your custom integrations.
- Export and import large volumes of data through Workday.
- Transform large datasets into a specific format. Example: You can transform CSV datasets into XML format.

Use Cases

You need:

- A custom integration that isn't available through EIB or connector templates. Example: An integration that implements XML-to-text (XTT) transformations on a dataset.
- An inbound integration to import bulk data to Workday from multiple data sources.
- An outbound integration that exports bulk data from Workday in a specific format.
- To conduct unit tests on the XML source code of a custom integration.

Questions to Consider

Question	Considerations
agreement with Oracle?	If yes, you can install Studio using Oracle JDK 1.8. If no, you can install Studio using OpenJDK 8.
Which platform are you using to install Studio?	Install the appropriate installation file for your platform:

Question	Considerations
	MacOS (64-bit)Windows (32-bit)Windows (64-bit)
Have you attended training for Studio?	For learners interested in taking Studio training, Workday offers a Creating Integrations Using Workday Studio course. Learn more in the Training Catalog.

Recommendations

Workday recommends that you deploy and test your custom Studio integrations in your Preview Sandbox environment before transferring them to your Production tenant.

Requirements

Studio integrations require a Java™ Development Kit (JDK) compatible with Java version 8. In addition, the Eclipse IDE requires a JDK compatible with Java version 11. If you:

- Have a license agreement with Oracle, use Oracle JDK 1.8 and Oracle JDK 1.11.
- Don't have an agreement with Oracle, use OpenJDK 8 and OpenJDK 11.

Both JDKs are required.

Limitations

Studio integration output files can be a maximum of:

- 1 GB (compressed) for individual files.
- 3 GB (compressed) total for all files.

Tenant Setup

You can access the source code of Studio integrations by selecting the Require Source Code check box on the Edit Tenant Setup - Integrations task in Workday. Accessing the source code of Studio integrations enables you to identify bugs and improve efficiency.

Security

Consider setting up these domains in the Integration functional area.

Domains	Considerations
Integration Build	Deploy integrations from Studio to Workday.
Integration Configure	Edit Studio integrations in Workday.
Integration Debug	Debug Studio integrations in Workday.
Integration Event	Launch Studio integrations in Workday.
Integration Security	Create an integration system user (ISU) account for your Studio integrations in Workday.

Business Processes

For Studio integrations, you can configure the:

- Integration Process Event business process in the Integration functional area to control how an integration runs.
- Integration business process step to launch an integration during a business process. Example: You can add an integration step to the Complete Form I-9 business process. This step launches an integration to send data for the worker in the business process.

Reporting

Workday provides these reports for Studio integrations:

Report	Description
Integration Events	Displays:
	 A summary of integration events that are in process or complete. The status of each integration event.
View Integration System	Displays all integration systems available in your Workday tenant.

Connections and Touchpoints

Studio interacts with different parts of Workday depending on the product area, purpose, and data sources of your integration:

- Inbound integrations add and update data in Workday.
- Outbound integrations extract data from Workday, but don't change the data in Workday.

Workday offers a Touchpoints Kit with resources to help you understand configuration relationships across your tenant. Learn more about the Workday Touchpoints Kit on Workday Community.

Studio Fundamentals

Download and Install Workday Studio for Windows

Context

Workday Studio is built on the Eclipse development platform. It comprises more than 150 Eclipse plugins in addition to platform and third-party dependencies. To use it, you need 2 versions of the Java™ Development Kit (JDK):

- Eclipse requires a JDK compatible with Java version 11.
- The Studio runtime requires a JDK compatible with Java version 8.

Install both JDKs and then ensure that:

- Your Java Runtime Environment is set to Java 8.
- Your JDK compiler compliance level is set to Java 1.8.

 Download and install a JDK that's compatible with Java version 11. You can download the software from Oracle or you can use the free open-source implementation, OpenJDK.

Source	Notes
	Requires a commercial license. You can download the Oracle JDK 1.11 installer for your operating system here.
OpenJDK 11	Doesn't require a commercial license. OpenJDK is available from a number of sources. Example: you can download the Zulu OpenJDK installer here.

2. Download and install a JDK that's compatible with Java version 8. You can download the software from Oracle or you can use the free open-source implementation, OpenJDK.

Note: Studio requires a JDK that's compatible with Java 8 specifically, not Java 8 as a minimum.

Source	Notes
	Requires a commercial license. You can download the Oracle JDK 1.8 installer for your operating system here.
OpenJDK 8	Doesn't require a commercial license. OpenJDK is available from a number of sources. Example: you can download the Zulu OpenJDK installer here.

- 3. Download the Workday Studio for Windows installer.
- 4. To launch the installation, double-click the installation executable file. To install Studio in the C: \Program Files folder, you must run the executable as an Administrator by right-clicking it and selecting Run as Administrator.

Note:

You can use the Command Prompt application to run a silent Studio installation. In Command Prompt, navigate to the directory where you saved the installation file and enter:

<Installation_Filename>.exe /S /J=<Java_Home> /D=<Installation_Directory>

where the argument:

- /S specifies silent installation.
- /J specifies the JDK 11 path.
- /RD installs Workday Report Designer.
- /D specifies the installation folder (this argument must be the last in the command).

Example: workday-studio-x86_64.exe /S /J=C:\Program Files\Zulu\zulu11.62.17-ca-jdk11.0.18-win_x64 /D=C:\Studio

- 5. Read the license agreement, then select the terms acceptance check box. Click Next.
- **6.** Browse to the location of your JDK 11 installation and click **Next**. Example: of JDK installation locations: C:\Program Files\Zulu\zulu11.62.17-ca-jdk11.0.18-win_x64.
- 7. If the JVM details are correct, click **Confirm**. Otherwise, click **Back**.
- **8.** Select the **Report Designer** pack to install it alongside Workday Studio. You can also install Report Designer later from within Studio.
- 9. Browse to the directory where you wish to install Studio. Click Next.

Note: Eclipse with Java 11 can't use a Workspace created by Eclipse with Java 8. On launch, you can update your existing Workspace to make it compatible with Java 11. Alternatively, you can create an entirely new compatible Workspace. Once you've updated your Workspace, you can't use it with earlier versions of Studio.

11.To ensure that Java 8 is available as a Java Runtime Environment in Studio, navigate to its **Preferences** panel: **Window** > **Preferences** > **Java** > **Installed JREs**

If Java 8 is missing, click **Add** and select *Standard VM* as the JRE Type. Specify the **Directory** where you installed the JDK 8.

- 12. Ensure that the check box beside the Java 8 JRE is selected.
- 13. Check the Execution Environments for a perfect match: Window > Preferences > Java > Installed JREs > Execution Environments

Select **JavaSE-1.8** in the **Execution Environments** panel, then select the environment described as a 'perfect match' in the **Compatible JREs** panel.

- **14.**In Studio's **Preferences** panel, navigate to **Java** > **Compiler**.
- 15. Under JDK Compliance, from the Compiler compliance level drop-down menu, select 1.8.
- 16.Click Apply and Close.

Note: Before configuring Studio, refer to this overview of Workday Data Centers. The data center page for your tenants contains information that your IT department can use to configure firewalls and ensure proper Studio access to Workday.

Download and Install Workday Studio for macOS

Context

Workday Studio is built on the Eclipse development platform. It comprises more than 150 Eclipse plugins in addition to platform and third-party dependencies. To use it, you need 2 versions of the Java™ Development Kit (JDK):

- Eclipse requires a JDK compatible with Java version 11.
- The Studio runtime requires a JDK compatible with Java version 8.

Install both JDKs and then ensure that:

- · Your Java Runtime Environment is set to Java 8.
- Your JDK compiler compliance level is set to Java 1.8.

Steps

1. Download and install a JDK that's compatible with Java version 11. You can download the software from Oracle or you can use the free open-source implementation, OpenJDK.

Note:

Users of Apple Silicon must use an Apple Silicon ARM JDK11. An x86_64 JDK will not work.

Source	Notes
	Requires a commercial license. You can download the Oracle JDK 1.11 installer for your operating system here.

Source	Notes
OpenJDK 11	Doesn't require a commercial license. OpenJDK is available from a number of sources. Example: you can download the Zulu OpenJDK installer here.

2. Download and install a JDK that's compatible with Java version 8. You can download the software from Oracle or you can use the free open-source implementation, OpenJDK.

Note: Studio requires a JDK that's compatible with Java 8 specifically, not Java 8 as a minimum.

Note:

Users of Apple Silicon must use an Apple Silicon ARM JDK8. An x86_64 JDK will not work.

Source	Notes
Oracle JDK 1.8	Requires a commercial license. You can download the Oracle JDK 1.8 installer for your operating system here.
OpenJDK 8	Doesn't require a commercial license. OpenJDK is available from a number of sources. Example: you can download the Zulu OpenJDK installer here.

- 3. Download the correct macOS Studio installer:
 - Apple Silicon
 - x86, 64 bit
- **4.** To launch the installation, open the installation .jar file.
- 5. Read the license agreement, then select the terms acceptance check box. Click Next.
- Browse to the location of your JDK 11 installation and click Next. Example: /Library/Java/ JavaVirtualMachines/zulu-11.jdk/Contents/Home.
- 7. If the JVM details are correct, click **Confirm**. Otherwise, click **Back**.
- **8.** Select the **Report Designer** pack to install it alongside Workday Studio. You can also install Report Designer later from within Studio.
- 9. Browse to the directory where you wish to install Studio. Click Next.
- 10. When Studio displays the Installation Complete message, click Next, then click Finish.

Note: Eclipse with Java 11 can't use a Workspace created by Eclipse with Java 8. On launch, you can update your existing Workspace to make it compatible with Java 11. Alternatively, you can create an entirely new compatible Workspace. Once you've updated your Workspace, you can't use it with earlier versions of Studio.

11.To ensure that Java 8 is available as a Java Runtime Environment in Studio, navigate to its **Preferences** panel: **Workday Studio** > **Preferences** > **Java** > **Installed JREs**

If Java 8 is missing, click **Add** and select *Standard VM* as the JRE Type. Specify the **Directory** where you installed the JDK 8.

- 12. Ensure that the check box beside the Java 8 JRE is selected.
- 13.Check the Execution Environments for a perfect match: Workday Studio > Preferences > Java > Installed JREs > Execution Environments

Select **JavaSE-1.8** in the **Execution Environments** panel, then select the environment described as a 'perfect match' in the **Compatible JREs** panel.

- **14.**In Studio's **Preferences** panel, navigate to **Java** > **Compiler**.
- 15. Under JDK Compliance, from the Compiler compliance level drop-down menu, select 1.8.

Note: Before configuring Studio, refer to this overview of Workday Data Centers. The data center page for your tenants contains information that your IT department can use to configure firewalls and ensure proper Studio access to Workday.

Concept: Workday Studio

Workday provides 2 ways to perform integrations:

- Connectors: Packaged integrations that connect to a variety of common third-party services.
- Enterprise Interface Builder (EIB): A simple tool for creating integrations without doing any programming.

Workday Studio is a third option that enables you to build, own, and support much more sophisticated integrations, which Workday hosts and runs on your behalf. Unlike Connectors and EIB, Studio isn't part of Workday. It's an Eclipse-based Integrated Development Environment (IDE) that you download separately. As with any other integrations in your tenant, you can launch, schedule, and audit the integrations you build with Studio. You can launch Studio-created integrations from Studio itself or from the Workday application.

The target user for Studio:

- · Has a development skill set.
- Is familiar with integration programming concepts.
- Is comfortable using an IDE.

The Studio platform has 4 principal components:

- The Studio IDE.
- Integrations, collections, and the Cloud Repository.
- · The Workday application.
- Cloud Runtimes.

The Studio IDE

Studio is an Eclipse-based IDE. You use it to construct integration flows that:

- Access information from Workday.
- Manipulate it.
- (Optional) Send it somewhere.

These flows are called assemblies. You create assemblies by adding and connecting graphical elements called components and steps in the Studio Assembly Editor.

Studio includes components and steps for many actions, including splitting, transforming, and routing. Workday-specific components have a built-in description of how Workday represents information.

You can test your integration in Studio before deploying it directly to your Workday tenant.

Studio supports the use of Java extensions in assembly projects. You can supply your own Java code and configure it as a Spring bean. In addition, you can package third-party Java libraries within your integrations.

Integrations, Collections, and the Cloud Repository

The Cloud Repository is Workday's term for its Studio integration storage. Before deployment, Studio assigns each integration to a collection. A collection can contain multiple integrations. An integration can belong to more than 1 collection. This means you can easily reuse assemblies and subassemblies across integrations and tenants.

Only 1 instance of a particular collection can run at any time. If you modify an assembly project within a collection and redeploy the project, it replaces any previously deployed version.

The binary file that Studio deploys to the Workday Cloud Repository is called a CLAR (CLoud ARchive). A CLAR contains:

- All of the artifacts from the included integration projects, such as their assembly.xml, XSLT, and Text Schema files.
- Any compiled Java code or third-party Java libraries that developers have added to the integration projects.

As binary objects, CLARs don't include source-code artifacts like Java source files.

The Cloud Repository stores CLARs in an encrypted format. However, don't store information like passwords directly in your integrations. Configure sensitive details in the Workday application instead so you can manage them dynamically.

The Workday Application

Workday uses an abstraction called an integration system to model integrations. In Workday, for each integration you can specify:

- Which users have permission to launch the integration and the rights the integration has while executing.
- How and when to notify different Workday users when the integration executes.

Because you design and configure your Studio integrations separately, you can redeploy an integration without affecting its configuration.

Workday enables integrations to launch in a number of different scenarios. You can:

- Manually launch integrations.
- Schedule integrations to run automatically as an event.
- Launch an integration automatically as part of a business process.
- Trigger launch remotely using a web service client to invoke a Workday Web Service.

You can use the Workday **Process Monitor** report to monitor the execution of an integration.

Cloud Runtimes

When an integration launches, Workday:

- Generates an integration event.
- Retrieves the integration from the Cloud Repository.
- Assigns a protected set of processing resources called a Cloud Runtime.
- Executes the integration in the Cloud Runtime.

If Workday is unable to execute an integration, it updates the **Process Monitor** with an integration launch status of Failed.

If Workday encounters a problem during execution, such as the unavailability of an external resource, it terminates and updates the **Process Monitor** with an integration launch status of Completed with errors.

Note: It's the integration developer's responsibility to deal with integrations marked as Completed with errors.

Workday terminates integrations that take longer than 2 hours to execute. Developer-supplied Java code can't, in general, read from or write to the file system or Java system properties. Developer-supplied Java code can't spawn new Java threads.

Studio supports 2 Cloud environments automatically:

- Sandbox
- Production

You can add connections to other Workday environments. It's your sole responsibility to ensure that you deploy the correct integrations to the appropriate environment. Standard Workday Web Services security policies apply to all data accessed using Studio integrations.

You can create assemblies offline in Studio, but you must have the appropriate security configuration to integrate them with Workday. Once deployed, integrations launch and run with the credentials and privileges of the user who runs them.

Workday has no insight into what your integration looks like or what it's designed to do. It's your responsibility to ensure that it behaves as expected. Your integration's interactions with your Workday tenant happen over the Workday Public APIs, so you inherit all the associated robustness and security guarantees.

Concept: Integration Development Lifecycle

You develop and monitor Studio integrations in these distinct phases, using either Workday Studio or the Workday application as appropriate:

Phase	Description
Integration Design	In Studio, develop the assemblies that form your integration. Optionally, create assembly modules, which enable you to reuse and share integration patterns and configurations.
	Each assembly has at least 1 workday-in transport, which denotes where execution begins. Each workday-in transport can optionally define:
	 Launch parameters, which enable a client to pass information to the integration as input. Example: A payroll integration might specify that it requires 2 launch parameters: payPeriod and payGroup. This enables the integration's users to specify the month and employee group to use when calculating payroll. Workday services that the assembly uses at runtime. Workday provides generic integration services for attribute mapping, sequence generation, transaction logging, document retrieval and delivery. It also provides a listener service, a report service, and a custom object service.
Integration Deployment	In Studio, connect to the Workday Cloud Repository to deploy your integration. For each workday-in transport defined in an integration, Workday registers an abstraction called an integration system. An integration system includes any required launch parameters and services.

Phase	Description
Integration Configuration	In Workday, you can configure certain aspects of your integration, including permissions and notifications.
Integration Launching	The integration system enables Workday to launch and track your integration. But to make development and testing easier, you can also launch from Studio.
Integration Monitoring and Troubleshooting	Track the progress of your integration in either Studio or Workday. In Studio, you can monitor the execution of the integration on the Process Monitor . You can also view a consolidated report of the integration process after it has completed.

Concept: MediationContext Object

During assembly execution, Workday creates a temporary holder object called a MediationContext. The MediationContext contains 3 main types of information:

- MediationMessage: an object containing the text or binary data message that Studio ultimately sends to an external target using an Out-transport. Examples: HTTP-Out, FTP-Out.
- Variables: temporary holders for message data.
- Properties: a map of name-object pairs that assembly elements use for storing transient data outside of a message.

All processing in assemblies involves either reading from or writing to the MediationContext.

Note: When you access the MediationContext object using MVEL, the accessor is context. Example: context.getErrorMessage(). In Java, it's mediationContext. Example: mediationContext.getErrorMessage().

Concept: Integration Systems and Events

Integration Systems

In Workday, an integration system is an abstraction of an integration with an external system or a Workday endpoint. Integration systems provide the framework by which Workday launches and tracks integrations. You can use an integration system to configure:

- Security: Specify who can launch the integration and what rights the integration has while executing.
- Notifications: Specify who gets notified as an integration executes.
- Parameters: You can parameterize the invocation of an integration. Example: you can configure the endpoints and user credentials an integration needs to upload data to an external SFTP site.
- Triggers: You can configure the integration to be triggered:
 - Manually.
 - · As part of a subscription.
 - · Using an API.
 - On a schedule.
 - · As part of a Business Process.

Workday represents all integrations, regardless of their origin, as integration systems.

Integration Events

When an integration launches, Workday creates an object called an integration event. This object is unique to each invocation and contains an ID called an integration event ID. Workday uses this unique ID to track all executing integrations. You can view integration events using the **Process Monitor** in Workday.

As well as creating an integration event object, Workday creates an integration event request message and sends it to the integration. This request contains information about the integration system and the integration event ID. It also contains values for any parameters supplied at launch time. The integration can then use this information when requesting information from Workday Web Services. The integration can also use this information to send update information back to Workday. Example: a status message that tells the user that it has processed 100 employee records successfully. Workday adds these updates to the integration event object.

Reference: Interface Fundamentals

The Workday Studio interface is composed of views. To display or hide views, select **Window** > **Show View** > **Other...**, then expand the **Workday** folder.

The most commonly used views in Studio are:

View	Description
Project Explorer	Studio's project navigator. Displays projects saved in the current workspace. Each folder contains all of the relevant files for that project and references the collections to which the project belongs.
Cloud Explorer	Displays the integration cloud servers to which Studio can deploy, as well as the currently deployed collections. You can add connections to multiple environments. If connection, authentication, or authorization errors occur, Studio displays an error or warning decorator on the connection icon.
Palette	Displays all the assembly components that you can add. Features 3 tabbed subviews: • Design: displays the assembly diagram. • Source: displays the XML source. • Message Builder: a graphical view that simplifies defining the message content for assembly elements such as the write step.
Assembly Editor	A diagrammatic representation of the assembly. To add new components and steps, drag and drop them from the Palette . To connect components, hover over a source component to display the connection handles, then drag the handle to the target component.
Properties	Displays configuration details for the assembly element currently selected in the assembly diagram. Edit properties and parameters using the

View	Description
	tabs that display along the left-hand side of the view.
Process Monitor	Displays information about the assembly process when you launch an integration. Select a process to display its details on the Process Details view.
Schema Explorer	Enables you to explore the contents of WSDL and XML Schema files and provides several utility features for developing assemblies that interact with web services.
Consolidated Report Viewer	Enables you to analyze assembly processing steps in an integration.

Integration Design

Assemblies

Create an Assembly Project

Context

Assemblies define message-based integration processes consisting of annotations, transports, mediation components, mediation steps, and error handlers.

Steps

- 1. Select File > New > Workday Assembly Project.
- **2.** In the **Project name** field, enter a name for your project. Project names must not contain spaces.
- 3. From the Target Runtime list, select Workday Runtime.
- **4.** From the **Configurations** list, select 1 of these configuration options:

Option	Description
Assembly	Creates a simple assembly project.
Assembly (with Java support)	Creates a project containing a Java facet.
Custom	Enables you to specify the project facets for your assembly project.

5. Click Next. Enter a Collection name.

The **Collection name** field automatically populates with your project name.

6. Click **Finish** to create your project.

Note: If you create an assembly project outside your workspace, you can give it a new name in Studio without changing the folder name in the original location. This also applies to projects you import from outside your workspace. To do so, select **File > Rename**.

Result

Your new assembly project displays on the **Project Explorer** view. It contains an assembly.xml file, which you can now open in the Assembly Editor.

Next Steps

Using the Assembly Editor, you can define your integration by adding and linking transports, mediation components, and mediation steps.

Add Steps to Components

Prerequisites

Create an assembly project.

Context

Steps perform individual operations on a message as it passes through an integration. You can add steps to **async-mediation** and **sync-mediation** components only.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. Add an async-mediation or sync-mediation component to the assembly.
- **3.** Drag a step from the **Palette** into your **async-mediation** or **sync-mediation** component. Place steps in order of execution. As you complete the task, consider:

Palette Category	Description
Transform	Displays mediation steps that enable you to transform messages as they pass through your integration.
Logging & Eventing	Displays mediation steps that enable you to log messages as they pass through your integration.
Message Manipulation	Displays mediation steps that enable you to manipulate messages as they pass through your integration.
Validation	Displays mediation steps that enable you to validate messages as they pass through your integration.
Encoding	Displays mediation steps that enable you to encode messages as they pass through your integration.
Other	Displays miscellaneous mediation steps that enable you to perform individual operations on messages as they pass through your integration.

4. Click Save.

Result

Studio displays the new step within the component on the assembly diagram.

Next Steps

Configure the properties of the new step.

Add Child Elements

Prerequisites

Create an assembly project.

Context

Some assembly elements support child elements. Child elements are optional.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. Add an assembly element that supports child elements to the assembly diagram.
- 3. Hover your cursor over the title of the assembly element to display its child element options.
- 4. Click a child element option to add it to your assembly element.

Result

Studio displays the child element on your assembly element.

Next Steps

Configure the properties of the child element.

Connect Assembly Elements

Prerequisites

Create an assembly project.

Context

Connections between assembly elements define the path of a message through your assembly. You can connect assembly elements using the **Outgoing connection** handle (blue square), or the **Incoming connection** handle (orange square) in the Assembly Editor.

Steps

- Open the assembly in the Assembly Editor.
- **2.** Add 2 assembly elements to the assembly diagram.
- Place your cursor over the title of the first assembly element to display its connection handles. Drag the
 Outgoing connection handle (blue square) from the first assembly element to the second assembly
 element.
- **4.** Alternatively, place your cursor over the title of the second assembly element and drag the **Incoming connection** handle (orange square) to the first assembly element.

Result

The message output from the first assembly element becomes the input for the second assembly element.

Configure Assembly Element Properties

Prerequisites

Add assembly elements to an assembly diagram.

Context

Each element on the Workday Studio Palette has a Properties view where you can configure its functionality.

Steps

- 1. Right-click an assembly element and select Show Properties View.
- 2. Required properties have an asterisk in the upper left-hand corner of the icon. As you complete the task, consider:

Property Icon	Property Description
*	Values that must be unique within the assembly.
₽ 1	Input to the assembly element.
4 11	Output from the assembly.
ede:	MVEL expressions.
DOMES!	MVEL templates.
62	Boolean values.
=	Options.
#	Numeric values.
0	Attribute values.
Θ	Java class implementations.
•	Spring beans that reference Java class implementations.

Note: When properties are MVEL-capable, the relevant MVEL icon is added to the property's own icon.

Example:



- 3. To compare property views:
 - a) Select a component in the assembly diagram.
 - b) Hold down the Ctrl key and select a second component.
 - c) Right-click either component and select Compare Properties. The first component's Properties view displays on the left. The second component's Properties view displays on the right, and is pinned to that selection. The view on the left changes when you select a different component.

4. In MVEL-capable property fields, press Ctrl+space to access content assist, a set of context-sensitive code completion options.

Note: Content assist is only available in assembly projects that contain the Java facet.

Manage Collections and Projects

Prerequisites

Create an assembly project.

Context

In Workday Studio, collections enable you to package and deploy multiple projects. A project always belongs to at least 1 collection, and can be a member of multiple collections simultaneously.

Steps

1. Click Workday > Manage Collections.

If you expand a collection in the left window pane, Studio displays the projects it contains. Projects that aren't a member of that collection display in the right window pane.

2. As you complete the task, consider:

Button	Description
New Collection	Adds a new collection to your workspace.
Rename Collection	Renames the selected collection.
Remove Collection	Removes the selected collection from your workspace.
Add to Collection	Adds the selected project to a collection.
Add All Integrations to the Collection	Adds all projects to the selected collection.
Remove the Integration from Collection	Removes the selected project from a collection.

Note: Ensure that all projects in a collection have the same assembly version. Otherwise, Studio displays an error marker. You can configure the **Version** property value for the assembly on the **Properties** view in the Assembly Editor.

3. Click Finish.

Declare Namespace Prefixes

Prerequisites

Create an assembly project.

Context

In Workday Studio, namespace prefixes are abbreviations with predefined URI values. You can declare namespace prefixes to refer to specific URI values in your assemblies.

Steps

- 1. Open an assembly in the Assembly Editor.
- 2. Right-click on the background of the assembly diagram, and select Show Properties View.
- 3. Click the Namespace Prefixes tab.

4. Click Add to add a new namespace prefix. As you complete the task, consider:

Option	Description
Prefix	Enter a prefix name here.
Namespace	Enter the namespace URL here.

- 5. To edit your new namespace prefix, click Edit.
- 6. To remove your new namespace prefix, click Remove.

Result

The namespace prefix for the assembly displays in the XML schema.

Create Path Variables

Prerequisites

Create an assembly project.

Context

Path variables specify the location of resource files in your workspace folder. You can use workspace path variables when you link platform resources in your assembly projects.

Steps

- 1. Select Windows > Preferences > General > Workspace > Linked Resources.
- 2. Click New.

As you complete the task, consider:

Option	Description
Name	Enter the name of your path variable.
Location	Enter the file location of your path variable.

3. Click Ok.

Result

Your new path variable now specifies the location of resource files in your workspace folder.

Concept: Assembly Palette

The **Palette** displays all the assembly elements available in Studio. To add an assembly element to an assembly diagram, drag it from the **Palette** onto the Assembly Editor. The **Palette** lists assembly elements under these categories:

Palette Category	Description
Favorites	Displays your favorite assembly elements. You can add assembly elements to this category by clicking the empty star icon beside them. You can remove elements from this category by clicking the highlighted star icon beside them.
Annotation	Displays annotations that enable you to structure, organize, and label your assembly diagram.

Palette Category	Description
Module Library	Displays module assembly elements that enable you to configure Workday Web Service calls and global error handlers for your integration.
In Transports	Displays in-transport assembly elements that receive messages from Workday or a local resource.
Out Transports	Displays out-transport assembly elements that send messages to a resource.
Components	Displays mediation components that enable you to manipulate and transform messages as they pass through your integration.
Common Components	Displays prepackaged subassemblies that you can use to build your integrations.
Workspace Components	Displays custom subassemblies that you've created and saved to your workspace.
Error Handlers	Displays error handlers that enable you to catch errors in your integrations.
Transform	Displays mediation steps that enable you to transform messages as they pass through your integration.
Logging & Eventing	Displays mediation steps that enable you to log messages as they pass through your integration.
Message Manipulation	Displays mediation steps that enable you to manipulate messages as they pass through your integration.
Validation	Displays mediation steps that enable you to validate messages as they pass through your integration.
Encoding	Displays mediation steps that enable you to encode messages as they pass through your integration.
Other	Displays mediation steps that enable you to perform individual operations on messages as they pass through your integration.
Connections	Displays the Route To and Route Response To connections that enable you to define the path of a message through your integration.

To manually filter the assembly elements displayed on the **Palette**, use the **type filter text** field. Studio also provides these preconfigured category filters directly underneath the **type filter text** field:

Category Filter	Description
Restore	Clears previous filter selections.
Transports	Displays only transport Palette categories.

Category Filter	Description
Components	Displays only mediation component Palette categories.
Steps	Displays only mediation step Palette categories.
Handlers and Connections	Displays only error handler and connection Palette categories.
Filter Categories	Displays the Palette Category Filter window.
Expand All	Expands all Palette categories.
Collapse All	Collapses all Palette categories.

Studio automatically displays the **Palette** beside the Assembly Editor. To display the **Palette** in a separate view, select **Window** > **Show View** > **Other** > **General** > **Palette** and click **OK**. You can also change the layout of the **Palette** by right-clicking on it and selecting **Layout**.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Concept: Components and Steps

You can add steps to **async-mediation** and **sync-mediation** components only.

Workday Studio provides steps that support operations such as transformation, validation, and logging. You can also write custom steps using Spring beans.

The **async-mediation** component supports 1 processing chain, handling request messages only. The **sync-mediation** component supports 2 processing chains, handling request messages and request-response messages.

Steps have **Input** and **Output** properties that specify where they obtain data as input and where they direct the output. There are 5 possible values:

Option	Description
message	The entire message, including rootpart and attachments. When you specify this option, Studio creates a new message, effectively removing any attachments.
soapbody	The contents of the SOAP body from the rootpart of the message.
attachment	A MIME attachment to the message. Specify the index value of the attachment you wish to access. You can also add a new attachment to the message by specifying an index value of -1.
rootpart	The content of the rootpart of a MIME message, or if the message isn't MIME, the message itself. When specified for the output attribute, this value preserves any attachments on the original message.
variable	A variable from the MediationContext. Specify the name of the variable to use.

Concept: Assembly Annotations

Annotations enable you to structure, organize, and label your assembly diagrams. Studio provides these options under the **Annotations** section of the **Palette**:

- Rectangle
- Ellipse
- Note
- Text
- Swimlane

You can:

- Use the Rectangle, Ellipse, Note, and Text annotations to add general explanatory text to your assembly.
- Use the Show/Hide annotations button to display or hide the Rectangle, Ellipse, Note, and Text
 annotations. You can only add new annotations to assembly diagrams when Show annotations is
 active
- Use the pin icon on **Rectangle**, **Ellipse**, **Note**, and **Text** annotations to pin them to your assembly. Pinned annotations always display on your diagrams, even when **Hide annotations** is active.

Swimlanes

Swimlanes enable you to organize assembly components into groups.

You can:

- Display or hide swimlane descriptions by clicking the Show/Hide swimlane descriptions button.
- Expand and collapse all swimlanes by clicking the Expand all swimlanes and Collapse all swimlanes buttons.
- Expand and collapse individual swimlanes by clicking the plus and minus icons in their headers. Swimlane status is persistent. When you open an assembly, swimlanes display in the collapsed or visible state they were in when the assembly was saved.

Swimlanes are nestable.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Concept: Linked Resource Files for Assembly Projects

Linked resources are files stored on your workspace that you can link to in multiple assembly projects.

To view a list of linked resources for a project, right-click on the project in the **Project Explorer** view. Select **Properties** > **Workday** > **Linked Resources** to display the **Linked Resources** window.

To remove a linked resource file from a project, right-click on the resource file in the **Project Explorer** view and select **Remove linked resource**.

To copy a linked resource to the project, right-click on the resource file in the **Project Explorer** view and select **Convert linked resource to copy**.

Concept: Quick Outline View

The **Quick Outline** view provides an easy way to locate various elements of your assembly. To access the **Quick Outline** view, press Ctrl+O when the **Assembly Editor** has focus.

Note: You can't access the Quick Outline view from the Window > Show View menu.

The **Quick Outline** view enables you to search your assembly by:

Search Type	Description
MVEL Expression	Search MVEL expression and template properties. Use this view to search for occurrences of text values.
ID	Search for assembly component IDs.
Variable	Search for variable names. Studio categorizes variables into 2 groups: those defined for accessing steps, and those defined for write steps.

To select a search type, click the relevant button under the search field at the top of the view.

To search, enter text in the search field. When you select an MVEL expression, component ID, or variable in the list of search results, Studio jumps to the relevant component in the assembly diagram.

Reference: Assembly Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the assembly.
Version	version	The assembly version number.
Audit Log	audit-log	The message log settings for the assembly. The options are:
		 True: Enables and stores all logs. False: Disables all logs. On Error: Enables all logs and stores only error logs.
Callback Handler Bean	callback-handler-bean	The Spring bean that handles asynchronous communication for the assembly.
Beans	beans	The Spring beans in the assembly.
Namespace Prefixes	xmlns	The namespace prefixes in the assembly.

Reference: Swimlane Properties

Common Tab

Property	Description
Name	The name of the swimlane. Displays in the header of the swimlane.
Description	A description of the swimlane. Displays when you select Show swimlane descriptions .
Orientation	The orientation of the swimlane. The options are: • HORIZONTAL • VERTICAL

Property	Description
Alignment	The alignment of components in the swimlane. The options are:
	BEGINNING MIDDLE END
Label Alignment	The alignment of the swimlane label. The options are: • LEFT • CENTER • RIGHT
Top border color	The color of the top border on the swimlane.
Line color	The color of the side and bottom borders of the swimlane.
Fill color	The background color of the swimlane.
Font	The font of the swimlane label.
Line style	The style of the side and bottom borders of the swimlane. The options are:
	 SOLID DASH DOT DASHDOT DASHDOTDOT

Reference: Connection Line Properties

Common Tab

Property	Description
Line Type	The type of line used to display Route To and Route Response To connections on an assembly diagram. The options are:
	straightcurved

Assembly Transports

Use Enumerations as Launch Parameters in Studio

Prerequisites

Create an assembly project containing a workday-in transport.

Context

In Workday Studio, you can use enumerations as integration launch parameters. This restricts the values you can select in the **Integration Criteria** tab when you launch the integration. You can define the enumerations in Studio or refer to existing enumeration definitions in your tenant.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. On the Launch Parameters tab of the Properties view for the workday-in transport, click Add Enumeration Type Parameter.
- 3. Click Edit Type.
- **4.** As you configure the enumeration, consider:

Option	Description
Enumeration Reference	Enter the Type Name of an existing enumeration definition in your tenant.
Enumeration Definition	Enter a unique Type Name for the enumeration definition.
	Note: When you enter the Type Name of an existing enumeration definition, Workday overwrites the definition.
	Add the values that the enumeration allows.

Next Steps
Deploy your integration.
Related Information
Tasks

Deploy Integrations to Workday on page 295

Concept: Assembly Transports

Studio provides 2 categories of assembly transports on the **Palette**:

- In Transports
- Out Transports

In-transports receive messages from Workday or a local resource, and forward them for processing to other elements defined within the assembly. In-transports always indicate the start of a processing chain.

Out-transports exchange messages with a resource such as an HTTP endpoint, Workday application, or FTP site. Assemblies containing a **local-out** transport can communicate with subassemblies containing a **local-in** transport.

Studio supports these in-transport assembly elements on the **Palette**:

Name	Function	Notes
workday-in	Defines a starting point for executing an assembly.	 Listens for Workday application request messages. Supports launch parameters and service definitions for your integration. Synchronous (request-response).

Name	Function	Notes
local-in	Defines an entry point to an assembly or a subassembly.	 Exchanges messages with assemblies containing a local-out transport. Supports parameters and outparameters. Synchronous (request-response).

Studio supports these out-transport assembly elements on the **Palette**:

Name	Function	Notes
workday-out-rest	Sends Workday application REST request messages to an HTTP URL.	Synchronous (request- response).
workday-out-soap	Sends Workday application SOAP request messages to an HTTP URL.	Synchronous (request- response).
local-out	Exchanges messages with assemblies and subassemblies containing a local-in transport.	Synchronous (request- response).
http-out	Sends HTTP request messages to an HTTP URL.	Supports these HTTP child elements:
		http-basic-authhttp-custom-authhttps-properties
		Synchronous (request- response).
ftp-out	Sends messages to an FTP server.	Asynchronous (request only).
ftps-out	Sends messages securely to an FTP server using the FTP over SSL (FTPS) protocol.	Asynchronous (request only).
sftp-out	Sends messages securely to an FTP server using the FTP over SSH (SFTP) protocol.	Asynchronous (request only).
xmpp-out	Writes text messages to a Jabber server. Example: a Google Gmail server.	Asynchronous (request only).
custom-out	Creates a customizable out- transport.	Synchronicity defined by the Spring bean implementation.

Name	Function	Notes
email-out	Writes e-mails to an SMTP (mail) server.	Studio checks these properties for preceding and trailing whitespace:
		 To Subject From Bcc Cc Host Port User Password Reply To Asynchronous (request only).

Concept: Enumerations

Enumerations restrict an attribute value to a set of literal values, such as cost center codes. You can use enumerations to define a set of constants to use as literal values when you design integrations. This allows you to restrict the range of data your integration uses.

You can create and maintain enumeration definitions in Workday using these tasks:

- Create Integration Enumeration Definition
- Edit Integration Enumeration Definition
- Delete Integration Enumeration Definition
- View Integration Enumeration Definition

You can use enumerations in these elements:

- Launch parameters.
- Integration attributes.
- Integration maps.

You can assign enumerations:

- In Studio.
- Using the Create Integration Generic Service task in Workday.

You can assign enumerations in Studio integrations using 1 of these methods:

- Create an enumeration definition in Studio and deploy it to your tenant when you launch the Studio integration.
- · Create an enumeration reference to an existing enumeration definition in your tenant.

You can use the same enumeration definition across multiple integrations by selecting 1 integration to provide the definition, and referring to it in the others.

Related Information

Tasks

Create Attribute Map Services on page 273

Reference: Workday-In Transport Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the workday-in transport within the assembly.
Routes To	routes-to	The assembly element towards which the workday-in transport directs the message.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Integration System Name	integration-system-name	The name of your integration system.

Launch Parameters Tab

Launch Parameter	Description	
Simple Type Parameter	Launch parameters that use string literal values.	
Reference Type Parameter	Launch parameters that use references to Workday CRFs and web services.	
Enumeration Type Parameter	Launch parameters that use Workday CRFs and enumeration definitions.	

Services Tab

Integration Service	Description	
Attribute Map Service	The integration attributes and integration maps used in your integration.	
Delivery Service	Delivers documents to a target endpoint from your Workday tenant.	

Integration Service	Description
Listener Service	Enables your integration to receive launch messages from third-party clients through your Workday tenant.
Retrieval Service	Retrieves documents from remote clients and stores them in your Workday tenant.
Sequence Generator Service	Generates unique, sequenced filenames for documents each time you run your integration.
Transaction Log Service	Displays the logs for transaction events that your integration system has subscribed to in your Workday tenant.
Report Service	Specifies aliases for any custom reports that you refer to in your integration.
Custom Object Service	Specifies aliases for any custom objects that you refer to in your integration.
Service Reference	References any integration service configured on another workday-in transport within the same collection.

Reference: Local-In Transport Properties

Common Tab

Property	XML Attribute Name	Description
Id	id	The unique ID of the local-in transport within the assembly.
Routes To	routes-to	The assembly element towards which the local-in transport directs the message.
Access	access	Specifies whether your subassembly is public or private .
		The Palette displays only public subassemblies in the Workspace Components category.
Use Global Error Handlers	use-global-error-handlers	Determines whether errors that occur within the subassembly are handled at the subassembly level. The default is false, meaning that errors are handled by the assembly that invoked the subassembly.
Icon	icon	Specifies a custom icon for the subassembly. Supports 24x24 pixel PNG or GIF icons.
Tooltip	tooltip	A tooltip for your subassembly.

Property	XML Attribute Name	Description
Store Message	store-message	Store Message doesn't apply to local-in transports. Studio ignores this setting for local-in transports.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.

Parameters Tab

The local-in transport's parameters specify any MediationContext properties you can set.

Property	XML Attribute Name	Description
Name	name	The name of your local-in parameter.
Documentation	documentation	A text description of your local-in parameter.
Required	required	Determines whether your local- in transport requires your parameter.
Туре	type	Specifies your parameter type. The options are: • string • integer • long • double • float • boolean
Default	default	The default value of your parameter.
Validation	validation	A Boolean MVEL expression that must evaluate as true, otherwise Studio throws an error. Enables subassembly developers to impose constraints on parameter values.

Out Parameters Tab

The **local-in** transport's out-parameters specify any MediationContext properties that the subassembly retrieves.

Property	XML Attribute Name	Description
Name	name	The name of your out-parameter.
Documentation	documentation	A text description of your outparameter.

Reference: Workday-Out-Rest Transport Properties

Common Tab

Property	XML Attribute Name	Description
Id	id	The unique ID of the workday- out-rest transport within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the workday-out-rest transport.
Execute When	execute-when	A condition that determines whether the workday-out-rest transport executes.
Extra Path	extra-path	Specifies the path in your Workday tenant through which Studio sends the REST request. Studio automatically sets up and appends the Workday service endpoint for this path. Example: the endpoint in the path below invokes a Workday Business Site Directory report, from a tenant named ACME, requested in JSON format: systemreport2/ACME/ Business_Site_Directory? format=json

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis.
		You can globally change the implementation classes by editing

Property	XML Attribute Name	Description
		the WEB-INF/classes/spring/ assembly-bean.xml file.
Method	method	Enables you to add a REST method to your workday-out-rest transport. Example: put, get, post.
Failure Message	failure-message	A custom message used to replace any exception message returned when you invoke a workday-out-rest endpoint.

Reference: Workday-Out-Soap Transport Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the workday- out-soap transport within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the workday-out-soap transport.
Execute When	execute-when	A condition that determines whether the workday-out-soap transport executes.
Application	application	The name of the Workday application to which the transport sends content. Studio uses the name that you enter in this field to create a URI that specifies the location of the Workday application.
Version	version	The web service version that the SOAP request calls. Note: When you specify a Web services version in an XSLT request, that version takes precedence.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.

Property	XML Attribute Name	Description
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required. You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Failure Message	failure-message	A custom message used to replace any exception message returned when you invoke a workday-out-soap endpoint.
Replace with Soap Fault	replace-with-soap-fault	Replaces a failed workday-out- soap message with a SOAP fault. The SOAP fault contains extracted faultcode and faultstring property values.

Reference: Local-Out Transport Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the local-out transport within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the local-out transport.
Execute When	execute-when	A condition that determines whether the local-out transport executes.
Endpoint	endpoint	The target endpoint address towards which the local-out transport directs the message.
		Endpoint addresses follow the format application-name/component-ID, where:
		 application-name is the name of the project containing the target assembly. component-ID is the ID of the target component.
		<pre>Example: <cc:local- endpoint="myassembly/ mediation1" id="local" out=""></cc:local-></pre>

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to create a copy of the request message processed by the localout transport, so that any subassembly modifying the message doesn't affect the others.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Property	XML Attribute Name	Description
Name	name	The name of the parameter child element.

Property	XML Attribute Name	Description
Value	value	The value of the parameter child element.

Reference: HTTP-Out Transport Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the http-out transport within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the http-out transport.
		Note: The http-out transport populates the MediationContext property http.response.status with the status of the HTTP response returned by the remote server. The assembly can use the value in this property to determine handling for different status codes.
Execute When	execute-when	A condition that determines whether the http-out transport executes.
Endpoint	endpoint	The target HTTP URL address towards which the http-out transport directs the request message.
		<pre>Example: http:// myhost.example.org/ MyService</pre>
Http Method	http-method	The HTTP request method supported by the http-out transport. Example: DELETE, GET, POST, PUT, and PATCH.
		Note: To use the PATCH method, you must set the wd.http.client property to apache. If you don't want downstream transports to also use the Apache HTTP client, reset the wd.http.client property to null.
		If you don't specify a method for this property, Studio uses the POST method.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support. To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required. You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property. Use the set-dynamic-endpoint step to specify WS-Addressing details.
Connect Timeout	connect-timeout	Specifies, in milliseconds, a timeout period for establishing a connection with an HTTP server. If you don't specify a value, the session times out after 300000 ms (5 minutes).
Response Timeout	response-timeout	Specifies, in milliseconds, a timeout period for awaiting a response from an HTTP server. If you don't specify a value, the session times out after 21600000 ms (6 hours). If the HTTP connection remains
		unresponsive for longer than this period, the http-out transport fails.
Error As Response	error-as-response	Enables you to copy an error response message from a server to the message on the http-out transport.
Close Connection	close-connection	Adds a Connection: close header to an outgoing http-out transport message.
Streaming	streaming	Enables HTTP streaming using PUT and POST HTTP methods.
	•	•

Property	XML Attribute Name	Description
Auto Inproc	auto-inproc	Specifies whether to use in- process transport communication for http-out request messages. Enables you to send messages directly to assembly endpoints located within the same server without using the network I/O capabilities of the local host.
Retries	retries	Specifies the number of retry attempts that the http-out transport makes if a transport exception occurs.
Retry Delay	retry-delay	Specifies in milliseconds a delay period between each retry attempt.
		Note: Workday complies with the Retry-After or RateLimit-Reset header value in an external endpoint's 429 Too Many Requests response provided it's shorter than the default maximum of 5 minutes or the retrydelay value you specify here.
		If the response header value is missing, Workday uses the retry-delay value.
		If both the retry-delay and header values are missing, Workday uses the 5 minute default.
		An integration will be unable to determine a retry delay and will fail if the header value is larger than both the retry-delay value and the default maximum.
Log Retries	log-retries	Enables you to log HTTP retry attempts to the server log file.
Accept Gzip	accept-gzip	Specifies whether to include an HTTP accept-encoding=gzip field in the http-out request header, which indicates whether to accept gzip content in the response.
Gzip Content	gzip-content	Specifies whether to include an HTTP content-encoding=gzip field in the http-out request header, which indicates whether to gzip the

Property	XML Attribute Name	Description
		message content in the outgoing request.
Accept	accept	Specifies the accept header value to send with an HTTP request, which defines 1 or more content types that are acceptable in the response from an HTTP server.

Note: For Amazon S3 transports, add a tag to your IAM user with a key of *workday-type* and a value of *integration*. This tag is case sensitive and doesn't ignore whitespace.

Reference: FTP-Out Transport Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the ftp-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the ftp-out transport.
Execute When	execute-when	A condition that determines whether the transport executes.
Endpoint	endpoint	Specifies the host (and optionally the port) and FTP directory to write files to.
		Follows the format ftp:// FTP-directory, where FTP- directory is the target location.
		<pre>Example: ftp:// ftpserver.example.org/ outputDir</pre>
		Note: The directory location you specify must already exist on the FTP server.
Binary File	binary-file	Specifies whether the output files are transferred as binary.
Input File Pattern	input-file-pattern	A filename pattern for matching files of a particular type.
		Example: specify *.xls to pick up Excel files only.
Input Content Type	input-content-type	The media type that the runtime includes for the content-type value in the message header. A media type comprises at least 2 parts: a type, a subtype, and 1 or

Property	XML Attribute Name	Description
		more optional parameters. The text subtype has an optional charset parameter, which specifies the character encoding.
		<pre>Example: text/html; charset=UTF-8</pre>
		This property is particularly useful in the case of non-XML text file formats where the media type and charset aren't explicitly stated in the file.
Output File Pattern	output-file-pattern	Specifies how the names of output files are generated. The pattern can contain literal strings as well as one or more of these tokens:
		 \${INFILE}, which is replaced with the name of the input file. \${UUID}, which is replaced with a universally unique identifier. \${EXT}, placed at the end of the pattern, which is replaced with a filename extension based on the content type of the data that's written to the assembly component's output.
Method	method	 Specifies the transfer method: put: writes files to the FTP endpoint that contains the remote directory. list: lists all files and directories at the FTP endpoint. Use the Input File Pattern property with list to apply a pattern to the listing being returned. You can access the results of the list method using the MVEL ftp object. Example: ftp.list() returns a list of strings that contains the last listing retrieved. get: retrieves the first file found to match the Input File Pattern property value.

Property	XML Attribute Name	Description
		delete: deletes the first file found to match the Input File Pattern property value.
		Note: A file isn't automatically deleted from the FTP site after a get has been performed. If you wish to delete a file, you must invoke a separate method. Example: you can include a separate ftp-out transport specifically to delete the file.
Password	password	The password associated with the username used to access the FTP server.
Username	username	The username used to access the FTP server.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Passive Mode	passive-mode	Specifies whether the transport supports FTP in passive mode.
		In passive mode, the FTP client initiates both connections required for the FTP transfer. The client contacts the server on

Property	XML Attribute Name	Description
		the command port and issues the PASV command. The server then replies, indicating which port it's listening to for the data connection. The client then initiates the data connection from its data port to the specified server data port. Finally, the server sends back an ACK to the client's data port. In active mode, the client initiates the command connection and the server initiates the data connection.
Timeout	timeout	Specifies in milliseconds a timeout period for FTP sessions between clients and the FTP server on which the transport is listening.
		If you don't specify a value, the session times out after 300000 ms (5 minutes).
Mime Types Map File	mime-types-map-file	The location of a map file for mapping between MIME types and file extensions. Use this property to:
		 Map MIME types to file extensions when the Method property is set to put. Map file extensions to MIME types when the Method property is set to get.
		The file for this mapping is ccx/conf/mime.types. You can provide your own version of this file.
		This transport can generate filenames for its output files using a \${EXT} token placed at the end of the output-file-pattern value.
Temp File Name	temp-file-name	Specifies a temporary filename. When the Method property is set to put, the file uploads using this temporary filename. After the FTP completes, the file is renamed to the name specified by the Output File Pattern property.

Property	XML Attribute Name	Description
Close Connection	close-connection	Specifies whether disconnection occurs when the FTP action is complete.
Pool Size	pool-size	The maximum number of simultaneous connections and sessions that can be supported on a per-host basis for this component. If more than the specified number of threads attempt to connect to the same host, some are forced to wait for access to the pool. To make the pool size unlimited, specify a negative number.
Debug	debug	Enables JSCAPE debug mode in the transport.

Reference: FTPS-Out Transport Properties

Property	XML Attribute Name	Description
ld	id	The unique ID of the ftps-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the ftps-out transport.
Execute When	execute-when	A condition that determines whether the transport executes.
Endpoint	endpoint	Specifies the host (and optionally the port) and FTP directory to write files to.
		Follows the format ftps:// FTPS-directory, where FTPS- directory is the target location.
		Example: ftps:// ftpsserver.example.org/ outputDir
		Note: The directory location you specify must already exist on the server.
Binary File	binary-file	Specifies whether the output files are transferred as binary objects.
Explicit SSL	explicit-ssl	Specifies connection type: explicit SSL (AUTH TLS) or implicit SSL

Property	XML Attribute Name	Description
		(AUTH SSL). Set to true to use explicit SLL.
		FTP clients can choose to continue the communication unencrypted as a normal FTP session or switch to FTPS mode by issuing the AUTH command.
Input File Pattern	input-file-pattern	A filename pattern for matching files of a particular type.
		Example: specify *.xls to pick up Excel files only.
Input Content Type	input-content-type	The media type that the runtime includes for the content-type value in the message header. A media type comprises at least 2 parts: a type, a subtype, and 1 or more optional parameters. The text subtype has an optional charset parameter, which specifies the character encoding.
		<pre>Example: text/html; charset=UTF-8</pre>
		This property is particularly useful in the case of non-XML text file formats where the media type and charset aren't explicitly stated in the file.
Output File Pattern	output-file-pattern	Specifies how the names of output files are generated. The pattern can contain literal strings as well as one or more of these tokens:
		 \$\{\text{INFILE}\}\text{which is replaced with the name of the input file.} \$\{\text{UUID}\}\text{which is replaced with a universally unique identifier.} \$\{\text{EXT}\}\text{placed at the end of the pattern, which is replaced}
		with a filename extension based on the content type of the data that's written to the assembly component's output.
Method	method	 Specifies the transfer method: put: writes files to the FTP endpoint that contains the remote directory.

Property	XML Attribute Name	Description
		• list: lists all files and directories at the FTP endpoint. Use the Input File Pattern property with list to apply a pattern to the listing being returned. You can access the results of the list method using the MVEL ftp object. Example: ftp.list() returns a list of strings that contains the last listing retrieved. • get: retrieves the first file found to match the Input File Pattern property value. • delete: deletes the first file found to match the Input File Pattern property value. Note: A file isn't automatically deleted from the FTP site after a get has been performed. If you wish to delete a file, you must invoke a separate method. Example: you can
		include a separate ftp-out transport specifically to delete the file.
Password	password	The password associated with the username used to access the FTP server.
Username	username	The username used to access the FTP server.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.

Property	XML Attribute Name	Description
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Passive Mode	passive-mode	Specifies whether the transport supports FTP in passive mode.
		In passive mode, the FTP client initiates both connections required for the FTP transfer. The client contacts the server on the command port and issues the PASV command. The server then replies, indicating which port it's listening to for the data connection. The client then initiates the data connection from its data port to the specified server data port. Finally, the server sends back an ACK to the client's data port. In active mode, the client initiates the command connection and the server initiates the data connection.
Timeout	timeout	Specifies in milliseconds a timeout period for FTP sessions between clients and the FTP server on which the transport is listening.
		If you don't specify a value, the session times out after 300000 ms (5 minutes).
Mime Types Map File	mime-types-map-file	Specifies the location of a map file for mapping between MIME types and file extensions. Use this property to:
		 Map MIME types to file extensions when the Method property is set to put. Map file extensions to MIME types when the Method property is set to get.
		The file for this mapping is ccx/conf/mime.types. You can

Property	XML Attribute Name	Description
		provide your own version of this file.
		This transport can generate filenames for its output files using a \${EXT} token placed at the end of the output-file-pattern value.
Temp File Name	temp-file-name	Specifies a temporary filename. When the Method property is set to put, the file uploads using this temporary filename. After the FTP completes, the file is renamed to the name specified by the Output File Pattern property.
Close Connection	close-connection	Specifies whether disconnection occurs when the FTP action is complete.
Pool Size	pool-size	The maximum number of simultaneous connections and sessions that can be supported on a per-host basis for this component. If more than the specified number of threads attempt to connect to the same host, some are forced to wait for access to the pool. To make the pool size unlimited, specify a negative number.
Debug	debug	Enables JSCAPE debug mode in the transport.

Reference: SFTP-Out Transport Properties

Property	XML Attribute Name	Description
ld	id	The unique ID of the sftp-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the sftp-out transport.
Execute When	execute-when	Specifies a condition that determines whether the transport executes.
Endpoint	endpoint	Specifies the host (and optionally the port) and FTP directory to write files to.

Property	XML Attribute Name	Description
		Follows the format sftp:// SFTP-directory, where SFTP- directory is the target location.
		<pre>Example: sftp:// sftpserver.example.org/ outputDir</pre>
		Note: The directory location you specify must already exist on the server.
Dual Authentication	dual-authentication	Specifies whether to enforce dual authentication with both a username/password combination and a private key. The default value is false, which means that a user can authenticate with either a private key or a username/password combination, but not both.
		If the property is set to false and a user enters a private key (by configuring the private key properties of the sftp-out component), then the authentication automatically uses that key value and the username, ignoring the password field. If the property is set to false and no private key is configured then the authentication uses the username/password combination.
		If the property is set to true then the authentication uses both the private key value and username/ password combination.
Host Key Fingerprint	host-key-fingerprint	The encryption key that the FTP server will use for SSH communications.
Username	username	The username used to access the FTP server.
Password	password	The password associated with the username used to access the FTP server.
Binary File	binary-file	Specifies whether the output files are transferred as binary.
Explicit SSL	explicit-ssl	Connection type: explicit SSL (AUTH TLS) or implicit SSL (AUTH SSL). Set to true to use explicit SSL.

Property	XML Attribute Name	Description
Input File Pattern	input-file-pattern	A filename pattern for matching files of a particular type.
		Example: specify *.xls to pick up Excel files only.
Input Content Type	input-content-type	The media type that the runtime includes for the content-type value in the message header. A media type comprises at least 2 parts: a type, a subtype, and 1 or more optional parameters. The text subtype has an optional charset parameter, which specifies the character encoding.
		<pre>Example: text/html; charset=UTF-8</pre>
		This property is particularly useful in the case of non-XML text file formats where the media type and charset aren't explicitly stated in the file.
Output File Pattern	output-file-pattern	Specifies how the names of output files are generated. The pattern can contain literal strings as well as one or more of these tokens:
		 \${INFILE}, which is replaced with the name of the input file. \${UUID}, which is replaced with a universally unique identifier. \${EXT}, placed at the end of the pattern, which is replaced with a filename extension based on the content type of the data that's written to the assembly component's output.
Method	method	Specifies the transfer method:
		 put: writes files to the FTP endpoint that contains the remote directory. list: lists all files and directories at the FTP endpoint. Use the Input File Pattern property with list to apply a pattern to the listing being returned. You can access the results of the list method using the MVEL ftp object. Example:

Property	XML Attribute Name	Description
		ftp.list() returns a list of strings that contains the last listing retrieved. • get: retrieves the first file found to match the Input File Pattern property value. • delete: deletes the first file found to match the Input File Pattern property value.
		Note: A file isn't automatically deleted from the FTP site after a get has been performed. If you wish to delete a file, you must invoke a separate method. Example: you can include a separate ftp-out transport specifically to delete the file.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Timeout	timeout	Specifies in milliseconds a timeout period for FTP sessions between clients and the FTP server on which the transport is listening.

Property	XML Attribute Name	Description
		If you don't specify a value, the session times out after 300000 ms (5 minutes).
Mime Types Map File	mime-types-map-file	Specifies the location of a map file for mapping between MIME types and file extensions. Use this property to:
		 Map MIME types to file extensions when the Method property is set to put. Map file extensions to MIME types when the Method property is set to get.
		The file for this mapping is ccx/conf/mime.types. You can provide your own version of this file.
		This transport can generate filenames for its output files using a \${EXT} token placed at the end of the output-file-pattern value.
Temp File Name	temp-file-name	Specifies a temporary filename. When the Method property is set to put, the file uploads using this temporary filename. After the FTP completes, the file is renamed to the name specified by the Output File Pattern property.
Close Connection	close-connection	Specifies whether disconnection occurs when the FTP action is complete.
Pool Size	pool-size	The maximum number of simultaneous connections and sessions that can be supported on a per-host basis for this component. If more than the specified number of threads attempt to connect to the same host, some are forced to wait for access to the pool.
		To make the pool size unlimited, specify a negative number.
Debug	debug	Enables JSCAPE debug mode in the transport.

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the xmpp-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the ftp-out transport.
Execute When	execute-when	A condition that determines whether the transport executes.
Endpoint	endpoint	Specifies the recipient of the Instant Message. Example: xmpp:logan.mcneil@gmail.cdr
Domain	domain	The domain where the username is registered. Example: gmail.com
Server	server	The host or IP address of the XMPP/Jabber server.
Port	port	The port number at which the XMPP transport listens for messages. The port used by most XMPP servers is 5222.
Username	username	The username used to access the FTP server.
Password	password	The password associated with the username used to access the FTP server.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's

Property	XML Attribute Name	Description
		header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.

Reference: Custom-Out Transport Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the custom-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the custom-out transport.
Execute When	execute-when	A condition that determines whether the transport executes.
Endpoint	endpoint	The endpoint to which the custom-out transport will send messages. Used by the custom-out Spring bean implementation.
Input	input	Specifies where the assembly component obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the assembly component directs the output. There are 5 possible values:

Property	XML Attribute Name	Description
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Spring Bean	spring-bean	Specifies the Spring bean that implements the transport's interface class.
Method Name	method-name	The name of the Java method in the custom Java class.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.

Property	XML Attribute Name	Description
		Use the set-dynamic-endpoint step to specify WS-Addressing details.

Reference: Email-Out Transport Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the email-out component within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the email-out transport.
Execute When	execute-when	A condition that determines whether the transport executes.
То	to	The primary email address of the intended recipient. Follows the format mailto: [emailaddress].
		If you want to use only BCC addresses, specify an empty mailto: value.
Subject	subject	The subject line of the email.
From	from	The email address that should display in the From field of the delivered email.
Ssl	ssl	Specifies whether the connection is SSL.
Starttls	starttls	Specifies whether to activate an immediate SSL negotiation with the remote SMTP server by issuing a STARTTLS command before starting the SMTP session. The SMTP server responds with one of these reply codes:
		 220 Ready to start. TLS 501 Syntax error (no parameters allowed). 454 TLS not available due to a temporary reason.
		Note: The SsI and starttIs properties are mutually exclusive.
Host	host	The name or IP address of the SMTP mail server that the

Property	XML Attribute Name	Description
		transport uses to deliver the message.
		If you're using OAuth, set this value to localhost.
Port	port	The port number at which the mail server is running. The default is 25, the standard SMTP port. Exceptions:
		 If the ssl property is set to true and no port is specified, the default is 465. If the Starttls property is set to true and no port is specified, the default is 587. Note:
User		The user name for accessing the email server.
Password	password	The password for the username specified in the User property.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Всс	bcc	Specifies blind carbon-copy email recipients, using a

Property	XML Attribute Name	Description
		semicolon separator. Example: logan.mcneil@workday.com; jake.lee@workday.com.
Cc	cc	Specifies carbon-copy email recipients, using a semicolon separator. Example: logan.mcneil@workday.com; jake.lee@workday.com.
Reply To	reply-to	The email address that's automatically inserted into the To field when a user replies to an email message. For most email messages, the address in the From field is sufficient, so there's no need to define the Reply To property. Specify multiple emails addresses using a semicolon separator. Example: logan.mcneil@workday.com; jake.lee@workday.com.
Timeout	timeout	Specifies, in milliseconds, a timeout period for FTP sessions between clients and the FTP server on which the transport is listening. If you don't specify a value, the session times out after 300000 ms (5 minutes).
Transient Exceptions	transient-exceptions	Transient exceptions are exceptions that could succeed without any modifications on retry. Nontransient exceptions are those that will continue to fail on retry until the underlying cause of the problem is corrected.
		By default, Workday treats only java.net.ConnectException and java.net.SocketException errors as transient exceptions.
		Specify additional transient exceptions as a comma, space, or comma and space-separated enumeration of class names. Examples:
		 java.net.UknownHostException java.net.ConnectException java.net.SocketException java.net.UknownHostException,

Property	XML Attribute Name	Description
		• java.net.UknownHostException, java.net.ConnectException, java.net.SocketException • @{new java.net.UnknownHostException(Note: If you specify additional transient exceptions, you must also include the default exceptions java.net.ConnectException and java.net.SocketException in the list. If you don't, Workday overwrites them.

SMTP Headers Tab

Property	XML Attribute Name	Description
Name	name	The name of a custom SMTP header.
		To add a new custom header below any existing rows, click Add, then supply a Name and Value.
		To add a new header above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the SMTP Headers tab to delete rows or reorder them.
Value	value	The value of a custom SMTP header.

OAuth Tab

To use Microsoft Outlook OAuth authentication with Studio's Email-Out component, register Studio as an app with Microsoft Azure, provide domain-wide delegation, grant administrator consent for Mail.Send permissions, and obtain various values. For details, see https://learn.microsoft.com/en-gb/azure/active-directory/develop/v2-oauth2-client-creds-grant-flow.

To use Google Gmail OAuth authentication with Studio's Email-Out component, register a Service Account with Google Cloud, provide domain-wide delegation, and obtain a JSON description of various values. For details, see https://support.google.com/cloud/answer/6158849?hl=en.

Property	XML Attribute Name	Description
Provider	provider	The name of the email provider, either MICROSOFT_OUTLOOK or GOOGLE_GMAIL.

Property	XML Attribute Name	Description
Name	name	The Workday-mandated names you associate with various values obtained from the Microsoft Azure Portal or Google Cloud Console.
		For Microsoft Outlook, enter these names:
		outlook.client.idoutlook.client.secretoutlook.tenant.idoutlook.user.id
		For Google Gmail, enter:
		gmail.service.account.key.jsongmail.delegated.user
Value	value	The values obtained from Microsoft or Google that you associate with the names above.
		For Microsoft Outlook, create these name/value pairs:
		Name Value
		outlook.client.id From a registered app's Overview page on the Microsoft Azure Portal: Application (client) ID.
		outlook.client.seoFe6m a
		registered app's Certificates & secrets page on the Microsoft Azure Portal:
		Client Secret ID.
		outlook.tenant.id From a registered app's Overview page on the Microsoft Azure Portal:

Property	XML Attribute Name	Description	
		Name	Value
			Directory (tenant) ID.
		outlook.user.id	The Outlook address of the account from which the email will be sent. Also entered in the From field on the Common tab.
		For Google Gma	
		Name	Value
		gmail.service.ad	from the file downloaded from the KEYS section of the Service accounts page on the Google Cloud Console.
		gmail.delegated	user Gmail address from which the email will be sent. Must be a Principal associated with the Google Service Account. Also entered in the From field on the Common tab.

Gmail over SSL or with STARTTLS

When configuring the **email-out** transport to use Gmail over SSL or STARTTLS, ensure that:

- user and password contain valid Gmail credentials.
- endpoint is mailto:[name]@gmail.com.
- host is smtp.gmail.com.
- ssl or starttls is set to true.

- port is either:
 - 465, if ssl is set to true.
 - 587, if **starttls** is set to true.
- timeout is 30000 (30 seconds).

Microsoft Office 365 over SSL or with STARTTLS

When configuring the email-out transport to use Microsoft Office 365 over SSL or STARTTLS, ensure that:

- user and password contain valid Office 365 user credentials.
- **endpoint** is mailto: [name]@[domain-name.top-level-domain].
- **host** is smtp.office365.com.
- ssl or starttls is set to true.
- port either:
 - 465, if **ssl** is set to true.
 - 587, if **starttls** is set to **true**.
- timeout is 30000 (30 seconds).

Configuring the Message Body and Attachment for Nonbinary Formats

When receiving incoming messages, many email applications match the first text part in the MIME message and use it as the message text. To set the MIME type of the root message part to text/plain, set the message Input and Output properties to message, then set the Output MIME Type to text/plain.

Use the **Message Builder** to define the message content for the email message body using a **text** element.

For the attachment, set the **Output** property to *attachment*, the **Output** attachment index to 0, and the **Output** MIME Type to *text/plain*.

Again, use the Message Builder to define the message content for the attachment using a text element.

To prevent some email applications displaying text attachments in the message body, set the attachment MIME type to *application/octet-stream*, even though it's actually text. To do so, use an MVEL expression within an **eval** step. Example: parts[1].setMimeType('application/octet-stream')

To set the attachment file name, use an MVEL expression to set its Content-Disposition header. Example: parts[1].setHeader('Content-Disposition', 'attachment; filename=payload.txt').

Finally, configure the **email-out** step.

Configuring the Message Body and Attachment for Binary Formats

To inject a binary file into the **MediationContext**, define a Retrieval service for the **workday-in** that retrieves the file from an FTP or SFTP transport.

Create the message body, then use an **eval** step to copy the retrieved file to a variable. You can use the da document accessor variable and the toVar method to achieve this. Example: da.toVar(Rising_2011_Logo.jpg', 'wd.retrieve.variable').

Use a **copy** step to copy the file from the wd.retrieve.variable to an attachment. To do so, set the **Input** property to *variable* and specify wd.retrieve.variable as the input variable. Set the **Output** property to *attachment*, specify an **Output** attachment index of 0, and an **Output** MIME Type of *image/jpeg*.

Finally, configure the email-out step.

Concept: HTTP-Out Transport Child Elements

The **http-out** transport supports these child elements:

Child Element	Description
http-basic-auth	Supports basic authentication on your http-out transport.
http-custom-auth	Supports custom authentication on your http-out transport.
https-properties	Supports HTTPS properties on your http-out transport.

Reference: HTTP-Basic-Auth Properties

Property	XML Attribute Name	Description
Password	password	A password for authentication.
Username	username	A username for authentication.
Realm	realm	The realm name used by a callback handler bean.
Callback-Handler Bean	callback-handler-bean	A bean that implements javax.security.auth.callback.Callba and handles the callback type com.capeclear.transport.impl.http.a to supply username and password details for authentication.
		If you don't specify password details for an http-basic-auth child element, you'll need to use a callback handler bean instead. Example: <http-basic-auth callback-handler-bean="myCallBackHandlerBean" username="me"></http-basic-auth> .
		If you don't specify username and password details for an http-basic-auth child element, you'll need to use a callback handler bean instead. Example: <a "="" href="http-basic-auth callback-handler-bean=" mycallbackhandlerbean"="">http-basic-auth callback-handler-bean="myCallBackHandlerBean"/ >.

Property	XML Attribute Name	Description
		If you specify username and password details for an http-basic-auth child element, you don't require a callback handler bean. Example: http-basic-auth username="me" password="mypassword"/>.

Reference: HTTP-Custom-Auth Properties

Property	XML Attribute Name	Description	
Password	password	A password for authentication.	
Username	username	A username for authentication.	
Realm	realm	The realm name used by a callback handler bean.	
Callback-Handler Bean	callback-handler-bean	A bean that implements javax.security.auth.callback.Cal and handles the callback type com.capeclear.transport.impl.htt to supply username and password details for authentication.	
		If you don't specify password details for an http-custom-auth child element, you'll need to use a callback handler bean instead. Example: <http-custom-auth callback-handler-bean="myCallBackHandlerBean" username="me"></http-custom-auth> .	
		If you don't specify username and password details for an http-custom-auth child element, you'll need to use a callback handler bean instead. Example: <a "="" href="http-custom-auth callback-handler-bean=" mycallbackhandlerbean"="">http-custom-auth callback-handler-bean="myCallBackHandlerBean"/>.	
		If you specify username and password details for an http-custom-auth child element, you don't require a callback handler bean. Example: http-custom-auth username="me" password="mypassword"/>.	

Property	XML Attribute Name	Description
Authenticator Bean		The spring bean that performs a custom authentication.

Reference: HTTPS Properties

Common Tab

Property	XML Attribute Name	Description
Accept Hosts	accept-hosts	The Java regular expression string to use for verifying host names specified in SSL certificates.
Key Password	key-password	The password to use when accessing the appropriate key within the keystore.
Keystore File	key-file	The location of the keystore file to use when connecting to an HTTPS endpoint.
Keystore Password	keystore-password	The password to use when accessing the keystore.
Proxy Host	proxy-host	The host name of a proxy server that you use to proxy HTTPS requests for this transport.
Proxy Port	proxy-port	The port of a proxy server that you use to proxy HTTPS requests for this transport.
Truststore File	truststore-file	The location of the truststore file to use when connecting to an HTTPS endpoint.
Truststore Password	truststore-password	The password to use when accessing the truststore.

FTPS-Out Transport Child Elements

Concept: FTPS-Out Transport Child Elements

The **ftps-out** transport supports these child elements:

Child Element	Description	Notes
proxy-properties	Proxy authentication properties.	
firewall-properties	Firewall connection properties.	The ftps-out transport is firewall-friendly by default because the connection is passive. However, some firewalls may request that you

Child Element	Description	Notes
		route all connections through them.
client-key-properties	Client-key authentication properties.	
server-key-properties	Server-key authentication properties.	

Reference: Proxy-Properties Properties

Common Tab

Property	XML Attribute Name	Description
Proxy Host	proxy-host	The host name of the proxy server to use when making a connection to the secure FTP site.
Proxy Password	proxy-password	The password for the proxy server to use when making a connection to the secure FTP site.
Proxy Port	proxy-port	The proxy server port number to use when making a connection to the secure FTP site.
Proxy Type	proxy-type	The proxy type of the proxy server to use when making a connection to the secure FTP site. The default type is http.
Proxy Username	proxy-username	The proxy server username to use when making a connection to the secure FTP site.

Reference: Firewall-Properties Properties

Property	XML Attribute Name	Description
Firewall Host	firewall-host	The host name or IP address of the firewall to use when making a connection to the secure FTP site.
Firewall Port	firewall-port	The firewall's port number.

Reference: Client-Key Properties

Common Tab

Property	XML Attribute Name	Description
Passphrase	passphrase	The private key passphrase to use when authenticating with the secure FTP site.
Private Key	private-key	The private key associated with the username for SFTP authentication. You can specify it in 2 ways:
		 As a URI using the attachment protocol and the Workday ID. Example, attachment:privatekey/@{WID}, where WID is a 32-character Workday ID. As a relative path location. Example: private_key.txt, where private_key.txt is a file located in the ws/WSAR-INF folder.

Reference: Server-Key Properties

Property	XML Attribute Name	Description
Passphrase	passphrase	The private key passphrase to use when authenticating with the secure FTP site.
Private Key	private-key	The private key associated with the username for SFTP authentication. You can specify it in 2 ways:
		 As a URI using the attachment protocol and the Workday ID. Example, attachment:privatekey/@{WID}, where WID is a 32-character Workday ID. As a relative path location. Example: private_key.txt, where private_key.txt is a file located in the ws/WSAR-INF folder.

Concept: SFTP-Out Child Elements

The **sftp-out** transport supports these child elements:

Child Element	Description	Notes
proxy-properties	Proxy authentication properties.	
private-key-properties	Private key authentication properties.	

Reference: Proxy-Properties Properties

Common Tab

Property	XML Attribute Name	Description
Proxy Host	proxy-host	The host name of the proxy server to use when making a connection to the secure FTP site.
Proxy Password	proxy-password	The password for the proxy server to use when making a connection to the secure FTP site.
Proxy Port	proxy-port	The proxy server port number to use when making a connection to the secure FTP site.
Proxy Type	proxy-type	The proxy type of the proxy server to use when making a connection to the secure FTP site. The default type is http.
Proxy Username	proxy-username	The proxy server username to use when making a connection to the secure FTP site.

Reference: Private-Key Properties

Property	XML Attribute Name	Description
Passphrase	passphrase	The private key passphrase to use when authenticating with the secure FTP site.
Private Key	private-key	The private key associated with the username for SFTP authentication. You can specify it as a relative path location. Example: private_key.txt,

Property	XML Attribute Name	Description
		where the private key file is located in the ws/WSAR-INF folder.

Components

Concept: Components

Components enable you to manipulate and transform messages as they pass through your integration. Workday Studio provides support for these components on the **Components** section of the Assembly **Palette**:

Mediation Component	Description	Notes
async-mediation	Supports 1 processing chain, which you can populate with steps to define a request message in your assembly.	
sync-mediation	Supports 2 processing chains, which you can populate with steps to define request messages and request-response messages in your assembly.	
custom-mediation	Creates a customizable component that supports both request messages and request-response messages.	
route	Implements routing strategies and subroutes to direct the flow of messages through your assembly.	
splitter	Implements splitter strategies and subroutes to direct the flow of messages through your assembly.	Signals to downstream aggregator components.
aggregator	Concatenates messages into batches that you can direct towards a configured destination.	Detects upstream splitter components.

Reference: Async-Mediation Component Properties

Property	XML Attribute Name	Description
ld		The unique ID of the async- mediation component within the assembly.

Property	XML Attribute Name	Description
Routes To	routes-to	The assembly element towards which the async-mediation directs the message.
Execute When	execute-when	A condition that determines if the async-mediation component executes.

Advanced Tab

Property	XML Attribute Name	Description
Continue After Error	continue-after-error	Indicates how Workday behaves when an error handler clears an error.
		The default value is rewind , which means that processing continues from the previous component in the assembly.
		The recover setting specifies that Workday skips to the next step in the mediation when an error occurs.
Handle Downstream Errors	handle-downstream-errors	Indicates whether to handle downstream errors.
		If set to false , local error handlers only address errors that occur within the async-mediation component. Global error handlers will address downstream errors instead.
		If set to true , local error handlers for the async-mediation component can handle downstream errors.

Reference: Sync-Mediation Component Properties

Property	XML Attribute Name	Description
ld	id	The unique ID of the sync- mediation component within the assembly.
Routes To	routes-to	The assembly element towards which the sync-mediation directs the message.

Property	XML Attribute Name	Description
Routes Response To	routes-response-to	The destination of the response message for the sync-mediation component.
Execute When	execute-when	A condition that determines whether the sync-mediation component executes.

Advanced Tab

Property	XML Attribute Name	Description
Continue After Error	continue-after-error	Indicates how Workday behaves when an error handler clears an error.
		The default value is rewind , which means that processing continues from the previous component in the assembly.
		The recover setting specifies that Workday skips to the next step in the mediation when an error occurs.
Handle Downstream Errors	handle-downstream-errors	Indicates whether to handle downstream errors.
		If set to false , local error handlers only address errors that occur within the sync-mediation component. Global error handlers will address downstream errors instead.
		If set to true , local error handlers for the sync-mediation component can handle downstream errors.

Reference: Custom-Mediation Component Properties

Property	XML Attribute Name	Description
ld		The unique ID of the custom- mediation component within the assembly.
Routes To	routes-to	The assembly element towards which the custom-mediation directs the message.

Property	XML Attribute Name	Description
Routes Response To	routes-response-to	The destination of the response message for the custom-mediation component.
Execute When	execute-when	A condition that determines whether the custom-mediation component executes.
Spring Bean	ref	The custom Spring bean Java class implemented by the custom-mediation.
Request Method	request-method	The name of the method used for request processing.
Response Method	response-method	The name of the method used for response processing.

Reference: Route Component Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the route component within the assembly.

Reference: Splitter Component Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the splitter component within the assembly.
No Split Message Error	no-split-error-message	Specifies whether Workday raises an error when the splitter component doesn't generate a split message for a bulk input message.
Split Until	split-until	Specifies when the splitter component ceases processing a bulk input message.

Reference: Aggregator Component Properties

Property	XML Attribute Name	Description
ld	id	The unique ID of the aggregator component within the assembly.

Property	XML Attribute Name	Description
Routes To	routes-to	The assembly element towards which the aggregator directs the message.
Collate When	collate-when	An MVEL expression that determines whether incoming messages get collated.
Force Batch On Last Message	force-batch-on-last- message	Forces batching once the splitter component receives the last message.
Force Batch When	force-batch-when	An MVEL expression that determines whether incoming messages get batched.

Advanced Tab

Property	XML Attribute Name	Description
Allow External Control	allow-external-control	Enables upstream components to control when the aggregator component collates, batches, or both.

Route Component Child Elements

Concept: Route Component Child Elements

The **route** component supports these child elements.

Child Element	Description	Notes
custom-strategy	A customizable routing strategy that you configure as a Spring bean.	
regex-strategy	Implements regular expressions that direct messages towards subroutes.	Implements choose-route child elements to indicate your target sub-route.
mvel-strategy	Implements MVEL expressions that direct messages towards subroutes.	Implements choose-route child elements to indicate your target sub-route.
round-robin-strategy	Directs messages towards subroutes in cyclical order.	
xpath-strategy	Implements XPath expressions that direct messages towards subroutes.	Implements choose-route child elements to indicate your target sub-route.
failover-strategy	Implements a failover mechanism that directs messages towards subroutes. If a sub-route child	

Child Element	Description	Notes
	element fails, the next sub-route replaces it.	
all-strategy	Directs messages to each subroute in turn.	
doc-iterator	Iterates over documents that your assembly retrieves from Workday.	
loop-strategy	Implements a looping mechanism that direct messages towards subroutes.	
choose-route	Indicates the target sub-route child element towards which your strategy directs the message.	Supports XPath, MVEL, or regular expressions.
sub-route	Receives messages from your routing strategy, and directs them towards other components and transports in your assembly.	

Reference: Custom-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Spring Bean	ref	The Spring bean that implements your custom-strategy interface class.
Repeatable	repeatable	Enables looping.
		If set to true , your assembly implements a loop that repeatedly calls your custom-strategy .
		If set to false , your assembly doesn't implement a loop for your custom-strategy .
Repeat Limit	repeat-limit	Limits the number of times a loop calls your custom-strategy .
Handle Error	handle-error	Indicates whether your parent route component handles exceptions for your sub-route.

Reference: Regex-Strategy Properties

Property	XML Attribute Name	Description
Filter	filter	Indicates whether Studio displays an error message when you

Property	XML Attribute Name	Description
		implement invalid regular expressions on a choose-route child element.

Reference: MVEL-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Filter	filter	Indicates whether Studio displays an error message when you implement invalid MVEL expressions on a choose-route child element.

Reference: Round-Robin-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Clone Request	clone-request	Indicates whether the round- robin-strategy sends a copy of the original mediation message to each of your sub-route child elements.
Failover	failover	Indicates whether the round- robin-strategy loops through your sub-route child elements when it encounters a failed sub- route.
Timeout	timeout	A millisecond value indicating how long a failed subroute is excluded from routing.

Reference: XPath-Strategy Properties

Property	XML Attribute Name	Description
Filter	filter	Indicates whether Studio displays an error message when you implement invalid XPath expressions on a choose-route child element.
Namespaces	namespaces	The namespaces used by your XPath expression in the format prefix namespace prefix2 namespace2. Overrides

Property	XML Attribute Name	Description
		namespace mappings in the assembly.xml file.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0, 2.0, or 3.0. Enter the value 1 for assembly versions through Workday 11. Enter 2 or 3 for assembly versions Workday 12 onwards.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version')

Reference: Failover-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Clear Fault	clear-fault	Indicates whether the failover- strategy clears exceptions generated by your sub-route child elements.
Clone Request	clone-request	Indicates whether the failover- strategy sends a copy of the original mediation message to each of your sub-route child elements.

Reference: All-Strategy Properties

Property	XML Attribute Name	Description
Clone Request	clone-request	Indicates whether the all- strategy sends a copy of the original mediation message to each of your sub-route child elements.
Ignore Errors	ignore-errors	Indicates whether the all- strategy ignores errors generated by your sub-route child elements.

Reference: Doc-Iterator Properties

Common Tab

Property	XML Attribute Name	Description
Variable Name	variable-name	The name of the variable in which the doc-iterator stores your retrieved document. The default value is wd.retrieve.variable.
Labels	labels	Specifies 1 or more labels attached to your retrieved document.
Sort By	sort-by	The sort order for retrieving and presenting documents. Options are: • FILENAME_ASCENDING • FILENAME_DESCENDING • NONE

Reference: Loop Strategy Properties

Property	XML Attribute Name	Description
Condition	condition	An MVEL expression that generates a Boolean value. The loop-strategy runs until the expression evaluates as false.
Increment	increment	An increment value for every loop iteration.
Init	init	The starting value of your loop.
Repeat Limit	repeat-limit	The maximum number of loops implemented by the loop-strategy.
		A route strategy can repeat up to 200,000 times in total. If the same strategy is called multiple times, the loop counter doesn't reset. It continues from the previous value. You can use a custom Java bean or a custom splitter to avoid this limit.

Reference: Choose-Route Properties

Common Tab

Property	XML Attribute Name	Description
Expression	expression	An expression used to match incoming message values.
Route	route	A target sub-route child element for matched expression values.

Reference: Sub-Route Properties

Common Tab

Property	XML Attribute Name	Description
Name	name	The unique name of the sub- route within the assembly.
Routes To	routes-to	The assembly element towards which the sub-route directs the message.

Splitter Component Child Elements

Concept: Splitter Component Child Elements

The **splitter** component supports these child elements.

Child Element	Description	Notes
custom-splitter	A customizable splitter strategy that you configure as a Spring bean.	
standard-splitter	Extracts data from bulk messages, splits the data into tokens, and directs the tokenized data towards your target subroutes.	Supports these child elements: • header-ends-with • header-fixed-lines • content-fixed-lines • content-starts-ends • content-starts-with • footer-fixed-lines • footer-starts-with
xpath-splitter	Implements an XPath expression to extract data from incoming bulk messages.	
xml-stream-splitter	Implements an XPath expression to extract data from incoming bulk messages. Supports XML streaming.	

Child Element	Description	Notes
json-splitter	Extracts JSON from bulk input messages.	
unzip-splitter	Extracts data from ZIP and TAR files, splits the data into individual messages, and directs the messages towards their target subroutes.	
mtable-splitter	Extracts data from an mtable object, and splits the data into individual rows.	
sub-route	Receives messages from your splitter strategy, and directs them towards other components and transports in your assembly.	

Reference: Custom-Splitter Properties

Common Tab

Property	XML Attribute Name	Description
Spring Bean	ref	The Spring bean that implements your custom-splitter interface class.

Reference: Standard-Splitter Properties

Common Tab

Property	XML Attribute Name	Description
Output Mimetype	output-mimetype	The MIME type of your tokenized output data.
Line Token Delimiter Regexp	line-token-delimiter- regexp	The delimiting regular expression that extracts tokenized data from bulk messages.
Multiple Lines Separator	multiple-lines-separator	A string that concatenates tokens spanning multiple lines.

Reference: XPath-Splitter Properties

Property	XML Attribute Name	Description
Namespaces	namespaces	The namespaces used by your XPath expression.
XPath	xpath	The XPath expression that extracts XML from bulk input messages.

Property	XML Attribute Name	Description
XPath Version	xpath-version	Specifies whether to use XPath version 1.0, 2.0, or 3.0. Enter the value 1 for assembly versions through Workday 11. Enter 2 or 3 for assembly versions Workday 12 onwards.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a property value. Example: @{props.get('the_version'

Reference: XML-Stream-Splitter Properties

Common Tab

Property	XML Attribute Name	Description
Namespaces	namespaces	The namespaces used by your XPath expression.
XPath	xpath	The XPath expression that extracts XML from bulk input messages.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0, 2.0, or 3.0. Enter the value 1 for assembly versions through Workday 11. Enter 2 or 3 for assembly versions Workday 12 onwards.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version')

Reference: JSON-Splitter Properties

Property	XML Attribute Name	Description
Json Path	json-path	The expression that extracts JSON from bulk input messages.

Reference: Unzip-Splitter Properties

Common Tab

Property	XML Attribute Name	Description
File Pattern	file-pattern	The regular expression that extracts data from ZIP and TAR input files.
Format	format	The format of your input files. The options are:
		• zip • tar

Reference: Mtable-Splitter Properties

Common Tab

Property	XML Attribute Name	Description
Mtable Name	mtable-name	The name of the MediationContext property that contains the mtable.
Row Name	row-name	The name of the MediationContext property that stores the iterated row.
Row Format	row-format	Determines the class of the iterated row. Supported values are: • array • map

Standard-Splitter Child Elements

Concept: Standard-Splitter Child Elements

The **standard-splitter** component supports these child elements.

Child Element	Description
header-ends-with	Indicates the end of the header section in your document.
header-fixed-lines	Indicates the number of lines occupied by the header section in your document.
content-fixed-lines	Indicates the number of lines occupied by the data records content section in your document.
content-starts-ends	Indicates the start point and end point of the data records content section in your document.

Child Element	Description
content-starts-with	Indicates the start point of the data records content section in your document.
footer-fixed-lines	Indicates the number of lines occupied by the footer section in your document.
footer-starts-with	Indicates the start point of the footer section in your document.

Reference: Header-Ends-With Properties

Common Tab

Property	XML Attribute Name	Description
Include In Header	include-in-header	Determines whether the matching line of your regular expression is part of the header.
Regexp	regexp	A regular expression that identifies the end of the header.

Reference: Header-Fixed-Lines Properties

Common Tab

Property	XML Attribute Name	Description
Lines Count	lines-count	The number of lines occupied by the header.

Reference: Content-Fixed-Lines Properties

Common Tab

Property	XML Attribute Name	Description
Ignore Lines Regexp	ignore-lines-regexp	A regular expression that excludes matching lines from the data records content section.
Lines Count	lines-count	The number of lines occupied by the data records content section.

Reference: Content-Starts-Ends Properties

Property	XML Attribute Name	Description
End Regexp	end-regexp	A regular expression that identifies the end of the data records content section.

Property	XML Attribute Name	Description
Start Regexp	start-regexp	A regular expression that identifies the start of the data records content section.

Reference: Content-Starts-With Properties

Common Tab

Property	XML Attribute Name	Description
Regexp		A regular expression that identifies the start of the data records content section.

Reference: Footer-Fixed-Lines Properties

Common Tab

Property	XML Attribute Name	Description
Ignore Lines Regexp	ignore-lines-regexp	A regular expression that excludes matching lines from the footer section.
Lines Count	lines-count	The number of lines occupied by the footer section.
Trim Eof Ignore Lines	trim-eof-ignore-lines	Determines whether the matching lines of your regular expression are trimmed from the footer.

Reference: Footer-Starts-With Properties

Common Tab

Property	XML Attribute Name	Description
Regexp	regexp	A regular expression that identifies the start of the data records content section.

Aggregator Component Child Elements

Concept: Aggregator Component Child Elements

The **aggregator** component supports these child elements.

Child Element	Description
	A customizable batching strategy that you configure as a Spring bean.

Child Element	Description
size-batch-strategy	Batches incoming messages based on a specified batch size value.
time-batch-strategy	Batches incoming messages based on a specified time period value.
custom-collater	A customizable collating strategy that you configure as a Spring bean.
message-content-collater	Aggregates the message content of the MediationMessage.
xml-message-content-collater	Aggregates the XML document content of an XML message stream.
json-collater	Aggregates JSON documents into a single output.
zip-file-collater	Aggregates multiple files into a single ZIP file.
mtable-collater	Aggregates mtable rows into a new mtable instance.

Reference: Custom-Batch-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Spring Bean	ref	The Spring bean that implements your custom-batch-strategy interface class.

Reference: Size-Batch-Strategy Properties

Common Tab

Property	XML Attribute Name	Description
Batch Size		The maximum number of messages that a batch concatenates.

Reference: Time-Batch-Strategy Properties

Property	XML Attribute Name	Description
Time Period	time-period	The duration of batch aggregation.
Time Unit	time-unit	The unit of time implemented by the Time Period property. The default value is seconds .

Common Tab

Property	XML Attribute Name	Description
Output	output	Specifies where the custom- collater child element directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Spring Bean	ref	The Spring bean that implements
Spring Bean	TET	your custom-collater interface class.

Reference: Message-Content-Collater Properties

Property	XML Attribute Name	Description
Output	output	Specifies where the message-content-collater child element directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments.

Property	XML Attribute Name	Description
		 soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Header Text	header-text	Adds a header to your output message.
Footer Text		Adds a footer to your output message.
Separator	separator	A string used when concatenating messages in a batch.

Reference: XML-Message-Content-Collater Properties

Property	XML Attribute Name	Description
Output	output	Specifies where the xml- message-content-collater child element directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message.

Property	XML Attribute Name	Description
		variable: save the output as a named variable in the MediationContext.
Header Text	header-text	Adds a header to your output message.
Footer Text		Adds a footer to your output message.
Separator	separator	A string used when concatenating messages in a batch.
Namespaces	namespaces	The namespaces used by your XPath expression.
XPath	xpath	An XPath expression that aggregates matching XML messages. If not specified, the xml-message-content-collater aggregates all XML message content into 1 output file.

Reference: JSON-Aggregator Properties

Property	XML Attribute Name	Description
Output	output	Specifies where the json-collater child element directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.

Common Tab

Property	XML Attribute Name	Description
Output	output	Specifies where the zip-file-collater child element directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Format	format	The format of your output files. The options are: • zip
Message Entity Name	message-entity-name	The name of each message added to your output file.

Reference: Mtable-Collater Properties

Property	XML Attribute Name	Description
Output	output	Workday ignores this setting for mtable-collater child elements.
Mtable Name	mtable-name	The name of the MediationContext property that stores your output mtable.

Property	XML Attribute Name	Description
Row Name	row-name	The name of the MediationContext property that stores your aggregated mtable row.
Column Names	column-names	A comma-separated list of columns that defines your output mtable.
Index Column	index-column	The index column name of your output mtable.
Allow Null Row	allow-null-row	Determines whether your output mtable supports null row values.

Common Components

Concept: Common Components

Workday Studio provides a range of prepackaged subassemblies that you can use to build your integrations. These subassemblies are available from the **Common Components** tab of the **Palette**. When you add one to your assembly diagram, Studio inserts a local-out element in the XML source with the appropriate endpoint in Workday.

It also displays the parameters you can use with that subassembly, with required parameters already selected. You can adjust parameters at any time in the subassembly's **Properties** view.

Studio includes these **Common Components** on the **Palette**:

Name	Function	Notes
Ftp	Routes to an ftp-out transport.	 Provides a single entry point for all FTP transports. Uses the wd.ftp.endpoint parameter value to determine the type of FTP transport implemented. Examples: ftp://, sftp://, or ftps://. Exposes the transport settings that are commonly used in Workday, such as username and password authentication. Hides more advanced public key authentication.
		Note: The FTP Subassembly is no longer available from the Studio Palette. In new integrations, you should use the ftp-out or sftp-out components to send documents to an FTP server. These components offer improved security, better performance, and enhanced

Name	Function	Notes
		reliability. They're also compatible with later versions of JSCAPE. The FTP Subassembly remains functional in existing integrations, but Workday recommends that, where practical, you replace it.
GetEventConfigurations	Retrieves the service configurations attached to a particular integration event.	
GetEventDocuments	Retrieves the documents attached to a particular integration event.	
GetIntegrationEvent	Retrieves an integration event based on a Workday reference ID.	
GetIntegrationSystems	Retrieves the integration system's configuration from Workday and parses it.	
PagedGet	Implements the paging logic required by any paged-get Web service operation, enabling pageby-page data retrieval.	Use the is.paged.get.process.endpoint parameter to send each page of response data to another subassembly for processing. Use the is.paged.get.aggregate.head is.paged.get.aggregate.root and is.paged.get.aggregate.xpat parameters to aggregate all pages of response data. Aggregated XML data is available as the message in the MediationContext when the subassembly returns. If a web service is expected to return a large number of pages, use the per-page processing approach.
PagedGetLocalPaging	Implements the paging logic required by any paged-get local Web service operation, enabling page-by-page data retrieval.	Enables the paging process to be performed locally at the ESB server, rather than remotely by Workday. Uses a single query to return all Workday IDs. Subsequent calls retrieve the data for each Workday ID.

Name	Function	Notes
PdfPrintStep	Converts custom report data from a workday-out-rest request to PDF format using a BIRT report design.	Specify a literal string value for each of the MVEL-capable parameters by enclosing it in single quotes.
PutIntegrationEvent	Updates an integration system's integration event status in Workday.	Uses the Put_Integration_Event web service operation. Puts the event response Workday ID returned from the Web service operation in the MediationContext property integrations.event.response.
PutIntegrationMessage	Sends update integration messages to Workday.	Can also add documents in the form of references to Workday document storage. Uses the Put_Integration_Message web service operation. Workday limits the number of calls a PutIntegrationMessage subassembly can make in a single integration to 500. Subsequent integration messages are logged to a log file and can't be viewed in the integration event. (Redirect doesn't apply to messages that have attachments or change the integration event status.)
SalesforceConnector	Sends authenticated messages to salesforce.com.	
PrismConnector	Sends CSV data to Prism Analytics.	

Reference: FTP Subassembly Properties

Common Tab

Note: The FTP Subassembly is no longer available from the Studio Palette. In new integrations, you should use the **ftp-out** or **sftp-out** components to send documents to an FTP server. These components offer improved security, better performance, and enhanced reliability. They're also compatible with later versions of JSCAPE. The FTP Subassembly remains functional in existing integrations, but Workday recommends that, where practical, you replace it.

Property	XML Attribute Name	Description
ld	id	The unique ID of the Ftp subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the Ftp subassembly.
Execute When	execute-when	A condition that determines whether the Ftp subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The Ftp component supports a vm://endpoint address. Example: vm://wcc/Ftp.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.

Property	XML Attribute Name	Description
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
wd.ftp.endpoint	The endpoint scheme used to determine which ftp-out transport to use. The endpoint must start with ftp://, sftp://, or ftps://.
wd.ftp.username	The username used to access the FTP server.
wd.ftp.password	The password associated with the username used to access the FTP server.
wd.ftp.method	The method or message action that the FTP subassembly implements when connecting with the endpoint. Enclose each action in single quotes. Valid options include:
	 'put': The FTP component sends the message to the FTP server and the message remains unchanged. 'get': The assembly replaces the root part of the message with the data that it receives from the FTP server. 'list': The message remains unchanged. Workday adds a context property called wd.ftp.files.list, which contains a
	List <string> object instance. Note: Using the 'list' method with a file pattern of *.txt or *.xml results in an exception. • 'delete': Workday requests a file deletion from the FTP server. The message remains</string>
	unchanged. • 'mget' (multiget): Workday downloads all files that match the input pattern and replaces the root part of the message with a ZIP file containing those files. • 'mdelete' (multidelete): Workday deletes all
	files that match the input pattern. The message remains unchanged.

Parameter	Description
wd.ftp.passive.mode	Specifies whether passive mode is used during the FTP connection.
wd.ftp.file.pattern	Specifies the file pattern used when performing the FTP operation. Examples:
	• *.xml
	• *.txt
	For most methods other than list, Workday supports wildcards and performs filtering on the client side. For the list method, Workday uses server-side filtering, based on regular-expression syntax. Examples:
	• wd.ftp.method is 'get' and wd.ftp.file.pattern is *.xml: Workday gets the first .xml file found on the FTP server in the specified directory.
	 wd.ftp.method is 'mget' and wd.ftp.file.pattern is *.xml: Workday gets all the .xml files found on the FTP server in the specified directory and returns them in ZIP format.
	 wd.ftp.method is 'list' and wd.ftp.file.pattern is ^.*\.(xml)\$: Workday lists all the .xml files found on the FTP server in the specified directory.
wd.ftp.temp.file.name	Specifies whether a temporary file should be used when performing an FTP put message action.
wd.ftp.timeout	A timeout for the message action in milliseconds.
wd.ftp.directory	The relative or fully qualified directory path.
wd.ftp.private.key	The private key associated with the username for SFTP authentication. Formatted as a URI using the attachment protocol and a Workday ID. Example: attachment:privatekey/@{WID}, where WID corresponds to a 32-character Workday ID.
wd.ftp.max.attempts	The maximum number of attempts to access the FTP server.
wd.ftp.debug	Specifies whether Workday will add debug logging to the logs.
wd.ftp.proxy.host	The hostname of the FTP proxy server.
wd.ftp.proxy.port	The FTP proxy server port.
wd.ftp.proxy.username	The username for accessing the FTP proxy server.
wd.ftp.proxy.password	The password of the FTP proxy server.

Parameter	Description
	Specifies the content type of files retrieved using FTP get. Example: text/plain; charset=Big5.

Reference: GetEventConfigurations Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the GetEventConfigurations subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the GetEventConfigurations subassembly.
Execute When	execute-when	A condition that determines whether the GetEventConfigurations subassembly executes.
Endpoint	endpoint	Specifies the target endpoint address for the subassembly. The GetEventConfigurations component supports a vm://endpoint address. Example: vm://wcc/ GetEventConfigurations.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the

Property	XML Attribute Name	Description
		value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly. A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
ie.event.wid	The Workday ID for the integration event whose service configurations you want to retrieve. Automatically populates with lp.isSet() ? lp.getIntegrationEventWID(): null.
is.event.disable.msg.storage	Switches off message storage when set to true.
ie.event.wws.version	The integration event Web Service version.

Reference: GetEventDocuments Subassembly Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the GetEventDocuments subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for

Property	XML Attribute Name	Description
		the GetEventDocuments subassembly.
Execute When	execute-when	A condition that determines whether the GetEventDocuments subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The GetEventDocuments component supports a vm://endpoint address. Example: vm://wcc/GetEventDocuments.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.

Property	XML Attribute Name	Description
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
ie.event.wid	The Workday ID for the integration event whose service configurations you want to retrieve. Automatically populates with lp.isSet()? lp.getIntegrationEventWID(): null. This means that the parameter's value defaults to the integration event WID if the launch document has been specified in the mediation context and to null if it has not.

Reference: GetIntegrationEvent Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
Id	id	The unique ID of the GetIntegrationEvent subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the GetIntegrationEvent subassembly.
Execute When	execute-when	A condition that determines whether the GetIntegrationEvent subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The GetIntegrationEvent component supports a vm://endpoint address. Example: vm://wcc/GetIntegrationEvent.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	1	Specify <i>none</i> unless otherwise advised by Workday Support.

Property	XML Attribute Name	Description
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
	The Workday ID for the integration event whose service configurations you want to retrieve.

Reference: GetIntegrationSystems Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the GetIntegrationSystems subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the GetIntegrationSystems subassembly.
Execute When	execute-when	A condition that determines whether the GetIntegrationSystems subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The GetIntegrationSystems component supports a vm://endpoint address. Example: vm://wcc/ GetIntegrationSystems.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.

Property	XML Attribute Name	Description
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
	The Workday ID for the integration system whose service configurations you want to retrieve and parse. Automatically populates with lp.getIntegrationSystemRefWID().

Reference: PagedGet Subassembly Properties

Property	XML Attribute Name	Description
ld	id	The unique ID of the PagedGet subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the PagedGet subassembly.
Execute When	execute-when	A condition that determines whether the PagedGet subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PagedGet component supports a vm: // endpoint address. Example: vm: //wcc/PagedGet.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
is.paged.get.request.current.page.xpath	The XPath location in the request document where the PagedGet component sets the number of the pages being requested.
is.paged.get.response.current.page.xpat	hThe XPath expression to extract the current page value from the web service response message.
is.paged.get.response.total.pages.xpath	The XPath expression to extract the total pages value from the web service response message.
is.paged.get.response.total.results.xpa	page value from the web service response message.
is.paged.get.process.endpoint	The local-in endpoint of the subassembly that processes each page of results. Example: vm://payrollInterface/ProcessPayeesLocalIn.
	Note: Workday ignores aggregate parameters when you set this parameter.
	These MediationContext properties are available in the processing subassembly:
	is.paged.get.request.current.page.xpatis.paged.get.response.current.page.xpais.paged.get.response.total.pages.xpatis.paged.get.response.total.results.xp
is.paged.get.aggregate.header	The header value for aggregated responses in the form of an XML fragment. Example: <alldata>.</alldata>
is.paged.get.aggregate.footer	The header value for aggregated responses in the form of an XML fragment. Example: .
is.paged.get.aggregate.xpath	The XPath expression to apply to the response message when aggregating.
is.paged.get.namespaces	Specifies namespaces that aren't available on the document.
is.paged.get.application	The application group of the web service you're invoking. Example: Human_Resources.
is.paged.get.version	The version of the public web service you're invoking. As best practice, use the latest WWS version at the time you're building the integration. Don't use a dynamic latest version that changes as the integration runs.
	For assemblies with a version before 2016.45, this parameter automatically populates with util.assemblyVersionAsWWSVersion.
	For assemblies with a version 2016.45 or later, you must explicitly supply the Web services version. Example: v27.2.

Parameter	Description
is.paged.get.page.zero	Specifies whether a response page should be generated for cases where the total number of pages is zero.
is.paged.get.parallel	Specifies whether to retrieve web service responses in parallel, enabling the subassembly named in the is.paged.get.process.endpoint parameter to process each paged response. Automatically populates with false, meaning that web service responses are aggregated rather than retrieved in parallel.
	Workday processes parallel responses using unique contexts that enable read-only access to the property values and variables that were set before the PagedGet was entered. When the subassembly finishes with each page, you lose any properties or variables set during that processing. The PagedGet still sets the is.paged.get.total.pages and is.paged.get.total.results properties on the calling MediationContext. The is.paged.get.current.page property is set in the parallel paged contexts.
	Workday processes nonparallel responses in the same context and processes the pages in the subassembly. This means that you can set properties and variables in the subassembly and check the state of previous pages.
is.paged.get.store.requests	Specifies whether to store the web service request messages for each page of data in the message store.
is.paged.get.overall.timeout.seconds	The overall timeout in seconds. The default, if unset, is 6 hours. The maximum timeout you can set is 30 hours.
is.paged.get.timeout.seconds	The timeout for processing each page. The default, if unset, is 6 hours. Can't exceed the overall timeout value.

Out Parameters

As the **PagedGet** subassembly processes, it passes these out-parameter values for use by downstream components:

Out-Parameter	Description
is.paged.get.last.page	The final page returned by the web service operation.
is.paged.get.current.page	The number of the page currently being processed.
is.paged.get.total.pages	The total number of pages to be processed.

Out-Parameter	Description
	The total number of results returned by the web service operation.

Reference: PagedGetLocalPaging Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
Id	id	The unique ID of the PagedGetLocalPaging subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the PagedGetLocalPaging subassembly.
Execute When	execute-when	A condition that determines whether the PagedGetLocalPaging subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PagedGetLocalPaging component supports a vm://endpoint address. Example: vm://wcc/PagedGet.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.

Property	XML Attribute Name	Description
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly. A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description	
is.paged.get.process.endpoint	Specifies the local-in endpoint of the subassembly that will process each page of results. Example: vm://payrollInterface/ProcessPayeesLocalIn.	
	Note: Workday ignores aggregate parameters when you set this parameter.	
	These MediationContext properties are available in the processing subassembly:	
	 is.paged.get.request.current.page.xpath is.paged.get.response.current.page.xpath is.paged.get.response.total.pages.xpath is.paged.get.response.total.results.xpat 	
is.paged.get.page.size	The number of records in each page of data to be retrieved. Automatically populates with 100.	
is.paged.get.response.reference.wid	ds.xpartie XPath expression used to find the WIDs in the get all WIDs invocation response message. Example: //wd:Payee_Reference/wd:ID[@wd:type='WID'].	

Parameter	Description
is.paged.get.request.reference.wids.par	eThe.XPathexpression used to find the parent element of the request message where WIDs will be indicated when getting each page of data.
is.paged.get.request.reference.wids.ele	metelement name for the WID to be used in the request for each page of data.
is.paged.get.application	The application group of the web service you're invoking. Example: Human_Resources.
is.paged.get.version	The version of the public web service you're invoking. As best practice, use the latest WWS version at the time you're building the integration. Don't use a dynamic latest version that changes as the integration runs.
	For assemblies with a version prior to 2016.45, this parameter automatically populates with util.assemblyVersionAsWWSVersion.
	For assemblies with a version 2016.45 or later, you must explicitly supply the Web services version. Example: v27.2.
is.paged.get.xpath.ns.prefix	The prefix for the Workday XML namespace used in all XPath expressions. Automatically populates with wd.

Reference: PdfPrintStep Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the PdfPrintStep subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the PdfPrintStep subassembly.
Execute When	execute-when	A condition that determines whether the PdfPrintStep subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PdfPrintStep component supports a vm://endpoint address. Example: vm://wcc/PdfPrintStep.

Advanced Tab

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/ assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
	The name of the integration variable that contains the report design, which defines the

Parameter	Description	
	layout for the printed custom report. Example: 'test.report.design'.	
	The report design definition is contained in a file with the extension.rptdesign.	
pdf.workday.report.variable	The name of the integration variable that contains the raw Workday report data. Example: 'test.workday.report'.	
pdf.timezone	The Java time zone for formatting purposes. Example:	
	'US/Eastern''GMT''CET'	
pdf.language	The language of the report for formatting purposes. Example:	
	'en_US''fr_FR''de_DE'	
pdf.locale	The locale of the report for formatting purposes. Example:	
	'en_US''fr_FR''de_DE'	
pdf.business.form.layout.wid	The Workday ID of the Business Form Layout being used. Enables retrieval of images defined as tokens on the layout.	
pdf.report.design.wid	The Workday ID of the report design being used. Enables translation.	
pdf.apply.report.design.per.row	Specifies whether Workday applies the report design to individual report rows, rather than to the report as a whole.	

Related Information Reference

The Next Level: Using BIRT in Studio Integrations

Reference: PutIntegrationEvent Subassembly Properties

Common Table

Property	XML Attribute Name	Description
ld	id	The unique ID of the PutIntegrationEvent subassembly within the assembly.

Property	XML Attribute Name	Description
Routes Response To	routes-response-to	The destination of the response message for the PutIntegrationEvent subassembly.
Execute When	execute-when	A condition that determines whether the PutIntegrationEvent subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PutIntegrationEvent component supports a vm://endpoint address. Example: vm://wcc/PutIntegrationEvent.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.

Property	XML Attribute Name	Description
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
is.event.wid	The Workday ID of the integration event to which Workday will link the message.
	If you don't specify this value and it isn't present in the lp MVEL variable, Workday uses the is.system.wid parameter instead, linking the message to the integration system. Automatically populates with lp.isSet() ? lp.getIntegrationEventWID() : null.
is.system.wid	The Workday ID of the integration system. Automatically populates with lp.isSet() ? lp.getIntegrationSystemRefWID(): null.
	Workday only uses this parameter if the integration event ID isn't available.
is.process.desc	The integration event description. Workday displays this value in its Process Monitor. Required when creating a new integration event.
is.event.initiated	The date and time when the integration event initiates. If you enter the string value 'current', the current date and time is sent to Workday.
is.event.completed	The date and time when the integration event completes. If you enter the string value 'current', the current date and time is sent to Workday.
is.response.msg	The most recent message or activity for the integration event. A free-form text field.
is.event.member.wids	A comma-separated list of Workday IDs representing members linked to this integration event.
is.percent.complete	A value that Workday uses to maintain the Percent Complete progress bar. The value can be any type

Parameter	Description	
	that can be converted to a Java BigDecimal object. It must be a value between zero and 100.	

Reference: PutIntegrationMessage Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the PutIntegrationMessage subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the PutIntegrationMessage subassembly.
Execute When	execute-when	A condition that determines whether the PutIntegrationMessage subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PutIntegrationMessage component supports a vm:// endpoint address. Example: vm://wcc/ PutIntegrationMessage.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.

Property	XML Attribute Name	Description
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description
is.event.wid	The Workday ID of the integration event to which Workday will link the message.
	If you don't specify this value and it isn't present in the lp MVEL variable, Workday uses the is.system.wid parameter instead, linking the message to the integration system. Automatically populates with lp.isSet() ? lp.getIntegrationEventWID(): null.
is.system.wid	The Workday ID of the integration system. Automatically populates with lp.isSet() ? lp.getIntegrationSystemRefWID() : null.
	Workday only uses this parameter if the integration event ID isn't available.
is.message.severity	Specifies the message severity level: 'CRITICAL', 'DEBUG', 'ERROR', 'INFO', or 'WARNING'. Automatically populates with 'INFO'.
is.message.summary	The message summary sent to Workday.
is.message.detail	The message detail sent to Workday.

Parameter	Description
is.message.detail.richtext	Determines whether the message detail is formatted as rich text. Automatically populates with true.
is.document.variable.name	The name of a variable in the MediationContext that contains the Atom schema output of an assembly store step. The variable content is used to add a reference to the integration event.
	The store step used to create the document must have the schema attribute set as follows: schema="http://www.w3.org/2005/Atom".
is.document.file.name	The filename for the document. If you don't provide one, Workday uses the document title from the Atom document.
is.document.owner.wid	The Workday ID of the document owner. If you don't provide one, Workday uses the current integration system user's ID.
is.document.labels	A comma-separated list of labels that are applied to the document when it's within the scope of the integration event ID or associated Business Process.
is.document.deliverable	Specifies whether the document added to the integration event is automatically delivered to a customer or external provider. Automatically populates with 'true'.
is.document.delivery.services	A comma-separated list of integration service names that's used to tag the document being attached to the integration event. By default, Workday uses all delivery services associated with the integration system.
is.document.retrieved	Specifies whether the document is treated as having been retrieved by the retrieval service. Automatically populates with 'false'.
is.message.targets	A comma-separated list of references to target objects for this message. These targets become object links in the Workday application View Integration Message tab.
is.message.targets.type	A target reference type. Automatically populates with 'WID'.
is.message.secured.instance.refs	A comma-separated list of secured instance references for this message.
is.message.secured.instance.refs.type	Enables the default type for secured instance refs to be overridden. Automatically populates with 'WID'.
is.message.storage.enabled	Determines whether the message is stored. Automatically populates with 'false'.

Reference: SalesforceConnector Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the SalesforceConnector subassembly within the assembly.
Routes Response To	routes-response-to	The destination of the response message for the SalesforceConnector subassembly.
Execute When	execute-when	A condition that determines whether the SalesforceConnector subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The SalesforceConnector component supports a vm://endpoint address. Example: vm://wcc/ SalesforceConnector.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support.
		To store messages, use Studio's store step.
Transport Class	transport-class	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.

Property	XML Attribute Name	Description	
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.	
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.	
		A subassembly stops processing when it marks the MediationContext as aborted.	
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.	

Parameters Tab

Parameter	Description
wd.sf.auth.username	Your salesforce.com developer account username.
wd.sf.auth.password	Your salesforce.com developer account password.
wd.sf.msg.varname	The XML message that Workday sends to the salesforce.com endpoint.
wd.sf.auth.token	Your salesforce.com developer account security token.
wd.sf.auth.endpoint	An optional salesforce.com endpoint. A default endpoint is already configured as part of the subassembly's http-out transport.
wd.sf.api.custom.version	An optional salesforce.com API version. If you don't provide a value, the endpoint API version is used.

The PrismAnalytics Subassembly

Steps: Send CSV Data to Prism Analytics

Prerequisites

Security: Security Administration domain in the System functional area.

Context

Workday Studio's **PrismAnalytics** component enables you to send CSV data to Workday Prism Analytics. Before you configure an assembly to use the **PrismAnalytics**, you must register a Prism API client in

Workday and obtain a REST API endpoint. You must also create a JSON description of the source CSV data.

Steps

1. Register a Workday Prism Analytics API Client on page 122.

In Workday, register an integrations API client with Prism Analytics as its scope. Obtain the **Client ID**, **Client Secret**, and **Refresh Token** values that the **PrismAnalytics** component requires as parameters.

2. Obtain the Workday REST API Endpoint on page 123.

In Workday, obtain the Workday REST API endpoint that the **PrismAnalytics** component requires as a parameter.

Describe the Source CSV Data on page 123.

Describe the source CSV data in JSON text for passing to the **PrismAnalytics** component as a variable.

4. Configure an Assembly with the PrismAnalytics Subassembly on page 129.

In Workday Studio, create an assembly that acquires CSV data and passes it to a properly configured **PrismAnalytics** component.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Register a Workday Prism Analytics API Client

Prerequisites

Security: Security Administration domain in the System functional area.

Context

To use Workday Studio's **PrismAnalytics** component, you must register an API client in Workday with Prism Analytics as its scope. The component requires the **Client ID** and **Client Secret** values that Workday generates during the registration process. It also requires a **Refresh Token** value.

Steps

1. Access the Register API Client for Integrations task. As you complete this task, consider:

Option	Description
Non-Expiring Refresh Tokens	Prevents the refresh token from timing out. Automatically selected by Workday. Don't clear.
Scope (Functional Area)	Select Prism Analytics.
Include Workday Owned Scope	Provides access to core Workday domains that aren't in any functional areas. Select this check box.

- 2. Copy the Client ID and Client Secret values. Studio's PrismAnalytics component requires them for its wd.prism.component.client.id and wd.prism.component.client.secret parameters.
- 3. From the related actions menu, select API Client > Manage Refresh Tokens for Integrations.
- **4.** Select a **Workday Account** to associate with the refresh token. The account must have permission to create Prism tables in Workday.

Note: You can't perform these steps as an Integration System User.

5. Select Generate New Refresh Token.

6. Copy the **Refresh Token** value. The **PrismAnalytics** component requires it for its wd.prism.component.refresh.token parameter.

Obtain the Workday REST API Endpoint

Prerequisites

Security: Security Administration domain in the System functional area.

Context

Studio's **PrismAnalytics** component requires a Workday REST API endpoint. You can find this endpoint in Workday.

Steps

- Access the View API Clients report.
- 2. Copy the Workday REST API Endpoint value.

Example: https://i-07d55d20e81e2d191.workdaysuv.com/ccx/api/v1/super.

- 3. Delete the https:// at the beginning and the /ccx/api/v1/<tenant_name> at the end. Example: i-07d55d20e81e2d191.workdaysuv.com.
- **4.** Copy the text. Studio's **PrismAnalytics** component requires it for its wd.prism.component.api.hostname parameter.

Describe the Source CSV Data

Context

Workday Studio's **PrismAnalytics** component requires a description of the source CSV data. You can create the JSON text in the tool of your choice and use it in Studio later. Example: paste it into a text message on the **Message Builder** tab of a **write** step.

Steps

- 1. Create JSON text containing 2 main nodes:
 - parseOptions: information about the format of the CSV data, including the character set and the delimiter character.
 - fields: information about each field in the CSV data, including data type and formatting.
- 2. In the parseOptions node, you can define these fields:

Field Name	Туре	Required	Description
charsetName	Object	Yes	The CSV data file's character set. Example:
			"charset": { "id": "Encoding=UTF-8" }
			Currently, Workday supports the UTF-8 encoding format only. Workday ultimately stores the data in Unicode format.

Field Name	Туре	Required	Description	
			Characters with no Unicode equivalent are stored as the Unicode replacement character, a question mark on a black diamond background.	
fieldsEnclosedBy	String	No	The character used to enclose fields in the CSV data. The default is double quote marks. If a double quote mark is used within a field, escape it by preceding it with another double quote mark. Example: "fieldsEnclosedBy":	
fieldsDelimitedBy	String	Yes	The character used to separate field values in the CSV data. Example: "fieldsDelimitedBy":	
headerLinesToIgnor	e Number	No	The number of lines for the parser to ignore as a header. Set to 0 if the CSV data doesn't have a header. Example: "headerLinesToIgnore"	":
type	Object	Yes	The input file's type. Currently, Workday supports delimited files only. Example: "type": { "id": "Schema_File_Type=De } Note: This value is case-sensitive. Note the upper-case D in Delimited.	elimit:

3. In the fields node, you can define these fields:

Field Name	Туре	Required	Description
ordinal	Number	Yes	The order of the field in the CSV dataset (index). The ordinal values: • Must start with 1.
			 Must be contiguous. Can't skip any number. Have a maximum of 1000.
name	String	Yes	The name of the CSV dataset field. Field names:
			 Must be unique in the dataset. Can contain up to 255 characters. Can only include alphanumeric and underscore characters. Must start with a letter. Can't end with an underscore character. Can't begin with WPA
description	String	No	The field's description. Maximum 1000 characters. Example: "description": "The worker's full name."
type	Object	Yes	The field's type. Options are: • Text • Numeric • Boolean • Date Example: "type": { "id": "Schema_Field_Type

Field Name	Туре	Required	Description
parseFormat String		Yes (for Date types)	The date's format. Example:
			"parseFormat": "dd-MM-yy HH24:mm:ss"
precision	Number	Yes (for Numeric types)	The maximum number of digits in a numeric value. Includes all numbers to the left and right of a decimal point but not the decimal point itself. Maximum value is 38. Example:
			"precision": 38
scale	Number	Yes (for Numeric types)	The number of digits to the right of the decimal point in a numeric value. Must be less than the precision value. Example:
			"scale": 2
defaultValue	Text	No	The default value for a field, if none is provided in the upload file.
			Express a default text value in double quotes. Example: "N/A".
			Default numeric values must agree with the specified precision and scale.
			Default date values must be in this format: yyyy-MM- dd'T'HH:mm:ss'Z'.
required	Boolean	No	Specifies whether a field must contain a value. Set to True if a field is required, otherwise set to False. If a field is required, its value can't be null in any insert, update, and upsert data operation.

Field Name	Туре	Required	Description
externalID	Boolean	Yes (to take advantage of update, upsert, and delete operations).	Specifies whether a field represents an External ID. Set to True to designate a field an External ID, otherwise set to False.
			Because External ID fields can't be null, you should specify that any External ID field is required. You can only specify 1 field as External ID.
			Specify an External ID in new tables if you want to take advantage of update, upsert, and delete functionality.
			To use update, upsert, and delete functionality with an existing table, you must modify it so it has a single field designated as External ID. The Prism public API doesn't support the modification of a table that contains data. In such cases, make the modification in Workday.

Example

Your source CSV file describes this table:

Employee	Employee ID	Job Title	Hire Date	Annual Salary
Logan McNeil	21001	Vice President, Human Resources	1/1/2010	213298.00
Oliver Reynolds	21003	Chief Information Officer	1/1/2010	394935.00
Maximilian Schneider	21004	Chief Operating Officer	1/1/2010	255373.00
Teresa Serrano	21005	Controller	1/1/2010	291785.00

You describe it using JSON like this:

```
{
   "parseOptions": {
     "fieldsDelimitedBy": ",",
```

```
"fieldsEnclosedBy": "\"",
   "headerLinesToIgnore": 1,
   "charset": {
     "id": "Encoding=UTF-8"
   "type": {
     "id": "Schema_File_Type=Delimited"
 "fields": [
   {
     "ordinal": 1,
     "name": "Employee",
     "description": "Employee",
     "precision": 255,
     "scale": 0,
     "parseFormat": null,
"type": {
      "id": "Schema_Field_Type=Text"
     "ordinal": 2,
     "name": "Employee_ID",
     "description": "Employee ID",
     "precision": 38,
     "scale": 0,
     "parseFormat": null,
     "type": {
       "id": "Schema_Field_Type=Numeric"
     "ordinal": 3,
     "name": "Job_Title",
     "description": "Job Title",
     "precision": 255,
     "scale": 0,
     "parseFormat": null,
     "type": {
       "id": "Schema Field Type=Text"
     "ordinal": 4,
     "name": "Hire_Date",
     "description": "Hire Date",
     "precision": 0,
     "scale": 0,
     "parseFormat": "MM/dd/yy",
     "type": {
       "id": "Schema_Field_Type=Date"
     "ordinal": 5,
  "name": "Annual_Salary",
     "description": "Annual Salary",
     "precision": 38,
     "scale": 2,
     "type": {
       "id": "Schema_Field_Type=Numeric"
```

```
],
  "schemaVersion": {
    "id": "Schema_Version=1.0"
}
```

Related Information Reference

Reference: Supported Date Formats for External Data in Tables and Datasets

Configure an Assembly with the PrismAnalytics Subassembly

Context

To send CSV data to Prism Analytics, your assembly must contain a **PrismAnalytics** component that:

- Receives CSV data as input, either in the rootpart of the message or as a variable.
- Receives a variable containing a JSON description of the CSV data.
- Has a number of parameters configured correctly.

Steps

1. Configure your assembly to obtain a source CSV file or source CSV files. Depending on the method you use to acquire the CSV data, you might need to provide a variable name or set a MIME type. As you complete the task, consider:

CSV Acquisition Method	Notes
sftp-out component	 Specify the CSV filename in the component's Input File Pattern property. You can use wildcards. Use the component's get method to retrieve a single file or its mget method to retrieve multiple files. Studio adds the CSV data to the message rootpart. No variable name is required. Studio automatically sets the MIME type correctly.
Retrieval or listener service	 Studio adds the CSV data to a variable. Name the variable using the wd.prism.component.csv.input.varname parameter. Studio automatically sets the MIME type correctly.
Any other method	 Studio adds the CSV data to the message rootpart or to a variable. If applicable, name the variable using the wd.prism.component.csv.input.varname parameter.

CSV Acquisition Method	Notes	
	Set the MIME type of the rootpart or the variable to: text/csv plain/csv	
	application/zip	

2. Create a text message on the **Message Builder** tab of a **write** step and add the JSON text that describes the data. Output a variable. Example: temp.schema.

Note: You can add the JSON text directly to the **Message Builder**. Alternatively, you can write it in the tool of your choice and paste it in.

3. Configure the **PrismAnalytics** component's parameters:

Parameter	Description	
wd.prism.component.schema.varname	The variable containing the JSON schema that describes the data.	
wd.prism.component.table.name	The name of the Prism table. Table names:	
	 Must be unique in the Data Catalog. Can contain up to 255 characters. Can only include alphanumeric and underscore characters. Must start with a letter. Can't end with an underscore character. 	
wd.prism.component.client.id	The Client ID assigned to the API client by Workday. Access the View API Clients report, then view the API Clients for Integrations tab.	
wd.prism.component.client.secret	The Client Secret assigned to the API client by Workday. Access the View API Clients report, then view the API Clients for Integrations tab.	
wd.prism.component.refresh.token	The Refresh Token assigned to the API client by Workday. Access the View API Clients report, then view the API Clients for Integrations tab.	
wd.prism.component.operation	The operation performed on the Prism table. Replace is the only option currently supported. It creates a table or replaces one of the same name.	
wd.prism.component.csv.input.varname	(Optional.) The variable containing the CSV input. Not required if you're adding the CSV data to the message rootpart.	
	Note: Studio doesn't automatically select this parameter for inclusion when you add a PrismAnalytics component to an assembly. Select it manually if required or add it later on the component's Parameters tab.	
wd.prism.component.api.hostname	The Workday REST API endpoint. Access the View API Clients report. Remove the https://	

Parameter	Description
	at the beginning and the /ccx/api/v1/ <tenant-name> at the end. Example: i-09e55d32d61e2e287.workdaysuv.com.</tenant-name>
wd.prism.component.table.description	(Optional.) A description for the table. Can contain up to 255 characters.
wd.prism.component.table.description.d	(ptila yalr)a The display name for the table. Can contain up to 255 characters.
wd.prism.component.table.field.varname	(Optional.) Defines a Prism table. Write the definition to a variable then pass it to this parameter using vars['variable-name'].

Next Steps

Deploy and launch the integration.

Reference: PrismAnalytics Subassembly Properties

Common Tab

Property	XML Attribute Name	Description
ld	id	The unique ID of the PrismAnalytics subassembly.
Routes Response To	routes-response-to	The destination of the response message for the subassembly within the assembly. PrismAnalytics subassembly.
Execute When	execute-when	A condition that determines whether the PrismAnalytics subassembly executes.
Endpoint	endpoint	The target endpoint address for the subassembly. The PrismAnalytics component supports a vm://endpoint address. Example: vm://wcc/PrismAnalytics.

Property	XML Attribute Name	Description
Store Message	store-message	Specify <i>none</i> unless otherwise advised by Workday Support. To store messages, use Studio's store step.

Property	XML Attribute Name	Description
Transport Class	transport	Specifies an alternative implementation class on a perassembly basis, if required.
		You can globally change the implementation classes by editing the WEB-INF/classes/spring/assembly-bean.xml file.
Ignore Dynamic Endpoints	ignore-dynamic-endpoints	Specifies whether to ignore the dynamic WS-Addressing (WSA) value in the incoming message's header or use it to override the value in the transport's Endpoint property.
		Use the set-dynamic-endpoint step to specify WS-Addressing details.
Clone Request	clone-request	Specifies whether to chain processing between subassemblies. Set to true to create a copy of the original message so that any subassembly modifying the request message won't affect the others. Set to false to pass the original message.
Propagate Abort	propagate-abort	Specifies whether an abort flag propagates from a subassembly to the calling assembly.
		A subassembly stops processing when it marks the MediationContext as aborted.
Unset Properties	unset-properties	Specifies whether all local- out properties reset after the local-out transport calls a subassembly.

Parameters Tab

Parameter	Description	
wd.prism.component.schema.varname	The variable containing the JSON schema that describes the data.	
wd.prism.component.table.name	The Prism table's identifier in the Data Catalog. Table names:	
	 Must be unique in the Data Catalog. Can contain up to 255 characters. Can only include alphanumeric and underscore characters. 	

Parameter	Description
	Must start with a letter.
	Can't end with an underscore character.
	You can't use this component to update a Prism table name, only to create one.
wd.prism.component.client.id	The Client ID assigned to the API client by Workday. Access the View API Clients report, then view the API Clients for Integrations tab.
wd.prism.component.client.secret	The Client Secret assigned to the API client by Workday.
wd.prism.component.refresh.token	The Refresh Token assigned to the API client by Workday. Access the View API Clients report, then view the API Clients for Integrations tab.
wd.prism.component.operation	The operation performed on the Prism dataset. Examples: Replace, Append.
	Replace creates a table or replaces one of the same name.
wd.prism.component.csv.input.varname	(Optional.) The variable containing the CSV input. Not required if you're adding the CSV data to the message rootpart.
	Note: Studio doesn't automatically select this parameter for inclusion when you add a PrismAnalytics component to an assembly. Select it manually if required or add it later on the component's Parameters tab.
wd.prism.component.api.hostname	The Workday REST API endpoint. Access the View API Clients report. Remove the https://at the beginning and the /ccx/api/v1/ <tenant-name> at the end.</tenant-name>
	Example: i-09e55d32d61e2e287.workdaysuv.com.
wd.prism.component.table.description	(Optional.) A description for the table. Can contain up to 255 characters.
wd.prism.component.table.display.name	(Optional.) The display name for the table. Can contain up to 255 characters.
	You can't use this component to update a Prism table display name, only to create one.
wd.prism.component.table.field.varname	(Optional.) Defines a Prism table. Write the definition to a variable then pass it to this parameter using vars['variable-name'].

Error Handler Components

Concept: Error Handler Components

Studio provides 3 different **Error Handlers** on the **Palette**:

Name	Function
send-error	Enables you to process the error using standard components and steps. A common pattern is to use send-error to report the error to the integration event by invoking the PutIntegrationMessage common component.
log-error	Logs the current error to the output log. Includes the error message and the stack trace of the Java exception. Use when there's no need to individually expose errors on the integration event but you want to log the message at the time of the error. Avoid logging large messages as they can degrade performance and might be truncated, leading to loss of diagnostic data.
custom-error-handler	Enables you to supply a Spring bean that uses Java to process the error. Use when error handling requires complex Java code.

You can add an error handler as a child element of a mediation component or as an individual element on the assembly. Error handlers added to mediation components are local. Error handlers on the assembly are global.

When Workday encounters an error in a Studio integration, it stops normal processing and unwinds the chain of processed components, looking for an error handler to invoke. It always attempts to process errors locally first. If no local error handler is available, responsibility passes to the global error handler. Use local error handlers when you want fine control over what happens when errors occur or need to report the detailed context of what the integration was doing at the time of the error. Think of global error handlers as a failsafe.

If every error handler has fired and an error still isn't marked as handled, Workday processes the message, generates an error from the exception, and marks the assembly as terminated. It describes the integration as Completed with Errors.

Notable default behaviors:

- Local error handlers only process errors that arise in their parent mediation component. However, they can also process errors in downstream components. To enable this behavior, set the **Handle Downstream Errors** property of the mediation component containing the error handler to **true**.
- Workday marks errors as handled when an error handler is invoked. However, if you set an error
 handler's Rethrow Error property to true, Workday doesn't clear the error. As a result, it's handled by
 the next in-scope upstream error handler or global error handler. Use this pattern to report the detail of
 an error locally but to handle the overall failure or completion at a higher level in the assembly.
- When Workday handles an error, it restarts message processing from the invoked error handler, continuing on the response path towards the element where the error was raised. However, you can specify that processing should instead resume at the element where the error was raised. To enable this behavior, set the Continue After Error property of the mediation component containing the error handler to recover. Use this behavior in situations where the code invoked by the error handler can correct the error condition, enabling a retry of the failed operation to succeed.

You can exercise greater control over error handlers by adding MVEL condition expressions on their **Properties** view. When condition expressions are present, Workday only invokes the error handler if they all evaluate to true.

You can force error raising using the context.setError or context.SetException methods in MVEL or Java code. When using the setError method, you can configure an error ID that can be detected by conditional expressions on the error handler. Use this technique when you're handling an error locally but want to pass some detail of the error type to an upstream error handler for common handling.

You can also handle errors using **Route** components:

- The **failover-strategy** attempts to use a route, and if an error occurs, executes the failover route, marking the error as handled.
- The **custom-strategy** enables you to supply a Spring bean. Spring beans implement the RoutingStrategy interface, which has an isHandleError method. Use this method to specify that the strategy handles errors.

Reference: Custom-Error-Handler Component Properties

Common Tab

Property	XML Attribute Name	Description
Error Handler ID	id	The unique ID of the custom- error-handler component within the assembly.
Rethrow Error	rethrow-error	Specifies whether the custom- error-handler component passes the error back to any upstream error handlers when it has completed processing. The default value is false, meaning that the custom-error-handler component processes the error alone, then marks it as having been handled.
		You can also mark errors as having been handled by calling the setErrorHandled method on the MediationContext object. Example: mediationContext.setErrorHandled(tr
Spring Bean	ref	The ID of a Spring bean that implements one of these 2 interface classes:
		• OnErrorHandler. • ConditionalOnErrorHandler, which extends OnErrorHandler with a Boolean method, invokeHandleError(MediationContex context). If this method returns true, Workday invokes the

Property	XML Attribute Name	Description
		handleError(MediationContext context) method.
		Note:
		If you implement the ConditionalOnErrorHandler interface, you override any conditional expressions you defined.

Expressions Tab

Property	XML Attribute Name	Description
Condition Expression	condition-expression	Enables you to enter MVEL condition expressions directly.
		If all the expressions evaluate to true, or if you don't provide an expression, the error handler is invoked. Otherwise, the error handler isn't invoked, error handling continues along the processing chain, and Workday adds an Audit Log entry of type ERROR_HANDLER_SKIPPED.
		To add a new expression below any existing rows, click Add , then enter the expression.
		To add a new expression above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the Expressions tab to delete rows or reorder them.

Reference: Log-Error Component Properties

Common Tab

Property	XML Attribute Name	Description
Error Handler ID	id	The unique ID of the log-error component within the assembly.
Rethrow Error	rethrow-error	Specifies whether the log-error component passes the error back to any upstream error handlers when it has completed processing. The default value is false, meaning that the log-error component processes the error

Property	XML Attribute Name	Description	
		alone, then marks it as having been handled.	
		You can also mark errors as having been handled by calling the setErrorHandled method on the MediationContext object. Example: mediationContext.setErrorHandled	(tr
Level	level	The Log4J logging level. There are 5 options:	
		debuginfowarnerror	
		• fatal	

Advanced Tab

Property	XML Attribute Name	Description
Category		Specifies part of the Log4J logger name. The default value is DEFAULT.

Expressions Tab

Property	XML Attribute Name	Description
Condition Expression	condition-expression	Enables you to enter MVEL condition expressions directly.
		If all the expressions evaluate to true, or if you don't provide an expression, the error handler is invoked. Otherwise, the error handler isn't invoked, error handling continues along the processing chain, and Workday adds an Audit Log entry of type ERROR_HANDLER_SKIPPED.
		To add a new expression below any existing rows, click Add , then enter the expression.
		To add a new expression above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the Expressions tab to delete rows or reorder them.

Reference: Send-Error Component Properties

Common Tab

Property	XML Attribute Name	Description
Error Handler ID	id	The unique ID of the send-error component within the assembly.
Rethrow Error	rethrow-error	Specifies whether the send- error component passes the error back to any upstream error handlers when it has completed processing. The default value is false, meaning that the send- error component processes the error alone, then marks it as having been handled. You can also mark errors as having been handled by calling the setErrorHandled method on the MediationContext object. MVEL example: context.setErrorHandled(true).
Routes To	routes-to	The ID of the assembly element towards which the send-error component directs the message.

Expressions Tab

Property	XML Attribute Name	Description
Condition Expression	condition-expression	Enables you to enter MVEL condition expressions directly.
		If all the expressions evaluate to true, or if you don't provide an expression, the error handler is invoked. Otherwise, the error handler isn't invoked, error handling continues along the processing chain, and Workday adds an Audit Log entry of type ERROR_HANDLER_SKIPPED.
		To add a new expression below any existing rows, click Add , then enter the expression.
		To add a new expression above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the Expressions tab to delete rows or reorder them.

Transform Steps

Convert Text to XML with a Text Schema File

Prerequisites

Create an assembly containing a **textschema** step. Obtain the sample text that will form the basis of your text schema.

Context

The **textschema** step enables you to convert text to XML using a text schema. To develop a text schema, you must know the structure of the data that you want to transform. The process is considerably simplified by having a small sample document containing representative data. This topic assumes that you have such a sample.

You can use the **textschema** step to convert XML to text or to transform delimited files, but in most cases it's simpler to use the **XTT** step and the **csv-to-xml** step, respectively.

Steps

- 1. In the textschema step's Properties view, click Create Text Schema File.
- 2. Select a parent folder for the text schema file and provide a filename. If required, specify the target namespace URI.
- 3. Studio opens the Text Schema Editor and displays the new text schema in its **Tree** view.
- **4.** Cut and paste your sample text into the area in the upper right of the Text Schema Editor, replacing initial-text.

Note: To strip the terminating linefeed from input files, add this attribute to the root schema element: ts:eofStrip="
".

Begin describing the sample text. Select the first field, then right-click it and select Create Field.

Note: If you don't have a sample of the text you want to convert but know its structure, you can edit the text schema's **Source** view directly.

6. On the **Identity** page of the **Create Field Wizard**, provide a basic description of the field. As you complete the task, consider:

Option	Description
Name	A name for the field.
Occurrence	The options are:
	 Default: The field is mandatory and occurs only once. Required: Same as default. Optional: The field is optional can occur only once. Multiple Optional: The field is optional and can occur multiple times. Multiple Required: The field is mandatory and can occur multiple times.
Start Tag	A regular expression that specifies the text that causes an element to be generated. Note that the text matching this expression doesn't form part of the output value. If you want the matched text to

Option	Description
	display in the output value, use the ts:format option.
End Tag	A regular expression that specifies the text that marks the end of an element. Note that the text matching this expression doesn't form part of the output value. If you want the matched text to display in the output value, use the ts:format option.
Truncate	Specifies whether to truncate overflowing data in a fixed-length field or throw an error. The default value is true.
Separator	A regular expression that specifies a character that separates repeated fields. Enabled only if you select the Multiple Optional or Multiple Required occurrence options.
Omit	Specifies whether to omit the field from the output in a text-to-XML or XML-to-text transformation. The default is no omission.

7. On the **Delimit** page of the **Create Field Wizard**, describe how many characters from the sample text represent a field:

Option	Description	
Format	A regular expression that identifies valid patterns of text for a field. Use this expression as an alternative to Start Tag and End Tag to ensure that all of the matched text displays in the output. You can also use it when dealing with multiply occurring values so it's clear when the end of the sequence occurs.	
Fixed Length	Specifies the length of fixed-length fields. Includes quotation marks and escape characters.	
Quoted	Indicates whether string values are treated as quoted strings. The options are: • Default: • always: • always-including-empty: • optional: • never:	
Padding	A regular expression that identifies any padding text within fixed-length fields.	
Preferred Padding	Specifies the value to be used if the Padding expression can match more than 1 possible string.	
Align	Specifies the alignment of fixed-length fields that require padding.	

8. On the **Interpret** page of the **Create Field Wizard**, describe how many characters from the sample text represent a field:

Option	Description
Туре	The field's data type.
Default Value	A default value for the field.
Date Format	Specifies a pattern for dates or datetimes. Supports any pattern allowed by Java's SimpleDateFormat.
Date Language	Specifies the date language to use when interpreting dates. Ensures that the name is handled in the appropriate language when the date format uses the names of months. The default value isen.
Two Digit Year	Specifies a value for interpreting 2-digit year dates. The text schema parser interprets 2-digit year dates that occur before that value as occurring in the current century. Example: if you enter 18, the parser interprets 14 as 2014 and 96 as 1996.
Number Format	Specifies a pattern for numbers. Supports any pattern allowed by Java's DecimalFormat.
Decimal Separator	Specifies the separator used for decimal numbers.
Grouping Separator	Specifies the thousands grouping separator for numbers.

- **9.** Repeat steps 6-9 for each field in the sample text, adding new elements in the **Tree** view. When you've created all of the required field definitions, delete the remaining Unparsed child element.
- **10.**To wrap all of the elements you've created into a complex type, select them, right-click them, and select **Wrap Elements**. Then provide a name and an occurrence value for the wrapper element.
- 11.In the wrapper element's **Properties** view, select /n from the **End Tag** drop-down list.
- **12.**The default schema root element is named File. On the **Schema** tab of the element's **Properties** view, provide a more meaningful name.
- **13.**In the **Properties** view of the top level schema element, the **Root Element** property has the value tns:File. Replace File with the meaningful name you selected for the root element.
- **14.**To remove any extra spaces from the generated output, select the **Properties** view of the top level schema element. Select + from the **Padding** drop-down list. Save the schema.

Concept: Transform Steps

Transform steps enable you to perform individual operations that restructure messages as they pass through your integration. Workday Studio provides these **Transform** steps on the **Palette**:

Transform Step	Function	Notes
xslt	Transforms an XML document using an XSL Transformation (XSLT) stylesheet.	 Supports XSLT 2.0. Compatible with assemblies with a version number up to 2017.05.

Transform Step	Function	Notes
XSLT+	Transforms an XML document using an XSL Transformation (XSLT) stylesheet.	 Supports XSLT 3.0 streaming functionality. Compatible with assemblies with a version number after 2017.05.
fop	Generates PDF and RTF documents from an XML file.	 Invokes the Apache Formatting Objects Processor (FOP) implementation. Implements an Apache FOP XML configuration file for registering custom fonts.
text-excel	Converts Excel files into comma- separated-value (CSV) text format files. Also converts CSV files into Excel files.	
textschema	Converts text to XML, or XML to text, using a text schema file.	
wrap-soap	Wraps the XML message in a SOAP envelope for forwarding to a SOAP-based web service.	
xml-to-java	Unmarshals XML to Java objects using JAXB.	 Implements XPath to extract XML from messages. Implements JAXB to convert the XML into Java objects. Inserts converted Java objects into the MediationContext.
json-transformer	Takes a JSON document as input and transforms it by mapping values to JSON Paths.	
xml-to-json	Converts an XML document to JSON format.	
json-to-xml	Converts a JSON document to XML format.	
java-to-xml	Marshals Java objects to XML using JAXB.	 Extracts Java objects from the MediationContext. Implements JAXB to convert Java objects to XML. Implements XPath to insert converted XML into messages.
xml-to-csv	Converts XML documents to CSV format, while streaming the input and output documents, producing a low-memory footprint.	

Transform Step	Function	Notes
csv-to-xml	Converts CSV documents to XML format, while streaming the input and output documents, producing a low-memory footprint.	
character-conversion	Performs character-conversion operations on the text content of an incoming message.	
mtable-builder	Creates and stores a mtable object in a MediationContext property.	 Supports these child elements: csv-mtable-reader json-mtable-reader
mtable-writer	Retrieves a mtable object from a MediationContext property. Displays the contents of a mtable object in an output message.	 Supports these child elements: csv-mtable-writer json-mtable-writer
etv	Transforms and validates elements in an XML document in accordance with attributes attached to those elements.	
xtt	Converts XML to text in accordance with attributes defined within the XML.	

Reference: XSLT Step Properties

Common Tab

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the xslt mediation step within the assembly.
Input	input	Specifies where the xslt mediation step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the

Property	XML Attribute Name	Description
		message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the xslt mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Url	url	The location of the XSLT file used by the xslt mediation step.

Property	XML Attribute Name	Description
Description	description	A description of the xslt mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the XSLT step executes.

Property	XML Attribute Name	Description
Use File Backed Managed Data	use-file-backed-managed- data	Specifies whether to stream all output to your local disk once you reach a data threshold.
Messages Property	messages-property	The MediationContext property that you intend to configure on a List object.
Reuse Strategy	reuse-strategy	Specifies the XSLT transformer reuse strategy. There are 4 options:
		 default: the MediationContext automatically determines your reuse strategy. no-reuse: your server doesn't reuse transformer objects. templates: your server builds a Templates object, from which it creates fresh transformer objects. transformer-pool: your server uses a pool of transformers. We only recommend this option if the transformer objects don't cache values. Example: Saxon caches the results of document() calls.
Secure Processing	secure-processing	Specifies whether to enable processing that could compromise security. If set to true , the xslt mediation step processes XML securely, setting limits on XML constructs to avoid conditions such as
		denial-of-service attacks. If set to false , the xslt mediation step ignores security issues such as limits on XML constructs.
Transformer Factory	transformer-factory	The class name of the XSLT TransformerFactory used by the xslt mediation step. Example: the value for Saxon is net.sf.saxon.TransformerFa

Reference: XSLT+ Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the XSLT + mediation step within the assembly.
Input	input	Specifies where the XSLT+ mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the XSLT+ mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message itself. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Url	url	The location of the XSLT file used by the XSLT+ mediation step.
Secure Processing	secure-processing	Specifies whether to enable processing that could compromise security.
		If set to true , the XSLT+ mediation step processes XML securely, setting limits on XML constructs to avoid conditions such as denial-of-service attacks.
		If set to false , the XSLT+ mediation step ignores security issues such as limits on XML constructs.

Property	XML Attribute Name	Description
Description	description	A description of the XSLT+ mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the XSLT+ step executes.
Messages Property	messages-property	The MediationContext property that you intend to configure with a List object.
Schema Validation Mode	schema-validation-mode	Specifies whether to validate the inputs and the outputs, based on the schemas provided, using the Saxon XSLT processor.

Schema URLs Tab

Property	XML Attribute Name	Description
Schema URL	schema-url	The location of the schema file that the XSLT+ mediation step uses to validate the output document.

Reference: FOP Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the fop mediation step within the assembly.
Input	input	Specifies where the fop mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the fop mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Author	author	Specifies an author value in the metadata of the document.
Base Url	base-url	The base URL that's used to resolve relative URLs. This location is also used for relative font locations, if no font-base-url is specified. It can be a relative path to the project's WSAR-INF or an absolute URL. Example:
		./fop
Creation Date	creation-date	Specifies a creation date value in the metadata of the document. Enter the value using the US date format. Example: 5/14/08 4:50 PM.
Creator	creator	Specifies a creator value in the metadata of the document.
Keywords	keywords	Specifies a keywords value in the metadata of the document.
Title	title	Specifies a title value in the metadata of the document.
User Password	user-password	Enables you to set a user password for PDF and RTF documents. The password enables these document privileges: • allow-copy-content
		allow-edit-annotationsallow-edit-contentallow-print

Property	XML Attribute Name	Description
Description	description	A description of the fop mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.

Property	XML Attribute Name	Description
Execute When	execute-when	A condition that determines whether the fop step executes.
Allow Copy Content	allow-copy-content	Specifies whether you can copy and paste content from the document when you access it using the user-password.
Allow Edit Annotations	allow-edit-annotations	Specifies whether you can edit annotations within the document when you access it using the user-password.
Allow Edit Content	allow-edit-content	Specifies whether you can edit content within the document when you access it using the user-password.
Allow Print	allow-print	Specifies whether you can print the document when you access it using the user-password.
Configuration XmI	configuration-xml	The path to the Apache FOP XML configuration file, which must be on your local disk and not a URL. This configuration file is the only way to register custom fonts.
Creation Date Format	creation-date-format	The date format used to parse the creation-date XML attribute. Supports these values:
		fulllongmediumshort
Creation Date Locale Country	creation-date-locale- country	The country value used to parse the creation-date XML attribute.
Creation Date Locale Language	creation-date-locale- language	The language value used to parse the creation-date XML attribute. The value must be a lowercase two-letter ISO-639 language code.
Creation Time Format	creation-time-format	The time format used to parse the creation-date XML attribute. Supports these values: • full • long • medium • short

Property	XML Attribute Name	Description
Font Base Url	font-base-url	The base URL that's used to resolve relative font URLs. Example:
		./fop/fonts
Hyphenation Base Url	hyphenation-base-url	The base URL that's used to resolve relative URLs to hyphenation-pattern files.
Owner Password	owner-password	Enables you to set an owner password for PDF and RTF documents. The password enables these document privileges:
		allow-copy-contentallow-edit-annotationsallow-edit-contentallow-print
Producer	producer	Specifies a producer value in the metadata of the document.
Target Resolution	target-resolution	The output resolution in dots per inch (DPI) for bitmap images generated by bitmap renderers, such as the TIFF renderer and Apache Batik.

Reference: Text-Excel Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the text- excel mediation step within the assembly.
Input	input	Specifies where the text-excel mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the

Property	XML Attribute Name	Description
		message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the text-excel mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Style	style	The conversion style of the textexcel mediation step. There are 3 options: • XLSX/XLS to Text: converts an Excel file of either XLSX or XLS format to a CSV file. • Text to XLS: converts a CSV file to an Excel file in the XLS format. • Text to XLSX: converts a CSV file to an Excel file in the XLSX format. Note: This component streams when converting to or from XLSX.

Property	XML Attribute Name	Description
Excel Style	excel-style	Specifies whether the text-excel mediation step converts an entire Excel workbook or a single Excel sheet.
Excel Sheet Number	excel-sheet-number	The target sheet number to convert in an Excel file.
		If you configure the Excel Style property to workbook, Workday ignores the Excel Sheet Number setting for your text-excel mediation step.

Property	XML Attribute Name	Description
Description	description	A description of the text- excel step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the text-excel step executes.
Use Values	usevalues	Specifies whether the text-excel mediation step uses the underlying values of the spreadsheet, rather than their formatted values as they display on-screen.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Reference: TextSchema Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the textschema mediation step within the assembly.
Input	input	Specifies where the textschema mediation step obtains data as input. There are 5 possible values:

Property	XML Attribute Name	Description
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the textschema mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Url	url	The location of the text schema XSD file used by the textschema mediation step, given as a relative path or an absolute URL. You can use an MVEL expression to extract the URL from the MediationContext. Example:

Property	XML Attribute Name	Description
		<pre>@{parts[1].xpath('/ script/location')}</pre>
Style	style	The conversion style of the textschema mediation step. There are 2 options:
		 text2xml: converts text to XML. xml2text: converts XML to text.

Property	XML Attribute Name	Description
Description	description	A description of the textschema mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the textschema step executes.
Use File Backed Managed Data	use-file-backed-managed- data	Specifies whether to stream all output to your local disk once you reach a data threshold.

Reference: Wrap-Soap Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the wrap-soap mediation step within the assembly.
Input	input	Specifies where the wrap-soap mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message.
		attachment: a MIME attachment within the

Property	XML Attribute Name	Description
		message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the wrap-soap mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the wrap-soap mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the wrap-soap step executes.
Interface	interface	The immediate child of the SOAP Body element.

Property	XML Attribute Name	Description
Soap Action	soap-action	The value of the SOAP action header. You must specify this value for SOAP HTTP requests.
Soap Version	soap-version	The version of the SOAP envelope.

Reference: XML-to-Java Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the xml-to- java mediation step within the assembly.
Input	input	Specifies where the xml-to-java mediation step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Property	property	The name of the MediationContext property into which the xml-to-java mediation step inserts the Java object.
Packages	packages	The semicolon separated list of Java packages required by the xml-to-java mediation step to convert XML to Java objects using JAXB.
Unwrap JAXB Element	unwrap-jaxbelement	Specifies whether the xml-to- java mediation step stores the

Property	XML Attribute Name	Description
		Java object within the JAXB element.
Namespaces	namespaces	The namespaces used by your XPath expression.
XPath	xpath	The XPath expression that extracts XML from the message to convert it to Java objects.

Property	XML Attribute Name	Description
Description	description	A description of the xml-to-java mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the xml-to-java step executes.
XPath Version	xpath-version	The XPath version used by the xml-to-java mediation step. Example: Version 1.0, Version 2.0, or Version 3.0.

Reference: JSON Transformer Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the json-transformer mediation step within the assembly.
Input	input	Specifies where the json-transformer mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the

Property	XML Attribute Name	Description
		message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the json-transformer mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the json-transformer mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the json-transformer step executes.

Mappings Tab

Property	XML Attribute Name	Description
Json Path	json-path	Specifies the location on the JSON tree where the associated Value is assigned.
Fail No Match	fail-no-match	Determines what happens when the specified JSON path doesn't return a node:
		true: Raise an error.fail: Ignore the missing path.

Reference: XML-to-JSON Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the xml-to- json mediation step within the assembly.
Input	input	Specifies where the xml-to- json mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the xml-to-json mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message,

Property	XML Attribute Name	Description
		effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Schema URL	schema-url	Specifies a relative URL so that the xml-to-json mediation step retrieves the XML schema file as a resource within the assembly web service project.
Schema	schema	Specifies where the xml-to-json step obtains the XML schema. There are 5 possible values: • message • soapbody • attachment • rootpart • variable
Ignore Attributes	ignore-attributes	Specifies whether the xml-to- json step ignores attributes when converting XML documents to JSON.

Property	XML Attribute Name	Description
Description	description	A description of the xml-to-json mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the xml-to-json step executes.

Reference: JSON-to-XML Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the json-to- xml mediation step within the assembly.
Input	input	Specifies where the json-to- xml mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the json-to-xml mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Root Element Name	root-element-name	The name of the outermost wrapping tag of the XML document.
Nested Array Name	nested-array-name	A name for anonymous nested arrays in JSON input.
Nested Object Name	nested-object-name	A name for anonymous nested objects in JSON input.

Property	XML Attribute Name	Description
Description	description	A description of the json-to-xml mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the json-to-xml step executes.

Reference: Java-to-XML Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the java-to- xml mediation step within the assembly.
Output	output	Specifies where the java-to-xml mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message.

Property	XML Attribute Name	Description
		attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Property	property	The name of the MediationContext property from which the java-to-xml mediation step extracts the Java objects.
Packages	packages	The semicolon separated list of Java packages required by the java-to-xml mediation step to convert Java objects to XML using JAXB.
Root Element Name	root-element-name	The name of the root element used for marshaling Java objects to XML.
Root Element Namespace	root-element-namespace	The namespace of the root element used for marshaling Java objects to XML.
Namespaces	namespaces	The namespaces used by your XPath expression.
XPath	xpath	The XPath expression that inserts XML into your message.

Property	XML Attribute Name	Description
Description	description	A description of the java-to-xml mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the java-to-xml step executes.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0, 2.0, or 3.0. Enter the value 1 for assembly versions

Property	XML Attribute Name	Description
		through Workday 11. Enter 2 or 3 for assembly versions Workday 12 onwards.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version')

Reference: XML-to-CSV Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the xml-to-csv step within the assembly.
Input	input	Specifies where the xml-to-csv step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the xml-to-csv step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments.

Property	XML Attribute Name	Description
		 soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Separator	separator	The separator character to insert after each data entry in the CSV output file.
Line Separator	line-separator	 The new line separator character to insert after each data entry in the CSV output file. Supports these values: LF for Linux and Mac OS X and later. CR for Mac OS version 9 or below. CRLF for Microsoft Windows.
Write Header Line	writeHeaderLine	Specifies whether the xml-to-csv step inserts the names of the sequential child elements from the XML document as commaseparated values in the first line in the output document.
Format	format	Specifies whether your CSV output documents are RFC-4180 compliant. You can enter either of these values: • rfc4180 • simple
		If you enter <i>rfc4180</i> , then your CSV output documents will comply with RFC-4180 standards. If you enter <i>simple</i> , or leave the field blank, then the xml-to-csv step: • Treats apostrophes as alternative quote marks.

Property	XML Attribute Name	Description
		 Trims initial whitespaces in values. Accepts any line endings (CR, LF, or CRLF).

Property	XML Attribute Name	Description
Description	description	A description of the xml-to-csv step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the xml-to-csv step executes.

Reference: CSV-to-XML Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the csv-to-xml step within the assembly.
Input	input	Specifies where the csv-to-xml step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.

Property	XML Attribute Name	Description
Output	output	Specifies where the csv-to-xml step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. Specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Col Names	colNames	The names of the columns that display in your XML output file.
		Enter the value for this property as a comma-separated list of names. Example:
		col1, col2, col3.
Namespace Prefix	namespacePrefix	The namespace prefix that displays in your XML output file.
Namespace URI	namespaceURI	The namespace URI that displays on the root element in your XML output file.
		Example: if you specify a URI of http:// example.workday.com/ SupplyChainManagement/ DataTypes.xsd and a namespace prefix of ns, the csv- to-xml step creates this root element in your XML output file: <ns:root xmlns:ns="http:// example.workday.com/ SupplyChainManagement/ DataTypes.xsd"></ns:root>

Property	XML Attribute Name	Description
Root Name	rootName	The name of the root element that displays in your XML output file.
Row Name	rowName	The names of the rows that display in your XML output file.
		Enter the value for this property as a comma-separated list of names. Example:
		row1, row2, row3.
Separator	separator	The separator character used in your CSV input file.
Format	format	Specifies whether your CSV input file is RFC-4180 compliant. You can enter either of these values:
		 rfc4180 simple
		If you enter <i>rfc4180</i> , then the csv-to-xml step assumes that your CSV input file complies with RFC-4180 standards.
		If you enter <i>simple</i> , or leave the field blank, then the csv-to-xml step:
		 Treats apostrophes as alternative quote marks. Trims initial whitespaces in values. Accepts any line endings (CR, LF, or CRLF).
Use First Line As Header	useFirstLineAsHeader	Specifies whether the csv-to-xml step uses the first line of your CSV input file to name the columns that display in your XML output file.

Property	XML Attribute Name	Description
Description	description	A description of the csv-to- xml step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the csv-to-xml step executes.

Reference: Character-Conversion Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the character- conversion mediation step within the assembly.
Input	input	Specifies where the character-conversion mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Output	output	Specifies where the character-conversion mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message itself. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Remove Accents	remove-accents	Specifies whether the character-conversion step replaces accented characters with non-accented characters in the output message.
		Example: if set to true, the character-conversion step replaces é with e.
Remove Eols	remove-eols	Specifies whether the character-conversion step removes end-of-line characters in the output message.
Uppercase	uppercase	Specifies whether the character-conversion step converts all characters to uppercase in the output message.

Property	XML Attribute Name	Description
Description	description	A description of the character-conversion mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the character-conversion step executes.
Replace Controls	replace-controls	Specifies whether the character-conversion step replaces ASCII control characters with spaces in the output message.

Reference: Mtable-Builder Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the mtable-builder mediation step within the assembly.

Property	XML Attribute Name	Description
Input	input	Specifies where the mtable-builder mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. variable: use a named variable from the MediationContext.
Mtable Name	mtable-name	The name of the MediationContext property that stores the mtable object.

Property	XML Attribute Name	Description
Description	description	A description of the mtable-builder mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the mtable-builder step executes.

Reference: Mtable-Writer Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the mtable-writer mediation step within the assembly.

Property	XML Attribute Name	Description
Output	output	Specifies where the mtable-writer mediation step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment to the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Mtable Name	mtable-name	The name of the MediationContext property that stores the mtable object.

Property	XML Attribute Name	Description
Description	description	A description of the mtable- writer mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the mtable-writer step executes.

Reference: ETV Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the etv mediation step within the assembly.
Input	input	Specifies where the etv mediation step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message. If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the etv mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message.

Property	XML Attribute Name	Description
		variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the etv mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the etv step executes.
Append Messages	append-messages	Specifies whether new messages replace existing messages or are appended to them.
Message Property	message-property	The name of the MediationContext property that stores messages created by the etv mediation step.

Reference: XTT Step Properties

Property	XML Attribute Name	Description
Step Id	id	The unique ID of the xtt mediation step within the assembly.
Input	input	Specifies where the xtt mediation step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. You must specify the attachment index. rootpart: the content of the root part of a MIME message.

Property	XML Attribute Name	Description
		If the message isn't MIME, the entire message is selected. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the xtt mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the xtt mediation step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the xtt step executes.
Append Messages	append-messages	Specifies whether new messages replace existing messages or are appended to them.
Message Property	message-property	The name of the MediationContext property that stores messages created by the xtt mediation step.

Mtable-Builder Child Elements

Concept: Mtable-Builder Child Elements

The **mtable-builder** step supports these child elements:

Child Element	Description	
csv-mtable-reader	Parses CSV content into a mtable object.	
json-mtable-reader	Parses JSON content into a mtable object.	

Reference: CSV-Mtable-Reader Properties

Common Tab

Property	XML Attribute Name	Description
Column Names	column-names	A comma-separated list of column names that display on your mtable object.
Contains Header Row	contains-header-row	Indicates whether your mtable object contains a header row.
Index Column	index-column	The name of the index column that displays on your mtable object.
Normalise Column Names	normalise-column-names	Indicates whether the column names on your mtable object display with spaces.
		If set to true, the column names on your mtable object display with spaces.
		If set to false, the column names on your mtable object display without spaces.
Separator	separator	The delimiter for separating fields in your mtable object.
Use Header Row	use-header-row	Indicates whether your mtable object uses the header row to display column names.

Reference: JSON-Mtable-Reader Properties

Property	XML Attribute Name	Description
Parse Target	parse-target	The name of the root JSON object or array that you want to parse into your mtable object.

Property	XML Attribute Name	Description
Ignore Id Column	ignore-id-column	Specifies whether the ID column from your JSON input data displays in your mtable object. If set to true, Workday ignores the ID column from your JSON input data in your mtable object. If set to false, Workday displays the ID column from your JSON input data in your mtable object.

Mtable-Writer Child Elements

Concept: Mtable-Writer Child Elements

The **mtable-writer** step supports these child elements:

Child Element	Description
	Displays the contents of a mtable object in CSV format.
-	Displays the contents of a mtable object in CSV format.

Reference: CSV-Mtable-Writer Properties

Property	XML Attribute Name	Description
Column Names	column-names	A comma-separated list of column names that display on your mtable object.
Line Separator	line-separator	The new line separator character in your mtable object. Supports these values:
		 LF for Linux and Mac OS X. CR for Mac OS version 9 or below. CRLF for Microsoft Windows.
Separator	separator	The delimiter for separating fields in your mtable object.
Write Column Names	write-column-names	Indicates whether your mtable object uses a header row to display column names in the MediationContext.

Reference: JSON-Mtable-Writer Properties

Common Tab

Property	XML Attribute Name	Description
Field Name	field-name	The name of the JSON field that displays the contents of the mtable object.
Write Mtable as Object	write-mtable-as-object	Indicates whether single-row mtable objects display as either:
		 JSON arrays containing 1 object element and multiple fields (True). JSON objects with multiple fields (False). The default setting is false.

Logging and Eventing Steps

Concept: Logging and Eventing Steps

Logging steps enable you to create customized log messages for output to different destinations. Workday Studio provides these **Logging & Eventing** steps on the **Palette**:

Name	Function	Notes
log	Creates a customized Log4j message that's written to Workday.	Press Ctrl+space when inserting an MVEL expression to access content assist.
cloud-log	Enables you to output customized messages about an integration process to a HTML or CSV, which you can send to the endpoint of your choice.	 The cloud-log step generates an output file, but doesn't direct it anywhere. Use another step to handle the file's storage or transfer. Example: use a Store step to send the output file to your tenant. The output file that the cloud-log step produces always includes 5 columns:
		TimestampLevelReference IDMessage SummaryMessage Details
		Use the Extra Columns tab to add extra information.
		The maximum size for the output file is 256 MB. If your

Name	Function	Notes
		output exceeds 256 MB, you're notified that the results are truncated.

Reference: Log Step Properties

Message Builder Tab

The **Message Builder** simplifies defining the message content for some assembly steps.

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the log step within the assembly.
Input	input	Specifies where the log step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Level	level	The Log4J logging level. There are 5 options: • debug • info • warn • error • fatal

Property	XML Attribute Name	Description
Description	description	A description of the log step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the log step executes.
Category	category	Part of the logger name. If you don't specify a value, Workday uses DEFAULT.

You can use the static-file child element to specify a character-encoding property for an input file. Example:

If you don't specify a character-encoding value, Workday uses the character set specified in the output-mimetype property. If a character set isn't specified there either, Workday uses UTF-8.

Reference: Cloud-Log Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the cloud-log step within the assembly.
Variable Name	variable-name	The name of the variable that stores the output file. You can give multiple cloud-log steps the same variable name to have their messages concatenated into a single report. You can use different variable names to produce separate output files.
Level	level	The severity level of the log message. There are 6 options:
		 debug info warn error fatal custom If you select custom, you must specify your custom property

Property	XML Attribute Name	Description
		using an MVEL expression in the adjacent field.
Header	header	The text for the cloud-log file header. If you leave this field blank, Studio uses the integration name as the header text.
		If your assembly has multiple cloud-log steps with defined headers, Studio uses the header from the first one in the flow.
Message	message	The text of the log message.
Message Details	message-details	A description of the log message.
Reference ID	reference-id	The Reference ID of a Workday object. Useful for troubleshooting.
Condition	condition	An MVEL boolean expression that specifies the circumstances under which Workday logs the message.
		If you don't specify a condition, Workday always logs the message.
Output File Type	output-file-type	The type of file the cloud-log step produces. There are 3 options:
		• HTML • CSV • XLSX
		The maximum size for the output file is 256 MB. If output exceeds 256 MB, Studio notifies you and truncates the results.

Property	XML Attribute Name	Description
Description	description	A description of the log message.
Execute When	execute-when	A condition that determines whether the cloud-log step executes.

Extra Columns Tab

Property	XML Attribute Name	Description
Key	key	The identifier for an additional custom message. Unique within 1 log variable.
Label	label	The user-facing label for an additional custom message.
Value	value	The text of an additional custom message.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Message Manipulation Steps

Concept: Message Manipulation Steps

Message manipulation steps enable you to customize the content of messages as they pass through your integration. Workday Studio provides these **Message Manipulation** steps on the **Palette**:

Name	Function	Notes
сору	Extracts individual parts of incoming messages and copies them to different parts of outgoing messages.	
javascript	Implements a JavaScript script or function to manipulate the incoming messages.	
set-headers	Manipulates the header of a mediation message.	
write	Enables you to construct custom data and set it as the content of a mediation message.	Press Ctrl+space when inserting an MVEL expression to access content assist.

Reference: Copy Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the copy step within the assembly.
Input	input	Specifies where the copy step obtains data as input. There are 5 possible values:

Property	XML Attribute Name	Description
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Input XPath	input-xpath	An XPath expression that extracts a matching section of XML input data from a message part or variable in the MediationContext.
Output	output	Specifies where the copy mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Output XPath	output-xpath	An XPath expression that replaces a matching section of XML output data from a message part or variable in the MediationContext.
Append to Output Element	append-to-output-element	Specifies whether the copy step appends the input XML element to the element that matches the output-xpath value.
Namespaces	namespaces	The namespaces used by your XPath expression in the format prefix namespace prefix2 namespace2. Overrides namespace mappings in the assembly.xml file.

Property	XML Attribute Name	Description
Description	description	A description of the copy step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the copy step executes.
Stream XPath	stream-xpath	Specifies whether the copy step provides streaming support for simple XPath expressions.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0 or 2.0. Enter the value 1 for assembly versions through Workday 11, and 2 for assembly versions Workday 12 onwards. Workday ignores this property if the stream-xpath value is set to true.
	You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version'	

Reference: JavaScript Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the javascript step within the assembly.
Input	input	Specifies where the javascript step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the javascript mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. You must specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message.

Property	XML Attribute Name	Description
		 variable: save the output as a named variable in the MediationContext.
Function	function	A filename containing a JavaScript function, which must be located in the ws/WSAR-INF directory of your project.
		Specify a value for either the Function or Script property, but not both. You can't deploy a javascript step with both values configured.
Script	script	A filename containing a JavaScript script, which must be located in the ws/WSAR-INF directory of your project.
		Specify a value for either the Function or Script property, but not both. You can't deploy a javascript step with both values configured.

Property	XML Attribute Name	Description
Description	description	A description of the javascript step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the javascript step executes.

Reference: Set-Headers Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the set-headers step within the assembly.
Output	output	Specifies where the set-headers mediation step directs the output. There are 5 possible values: • message: the entire message,

Property	XML Attribute Name	Description
		attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. Specify the attachment index. • rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the set-headers step. Displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the set-headers step executes.
Clear All	clear-all	Clears all headers from mediation messages.
Clear All Exclude	clear-all-exclude	A list of header names that won't be deleted when Clear All is set to true.

Headers Tab

Add Headers

Property	XML Attribute Name	Description
Name	name	The name of the header that you want to add to a mediation message.
Value	value	The value of the header that you want to add to a mediation message.

Remove Headers

Property	XML Attribute Name	Description
Name	name	The name of the header that you want to remove from a mediation message.

Reference: Write Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the write step within the assembly.
Input	input	Specifies where the write step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the write mediation step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment to the message. Specify the attachment index.

Property	XML Attribute Name	Description
		 rootpart: the content of the root part of a MIME message, or if the message isn't MIME, the message itself. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the write step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the write step executes.

Validation Steps

Concept: Validation Steps

Validation mediation steps enable you to evaluate messages as they pass through your integration. Workday Studio provides these **Validation** steps on the **Palette**:

Name	Function	Notes
eval	Enables you to evaluate expressions directly.	
validate	Validates a mediation message to ensure that it adheres to an XML schema or a Document Type Definition (DTD), or that it contains well-formed XML.	 On validation failure, either raises an error or discards the message, depending on the value of the Filter property. You can specify a custom error message. You can provide a schema or DTD for validating selected elements only, and select those elements from a mediation message by supplying XPath expressions.
validate-exp	Validates an incoming message using one or more MVEL expressions.	MVEL expressions are defined as a sequence of child elements.

Name	Function	Notes
validate-xpath	Validates a message using an XPath expression, which is evaluated as a Boolean.	Validation is considered successful if the returned XPath expression isn't empty.

Reference: Eval Step Properties

Expressions Tab

Property	XML Attribute Name	Description
Expression	expression	Enables you to enter MVEL condition expressions directly.
		To add a new expression below any existing rows, click Add , then enter the expression.
		To add a new expression above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the Expressions tab to delete rows or reorder them.

Common Tab

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the eval step within the assembly.

Property	XML Attribute Name	Description
Description	description	A description of the eval step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the eval step executes.
Language	language	Specifies the expression language you want to use. MVEL is the only language currently supported.

Reference: Validate Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the validate step within the assembly.
Input	input	Specifies where the validate step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Studio selects the entire message. variable: use a named variable from the MediationContext.
Schema	schema	The location of the schema file that the step uses to validate the message. If you specify a location instead of an MVEL template, Workday uses pooled validators.
Namespaces	namespaces	The namespaces used by your XPath expression in the format prefix namespace prefix2 namespace2. Overrides namespace mappings in the assembly.xml file.
Xpath	xpath	An XPath expression that selects elements for validation.
Failure Message	failure-message	A custom error message that overrides the default error message when a validation error occurs. Error messages display only when you set the Filter property to false .

Property	XML Attribute Name	Description
Description	description	A description of the validate step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the validate step executes.
Mode	mode	 The type of validation performed. The options are: schema: validates against a W3C XML schema. dtd: validates against a Document Type Definition. well-formed: verifies that the XML is well-formed.
DTD	dtd	The location of the DTD file that the step uses to validate the message.
Replace Message	replace-message	Indicates whether to use the custom error message set as the Failure Message property when validation fails.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0 or 2.0. Enter the value 1 for assembly versions through Workday 11, and 2 for assembly versions Workday 12 onwards. Workday ignores this property if the stream-xpath value is set to true.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version'
Filter	filter	Specifies whether to interrupt mediation message processing when validation fails. The default value is false , meaning Studio passes validation errors to errorhandlers defined within the component.
		If set to true , Studio executes response steps for the component but discards the

Property	XML Attribute Name	Description
		message and invokes no further steps. It doesn't raise an error.

Reference: Validate-Exp Step Properties

Expressions Tab

Property	XML Attribute Name	Description
Value	expression	Enables you to enter MVEL condition expressions directly.
		To add a new expression below any existing rows, click Add , then enter the expression.
		To add a new expression above an existing row, place the cursor in that row, then click Insert on the Add drop-down menu.
		Use the buttons to the right of the Expressions tab to delete rows or reorder them.
Failure Message	failure-message	Text to add to the exception message when a validation expression fails.
Error Number	error-number	An error number to add to the exception message returned when a validation expression fails.
Replace	replace	Indicates whether to replace the failure message returned by Workday with the text specified in the Failure Message property.

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the validate- exp step within the assembly.
Filter	filter	Specifies whether to interrupt mediation message processing when validation fails. The default value is false , meaning Workday passes validation errors to errorhandlers defined within the component.
		If set to true , Workday executes response steps for the component but discards the

Property	XML Attribute Name	Description
		message and invokes no further steps. It doesn't raise an error.

Property	XML Attribute Name	Description
Description	description	A description of the validate- exp step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the validate-exp step executes.

Reference: Validate-Xpath Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the validate- xpath step within the assembly.
Input	input	Specifies where the validate- xpath step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Filter	filter	Specifies whether to interrupt mediation message processing when validation fails. The default

Property	XML Attribute Name	Description
		value is false , meaning Workday passes validation errors to error-handlers defined within the component.
		If set to true , Workday executes response steps for the component but discards the message and invokes no further steps. It doesn't raise an error.
Namespaces	namespaces	The namespaces used by your XPath expression in the format prefix namespace prefix2 namespace2. Overrides namespace mappings in the assembly.xml file.
Xpath	xpath	An XPath expression that selects elements for validation.

Property	XML Attribute Name	Description
Description	description	A description of the validate- xpath step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the validate-xpath step executes.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0 or 2.0. Enter the value 1 for assembly versions through Workday 11, and 2 for assembly versions Workday 12 onwards. Workday ignores this property if the stream-xpath value is set to true.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version'

Encoding Steps

Concept: Encoding Steps

Encoding steps enable you to encode, decode, compress, and decompress the contents of the MediationContext.

Workday Studio provides these **Encoding** steps on the **Palette**:

Name	Function	Notes
pgp-encrypt	Retrieves a public key and encrypts outbound data using PGP.	 To encrypt messages using keys stored in Workday, configure a delivery service for your integration. Studio integrations don't have access to keys stored in Workday. You can also reference a local PGP key using the file:// protocol, then deploy it with the integration. However, the delivery service method is best practice for Studio integrations.
pgp-decrypt	Retrieves a private key and decrypts inbound data that was encrypted using PGP.	
base64-decode	Decodes a Base64 encoding of attachment data to binary format.	
base64-encode	Encodes binary attachment data in Base64-encoding format.	
zip	Transforms the root part and attachments from the MediationContext into a ZIP file.	
unzip	Extracts the contents of a ZIP file.	If the ZIP contains more than 1 file, a multipart structure like the mediation message is preferred. Example: if you use the default output option of message, the first file in the ZIP becomes the root part and the other files in the ZIP become attachments.
compress	Transforms a single file in the MediationContext to a GZIP or BZIP2 file.	Unlike the ZIP step, this step doesn't support file archiving. Use it to compress single files.
decompress	Extracts the contents of a single GZIP or BZIP2 file.	

Concept: PGP Filenames

As a security measure, when a plaintext file is encrypted with PGP, the encrypted file can be given a filename that's unrelated to the original, giving no hint of its contents. However, the original filename isn't discarded. It's embedded in the encrypted file for later retrieval by the recipient's decrypting system. Example: you encrypt a file named myPlaintext.txt. The resulting file is called myEncryption.pgp. Part of its encrypted content is the original filename. When your recipient decrypts it, their system names the resulting file myPlaintext.txt.

Workday Delivery and Retrieval Services

The Workday Delivery and Retrieval Services follow the typical PGP file-naming practice when possible.

The Workday Delivery Service embeds the plaintext filename in the outgoing PGP file so it can be recovered during decryption.

When the Workday Retrieval Service decrypts an incoming PGP file attached to an integration event, it uses the embedded plaintext filename to name the decrypted file.

Sometimes, however, an incoming PGP file has no embedded plaintext filename. If so, the Workday Retrieval Service bases the name of the decrypted file on the name of the PGP file:

- If the PGP filename ends with .pgp, the Retrieval Service removes that suffix from the decrypted filename. Example: the PGP file myFile.csv.pgp is decrypted as myFile.csv, the PGP file myFile.pgp is decrypted as myFile.
- If the PGP filename ends with .xlsx, the Retrieval Service leaves it unchanged. Example: the PGP file myFile.xslx is decyrpted as myFile.xslx.
- In all other cases, the Retrieval Service adds the suffix .plaintext. Example: the PGP file myFile.doc is decrypted as myFile.plaintext.

Workday Studio

When you use Studio's **pgp-encrypt** step to encrypt a message, you can specify the plaintext filename using the **Decrypted Filename** step property. Studio then embeds that filename in the encrypted file for subsequent retrieval in the normal manner.

Likewise, Studio's **pgp-decrypt** step uses any embedded plaintext filename to name the decrypted file. You can use the **Decrypted Filename** step property to provide a filename for situations where none is embedded.

Troubleshooting

Problems can arise when a remote party encrypting a file unintentionally sets the embedded plaintext filename to some value other than that required by a recipient system. Because the PGP filename is entirely unrelated to the plaintext filename, there is no way to deduce the latter. The recipient has no options in this scenario.

Example: a Retrieval Service is configured to retrieve and decrypt a file. When run, it collects a PGP encrypted file named ExternalStudents.pgp, but a file named _CONSOLE is attached to the integration event for processing by an integration. In this case, the remote system has set _CONSOLE as the embedded plaintext filename. The result is the file is identified to Workday integrations as _CONSOLE.

The only way to prevent such problems is to ensure that senders of PGP files understand how to correctly embed the required plaintext filename.

Reference: PGP-Encrypt Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the pgp- encrypt step within the assembly.
Input	input	Specifies where the pgp-encrypt step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the pgp-encrypt step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Ascii Armored	ascii-armored	Indicates whether the pgp- encrypt step generates PGP data in ASCII-armored format (a PGP version of Base64) or in pure binary. ASCII-armored formatting produces email-friendly text, including a header and a footer.
Certificate	certificate	The certificate used for encryption, provided by 1 of these types of URL:
		• An attachment URL for retrieving the public key from the tenant. Must follow the pattern attachment:certificate/ WIDvalue, where WIDvalue is the WID of the public key stored in the tenant. Example: you can configure the reference using an integration attachment in the form attachment:certificate/ @ {intsys.getAttributeReference Encryption Key', 'WID')} where PGP Encryption Key is the name of the integration attribute. • An mctx URL for retrieving the public key from the context variable where the integration stored it. Example: mctx:vars/MyPublicKey where MyPublicKey is the name of the context variable. • The filename of a public key stored in the assembly's WSAR-INF folder or in one of its subfolders. Examples: PublicKey.asc or /keys/ PublicKey.asc.
Containing Integrity Check	containing-integrity-	PublicKey.asc. Indicates whether the pgp- encrypt step generates a

Property	XML Attribute Name	Description
		message signature for integrity checking by the receiver.
Decrypted Filename	decrypted-filename	A name for the decrypted file. Example: yourname.plaintext.mail. Workday includes the specified value in the hash string.
Pgp26x Compatible	pgp26x-compatible	Indicates whether the pgp- encrypt step generates encrypted data that is backward compatible with the older pgp26x version.
Private Key Passphrase	private-key-passphrase	Specifies the passphrase for the private key.
Signing Private Key	signing-private-key	The private key used to sign messages as a filename, using the file://protocol.
		Note: Best practice for Workday Studio integrations is to use a delivery service rather than the pgp-encrypt step to perform encryption.
Textmode	textmode	Specify true to indicate that the data to be encrypted is in text format, containing <cr><lf> line endings.</lf></cr>
		Note: If you specify true for data that doesn't contain <cr><lf> line endings, Workday reports an error.</lf></cr>

Property	XML Attribute Name	Description
Description	description	A description of the pgp- encrypt step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it's operating.
Execute When	execute-when	A condition that determines whether the pgp-encrypt step executes.

Related Information Reference

Workday 31 What's New Post: Workday Studio

Reference: PGP-Decrypt Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the pgp- decrypt step within the assembly.
Input	input	Specifies where the pgp-decrypt step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the pgp-decrypt step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Private Key	private-key	The filename or URI for the Workday private key. Use the file:// protocol to specify it as a filename.
Passphrase	passphrase	Specifies the passphrase for the private key.
Decrypted Filename	decrypted-filename	Sets the content- disposition attribute on the output of the pgp-decrypt step or, if the output is a variable, the filename. If the pgp-encrypt step specifies a decrypted-filename value, however, that value takes precedence.

Property	XML Attribute Name	Description
Description	description	A description of the pgp-decrypt step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the pgp-decrypt step executes.

Reference: Base64-Decode Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the base64-decode step within the assembly.
Input	input	Specifies where the base64-decode step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments.

Property	XML Attribute Name	Description
		 soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the base64- decode step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the base64- decode step that displays in the consolidated log. You can use this feature to describe the step's

Property	XML Attribute Name	Description
		function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the base64-decode step executes.

Reference: Base64-Encode Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the base64-encode step within the assembly.
Input	input	Specifies where the base64- encode step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the base64-encode step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message,
		 effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message.

Property	XML Attribute Name	Description
		 attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Description	description	A description of the base64-encode step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the base64-encode step executes.

Reference: Zip Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the zip step within the assembly.
Input	input	Specifies where the zip step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index.

Property	XML Attribute Name	Description
		 rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the zip step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Format	format	The format of the zipped file. The options are: • zip • tar Note: The TAR format supports archiving but not compression. To compress TAR files, use either of these commands: • gzip, which replaces the .tar file extension with .tar.gz or .tgz • bzip2, which replaces the .tar

Property	XML Attribute Name	Description
		You can compress and decompress TAR archives produced in the zip step using the compress and decompress steps, respectively.
Level	level	The level of compression in the range zero to 9, with 9 being maximum compression. The default value is -1.

Property	XML Attribute Name	Description
Description	description	A description of the zip step. Displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the zip step executes.
Comment	comment	A comment that's embedded in the ZIP file. The comment is an arbitrary ASCII string of up to 65,535 bytes.

Reference: Unzip Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the unzip step within the assembly.
Input	input	Specifies where the unzip step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME

Property	XML Attribute Name	Description
		message. If the message isn't MIME, Workday selects the entire message. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the unzip step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Format	format	The format of the zipped file. The options are: • zip
		• tar
		Note:
		The TAR format supports archiving but not compression. To compress TAR files, use either of these commands:
		 gzip, which replaces the .tar file extension with .tar.gz or .tgz bzip2, which replaces the .tar file extension with .tar.bz2
		You can compress and decompress TAR archives produced in the zip step using

Property	XML Attribute Name	Description
	1	the compress and decompress steps, respectively.

Property	XML Attribute Name	Description
Description	description	A description of the unzip MediationContext.
Execute When	execute-when	A condition that determines whether the unzip step executes.
Filename	filename	The name of the file created when the content unzips.

Reference: Compress Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the compress step within the assembly.
Input	input	Specifies where the compress step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the compress step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and

Property	XML Attribute Name	Description
		attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Format	format	The format of the zipped file. The options are <i>gzip</i> and <i>bzip2</i> . The default format is <i>gzip</i> .

Property	XML Attribute Name	Description
Description	description	A description of the compress step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the compress step executes.
Filename	filename	The name of the file created when the content unzips.

Reference: Decompress Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the decompress step within the assembly.

Property	XML Attribute Name	Description
Input	input	Specifies where the decompress step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the decompress step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.

Property	XML Attribute Name	Description
Format	format	The format of the zipped file. The options are <i>gzip</i> and <i>bzip2</i> . The default format is <i>gzip</i> .

Property	XML Attribute Name	Description
Description	description	A description of the decompress step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the decompress step executes.
Filename	filename	The name of the file created when the content unzips.

Other Steps

Concept: Other Steps

Steps enable you to perform individual operations on messages as they pass through your integration. Workday Studio provides these **Other** steps on the **Palette**:

Name	Function
custom	Enables you to apply custom code written using Spring beans to incoming messages.
set-dynamic-endpoint	Configures WS-Addressing (WSA) endpoint information for an out-transport.
store	Creates a persistent copy of a document that's available to other users and/or can be viewed as an attachment to the integration event.
	The individual message size limit for store steps is 1 GB (compressed). The cumulative limit is 3 GB (compressed). Workday terminates integrations that exceed these limits. Where possible, use splitters or streaming to break up large files in your integrations.
retrieve	Retrieves a persistent copy of a document that was previously stored by a store step.
xmldiff	Compares 2 XML input documents.
enqueue-message	Organizes messages into a queue.

Reference: Custom Step Properties

Property	XML Attribute Name	Description
Step ID	id	Specifies the unique ID of the custom step within the assembly.
Input	input	Specifies where the custom step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. • variable: use a named variable from the MediationContext.
Output	output	Specifies where the custom step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Method Name	method-name	The name of the Java method within your custom Java class.
Spring Bean	ref	The custom Spring bean Java class implemented by the custom step.

Property	XML Attribute Name	Description
Description	description	A description of the custom step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the custom step executes.

Reference: Set-Dynamic-Endpoint Step Properties

Common Tab

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the set- dynamic-endpoint step within the assembly.
Endpoint	endpoint	The address of the dynamic endpoint.

Property	XML Attribute Name	Description
Description	description	A description of the set-dynamic-endpoint step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the set-dynamic-endpoint step executes.

Reference: Store Step Properties

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the store step within the assembly.
Input	input	Specifies where the store step obtains data as input. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Output	output	Specifies where the store step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value

Property	XML Attribute Name	Description
		preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
		The store step stores a message's mimetype along with the message itself. Example: text/plain. When you retrieve the message with a retrieve step, Workday automatically marks it with the stored mimetype so later steps can process it correctly.
		The individual message size limit for store steps is 1 GB (compressed). The cumulative limit is 3 GB (compressed). Workday terminates integrations that exceed these limits. Where possible, use splitters or streaming to break up large files in your integrations.
Collection	collection	The name of the collection that stores your document.
Expires In	expiresIn	The period of time before your document expires.
		Specify the value in XSD duration format.
		Example: to indicate 1 year, 3 months, 5 days, 8 hours, 45 minutes, and 10 seconds, enter P1Y3M5DT8H45M10S.
Summary	summary	A summary of your document. Displays in your Workday tenant.
Title	title	The title of your document.
Create Document Reference	createDocumentReference	Specifies whether the store step automatically calls Workday to create a document reference.

Advanced Tab

Property	XML Attribute Name	Description
Description	description	A description of the store step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.

Property	XML Attribute Name	Description
Execute When	execute-when	A condition that determines whether the store step executes.
Content Disposition	contentDisposition	The content-disposition header for your document.
		Overrides the title property value, if specified.
Blobitory URI	blobitoryURI	The URI of the cc-blobitory service implemented in your Workday tenant.
		Example: https://machine-name.workday.com:8080/ccx/cc-blobitory.
Expires On	expiresOn	The date and time at which your document expires.
		Overrides the Expires In property value, if specified.
		Enter the value for this property in CCYY-MM-DDThh: mm:ssZ format.
		Example: to indicate 11.59 p.m. on December 31, 2009, enter 2009-12-31T23:59:00Z.
Schema	schema	The URI for the schema that references your document. There are 2 possible values:
		 http://www.w3.org/2005/
		• urn:com.workday/bsvc/blob
Entry ID	entryID	Specifies an Entry ID for each document. Must be unique in your tenant. If you don't specify an Entry ID value, Workday generates one. If you specify one that already exists, Workday overwrites the document, provided it's mutable. You can't reuse an Entry ID if the existing document is immutable.
		When updating documents using the REST API:
		 Use the PUT HTTP method for documents with predefined Entry IDs. Use the POST HTTP method when the Entry ID isn't

Property	XML Attribute Name	Description
		specified or evaluates to null or an empty string.
Is Attachment	isAttachment	Specifies whether your document is an OMS attachment.
Immutable	immutable	Specifies whether you can modify your document after you create it.
Assign Owner	assignOwner	Specifies whether Workday assigns you as the owner of your document.
Document Reference Description	documentReferenceDescripti	Andescription of your document. Displays in your Workday tenant.

Reference: Retrieve Step Properties

Common Tab

Property	XML Attribute Name	Description
Step ID	id	Specifies the unique ID of the retrieve step within the assembly.
Output	output	Specifies where the retrieve step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments.
		 soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment within the message. Specify the attachment index.
		 rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
		When you configure a Document Retrieval Service on a Business Process, Workday uses the string

Property	XML Attribute Name	Description
		you enter in the Custom Content Type field as the mimetype for the document stored by that service.
		When you retrieve the document with a retrieve step, either directly or through a document iterator or document accessor helper object, Workday automatically marks it with the stored mimetype so later steps can process it correctly. If you don't enter a Custom Content Type , Workday uses UTF-8 encoding. To avoid errors, always enter the appropriate Custom Content Type for data that isn't UTF-8 encoded.
Collection	collection	The name of the collection that stores your document.
Entry	entry	The identifier of the document in your collection. Retrievable from the MediationContext using an MVEL expression.
		<pre>Example: @{parts[0].xpath('// blob:entry', 'blob urn:com.workday/bsvc/ blob')}</pre>
Password	password	The password credentials for accessing your document.
Username	username	The username credentials for accessing your document.

Advanced Tab

Property	XML Attribute Name	Description
Description	description	A description of the retrieve step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the retrieve step executes.

Reference: Xmldiff Step Properties

Common Tab

Property	XML Attribute Name	Description
Step ID	id	Specifies the unique ID of the xmldiff step within the assembly.
First Input	first-input	Specifies the first data input source for the xmldiff step. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. variable: use a named variable from the MediationContext.
Second Input	second-input	Specifies the second data input source for the xmldiff step. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message.

Property	XML Attribute Name	Description
		variable: use a named variable from the MediationContext.
Output	output	Specifies where the xmldiff step directs the output. There are 5 possible values: • message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. • soapbody: the content of the SOAP body from the rootpart of the message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. • variable: save the output as a named variable in the MediationContext.
Copy To Output	copy-to-output	Specifies whether the xmldiff step copies the output to the mediation message or a variable. If set to true, the xmldiff step copies the output to the mediation message. If set to false, the xmldiff step copies the output to a variable.
Ignore Attributes	ignore-attributes	Specifies whether the xmldiff step ignores attributes when comparing 2 XML documents.
Namespaces	namespaces	Namespace override definitions for XPath expressions implemented by the xmldiff step.

Advanced Tab

Property	XML Attribute Name	Description
Description	description	A description of the xmldiff step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the xmldiff step executes.
XPath Version	xpath-version	Specifies whether to use XPath version 1.0 or 2.0. Enter the value 1 for assembly versions through Workday 11, and 2 for assembly versions Workday 12 onwards. Workday ignores this property if the stream-xpath value is set to true.
		You can enable Workday to set the version dynamically using an MVEL template that inserts a system property value. Example: @{props.get('the_version'

Definitions Tab

Property	XML Attribute Name	Description
Name	name	Specifies the name of the sub- diff to use when looking up results of the xmldiff step.
Ignore Deletions	ignore-deletions	Specifies whether the xmldiff step ignores deletions in the output.
Different Nodes Only	result-document- different-nodes-only	Specifies which nodes display in the output document for the xmldiff step.
		If set to true, only top-level nodes display in the output document.
		If set to false, all child nodes display in the output document.
Result Document Inclusion	result-document-inclusion	Specifies whether the xmldiff step records differences between nodes in the output document. There are 3 possible values:
		Always: the selected node and its children always display in the result document.

Property	XML Attribute Name	Description
		 Different: the selected node and its children only display in the result document if differences are found. Never: the selected node and its children never display in the result document.
XPath	xpath	The XPath expression implemented by the xmldiff step to find nodes in your input document.

Matcher XPath Tab

On the **Matcher XPath** tab, you can add XPath expressions that locate nonsequential matching nodes in your input documents.

Reference: Enqueue-Message Step Properties

Common Tab

Property	XML Attribute Name	Description
Step ID	id	The unique ID of the enqueue- message step within the assembly.
Input	input	Specifies where the enqueue- message step obtains data as input. There are 5 possible values: • message: the entire message, including rootpart and attachments. • soapbody: the content of the SOAP body from the rootpart of the message. Only applicable when the input contains a SOAP message. • attachment: a MIME attachment within the message. Specify the attachment index. • rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. • variable: use a named
		variable from the MediationContext.

Property	XML Attribute Name	Description
Output	output	Specifies where the enqueue- message step directs the output. There are 5 possible values:
		 message: the entire message, including rootpart and attachments. This value creates a new message, effectively removing any attachments. soapbody: the content of the SOAP body from the rootpart of the message. attachment: a MIME attachment within the message. Specify the attachment index. rootpart: the content of the rootpart of a MIME message. If the message isn't MIME, Workday selects the entire message. This value preserves any attachments on the original message. variable: save the output as a named variable in the MediationContext.
Content Type	contentType	Overrides the content type of your output message, which is text/xml by default.
Queue Name	queueName	The name of the queue where the enqueue-message step directs the output.
File Name	fileName	Overrides the filename in the header of the mediation message.

Advanced Tab

Property	XML Attribute Name	Description
Description	description	A description of the enqueue- message step that displays in the consolidated log. You can use this feature to describe the step's function and the data on which it is operating.
Execute When	execute-when	A condition that determines whether the enqueue-message step executes.

Assembly Modules

Create Assembly Modules

Prerequisites

Create an assembly project.

Context

Workday Studio assembly modules provide parameterized templates for building assemblies. They enable you to create and reuse preconfigured sets of components and steps that perform particular tasks.

Steps

- 1. Add the elements that you want to include in your assembly module and configure their properties as required. You can create a module from a functionally complete assembly or from a smaller set of components and steps. Users can adjust parameters when they implement the module.
- **2.** Save your assembly.
- 3. In the Project Explorer, right-click the assembly project, then select Create Assembly Module....
- 4. Provide a name and description for the module. The description displays as the tooltip for the module.
- 5. Select an icon for the module. You can use the default icon or upload one of your own.
- **6.** Studio organizes module parameters into collections called pages. A parameter must belong to a page. Each page has a name and a description. Each parameter has a name, a label (which displays in the **Configure Module** wizard), a description, a type, and a default value. There are 6 parameter types:

Туре	Description	Example
String	A text value.	"HelloWorld"
XMLRequest	An XML literal for a request message. Module users specify a value for the Web service request using either the Create Literal XML or Create Workday Web Service Request wizard.	<pre><?xml version="1.0" encoding="UTF-8"? > </pre>

Туре	Description	Example	
		<br env:Envelope>	
Prompt	You can use Class Report Fields (CRFs) to provide a prompt for launch parameters of Workday objects of a particular type. To specify a CRF Reference, click Select reference id .	fbbe44a681251000039acc2ff	657000a
	Note: To specify a CRF reference, you must connect to a Workday tenant.		
File	A filename. You can specify the file extension as a data value.	*.xslt	
Enum	A single literal value or multiple values separated by a comma or space.	code1 code2 code3	
Boolean	A Boolean value.	true	

- 7. When you finish adding parameters and save the module, Studio opens its XMI file in the XML editor. The file contains a params element for each parameter that you specified. The assemblyText and diagramText elements contain the assembly XML and diagram details, encapsulated within <! [CDATA[]] > tags. You can edit the XMI file directly.
- 8. Close the XMI file.

Add Assembly Modules to a Project

Prerequisites

Create an assembly project or open an existing assembly project.

Context

Workday Studio assembly modules provide parameterized templates for building assemblies. They enable you to create and reuse preconfigured sets of components and steps that perform particular tasks.

Steps

1. Drag the module from the **Modules** section of the **Palette** to the Assembly Editor. Studio opens the **Configure Module** wizard.

Note: The **Module Library** displays only those assembly modules that you select on the **Window** > **Preferences** > **Workday** > **Assembly Editor** > **Modules** preference page.

- 2. Configure the module's parameters.
- 3. If the assembly module contains a parameter of type XMLRequest, click either Create Literal XML or Create Workday Web Service Request to specify a value for the Web service request. As you complete this task, consider:

Wizard	Operations	Notes
Create Literal XML	Get, Put	Can be used for any Web service.

Wizard	Operations	Notes
		Select the Web service name and Web service version values for the request from the lists below the text pane.
Create Workday Web Service Request	Get	Use for Workday Web services only. Studio populates Web service name and version values automatically when you select an operation.

^{4.} Studio displays a preview of the assembly elements that the module contains. When you complete the wizard, Studio adds those elements to the assembly.

Concept: Assembly Modules

Workday Studio assembly modules provide parameterized templates for building assemblies. They enable you to create and reuse preconfigured sets of components and steps that perform particular tasks. You can create a module from an entire assembly or from a segment of one.

An assembly that you build using a module is no different from an assembly that you build from scratch. They look and behave identically.

Studio saves a module as a template in the XML Metadata Interchange (XMI) format, with an xmi file extension. Access your saved modules from the **Module Library** on the Studio **Palette**. To enable other developers to access your modules, save them in a shared location.

Sharing tried-and-tested assembly modules helps speed up and reduce the cost of integration development.

The **Module Library** displays only those assembly modules that you select on the **Window** > **Preferences** > **Workday** > **Assembly Editor** > **Modules** preference page.

Subassemblies

Create Subassemblies

Prerequisites

Create an assembly.

Context

A subassembly is a processing chain whose first component is a **local-in** transport. You invoke it with a **local-out** transport, either from within the same assembly or from a separate assembly.

Steps

- 1. Add and configure the **local-in** transport that defines the beginning of the subassembly.
 - a) Add a **local-in** transport at the beginning of the processing chain that you want to turn into a subassembly.
 - b) On the **Common** and **Advanced** tabs of its **Properties** view, configure the transport's properties. You can provide an icon for the subassembly and text that displays as its tooltip.
 - c) On the **Parameters** tab, define parameters that the subassembly requires as input. You can configure these parameters on the **local-out** transport that calls the subassembly. Studio stores them as MediationContext properties.
 - d) On the Out Parameters tab, define the MediationContext properties that the subassembly sets.
 - e) Save the assembly.
- 2. Add and configure the **local-out** transport that invokes the subassembly.
 - a) Add a **local-out** transport to the assembly that invokes the subassembly.
 - b) On the **Common** and **Advanced** tabs of its **Properties** view, configure its properties. Specify the subassembly **local-in** as the **endpoint** property. Use the format vm://assembly-name/local-out-ID, or click **Select local-in sub-assembly**.
 - c) On the **Parameters** tab, set MediationContext properties. You can create new parameters by clicking **Create 'set' element**. You can also select any that parameters that you define in the **localin** transport and assign them values by clicking **Select Parameter**.

Note: In the **Select Parameters** wizard, an asterisk indicates that the property is required. A question mark indicates that usage is dynamic.

d) Save the assembly.

Concept: Subassemblies

A subassembly is a processing chain whose first component is a **local-in** transport. The **local-in** defines an entry point to the processing chain, enabling it to be called by a **local-out** transport in the same assembly or in another assembly. You can include several subassemblies and **local-out** transports within the same assembly.

Note: You can't deploy subassemblies to Workday on their own because they don't begin with a **workday-in** transport.

Because you can invoke them at will, subassemblies enable you to encapsulate processing logic for reuse. You can think of them as programming subroutines. The default ID for a **local-in** transport is SubRoutine. The default ID for a **local-out** transport is CallSubRoutine.

Subassemblies have parameters. You specify them on the **local-in** transport and assign them values on the **local-out**. These parameters define properties in the MediationContext.

When you save a subassembly, Workday Studio automatically adds a **local-out** transport that invokes it to the **Workspace Components** category on the **Palette**. This **local-out** transport uses the custom icon from the subassembly's **local-in** transport, if you supplied one. Otherwise it uses a question mark icon.

The **Palette** always displays public subassemblies. It displays private subassemblies only if they occur in the assembly. Studio provides several prepackaged subassemblies in the **Common Components** category on the **Palette**.

To locate the **local-in** transport that a **local-out** references, right-click the **local-out** and select **Declaration in Workspace**.

To locate the **local-out** transports that are referenced by a **local-in**, right-click the **local-in** and select **References in Workspace**.

Related Information Concepts

Concept: Common Components on page 94

Custom Assembly Components

Create Custom Java Classes and Spring Beans

Prerequisites

Create an assembly project.

Context

You can create 4 custom assembly elements from the Palette in Workday Studio:

- · custom-mediation component
- custom step
- **custom-out** transport
- · custom-error-handler

A fifth custom element, custom routing strategy, is available from the **Route** component's context toolbar.

Steps

- 1. Open an assembly in the Assembly Editor.
- 2. Add one of these custom elements to the assembly:
 - · custom-mediation component
 - · custom step
 - **custom-out** transport
 - · custom-error-handler
- 3. Configure the custom element's properties in its **Properties** view.
- 4. Click Create Spring Bean Properties and Java Class, to the right of the Spring Bean field. The properties that Studio displays vary slightly depending on the custom element type. As you complete the task, consider:

Option	Description	
Id	Provide a unique Spring bean identifier.	
Scope	 Select singleton to return the same bean instance with each reference. Select prototype to return a different bean instance with each reference. 	
Package	Specify the Java package.	
Name	Specify the class name.	
Input Type	Select the input type to pass to the Java method. You don't need to specify implementation details for accessing the message part and converting it to the appropriate type. Workday inspects the method's first parameter and converts the message part to the same type.	
Output Type	Select the method's output (return) type.	
Method Name	Enter the name of the Java method that you want to define within the Java class. The default value is process.	

Option	Description
Include argument for dynamic endpoint	Specifies whether to include an argument for a dynamic endpoint.
Annotate Java class to appear in palette	Select this check box to display the custom element on the Palette . This option adds an annotation to the generated Java class, which is located in the src folder of your assembly project folder.
Tooltip	Enter the text that displays as the custom element's description.

5. Save the assembly.

Result

Studio generates the Java class representing the custom element within the package specified. It also adds a reference to the new custom Spring bean at the bottom of the assembly.xml file.

Next Steps

Add the required code to your custom Java class.

Concept: Custom Assembly Elements

You can create 5 types of custom assembly elements in Workday Studio:

Custom Element	Procedure
Mediation component	Add a custom-mediation component from the Components category on the Palette .
Mediation step	Add a custom step from the Other category on the Palette .
Out transport	Add a custom-out transport from the Out Transports category on the Palette .
Error handler	Add a custom-error-handler component from the Error Handlers category on the Palette .
Routing strategy	Select Create custom-strategy from a Route component's context toolbar.

In each case, the custom element consists of 3 parts:

- The underlying Java implementation, which defines the classes and methods used by the element.
- The Spring bean configuration, which tells Workday how to create instances of the Java classes.
- The assembly component configuration, which places your custom element on the graphical assembly view.

Custom assembly elements can access message parts in the normal way when processing incoming data. You can also specify the message part where Workday should direct the custom element's output.

To share a custom element, export the Java package as a binary JAR. Other developers can then add the JAR to their project's classpath.

Custom Steps

When writing a Java implementation for a custom step, consider these points:

- The method must be declared public so it can be called from outside the class.
- · The method must be nonstatic.
- Each method must have a unique name.
- Parameter lists must match the supported combinations.
- The method can throw any type of exception.
- If you don't provide a method name, Workday selects any public method (ignoring getters and setters) with a parameter list matching the supported method signatures. If there's any ambiguity, Workday reports an error during deployment, which you can resolve by specifying a method name.

A **custom** step must provide a method that adheres to one of these signatures:

Signature	Usage	Example
<pre>public return type method(input parameter type input) [throws any Exception]</pre>	Defines the return type of the method and an input parameter.	<pre>public String addTimestamp(byte[] messageContent) throws IOException {</pre>
<pre>public void method(input parameter type input, output parameter type output) [throws any Exception]</pre>	Defines supported input and output parameters.	<pre>public void addTimestamp(byte[] messageContent, OutputStream out) throws IOException {</pre>

The **custom** step supports these input, return, and output parameter types:

In	put Types	Return Types	Output Parameter Types
•	java.lang.String byte[] java.io.InputStream javax.activation.DataHadiavax.activation.DataSolorg.w3c.dom.Element org.w3c.dom.Document javax.xml.transform.Soudjavax.xml.transform.str	• void • boolean (custom step only) • java.lang.String nellewte[] arcejava.io.InputStream • javax.activation.DataHar • javax.activation.DataSor	• java.io.OutputStream • javax.xml.transform.Resu
•	-	.DOM/Saværscexml.transform.Sou	rce

If a **custom** step returns a void type or a null value, it doesn't alter the mediation message.

Concept: Custom Element Packaging

Java Class Annotations

If you want to reuse a custom assembly element in different projects, use annotations to have the element display on the **Palette**.

To do so, select the **Annotate Java class to appear in palette** check box when you create the Java class and Spring bean. Studio adds an @Component annotation in the generated Java class, which is located in your assembly project's **src** folder. Example:

```
import com.capeclear.assembly.annotation.Component;
import com.capeclear.assembly.annotation.ComponentMethod;
import com.capeclear.assembly.annotation.Property;
import static com.capeclear.assembly.annotation.Component.Type.*;
```

```
@Component(
    name = "TimeStamperCustomMediationStepImpl",
    type = mediation,
    toolTip = "This custom code step adds the current time on the first
line of the message.",
    scope = "singleton",
    smallIconPath = "icons/TimeStamperCustomMediationStepImpl_16.png",
    largeIconPath = "icons/TimeStamperCustomMediationStepImpl_24.png"
    )
```

You can manually edit this information.

Note that Studio stores icons for the custom element in the project's src/icons folder. There are 2
versions, 16x16 and 24x24 pixels. To use custom icons, replace the _16.png and _24.png files with your
own images.

Exposing Customized Assembly Element Properties

If your custom Java code has properties that you want users to set, you can display them on the **Bean** tab of the custom element's **Properties** view.

To do so, provide getter and setter methods that follow the bean pattern. Example: for property abc, provide getter and setter methods such as getAbc and setAbc.

Then add the @Property annotation to either the set or the get method. The name value defines the label for the property in the **Properties** view and the toolTip value defines the text that Studio displays when you mouse-over the label. You can control the order in which properties are listed using an order value. Lower values display first. An editelement value specifies the type of button displayed next to the property input field, as follows:

```
// Displays a text box with a Select button to enable you to select a Spring
bean.
@Property(name="Text", edit=Edit.BEAN_REF)

// Displays a text box with a Select button to enable you to select a Java
class.
@Property(name="Text", edit=Edit.CLASS)

// Displays a text box with a dialog box that enables you to specify a cron
expression.
@Property(name="Text", edit=Edit.CRON)

// Displays a text box without a button.
@Property(name="Text", edit=Edit.DEFAULT)

// Displays a Browse button to enable you to specify a file.
@Property(name="Text", edit=Edit.FILE)

// Displays a Browse button to enable you to specify a folder.
@Property(name="Text", edit=Edit.FOLDER)
```

Studio looks for customization classes on the project classpath of the project that contains the assembly.xml file being edited. To distribute your custom component to multiple assembly projects, package the customization in binary form as a JAR file containing the class files and icon images. Other users can include this JAR within the project's classpath to make it available in their Assembly Editor.

The Assembly Editor automatically loads any customized components it finds in its classpath at startup. Right-click on the assembly diagram background and select **Refresh Customizations** to reload any recently added custom components.

Spring Bean Configuration

Concept: Spring Bean Configuration

You can edit Spring bean properties on the Beans tab on the Assembly Editor's Properties view.

Studio displays all of the assembly's beans on the left of the view beneath a top-level **beans** node. The properties associated with the **beans** node are global, affecting all beans in the assembly.

Various options display above the beans. Their availability depends on your selection in the beans list. The options are:

Option	Description
Create 'bean'	Creates a Spring bean element in the assembly file. Select the top-level beans node to make this option available.
Create 'alias'	Creates an alias for a Spring bean element in the assembly file. Select the top-level beans node to make this option available.
Create 'property'	Creates a property element for the selected bean.
Create 'constructor-arg'	Creates a constructor-arg element for the selected bean.
Create 'ref'	Creates a ref element, enabling other beans to reference the selected property.
Create 'list'	Creates a list element for the selected property, enabling you to define the properties of a List Java collection.
Create 'map'	Creates a map element for the selected property, enabling you to define the properties of a Map Java collection.
Create 'import'	Creates a top-level import element within the assembly's beans definition, enabling you to specify a resource file containing one or more bean definitions. Select the top-level beans to make this option available.
Create 'value'	Creates a nested value element within the selected property definition, enabling you to specify the property as a human-readable string.

Reference: Global Bean Properties

Property	XML Attribute Name	Description
Default Autowire	default-autowire	Inspects the BeanFactory to automatically resolve beans.
Default Autowire Candidate	default-autowire- candidate	Enables you to limit autowiring to a set of bean candidates based on pattern matching against bean names.

Property	XML Attribute Name	Description
Default Dependency Check	default-dependency-check	Specifies whether Studio checks for unresolved bean dependencies.
Default Destroy Method	default-destroy-method	Checks every bean for the specified destroy callback method.
Default Init Method	default-init-method	An initialization callback method for every bean.
Default Lazy Init	default-lazy-init	Specifies whether bean instances are created at startup or when first requested. If you don't want a singleton bean to be preinstantiated when using an ApplicationContext, set to true.
Default Merge	default-merge	Determines whether Studio merges collections by default.

Reference: Individual Bean Properties

Property	XML Attribute Name	Description
Id	id	The unique ID of the custom bean element within the assembly.
Abstract	abstract	Indicates whether the bean is usable only as a parent bean definition that will serve as a template for child definitions. The default value is false.
Autowire	autowire	Inspects the BeanFactory to resolve beans automatically.
Autowire Candidate	autowire-candidate	Enables you to limit autowiring to a set of bean candidates based on pattern matching against bean names.
Class	class	The implementation class name.
Dependency Check	dependency-check	Indicates whether Studio checks for unresolved bean dependencies.
Depends On	depends-on	Forces initialization of one or more beans before the bean using this element initializes. To express dependency on multiple beans, list their names separated by commas, whitespace, or semicolons.

Property	XML Attribute Name	Description
Destroy Method	destroy-method	Checks the bean for the specified destroy callback method.
Factory Bean	factory-bean	The bean in the current or parent container that holds the instance method whose invocation creates the object.
Factory Method	factory-method	The name of the factory method to use when instantiating the bean.
Init Method	init-method	A generic initialization method for the bean.
Lazy Init	lazy-init	Indicates whether the bean instance should be created at startup or when first requested. If you don't want a singleton bean to be preinstantiated when using an ApplicationContext, set to true. By default, this property takes its value from the container-level setting.
Name	name	A name for the bean.
Parent	parent	The parent bean. If specified, the current bean inherits its configuration data.
Primary	primary	Designates the current bean definition as the primary autowire candidate. The default value is false.
Scope	scope	The scope of the objects created from the bean definition. The default value is singleton.

Reference: Alias Properties

Property	XML Attribute Name	Description
Alias	alias	The alias name.
Name	name	The ID of the original bean.

Reference: Property Properties

Property	XML Attribute Name	Description
Name	name	The property name.
Spring Bean	spring-bean	The ID of another bean in the container.
Value	value	The property value.

Reference: Constructor-Arg Properties

Property	XML Attribute Name	Description
Index	index	A zero-based index for the constructor argument.
Spring Bean	spring-bean	The ID of another bean in the container. The constructor arguments specified in the bean definition are used to pass in as arguments to the constructor of the referenced bean.
Туре	type	The type of the constructor argument.
Value	value	The value of the constructor argument.

Reference: Ref Properties

Property	XML Attribute Name	Description
Bean	bean	References a target bean by specifying one of the values in its Name or its Id .
Local	local	References a local target bean by specifying its Id attribute. Enables the XML parser to validate XML ID references within the same file.
Parent	parent	References a target bean in a parent container of the current container. Specifies one of the values in its Name or its Id .

Reference: List Properties

Property	XML Attribute Name	Description
Merge	merge	Specifies whether Java List collections are merged. By default, the merge property takes its value from the container-level default-merge setting.
Value Type	value-type	The Java type for value elements in the list.

Reference: Map Properties

Property	XML Attribute Name	Description
Merge	merge	Specifies whether Java Map collections are merged. By default, the merge property takes

Property	XML Attribute Name	Description
		its value from the container-level default-merge setting.
Value Type	value-type	The Java type for value elements in the list.
Кеу Туре	key-type	The Java type for key elements in the map.

Message Builder

Create XML Literals Based on Schema or WSDLs

Prerequisites

Create an assembly containing 1 of these elements:

- A write step
- A log step
- A log-error error handler

Context

Workday Studio's Literal Builder enables you to create simple XML documents that conform to selected schema or SOAP request messages that conform to selected WSDLs. You can append WS-Security headers to SOAP request messages.

Steps

- 1. Add a **text** element to 1 of these assembly elements:
 - A write step
 - A log step
 - A **log-error** error handler
- 2. In the right pane, click **Generate XML literal**.
- 3. In the Literal Builder wizard, select the schema or WSDL element that you want to generate the XML literal for. As you complete the task, consider:

Option	Description
Show Messages	By default, Studio displays WSDL elements as messages. To display them as interface definitions with portTypes, operations, input messages, and output messages, deselect this option.
Wrap SOAP	Wraps the selected XML definition in a SOAP envelope.
Add WS-Security Header	Adds a SOAP Header element to the SOAP request. The SOAP header includes the WS-Security credentials you provide within a UsernameToken element. Only available if you select Wrap SOAP .

Option	Description	
Wrap XSLT	Creates an XML literal wrapped in an XSL stylesheet. You can save the stylesheet as an XSLT file for later use.	
Ask for Choices Selection	Prompts you to select a particular choice from a schema when creating and copying an XML literal or SOAP literal. If you don't select this option, Studio uses the first choice in a particular set.	

Result

Studio displays a preview of the XML literal, which you can edit.

Create XPath Expressions Based on Schema or WSDLs

Prerequisites

Create an assembly containing 1 of these steps:

- java-to-xml
- validate
- xml-to-java

Context

In Workday Studio, the XPath Expression Builder enables you to create XPath expressions based on selected schema or WSDLs.

Steps

- 1. On the Properties view of 1 of these steps, click Build XPath Expression, next to the XPath property:
 - java-to-xml
 - validate
 - · xml-to-java
- **2.** On the lower pane of the **XPath Expression Builder** wizard, select the schema or WSDL element that the XPath expression will match. As you complete the task, consider:

Option	Description	
Show Messages	By default, Studio displays WSDL elements as messages. To display them as interface definitions with portTypes, operations, input messages, and output messages, deselect this option.	
Prefix SOAP	By default, Studio prefixes the XPath expressions you create with this expression, as shown in the upper text pane: env:Envelope/env:Body. To remove the prefix, deselect this option.	

3. If required, you can edit the XPath expression manually in the upper text pane. Example: you might want to use a predicate to filter the nodeset that the XPath returns.

Concept: Workday Studio Message Builder

Workday Studio's **Message Builder** provides a graphical view that simplifies message content definition for these assembly elements:

- The write step
- The log step
- The log-error error handler

The **Message Builder** tab in the Assembly Editor provides a single location where you can define message content for any relevant element in the assembly. **Message Builder** is also available as a tab in the **Properties** view of individual **write**, **log**, and **log-error** elements.

The left **Message Builder** pane enables you to define the message content type. Use the options at the top to add various types of message elements:

Option	Description
Create 'message-content'	Adds the content of the mediation message to the message.
Create 'text'	Adds a string literal to the message. There are 3 options:
	 Enter the text manually, then click Apply changes. Click Insert MVEL Expression, enter MVEL expressions (in combination with plain text, if required), then click Apply. Click Generate XML literal and select the defining schema or WSDL element.
Create 'exception'	Adds an exception to the message if one exists in the mediation context. For use in the log-error error handler only.
Create 'line-separator'	Adds a new-line character to the message.
Create 'xpath'	Adds the result of an XPath expression to the message.
Create 'xslt'	Adds the result of an XSL transformation to the message.
Create 'xml-stream'	Creates the content for the log or write step.
Create 'regex-match'	Applies a regular expression to the message content and adds all matching occurrences to the mediation message.
Create 'static-file'	Specifies an input file that populates the message with its entire contents.
Create 'message-store-id'	Adds the message store ID of the message. Applies only if you set the store-message property for the transport.
Create 'header'	Adds the value of a named message header to the message.
Create 'headers'	Adds complete header sets in the form of name- value header pairs separated by new-line characters.
Create 'customer-id'	Adds the customer ID from the MediationContext to the message. Displays 'null' in the message if the customer ID isn't set.

The right pane is where you define the message element's value. The contents of the value pane vary depending on the message element type.

To reorder or delete message elements, use the buttons on the right of the content pane. Their order in **Message Builder** is mirrored in the XML.

Reference: Message Element Properties

Use the buttons at the top of **Message Builder** to add message elements to **write**, **log**, and **log-error** elements.

Not every message element has properties.

message-content

Property	XML Attribute Name	Description
Limit	limit	A limit on the number of characters the message can contain. The default value of zero indicates no character limit.

exception

Property	XML Attribute Name	Description
Escape XmI	escape-xml	Enables escaping of XML on exceptions in the write step.

xpath

Property	XML Attribute Name	Description
Namespaces	namespaces	Enables you to specify any namespace required by the XPath expression in the format <pre><prefix1> <namespace1> <prefix2> <namespace2>.</namespace2></prefix2></namespace1></prefix1></pre>
XPath	xpath	The XPath expression used to extract a value from the incoming message.
XPath Version	xpath-version	Workday Studio supports XPath versions 1.0 and 2.0. The default value is 2 for assembly versions from Workday 12 onward and 1 for earlier versions.

xslt

Property	XML Attribute Name	Description
Allow Saxon Bytecode Generation		Specifies whether to allow Saxon bytecode generation. The default is false.
Reuse Strategy		Specifies the XSLT transformer reuse strategy:

Property	XML Attribute Name	Description
		default: if you specify the url property using the mctx URL protocol or an MVEL expression, the default behavior is no-reuse. Otherwise, it's transformer-pool. Note: When you set transformer-factory to Saxon, the default behavior is templates.
		 no-reuse: Workday doesn't reuse transformer objects. templates: Workday builds a Templates object, from which it creates fresh transformer objects. These transformers aren't reused. transformer-pool: Workday uses a pool of transformers. Not recommended if the transformer object caches values.
Secure Processing		Specifies whether a transformer performs XSLT standard processing only. Set to true to impose limits on XML constructs. Example: ignore JavaScript or Java extension processing. Set to false to process XML according to the XML specifications.
Transformer Factory		The class name of the TransformerFactory that you want to use. The default is the JAXP factory. There are 3 other options:
		 net.sf.saxon.TransformerFactory: for Saxon. org.apache.xalan.processor.Transfor Xalan.
		net.sf.joost.trax.TransformerFactor for Joost.
Url		The XSLT file location, either a relative path or an absolute URL. Supports MVEL expression templates.
		You can load XSLT directly from the message content using the mctx (mediation context) URL protocol. Example: to load

Property	XML Attribute Name	Description
		an XSLT file contained in an attachment, use mctx:parts/1.

xml-stream

Property	XML Attribute Name	Description
Namespaces	namespaces	Enables you to specify any namespace required by the XPath expression in the format <pre><prefix1> <namespace1> <namespace2>.</namespace2></namespace1></prefix1></pre>
XPath	xpath	The XPath expression to apply to the message when retrieving XML elements. Workday uses Streaming API for XML (StAX) processing. This library reads XML messages and translates them into events, rather than DOM. It doesn't perform any transformations itself.
		The XPath expression is the same simplified XPath subset you use in the xml-stream-splitter strategy. Workday supports qualified or local element names and asterisks. It doesn't support the full XPath standard.
		<pre>Examples: /order/item, / ns:order/ns:order //item, //ns:item, / ns:order/item /*/*, //* /*/*</pre>
XPath Version	xpath-version	Workday Studio supports XPath versions 1.0 and 2.0. The default value is 2 for assembly versions from Workday 12 onward and 1 for earlier versions.
Limit	limit	Constrains the number of XML fragments to match based on the XPath expression. Useful mainly for performance reasons. If you know there's just 1 matching XML fragment, set the limit to 1 to prevent pull-parsing of the document after the result has been retrieved. The default value

Property	XML Attribute Name	Description
		is -1, which means an unlimited result set.

regex-match

Property	XML Attribute Name	Description
Delimiter	delimiter	Specifies a string used to separate 2 or more occurrences. The default value is a single space.
Limit	limit	Specifies the number of occurrences to include in the result set. The default value is zero, which means all occurrences.
Regex	regex	Defines the matching expression.

static-file

Property	XML Attribute Name	Description
Character Encoding	character-encoding	Specifies the character encoding. The default value is UTF-8.
Input File	input-file	Specifies the file.

header

Property	XML Attribute Name	Description
Include Name	include-name	Specifies whether Studio inserts the header name.
Name	name	The header name.
Not Set Value	not-set-value	A string that's emitted if the header isn't found or is empty.

Transport Bindings

Concept: Transport Bindings

Transport bindings are optional child elements that you can configure on out-transports in Studio. Transport bindings enable out-transports to support web services in a specified format.

Example: you can configure a **rest-binding** child element on an **http-out** transport when you want to invoke a RESTful web service.

You can configure transport bindings on these out-transports:

- http-out
- ftp-out
- ftps-out

- sftp-out
- xmpp-out
- custom-out
- email-out

Studio supports these transport bindings:

Transport Binding	Description	Notes
rest-binding	Enables you to invoke RESTful web services using HTTP request methods.	Supports these HTTP methods: GET PUT POST
wsdl-http-binding	Enables you to invoke web services using HTTP request methods and a WSDL file.	Supports these HTTP methods: GET PUT POST
wsdl-soap-binding	Enables you to invoke SOAP-based web services using HTTP request methods.	Supports these HTTP methods: • GET • PUT • POST
		Supports these child elements custom-policy ws-rm ws-security ws-ut

Reference: WSDL-HTTP-Binding Properties

Common Tab

Property	XML Attribute Name	Description
Endpoint Name	endpoint-name	The endpoint from which the wsdl-http-binding element accesses a web service.
Interface Name	interface-name	The portType (or interface) name for the web service.
Service Name	service-name	The name of the web service.
Wsdl File	wsdl-name	The WSDL file that describes the web service.
Serialize Params	serializeParams	Not currently in use.

Reference: WSDL-SOAP-Binding Properties

Common Tab

Property	XML Attribute Name	Description
Endpoint Name	endpoint-name	The endpoint from which the wsdl-soap-binding element accesses a web service.
Interface Name	interface-name	The portType (or interface) name for the web service.
Service Name	service-name	The name of the web service.
Wsdl File	wsdl-name	The WSDL file that describes the web service.
Fault Handling	fault-handling	Specifies the error-handling process of the wsdl-soap-binding element for HTTP 500 response codes. Options are: • ignore • error • abort

WSDL-SOAP-Binding Child Elements

Concept: WSDL-SOAP-Binding Child Elements

The **wsdl-soap-binding** transport binding supports these child elements:

Child Element	Description
custom-policy	Supports a custom web service security policy for an out-transport.
ws-rm	Supports a messaging security policy for an outtransport.
ws-security	Implements a local file containing the web service security policy for SOAP requests on an outtransport.
ws-ut	Enables the Workday integration server to extract, validate, and propagate username and password security credentials on an out-transport for an assembly.

Reference: Custom-Policy Properties

Common Tab

Property	XML Attribute Name	Description
Method	method	The method invoked on your custom security policy.
Spring bean	ref	The custom Spring bean that implements your custom security policy.

Reference: WS-Rm Properties

Common Tab

Property	XML Attribute Name	Description
File	file	The path to the file that describes your messaging security policy configuration.

Reference: WS-Security Properties

Common Tab

Property	XML Attribute Name	Description
File	file	The path to the file that describes your web service security configuration.

Reference: WS-Ut Properties

Common Tab

Property	XML Attribute Name	Description
Username	username	Inserts a username into the security header of outbound SOAP messages in the MediationContext.
Password	password	Inserts a password into the security header of outbound SOAP messages in the MediationContext.
Password Digest Algorithm	password-digest-algorithm	Applies a hashing algorithm to passwords in the security header of outbound SOAP messages in the MediationContext. Options are: • SHA-1
		• SHA-256

Property	XML Attribute Name	Description
		SHA-384SHA-512none
Spring Bean	ref	An optional Spring bean that authenticates username and password values in the security header of outbound SOAP messages in the MediationContext.
Created	created	Creates a timestamp element in the security header of outbound SOAP messages in the MediationContext.
Nonce	nonce	Creates a nonce element in the security header of outbound SOAP messages in the MediationContext.

Schema Explorer

Display WSDL and XSD Files

Context

The **Schema Explorer** view displays WSDL and XSD files in read-only format. You can copy content from these files to your clipboard, enabling you to reuse the data in other text editor views in Studio.

Steps

- 1. Select Window > Show View > Schema Explorer.
- 2. On the Schema Explorer view, click Add WSDL or XSD.
- 3. Select a WSDL or XSD file.
- **4.** On the **Schema Explorer** view, expand the WSDL or XSD file to view its structure.

Result

Studio displays the WSDL or XSD file on the **Schema Explorer** view.

Next Steps

Copy content from the WSDL or XSD file to your clipboard.

Display Workday Web Service WSDLs

Context

The **Schema Explorer** view displays WSDL and XSD files in read-only format. You can copy content from these files to your clipboard, enabling you to reuse the data in other text editor views in Studio.

Steps

- 1. Select Window > Show View > Schema Explorer.
- 2. On the Schema Explorer view, click Add Workday Web Services.
- 3. Select and expand a Workday Web Service.
- 4. Select wsdl.
- 5. On the Schema Explorer view, expand the Workday Web Service WSDL to view its structure.

Result

Studio displays the Workday Web Service WSDL on the **Schema Explorer** view.

Next Steps

Copy content from the Workday Web Service WSDL to your clipboard.

Display Custom RaaS Report Schemas

Context

The **Schema Explorer** view displays WSDL and schema (XSD) files in read-only format. You can copy content from these files to your clipboard, enabling you to reuse the data in other text editor views in Studio.

Steps

- 1. Select Window > Show View > Schema Explorer.
- 2. On the Schema Explorer view, click Add Custom Raas Report Schema.
- 3. On the Add Custom RaaS Report window, consider:

Option	Description
	The Workday environment that contains your custom report.
Report name	The name of your custom report.

- 4. On the **Select Reports** window, select a custom report.
- 5. Click Finish.
- **6.** On the **Schema Explorer** view, expand the custom report schema to view its structure.

Result

Studio displays the custom report schema on the **Schema Explorer** view.

Next Steps

Copy content from the custom report schema to your clipboard.

Concept: Schema Explorer

The **Schema Explorer** view displays WSDL and XSD files in read-only format. You can copy content from these files to your clipboard, enabling you to reuse the data in other text editor views in Studio.

You can filter the contents of the Schema Explorer view by entering keywords in the type filter text field.

By default, the **Schema Explorer** view displays on the top right-hand side of the screen. You can drag and drop the **Schema Explorer** view to your preferred location on the Studio user interface.

MVEL

Concept: MVEL Fundamentals

Syntax

MVEL is an expression language for Java-based applications. Its syntax is similar to Java's but it has some additions that make it more efficient at matching content.

Note:

- MVEL uses Java namespaces and classes, but can't itself declare either.
- Unlike Java, MVEL is dynamically typed, with optional typing.
- MVEL expressions can be single statements or multiline scripts. For multiline scripts, use a semicolon to separate each statement.
- MVEL operates on the principle of last value out. It supports the return keyword but doesn't generally require it.
- MVEL supports operator precedence rules and uses bracketing to control execution order.
- You can enclose MVEL string literals in single or double quotation marks.
- The semicolon is a reserved character in MVEL. You can't use it in expressions. Use (char) 59 instead. Example: props['string']='a;b' throws an error. This code does not:

```
props['string']= (char) 59
props['string_new']='a'props['string']'b'
```

MVEL expressions can include:

- · Boolean expressions
- · Method invocations
- Property expressions
- Variable assignments

An example of a simple MVEL property expression:

```
context.errorMessage
```

It extracts the property errorMessage from the variable or context object context.

MVEL supports all of the usual Java comparison, mathematical, and logical operators. This table summarizes other notable MVEL operators:

Operator	Description	Example
new	Instantiates an object.	new String("foo")
with	Performs multiple operations on a single object instance.	with (value) { name = 'Foo', age = 50, sex = Sex.MALE }
assert	Asserts that a value is true or fails with an AssertionError.	assert foo != null
contains	Determines whether the value on the left contains the value on the right.	var contains "Foo"

Operator	Description	Example
is or instance of	Determines whether the value on the left is a member of the class on the right.	var instanceof String
strsim	Compares strings and returns their similarity expressed as a percentage.	"foobol" strsim "foobar"
soundslike	Performs a soundex comparison between 2 strings.	"foobar" soundslike "fubar"
&	Performs a Bitwise AND operation.	foo & 5
	Performs a Bitwise OR operation.	foo 5
^	Performs a Bitwise XOR operation.	foo ^ 5
+	Overloaded operator for concatenating 2 strings.	"foo" + "bar"
#	Concatenates 2 literals as strings.	8 # 9
in	Inspects objects inside a collection.	(foo in list)
=	Assigns a value to a variable.	var = "foobar"

Value Testing

In Java, the operator == checks whether references point to the same object. In MVEL, however, the comparison operator == checks whether values are equal. The MVEL expression foo == 'bar' is the equivalent of Java's foo.equals("bar").

An example of an MVEL boolean expression:

```
user.name == 'John Smith'
```

It returns true if the name property of the variable or context object user is John Smith.

MVEL employs type coercion. If you compare 2 values of different types, MVEL tries to coerce the value on the right to the type on the left. If that isn't possible, it tries to coerce the value on the left to the type on the right. Example:

```
"123" == 123;
```

This expression returns true because MVEL coerces the value on the right to a string before it performs the comparison.

Lists, Maps, and Arrays

Enclose MVEL lists in square brackets. Separate items with commas. Example:

```
["Paris", "London", "Berlin"]
```

Enclose MVEL maps in square brackets. Separate keys and values with colons. Example:

```
["Foo" : "Bar", "Bar" : "Foo"]
```

Enclose MVEL arrays in braces. Separate items with commas. Example:

```
{"Bill", "Bob", "Ben"}
```

Property Navigation

MVEL provides a single, unified syntax for accessing properties, static fields, lists, maps, and arrays.

In Java, you might access a property from an object using this statement:

```
context.getException().getCause()
```

In MVEL you can access the same property using this expression:

```
context.exception.cause
```

Access lists and arrays in the same manner. Example:

```
parts[2]
```

You access maps in the same way as arrays but can pass any object as the index value. Example:

```
props["foobar"]
```

If a map uses a string as a key, you can treat the map itself as a virtual object. Example:

```
props.foobar
```

MVEL treats strings as arrays for indexing purposes.

This example returns B:

```
foo = "Berlin";
foo[0];
```

Assignment

You can assign variables in an MVEL expression for use within the expression or for extraction at runtime.

Because MVEL is a dynamically typed language, you don't need to specify a type when you declare a new variable. But you can do so.

Both of these examples are valid in MVEL:

```
str = "Some string";
String str = "Some string";
```

When assigning a value to a typed variable, MVEL attempts to perform automatic type conversion. Example:

```
String num = 1;
```

You can cast the value of a dynamically typed variable to another type. Example:

```
String num = 1;
```

Section: Typing and Coercion

MVEL uses dynamic typing, with optional static typing. Native Java objects are statically typed. To interact with them, MVEL must sometimes perform type coercion, which can have implications for performance.

MVEL automatically coerces type to what seems best for the current value. This means you must be careful when working with numbers. Errors can arise in floating point arithmetic because MVEL automatically casts away from infinite precision <code>java.math.BigDecimal</code> to <code>java.lang.Double</code> and <code>java.lang.Long</code>. This can cause problems when the type of the stored value is not what you expect. In general, you should avoid performing noninteger arithmetic with financial values in MVEL.

MVEL's type coercion means you can call Java methods without adjusting inputs. The interpreter or compiler analyzes the types you're passing to the method and determines what coercion is required.

In the event of an array type conflict, MVEL attempts to coerce the entire array to the needed input type.

MVEL performs any necessary coercion on a statically typed variable, provided the assigned value is coercible. If it isn't, an exception occurs.

Concept: MVEL and Studio

In Workday Studio, MVEL enables you to inspect and manipulate message parts and component parameters in your assemblies. You can use MVEL to:

- Extract information from a message.
- · Format numbers and dates.
- Replace specific characters in a string.
- Retrieve integration attributes or launch parameters.

You should avoid using MVEL to manipulate large strings of data. Example: converting messages to strings can create performance and scalability issues.

In an MVEL-capable field, you can press Ctrl+Space to display a content assist popup window.

MVEL expressions can be single statements or multiline scripts. For multiline scripts, use a semicolon to separate each line.

Note: Studio evaluates multiline expressions as a unit, not sequentially.

MVEL-capable fields expand to accommodate new lines. After 6 lines, they stop expanding and become scrollable. Studio applies syntax coloring to MVEL expressions.

MVEL implements operator precedence during execution. You can use brackets to control the execution order of MVEL expressions.

Note: Because they're processed in memory, there's a 1 million character limit on XPath methods such as xpath, xpathB, and xpathF. You will not receive an error if your query exceeds this limit. You should use streaming APIs such as the **write** step's xml-stream element if you need to process large messages.

Reference: Studio Helper Objects

Studio provides a number of helper objects that enable you to access an integration's runtime properties using MVEL. You can use the helper objects to make simple changes to runtime values, or to extract them and pass them to components in the assembly.

Helper Object	Purpose
	Provides access to the MediationContext object - that is, to the dynamic state of the integration at runtime. The MediationContext object links to the current message, mediation properties, mediation variables, and current error information.

Example: This expression retrieves the value of the property myProperty from the MediationContext: context.getProperty('myProperty') Example: This expression retrieves the property someProperty from the MediationContext if the property value is set to someValue: context.getProperty('someProperty') The Document Accessor helper object. Provides access to the list of documents that were attache to the integration event before this integration rar Effectively combines a Get Event Documents we service call with the retrieval of the documents referenced in the web service response. The da helper object has some limitations: It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an integration to use that strategy to retrieve input
Example: This expression retrieves the property someProperty from the MediationContext if the property value is set to someValue: context.getProperty('someProperty') The Document Accessor helper object. Provides access to the list of documents that were attache to the integration event before this integration rar Effectively combines a Get Event Documents we service call with the retrieval of the documents referenced in the web service response. The da helper object has some limitations: It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
someProperty from the MediationContext is the property value is set to someValue: context.getProperty('someProperty') The Document Accessor helper object. Provides access to the list of documents that were attache to the integration event before this integration rar Effectively combines a Get Event Documents we service call with the retrieval of the documents referenced in the web service response. The da helper object has some limitations: It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
The Document Accessor helper object. Provides access to the list of documents that were attache to the integration event before this integration rar Effectively combines a Get Event Documents we service call with the retrieval of the documents referenced in the web service response. The da helper object has some limitations: It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
access to the list of documents that were attache to the integration event before this integration rar Effectively combines a Get Event Documents we service call with the retrieval of the documents referenced in the web service response. The da helper object has some limitations: It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
 It must explicitly include logic to handle cases where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
where an unexpected number of attachments available. It can't access the filetype of the attachment. It can't access the character encoding of the attachment. The doc-iterator router strategy handles unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
unexpected numbers of attachments automatical and it can access both MIME type and character encoding. It's often more appropriate for an
documents, rather than this helper object.
Example: This expression retrieves a document from an integration event with filename eib_transform_output.txt and adds a variable named var1:
<pre>da.toVar('eib_transform_output.txt' 'var1')</pre>
Example: This expression retrieves a document with the given label:
da.getDocsMatching('label')
Provides access to the list of files returned when issuing the LIST request to an ftp, ftps, or sftp server.
Example: This expression retrieves a list of files f a URL:
ftp.list('URL')

Helper Object	Purpose
intsys	Provides convenient and high-performance access to the integration system configuration as returned by the Get Integration Systems web service call.
	Example: This expression retrieves an integration attribute named username:
	<pre>intsys.getAttribute('username')</pre>
	Example: This expression displays as true if an integration service with the given name exists:
	<pre>intsys.isServiceEnabled('name')</pre>
	Note: If you use intsys to access an attribute, you must first define a service on the workday-in transport for the integration system.
lp	Provides access to launch parameters and other information in the integration launch event.
	Example: This expression retrieves the value of a launch parameter with the given name:
	lp.getSimpleData('name')
	Example: This expression displays as true if a parameter with the given label exists:
	<pre>lp.exists('label') == true</pre>
	Note: Before using the lp variable, you need to assign the launch parameters XML to the variable wd.launchparameters.
message	Provides access to the current message and its header information. Use this object to assign new content to the message.
	Example: This expression retrieves the root part of a message as text from the MediationMessage interface:
	message.rootPartAsText
	Example: This expression retrieves MediationContext variables:
	message.variables
mtable	Provides access to the MTableAdapter interface, which defines the operations on an mtable instance.

Helper Object	Purpose
	Example: This expression sets data in an mtable:
	<pre>mtable['my_property'].set(0, 'Data_Column', 'my_test_data')</pre>
parts	Provides access to the individual parts of the current message. Most messages in Workday integrations have a single part, the root part. Use parts[0] to access the root part.
	Example: This expression retrieves the header someHeader from the root part:
	parts[0].getHeader('someHeader')
	Example: This expression implements the xpathB method to evaluate an XPath Boolean expression:
	parts[0].xpathB('/a/b')
props	Provides access to MediationContext properties.
	Example: This expression retrieves the value of the property myProperty from the MediationContext:
	props.myProperty
	Example: This expression retrieves the value of the property bean.property from the MediationContext:
	props['bean.property']
spring	Provides access to the creation and retrieval beans defined in an assembly's Spring configuration.
	Example: This expression retrieves the name attribute of the bean called Fred in the Spring context:
	spring.getBean('fred').name
	Example: This expression accesses the Spring application context:
	spring.parent ApplicationContext
util	A set of utility functions for performing common operations such as escaping values for insertion into XML or creating an HTTPS URL.
	Example: This expression checks whether the current message in the MediationContext is

Helper Object	Purpose
	the last message that the splitter component will generate:
	<pre>props['is.last.record'] = util.isLastMessageInBatch()</pre>
	Some util functions have crucial limitations. Example: the xpathToCommaDelimString function produces a comma-separated list from the string values of the node sequence returned by an XPath expression operating on a given XML string. You can then split and manipulate the comma-separated list using Java string manipulation functions in MVEL. However, the function has these limitations:
	 It only supports XPath 1. It can't produce CSV files since it doesn't correctly escape newlines, commas, and quotation characters. It can't reliably separate data containing commas. Its requirement for XML as a string encourages nonscalable practices such as converting the current context message or variable to a string.
	Note: Workday strongly recommends the use of explicit, versioned, web service requests for stability and backward compatibility. Using MVELUtilHelper.getLatestWWSVersion() in integrations isn't best practice, and can lead to integrations with unexpected failures or results.
vars	Provides access to MediationContext variables. Example: This expression retrieves the length of the variable myVariable:
	vars['myVariable'].length
	Example: This expression retrieves the length of the variable myVariable:
	vars['myVariable'].length
xmldiff	Provides programmatic access to the results of document comparison with the xmldiff component.
	Example: This expression checks whether there are differences between 2 documents:
	<pre>xmldiff.isDifferent() == true</pre>

Helper Object	Purpose
	Example: This expression retrieves a list of differences between 2 documents:
	xmldiff.changes

Reference: Document Accessor Helper Object

Useful Functions

Name	Arguments	Return Value Type	Notes
getData Integer index	Integer index	Source	Retrieves the document at the specified zero-based index. Use in combination with the message.setMessage helper function to populate the current message with the retrieved data in a memory-efficient manner.
			Example: this code populates the current message with a UTF-8 XML message retrieved from the first attachment:
			<pre>message.setMessage(da.ge 'text/xml')</pre>
			Results in an error if there's no integration attachment with the specified index.
	String filename	Source	Retrieves the document with the specified filename. Use in combination with the message.setMessage helper function to populate the current message with the retrieved data in a memory-efficient manner.
			Example: this code populates the current message with a UTF-8 XML message

Name	Arguments	Return Value Type	Notes	
			attachment with the name input.xml:	
			<pre>message.setMessage('text/xml')</pre>	da.getI
			Results in an error if there's no integration attachment with the specified filename.	
getDocumentIndexes	List <string> labels</string>	List <integer></integer>	Returns a Java List of integers giving the indexes of documents tagged with all of the specified labels.	
			Note that if one of the labels is '*' then any label is matched and the function returns all indexes for documents with at least 1 label.	
getDocsMatching	List <string></string>	List <source/>	Retrieves documents tagged with all of the specified labels.	
			Note: Workday stores documents smaller than 100 KB in memory and larger documents on disk. Be aware of runtime memory and disk space limits.	
	String label	Source	Retrieves documents tagged with the specified label.	
			Note: Label here means integration attachment label. Synonymous with document tag.	
	String[] labels	Source	Retrieves documents tagged with all of the labels in the string array.	
getFileName	Integer index	String	Retrieves the filename with the specified index.	
	String label	List <string></string>	Retrieves a Java List of the filenames of all the documents tagged with the specified label.	

Name	Arguments	Return Value Type	Notes
	List <string> labels</string>	List <string></string>	Retrieves a Java List of the filenames of all the documents tagged with the specified labels.
	String label, integer index	String	Retrieves the nth filename of all the documents tagged with the specified label.
			Functionally equivalent to this code:
			da.getFileNames(label)
		In most cases, you must use da.getFileNames(label) to find the number of matching filenames before you can use an index. The only exception is the limited case where you require the first (zero index) value.	
	List <string> labels, integer index</string>	String	Retrieves the nth filename of all the documents tagged with the specified labels.
			Functionally equivalent to this code:
			da.getFileNames(labels
		In most cases, you must use da.getFileNames(labels) to find the number of matching filenames before you can use an index. The only exception is the limited case where you require the first (zero index) value.	
	String[] labels, integer index		Retrieves the nth filename of all the documents tagged with the specified labels.

Name	Arguments	Return Value Type	Notes
			Functionally equivalent to this code:
			da.getFileNames(java.uti
			In most cases, you must use da.getFileNames(labels) to find the number of matching filenames before you can use an index. The only exception is the limited case where you require the first (zero index) value.
nasFile	String filename	Boolean	Determines whether there's an integration attachment with the specified filename.
	String label, String filename	Boolean	Determines whether there's an integration attachment with the specified filename and tagged with the specified label.
	List <string> labels, String filename</string>	Boolean	Determines whether there's an integration attachment with the specified filename and tagged with all of the labels in the list.
sort	String order	None	Sorts the attached documents by filename. Valid order values are: • "FILENAME_ASCENDING" • "FILENAME_DESCENDING" Any attachments with no filename place last.
size	None	Integer	Returns the number of attached documents.
	List <string> labels</string>	Integer	Returns the number of documents tagged with all of the specified labels.
	String label	Integer	Returns the number of documents tagged with the specified label.

Name	Arguments	Return Value Type	Notes
	String[] labels	Integer	Returns the number of documents tagged with all of the labels in the string array.
toVar	Integer index, String var_name	MessageVariable	Retrieves the document at the specified index and places it in a memory-efficient manner into the specified assembly variable. Example: da.toVar(0, 'myInputDocument')
	String filename, String var_name	MessageVariable	Retrieves the document with the specified filename and places it in a memory-efficient manner into the specified assembly variable. Example: da.toVar('WorkerData'nyInputDocument')

Reference: Launch Parameters Helper Object

Useful Properties

Name	Notes
integrationEventWID	Returns the WID for the integration event relating to the current launch of the integration. Useful when making webservice calls such as Get_Event_Documents, Put_Integration_Message, or Put_Integration_Event. Automatically provides a default parameter to the wcc://GetEventDocuments, wcc:// PutIntegrationMessage, and wcc:// PutIntegrationEvent common components.
integrationSystem	Returns the Integration_System_ID for the current integration system. Useful when populating webservice calls for event subscription or field override requests.

Name	Notes
integrationSystemRefWID	Returns the WID for the current integration system. An entirely equivalent alternative to the integrationSystem property.
parentEventWID	Returns the WID for the current launch event's parent event.
sentOn	Returns the date and time of the integration's launch formatted as an ISO-8601 date and time.
sentOnAsDate	Returns the date and time of the integration's launch in the form of a java.util.Date object.

Useful Functions

Note:

Some of these functions specify a launch parameter by its name alone. Others specify both the launch parameter's name and the name of the integration service that provides it. The latter are useful when a launch parameter with the same name exists in multiple integration services configured on the integration system. Most integrations don't need to accommodate launch parameter names that are duplicated across multiple services, so those functions are less frequently required.

Name	Arguments	Return Value Type	Notes
exists	String name	Boolean	Returns true if the named launch parameter has a nonempty value.
	String service_name, String name	Boolean	Returns true if the named launch parameter in the specified integration service has a nonempty value.
			Preferable to the single argument version only when a launch parameter of the same name exists in multiple integration services enabled on the integration system.
getDate	String name	String	Returns the String- formatted date value of the runtime parameter. The format is YYYY-MM- DDZ or YYYY-MM-DD+/- offset.
	String service_name, String name	String	Returns the String- formatted date value of the runtime parameter of the specified service. The format is YYYY-MM- DDZ or YYYY-MM-DD+/- offset.

Name	Arguments	Return Value Type	Notes	
getParameterData	String name	org.w3c.dom.Element	Returns the XML element Integration_Runtime which holds the named launch parameter from the Launch_Integration_ message that's sent to the integration at startup.	_Event
	String service_name, String name	org.w3c.dom.Element	Returns the XML element Integration_Runtime which holds the named launch parameter of the specified service from the Launch_Integration_ message that's sent to the integration at startup.	
getReferenceData	String name, String type	String	Returns the reference ID of the given type for the launch parameter with the specified name. Example: this code returns the employee ID for a launch parameter named Employee: lp.getReferenceDat 'Employee_ID')	a('Employ€
getReferenceDataLis	String name, String type	List <string></string>	Returns a Java List containing zero or more reference IDs from a multi-instance launch parameter.	
	String service_name, String name, String type	List <string></string>	Returns a Java List containing zero or more reference IDs from a multi-instance launch parameter of a specified service.	
getSequencedValue	String name	String	Returns the current value of the sequence generator with the specified name.	
	String service_name, String name	String	Returns the current value of the specifed sequence generator	

Name	Arguments	Return Value Type	Notes
			declared on the specified
			service.

Reference: Util Helper Object

Useful Functions

Name	Arguments	Return Value Type	Notes	
cleanString	String value	String	Used to escape any input characters that must be escaped in XML documents.	
			Example:	
			<pre><value>@{util.clea root/row/ a_value'))}<!-- Value--></value></pre>	nString(pa
getExtForContentTy	⊵eString mimetype	String	Enables an integration to obtain a file extension such as .txt or .xml, based on the specified MIME type.	
getFilenameFromCon	t Satring sponteint i on disposition	String	Extracts a filename from a content-disposition string. Some assembly components such as the document iterator strategy populate the content-disposition message header with filename information. Example: this code returns the value testfile.pdf: util.getFilenameFr filename=testfile	
readFileToVar	String var_name, String filename		Enables nontext files to be read into a variable. This is the only delivered means by which nontext documents can be loaded. Note that the write step's static-file attribute can only load text documents into a message or variable. The file is specified	

Name	Arguments	Return Value Type	Notes
			relative to the WSAR-INF directory.
			Example: this code reads the image file icon-32.png from the WSAR-INF directory into the context variable v1: util.readFileToVar('v1 'icon-32.png')
readFileToVar	String var_name, String filename,String mimetype		Enables nontext files to be read into a variable whose MIME type you specify. This is the only delivered means by which nontext documents can be loaded. Note that the write step's static-file attribute can only load text documents into a message or variable. The file is specified relative to the WSAR-INF directory. Example: this code reads the image file icon-32.png from the WSAR-INF directory into the context variable v1 with the MIME type image/png:
			util.readFileToVar('v1 'icon-32.png', 'image/png')

Reference: Sample Studio MVEL Expressions

Variable	Sample Expression	Description
context	context.getProperty('n	Retrieves the value of the property myProperty from the MediationContext.
	context.getProperty('s	Retrieves the property some Property company some Property company MediationContext if

Variable	Sample Expression	Description
		the property value is set to someValue.
da	<pre>da.toVar('eib_transform_ 'var1')</pre>	Retrieves a document from an hitegration event with filename eib_transform_output.txt and adds a variable named var1.
	da.getDocsMatching('labe	Retrieves a document with the given label.
ec	ec.getAttribute('attribu	Retrieves an attribute name.
	ec.integrationMapLookup('key')	Retrieves an integration map
env	env['cc.hostname']	Retrieves the cc.hostname environment property set as -

Variable	Sample Expression	Description
		Dcc.hostname on the command line.
	env.containsKey('key')	Displays as true if environment properties contain the given key.
ftp	ftp.list('URL')	Retrieves a list of files for a URL.
intsys	intsys.getAttribute('use	Retrieves an integration attribute
	intsys.isServiceEnabled(Displays as true if an integration service with the given name exists.
lp	lp.getSimpleData('name')	Retrieves the value of a launch parameter with the given name.
	<pre>lp.exists('label') == true</pre>	Displays as true if a parameter with the given label exists.
message	message.rootPartAsText	Retrieves the root part of a message as text from the MediationMessage interface.
	message.variables	RetrievesMediationContext variables.
mtable	<pre>mtable['my_property'].set 'Data_Column', 'my_test_data')</pre>	Sets data in an mtable.
	<pre>mtable['my_property'].get 'Data_Column')</pre>	Retrieves data from an mtable.
parts	parts[0].getHeader('some	Retrieves the header
	parts[0].xpathB('/a/b')	Implements the xpathB method to evaluate an XPath Boolean expression.
props	props.myProperty	Retrieves the value of the property myProperty from the MediationContext.
	props['bean.property']	Retrieves the value of the property bean.property from the MediationContext.
spring	spring.getBean('fred').na	Retrieves the name attribute Of the bean called Fred in the Spring context.
	spring.parent ApplicationContext	Accesses the Spring application context.
v Inc. All rights reserved		Workday Proprietary and Co

©2025 Workday, Inc. All rights reserved

Util

Props['is.last.record']

Workday Proprietary and Confidential
Checks whether the

Variable	Sample Expression	Description	
		last message that the splitter component will generate.	
	<ns:message_summary>@{utins:Message_Summary></ns:message_summary>	Implements the cleanstring (props ['is.me function to ensure that an assembly component produces well-formed XML.	ssage.sum
vars	vars['myVariable'].length	Retrieves the length of the variable myVariable.	
	vars['myVariable'].mimeTy	Retrieves the MIME type Passociated with the variable myVariable.	
xmldiff	<pre>xmldiff.isDifferent() == true</pre>	Checks whether there are differences between 2 documents.	
	xmldiff.changes	Retrieves a list of differences between 2 documents.	

Reference: Studio MVEL Auto-Conversion Syntax Samples

Function	Sample Expression	Description
Auto-convert a string to a variable.	<pre>vars['fred'] = '<hello>world</hello>'</pre>	Creates a new variable called fred with the content <hello>world</hello> .
		Use this method to create small messages only. Using expressions to create large strings can lead to poor performance.
		In most cases, you should use the write step to create content for a variable.
Supply content and MIME type information to a variable.	<pre>vars['fred'] = ['Hello World', 'text/plain']</pre>	Creates a new variable called fred with the content Hello World and MIME type text/plain.
		Use this method to create small messages only. Using expressions to create large strings can lead to poor performance.
		In most cases, you should use the write step to create content

Function	Sample Expression	Description
		for a variable and configure the MIME type.
Copy from an attachment to a variable.	<pre>vars['fred'] = parts[1]</pre>	Creates a new variable fred from the first attachment of the current message.
		In most cases, you should use the copy step to take input from an attachment.
Copy from a message to a variable.	vars['fred'] = message	Creates a new variable fred from the entire message.
		In most cases, you should use the copy step to take input from the current message.
Supply content and MIME type information to a variable whose value is an expression.	<pre>vars['fred'] = [23 + 5, 'text/plain']</pre>	Creates a new variable called fred with content 28 and MIME type text/plain.
Create a variable from an XPath fragment in the message root part.	<pre>vars['fred'] = parts[0].xpathF('/ dink/donk')</pre>	Creates a new variable called fred with an XPath fragment from the root part of the current message.
		Use this method to create small messages only. Using XPath expressions to create large strings can lead to poor performance.
Nullify a variable.	<pre>vars['fred'] = null</pre>	Removes the variable called fred.
Assign content to the root part.	<pre>parts[0] = '<hello>world</hello>'</pre>	Assigns the content <hello>world</hello> to the root part.
		Use this method to create small messages only. Using expressions to create large strings can lead to poor performance.
		In most cases, you should use the write step to assign content to an attachment and configure the MIME type.
Assign content to the first attachment.	<pre>parts[1] = ['Hello World', 'text/plain']</pre>	Assigns the content Hello World and MIME type of text/ plain to the first attachment.
		Use this method to create small messages only. Using expressions to create large

Function	Sample Expression	Description
		strings can lead to poor performance.
		In most cases, you should use the write step to assign content to an attachment and configure the MIME type.
Assign content to the root attachment and specify the MIME type.	parts[0] = [23 + 5, 'text/plain']	Assigns root part with content 28 and MIME type text/plain.
Assign content from a variable to the message part.	parts[0] = vars['fred']	Assigns the content of the variable fred to a message part.
		In most cases, you should use the copy step to take input from a variable and assign it to a message part.
Remove the root part.	parts[0] = null	Removes the root part.
Copy an attachment.	parts[2] = parts[1]	Copies the first attachment into a second attachment.
		In most cases, you should use the copy step to take input from one attachment and assign it to another.
Create a new message with the default MIME type.	<pre>context.message = '<hello>world</hello>'</pre>	Creates a new message <hello>world</hello> with a default MIME type of text/xml.
		In most cases, you should use the write step to create a new message.
Create a new message with MIME type of text/plain.	<pre>context.message = ['Hello World', 'text/plain']</pre>	Creates a new message Hello World with a MIME type of text/plain.
		In most cases, you should use the write step to create a new message.
Create a new message from variable content.	<pre>context.message = vars['fred']</pre>	Creates a new message with the same content and MIME type as the variable fred.
		In most cases, you should use the copy step to create a new message from a variable.
Create a new message from the root part of the current message.	<pre>context.message = parts[0]</pre>	Creates a new message from the root part of the current message.

Function	Sample Expression	Description
		In most cases, you should use
		the copy step to create a new
		message from a message part.

Reference: MVEL Methods

Method	Description	Sample Code	Sample Output	
getClass().getName(Retrieves the type of a property or variable.		y java.lang.Boolean	me()
getEndpoint()	Retrieves the endpoint of a RaaS report when using a SOAP request.	@{intsys.reportSer Alias')}	v customreport2/ s <tenant_name>/ <username>/ report_name_in_XML</username></tenant_name>	port _format
getExtrapath()	Retrieves the extra path of a RaaS report.	intsys.reportServi workday-in Report Service Alias>')	c customreport2/ <tenant_name>/ <username>/ <custom report<br="">Name></custom></username></tenant_name>	ur
indexOf()	Retrieves the position of a specific character within an input string.	<pre>props['index.of.se</pre>	llection/4d196113'	lexOf("/")
leftPad()	Adds characters to the beginning of an input string.	org.apache.commons	. 0000001234	ftPad('12
listToCommaDelimStr	i@gniverts a list of array values to a string and separates them with commas.	<pre>props[p.workers]</pre>		workers']
replaceAll()	Replaces all instances of specified characters within an input string.	<pre>props['p.employee.</pre>	i 12345	

Method	Description	Sample Code	Sample Output	
		<pre>props['p.current.i</pre>	d'] .id'].replaceAll('[^	0-9]','')
substring()	Retrieves part of an input string.	<pre>props['p.test.stri</pre>		
toUpperCase()	Converts a string to uppercase.	<pre>props['p.test.stri</pre>	r WORKDAY STUDIO	
URLEncoder ()	Retrieves a string containing only valid URL characters.	<pre>props['p.report.pa</pre>	r Full_Name=Logan %20McNeil er.encode(props['p.r	eport.para

Studio Integration Services

Create Attribute Map Services

Prerequisites

Create an assembly project.

Context

The attribute map service enables you to define attributes and maps for your integration. Attributes are configurable values that define your integration. You can create these types of attributes:

- Simple.
- · Reference.
- Enumeration.

Maps reconcile internal Workday values with the external attribute values defined on your integration. You can create these types of maps:

- Simple.
- · Class Report Field.
- Enumeration.

- **1.** Open the assembly in the Assembly Editor.
- 2. Drag a workday-in transport from the Palette to the Assembly Editor.

- 3. On the Services tab of the Properties view for the workday-in transport, click Create attribute-mapservice.
- 4. On the Service Name window, enter a name for your attribute map service.
- **5.** On the **Integration Attributes** tab, consider:

Option	Description
Name	The name of the attribute. Must be unique across all integration systems.
Туре	The attribute type definition.
Add Simple Type Attribute	Adds an attribute type that uses string literal values.
Add Reference Type Attribute	Adds an attribute type that uses references to Workday Class Report Fields (CRFs) and web services.
Add Enumeration Type Attribute	Select Edit Type to configure the enumeration. You can:
	 Use an Enumeration Reference to an existing enumeration definition in your tenant by entering its Type Name. Create a new enumeration by entering a unique Type Name on the Enumeration Definition tab and specifying the values that it allows. Note: When you enter the Type Name of an
	existing definition on the Enumeration Definition tab, Workday overwrites the definition.

- **6.** On the **Integration Maps** tab, select **Add** to add a map.
- **7.** As you configure the **Internal Type** and **External Type**, consider:

Option	Description
Simple Type	You can select these simple types: • Boolean • Date • Datetime • Number • Text
Class Report Field	Select Browse for CRF.
Enumeration	Configure your Enumeration Reference or Enumeration Definition.

Result

Studio saves the attribute map service on the **workday-in** transport of your integration.

Next Steps

Deploy your integration.

Related Information

Concepts

Concept: Enumerations

Tasks

Deploy Integrations to Workday on page 295
Set Up Attributes and Maps in Benefits Integration

Create Delivery Services

Prerequisites

Create an assembly project.

Context

The delivery service enables you to deliver documents to a target endpoint from your Workday tenant.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- **4.** In the Assembly Editor, click the **workday-in** transport.
- 5. On the **Services** tab of the **Properties** view for the **workday-in** transport, click **Create delivery-service**.
- **6.** On the **Service Name** window, enter a name for your delivery service.
- 7. Click Save.

Result

Studio saves the delivery service on the workday-in transport of your integration.

Next Steps

Deploy your integration and configure the delivery service on your integration system in Workday.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Set Up Integration Delivery

Create Listener Services

Prerequisites

Create an assembly project.

Context

The listener service enables your integration to receive launch messages from third-party clients through your Workday tenant.

Steps

1. Open the assembly in the Assembly Editor.

- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- On the Services tab of the Properties view for the workday-in transport, click Create listenerservice.
- **6.** On the **Service Name** window, enter a name for your listener service.
- 7. Click Save.

Result

Studio saves the listener service on the **workday-in** transport of your integration.

Next Steps

Deploy your integration and configure the listener service for your integration system in Workday.

Note: You can only deploy integrations that use listener services if they have no launch parameters.

Related Information

Concepts

Concept: Listener Service API

Tasks

Deploy Integrations to Workday on page 295

Create Retrieval Services

Prerequisites

Create an assembly project.

Context

The retrieval service enables your integration to retrieve documents from remote clients and store them in your Workday tenant.

Steps

- **1.** Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- **4.** In the Assembly Editor, click the **workday-in** transport.
- 5. On the **Services** tab of the **Properties** view for the **workday-in** transport, click **Create retrieval-service**.
- 6. On the Service Name window, enter a name for your retrieval service.
- 7. Click Save.

Result

Studio saves the retrieval service on the workday-in transport of your integration.

Next Steps

Deploy your integration and configure the retrieval service on your integration system in Workday.

Related Information Tasks

Deploy Integrations to Workday on page 295 Set Up Integration Retrieval

Create Sequence Generator Services

Prerequisites

Create an assembly project.

Context

The sequence generator service enables you to generate unique, sequenced filenames for documents each time you run your integration. In Studio, you configure the sequence generator service on a **workday-in** transport. Before you can launch your integration, you must also configure the sequence generator service in your Workday tenant.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. In the Assembly Editor, click the workday-in transport.
- 3. On the Services tab of the Properties view for the workday-in transport, click Create sequence-generator-service.
- 4. On the Service Name window, enter a name for your sequence generator service.
- 5. On the Properties view for the sequence generator service, click Add to add a sequencer.
- **6.** On the **Sequencer** field, enter a name for your sequencer.
- 7. On the Project Explorer view, right-click your assembly project and select Deploy to Workday.
- **8.** On the **Cloud Explorer** view, navigate to your deployed assembly project.
- 9. Right-click the integration node of your deployed assembly project.
- 10. Select Workday: Integration System.
- 11.On the Workday tab, consider:

Option	Description
	The username credentials for your Workday tenant.
Password	The password credentials for your tenant.

- **12.**In your Workday tenant, on the **Integration Services** column of the **Custom Integration Services** section, locate the name of your sequence generator service and select **Related Actions and Preview**.
- 13. Select Integration Sequence Generator Service > Configure Integration Sequence Generators.
- **14.**In the **Increment Sequence ID By** field, enter the value 1.
- **15.**In the **Sequence ID Format** field, enter the value file[Seq].csv.
- 16.Click OK.
- 17.Click Done.

Result

Studio saves the sequence generator service on the **workday-in** transport of your integration. Workday saves your sequence generator settings on your integration system.

Next Steps

Launch your integration.

Related Information

Tasks

Launch Integrations from Studio on page 301 Set Up Integration Sequence Generators

Create Transaction Log Services

Prerequisites

Create an assembly project.

Context

The transaction log service enables you to display the logs for transaction events that your integration has subscribed to in your Workday tenant.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- 5. On the Services tab of the Properties view for the workday-in transport, click Create transaction-log-service.
- 6. On the Service Name window, enter a name for your transaction log service.
- 7. Click Save.

Result

Studio saves the transaction log service on the workday-in transport of your integration.

Next Steps

Deploy your integration and configure the transaction log service on your integration system in Workday.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Steps: Set Up Directory Service Integration

Create Report Services

Prerequisites

Create an assembly project.

Context

The report service specifies aliases for any custom reports that you refer to in your integration.

Steps

1. Open the assembly in the Assembly Editor.

- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- 5. On the Services tab of the Properties view for the workday-in transport, click Create report-service.
- **6.** On the **Service Name** window, enter a name for your report service.
- 7. On the Properties view for the report service, click Add New Entry to add a new alias. As you complete the task, consider:

Option	Description
Alias	The alias of your custom report.
Description	A text description of your custom report.
Report Reference	The name of your custom report as it displays in your Workday tenant.

8. Click Select a RaaS Report. As you complete the task, consider:

Option	Description
	The Workday environment that contains your custom report.
Report name	The name of your custom report.

- 9. Click Next.
- 10. Select your custom report.
- 11.Click Finish.
- 12.Click Save.

Result

Studio saves the report service on the **workday-in** transport of your integration.

Next Steps

Deploy your integration and configure the report service for your integration system in Workday.

Related Information

Concepts

Concept: Custom Reports

Tasks

Deploy Integrations to Workday on page 295

Create Custom Object Services

Prerequisites

Create an assembly project.

Context

The custom object service specifies aliases for any custom objects that you refer to in your integration.

- 1. Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.

- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- On the Services tab of the Properties view for the workday-in transport, click Create custom-objectservice.
- **6.** On the **Service Name** window, enter a name for your custom object service.
- 7. On the **Properties** view for the custom object service, click **Add New Entry** to add a new alias. As you complete the task, consider:

Option	Description
Alias	The alias of your custom object.
Description	A text description of your custom object.
Custom Object Reference	The name of your custom object as it displays in your Workday tenant.

- 8. Click Select a Custom Object.
- On the Select Custom Object window, specify your Workday tenant environment and browse to your custom object.

10.Click OK.

11.Click Save.

Result

Studio saves the custom object service on the workday-in transport of your integration.

Next Steps

Deploy your integration and configure the custom object service on your integration system in Workday.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Set Up Integration Custom Objects

Create Data Initialization Services

Prerequisites

Create an assembly project.

Context

The Data Initialization Service enables you to gain faster and more efficient access to Workday data in your Studio integrations.

- 1. Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- 5. On the **Services** tab of the **Properties** view for the **workday-in** transport, click **Create data-initialization-service**.
- **6.** On the **Service Name** window, enter a name for your data initialization service.

7. Click Save.

Result

Studio saves the data initialization service on the workday-in transport of your integration.

Next Steps

Deploy your integration and configure the data initialization service for your integration system in Workday.

Create Service References

Prerequisites

Create an assembly project.

Context

Service references enable you to reference any integration service configured on another **workday-in** transport within the same collection.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. On the Palette, expand the In Transports tab.
- 3. Drag a workday-in transport from the Palette to the Assembly Editor.
- 4. In the Assembly Editor, click the workday-in transport.
- On the Services tab of the Properties view for the workday-in transport, click Create servicereference.
- **6.** On the **Service Reference** window, select a service reference.
- 7. Click OK.
- 8. Click Save.

Result

Studio saves the service reference on the workday-in transport of your integration.

Next Steps

Deploy your integration.

Related Information

Tasks

Deploy Integrations to Workday on page 295

Add References to Custom Reports on Workday-Out-Rest Transports

Prerequisites

Create an assembly project that contains a workday-out-rest transport.

Context

The **workday-out-rest** transport enables you to send REST request messages to an HTTP URL. You can add a reference to a custom report as an extra path value on a **workday-out-rest** transport.

Steps

- 1. Open the assembly in the Assembly Editor.
- 2. In the Assembly Editor, click the workday-out-rest transport.
- On the Common tab of the Properties view for the workday-out-rest transport, click Select a RaaS Report.
- 4. On the Add Custom RaaS Report window, consider:

Option	Description
	The Workday environment that contains your custom report.
Report name	The name of your custom report.

- **5.** On the **Select Reports** window, select your custom report.
- 6. On the Report Service Configuration window, consider:

Option	Description
Report Alias	The alias of your custom report.
Description	A text description of your custom report.

7. Click Finish.

Result

Studio adds a reference to your custom report on the workday-out-rest transport of your integration.

Next Steps

Launch your integration.

Related Information

Tasks

Launch Integrations from Studio on page 301

Add References to Custom Objects on Workday-Out-Rest Transports

Prerequisites

Create an assembly project that contains a workday-out-rest transport.

Context

The **workday-out-rest** transport enables you to send REST request messages to an HTTP URL. You can add a reference to a custom object as an extra path value on a **workday-out-rest** transport.

- 1. Open the assembly in the Assembly Editor.
- 2. In the Assembly Editor, click the workday-out-rest transport.
- On the Common tab of the Properties view for the workday-out-rest transport, click Select a Custom Object.
- 4. On the Add Custom Object window, consider:

Option	Description
	The Workday environment that contains your custom object.

Option	Description
HTTP Methods	Options are:
	POSTPUTGETDELETE

5. On the Select Custom Object window, consider:

Option	Description
Select an existing custom object alias	Displays a list of existing custom object aliases.
Create a new custom object alias	Enables you to create a new custom object alias.

Skip to step 7 if you selected the **PUT**, **GET**, or **DELETE** HTTP methods.

6. If you selected the **POST** HTTP method, Studio displays the **POST Query Parameters** window. As you complete the task, consider:

Option	Description
updatelfExists	Updates an existing custom object.
bulk	Creates or updates a collection of custom objects.

- 7. If you selected the PUT, GET, or DELETE HTTP methods, select a custom object id reference from the Custom Object Id Reference Selection window.
- 8. Click Finish.

Result

Studio adds a reference to your custom object on the workday-out-rest transport of your integration.

Next Steps

Launch your integration.

Related Information

Tasks

Launch Integrations from Studio on page 301

CLAR Files

Generate Manifest Files

Context

Manifest files enable you to export assembly collections as CLAR files. You must save manifest files to a project folder in an assembly collection. Manifest files contain the metadata of your assembly collections.

- 1. On the Studio menu bar, select Workday > Solution > Generate Workday Manifest.
- 2. Double-click the target project folder for the manifest file.

Result

Studio saves the manifest file to the project folder.

Next Steps

Export the assembly collection as a CLAR file.

Import CLAR Files

Prerequisites

Save a CLAR file to your file system.

Context

You can add assemblies to your workspace by importing CLAR files.

Steps

- 1. On the Studio menu bar, select File > Import....
- Select the CLAR file import wizard.
- 3. Click Browse and select a CLAR file to import.
- 4. Click **Next** to display the collections and projects in the CLAR file.
- 5. Select collections and projects to import from the CLAR file.

Studio automatically selects every collection and project in the CLAR file. Modify your selection using the check boxes. Studio displays decorators on collections and projects with name conflicts.

- 6. Edit all project name conflicts.
 - a) Select a project with a name conflict.
 - b) Click Edit....
 - c) In the **Project Name** field, rename the project.
- 7. Edit all collection name conflicts.
 - a) Select a collection with a name conflict.
 - b) Click Edit
 - c) In the **Collection Name** field, rename the collection.
- 8. Click Finish.

Result

Studio imports the contents of the CLAR file to your workspace.

Export CLAR Files

Prerequisites

- · Create an assembly project.
- · Generate a manifest file.

Context

You can export assemblies from your workspace as CLAR files. You can use CLAR files to share your assemblies with other Studio integration developers. Example: by uploading them to the Contributed Solutions page on Workday Community.

Steps

- 1. On the Studio menu bar, select File > Export....
- Select the CLAR file export wizard.
- 3. On the CLAR File Specification window, select a collection to export as a CLAR file.
- 4. On the Workday Manifest Specification window, select Use existing manifest from collection.
- 5. On the Export Destination window, specify the target destination of the CLAR file.
- 6. Click Finish.

Result

Studio exports the assemblies as a CLAR file.

Related Information Reference

All Contributed Solutions

Concept: CLAR Files

CLAR Files

A CLAR (Cloud Archive) file is a package file that stores assembly collections, projects, and metadata. CLAR files enable you to import and export assemblies through your workspace. You can use CLAR files to share your assemblies with other Studio integration developers.

Manifest Files

Manifest files enable you to export assembly collections as CLAR files. You must save manifest files to a project folder in an assembly collection. Manifest files contain the metadata of your assembly collections.

Contributed Solutions

The Contributed Solutions page is an online repository that enables you to access and share CLAR files. You can access the Contributed Solutions page on Workday Community.

JAXB Projects

Create JAXB Projects

Prerequisites

Save an XML schema file to your file system.

Context

JAXB is a binding framework that enables you to convert data between XML and Java formats. In Studio, you can convert XML schema files into Java classes by creating a JAXB project. Once you create a JAXB project, you can implement its Java classes in an integration by adding it as a dependency in an assembly project.

Steps

1. Select File > New > Workday Schema to Java (JAXB) Project.

2. On the Project Configuration Details window, consider:

Option	Description
Project name	The name of your project.
Target runtime	The target runtime server for your project. Automatically populates as Workday Runtime.
Configuration	The facet configuration of your project. Automatically populates as Workday Schema to Java (JAXB) Project.

3. On the Source Folders window, consider:

Option	Description
Generation directory	The directory folder for your JAXB generated Java classes. Automatically populates as <i>jaxb-gen</i> .
Mark generated resources as derived	Marks your JAXB generated Java classes as derived resources. Studio automatically selects this check box.

4. On the JAXB Schema Selection and Generation Settings window, consider:

Option	Description
Schema Files	The location of your XML schema files. Studio displays these options:
	WorkspaceExternalURL
JAXB External Binding Files (optional)	The location of any binding files for your XML schemas. Studio displays these options:
	Workspace External
Generate default binding file for unmapped schemas	Creates generic binding files for your XML schemas.
Location within Project	The directory folder for generic binding files. Automatically populates as jaxb-resources/bindings.xjb.
Choose how to manage Schema and External JAXB Binding files	Select Create links in the project to external Schema/Binding files to create links to your schema and binding files in your new JAXB project. Studio automatically selects this option.
	Select Copy Schema/Binding files to project now to copy your schema and binding files into your new JAXB project.
Compiler Options	Studio displays these options:
	 Specify target package (overrides all other package definitions) Apply less strict validation to schemas Suppress package level annotations Automatic name conflict resolution

5. Click Finish.

Result

Studio displays the JAXB project on the **Project Explorer** view.

Next Steps

Add the JAXB project as a dependency in an assembly project.

Add JAXB Projects as Dependencies in Assembly Projects

Prerequisites

- · Create an assembly project.
- Create a JAXB project.

Context

JAXB is a binding framework that enables you to convert data between XML and Java formats. In Studio, you can implement JAXB Java classes in your integrations by adding JAXB projects as dependencies in assembly projects.

Steps

- 1. On the **Project Explorer** view, right-click an assembly project.
- 2. Select Build Path > Configure Build Path....
- 3. On the Java Build Path window, select the Projects tab.
- 4. Click Add....
- **5.** Select a JAXB project to add to your assembly project.
- 6. Click OK.
- 7. Click Apply and Close.

Result

Studio adds the JAXB project as a dependency in the assembly project. You can now implement your JAXB Java classes in integrations stored within that assembly project.

Next Steps

Deploy your integration.

Concept: JAXB Support in Studio

JAXB is a binding framework that enables you to convert data between XML and Java formats.

JAXB Projects

In Studio, you can convert XML schema files into Java classes by creating a JAXB project. Once you create a JAXB project, you can implement its Java classes in an integration by adding it as a dependency in an assembly project.

JAXB Mediation Steps

In your assembly projects, you can invoke JAXB on the **Properties** view of these mediation steps:

java-to-xml

xml-to-java

Studio Ivy Plugin

Configure the Ivy Plugin

Context

Workday Studio supports an Apache Ivy[™] plugin that enables you to manage project dependencies. You can configure the Ivy plugin as a preference in Studio.

Steps

- 1. Click Window > Preferences > Workday > Ivy.
- 2. On the Configure Ivy Engine window, consider:

Option	Description
Ivy settings URL	The URL for your ivysettings.xml file.
Ivy Properties	The URL to your ivyproperties.xml file.
Load ivy.properties file from home directory if present	Loads the ivy.properties file automatically from your home directory.

Result

Studio applies your Ivy plugin preferences to your assembly projects.

Add Workday Ivy Natures on Workday Studio Projects

Prerequisites

- Configure the Apache Ivy[™] plugin for Workday Studio.
- Create an assembly project.

Context

Workday Studio supports an Apache Ivy plugin, which enables you to manage project dependencies by configuring projects with the Workday Ivy nature.

- 1. On the **Project Explorer** view, right-click an assembly project.
- 2. Select Configure > Add Workday Ivy Nature.
- **3.** Expand the assembly project folder.
- 4. Open the ivy.xml file.
- 5. Expand the info node. As you complete the task, consider:

Option	Description
Module	The module name.
Add your content here	Insert a parent <dependencies> element, enclosing one or more child <dependency> elements.</dependency></dependencies>

Result

Studio adds a Workday Ivy nature to the project.

Resolve Dependencies for Projects with Ivy Definitions

Prerequisites

- Configure the Apache Ivy[™] plugin for Workday Studio.
- · Configure an assembly project with the Workday Ivy nature.

Context

Workday Studio supports an Apache Ivy plugin, which enables you to manage project dependencies by configuring projects with the Workday Ivy nature. If your project displays a build error relating to missing dependencies, you can resolve these dependency issues.

Steps

- 1. On the Project Explorer view, right-click an assembly project with the Workday Ivy nature.
- 2. Select Resolve.

Result

The **Console** view displays a resolution report.

Add Dependent JARs to Projects with Ivy Natures

Prerequisites

- Configure the Apache Ivy[™] plugin for Workday Studio.
- · Configure an assembly project with the Workday Ivy nature.

Context

Workday Studio supports an Apache Ivy plugin, which enables you to manage project dependencies by configuring projects with the Workday Ivy nature. If a Studio project has an Ivy nature with dependency elements in its ivy.xml file, you can configure the project to include any dependent JAR files.

Steps

- 1. On the Project Explorer view, right-click an assembly project with the Workday Ivy nature.
- 2. Select Properties.
- 3. On the Java Build Path window, click Libraries.
- 4. Click Ivy-Workday IDE.
- 5. Click Add JARs.
- 6. On the JAR Selection window, select the JAR files to add to your project and click OK.
- 7. On the Java Build Path window, click Apply and Close.

Result

Studio adds the dependent JAR files to your project.

Next Steps

Deploy your project.

Prerequisites

- Configure the Apache Ivy[™] plugin for Workday Studio.
- Configure an assembly project with the Workday Ivy nature.

Context

Workday Studio supports an Apache Ivy plugin, which enables you to manage project dependencies by configuring projects with the Workday Ivy nature. You can add and remove the Workday Ivy nature from projects as required.

Steps

- 1. On the **Project Explorer** view, select an assembly project folder.
- 2. Select Workday > Ivy > Remove Workday Ivy Nature.

Result

Studio removes the Workday Ivy nature from your project.

Next Steps

Deploy your project.

Integration Deployment

Add a Connection

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Click Add....
- 3. On the Add Connection window, consider:

Option	Description
Name	The name of the connection.
URL	The URL of the connection.
Group	Adds the connection to a group.

Note: To use OAuth 2.0 authorization, you must first register an API client. Users of that client who are enrolled in Workday multifactor authentication are required to use a second authentication method when connecting to Workday from Studio.

Option	Description
Basic Auth	Specify the Username and Password for the connection.
OAuth 2.0	 Specify these details for the connection: Grant Type Client ID Authorization Endpoint Token Endpoint Access Token

5. Click Test Connection.

Studio confirms whether it can access the connection.

Result

The connection displays on the **Connections** preferences page.

Next Steps

Build an assembly.

Related Information

Tasks

Enable Multifactor Authentication in Workday Studio on page 298

Add a Group of Connections

Context

In Studio, you can create and manage connections to Workday. You can organize these connections into groups. You can use these connections when you deploy and launch assemblies.

Steps

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Click Add Group....
- 3. On the Add Group window, consider:

Option	Description
Name	The name of the connection group.
	Filters the connection group out of the Cloud Explorer view and the Deploy to Workday page.

Result

The connection group displays on the **Connections** preferences page.

Build an assembly.

Edit a Connection

Prerequisites

Add a connection to Workday.

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

Steps

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Select a connection.
- 3. Click Edit Environment URL. As you complete the task, consider:

Option	Description
Host	The host id of the connection.
URL	The URL of the connection.

Result

The connection displays on the **Connections** preferences page.

Next Steps

Build an assembly.

Edit a Group of Connections

Prerequisites

Create a group of connections to Workday.

Context

In Studio, you can create and manage connections to Workday. You can organize these connections into groups. You can use these connections when you deploy and launch assemblies.

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Select a connection group.
- 3. As you complete the task, consider:

Option	Description
Name	The name of the connection group.

Option	Description
	Filters the connection group out of the Cloud Explorer view and the Deploy to Workday page.

Result

The connection group displays on the **Connections** preferences page.

Next Steps

Build an assembly.

Remove Connections

Prerequisites

Add a connection to Workday.

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

Steps

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Select a connection.
- 3. Click Remove....

Result

Studio removes the connection from the **Connections** preferences page.

Next Steps

Build an assembly.

Import Connections

Prerequisites

Access an XML file containing Workday connection details.

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Click Import....
- 3. Click Browse....

4. Select a Workday connection XML file.

Result

Studio displays the connection on the **Connections** preferences page.

Next Steps

Build an assembly.

Export Connections

Prerequisites

Add a connection to Workday.

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

Steps

- 1. Select Windows > Preferences > Workday > Connections.
- 2. Click Export....
- 3. Select a connection.
- 4. Click Browse...
- 5. Select a target destination for the Workday connection XML file.

Result

Studio exports the connection to the target destination.

Next Steps

Build an assembly.

Connect to Workday

Prerequisites

Add a connection to Workday.

Context

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

Steps

1. From the Studio **Preferences** menu, select **Workday** > **Connections**.

Option	Description
Tenant	Specify the name of your tenant.
Username	Enter the username credentials for your tenant.
Password	Enter the password credentials for your tenant.

3. Click Test Connection.

Studio confirms whether it can access your tenant.

4. Click Apply and Close.

Result

Studio connects to your Workday tenant.

Next Steps

Deploy an assembly to Workday.

Deploy Integrations to Workday

Prerequisites

- Create an assembly project.
- Security: Integration Build and Integration Configure domains in the Integration functional area.

Context

In Studio, you can deploy your integrations to Workday. Once you deploy an integration, you can launch it in your Workday tenant.

Steps

- 1. On the Project Explorer view, right-click an assembly project.
- 2. Select Deploy to Workday.
- 3. On the **Deploy to Workday** window, consider:

Option	Description
	Select a target Workday environment for deploying your integration.
Collection being deployed	Select a collection to deploy to Workday.

4. Click Finish.

Result

Studio deploys your integration to Workday.

Next Steps

Launch your integration.

Prerequisites

- Deploy an integration to Workday.
- · Security: Integration Build and Integration Configure domains in the Integration functional area.

Context

In Studio, you can deploy your integrations to Workday. You can view your deployed integrations when you sign in to your Workday tenant.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Workday: Integration System.
- 5. On the Workday tab, sign in to your Workday tenant. As you complete the task, consider:

Option	Description
	Enter the username credentials for your Workday tenant.
Password	Enter the password credentials for your tenant.

Result

Your deployed integration displays on the **Workday** tab in Studio.

Next Steps

Launch your integration.

Configure Studio to Use a HTTPS Proxy Server

Context

If you need to connect Workday Studio to a training or test environment on a port other than 443 and your organization's firewall doesn't allow that by default, you might be able to connect using a proxy server in your network.

Steps

- Select Windows > Preferences > General > Network Connections.
- 2. From the **Active Provider** drop-down menu, select *Manual*.

Note: When you select *Manual*, the checkboxes for all 3 **Schemas** in the **Proxy entries** table, HTTP, HTTPS, and SOCKS, are selected. You can't clear these selections individually.

- 3. Next to the HTTPS Schema, enter a Host IP address and a Port number for the proxy server.
- 4. Click Apply and Close.

In Studio, you can create and manage connections to Workday. You can use these connections when you deploy and launch assemblies.

Note: All connection names must be unique. Studio provides **Sandbox** and **Production** as default connections. You can't rename these connections. For security reasons, Studio doesn't save username and password details to your workspace after you exit from your Studio session.

Concept: Cloud Explorer

The **Cloud Explorer** view displays your cloud server connections. You can expand each cloud server node to view its collections. You can expand each collection node to view integrations available for launch.

Note: The Cloud Explorer view displays a maximum of 999 collections.

The Cloud Explorer view uses the same date formatting settings as your local operating system.

Reference: Connection Errors

Connection Error	Notes
Your user login credentials failed to authenticate.	Check your credentials, then try again. Remember that tenant names are case-sensitive.
Your tenant is not available.	Use a web browser to check that your tenant is online. Enter the tenant URL in the form:
	https://host-name/tenant-name/ccx/cc-cloud-repo/collections
	Example:
	https://wd5.myworkday.com/gms/ccx/cc-cloud-repo/collections
	Use the same credentials you're trying to use in Studio but combine your user and tenant names with an @ character. Example:
	lmcneil@gms
	If the connection succeeds, the browser displays all Studio integration collections that are deployed in your tenant. Next, check your browser's connection preferences to see whether it's making a direct connection or going through a proxy server. If it's configured to use a proxy server, then you'll need to configure Studio to also use that proxy.
Permission to deploy denied.	To deploy integrations to Workday, you must be a member of a security group with <i>Modify</i> permissions in the <i>Integration Build</i> domain. Contact your Workday System Administrator.

Multifactor Authentication in Workday Studio

Enable Multifactor Authentication in Workday Studio

Context

You can configure Workday Studio to use OAuth 2.0 authorization when it connects to a tenant. To do so, you must register an API client. Users of the client who are enrolled in Workday multifactor authentication in a tenant are required to use a second authentication method when connecting to that tenant from Studio. They can't use basic authentication.

1. Set up multifactor authentication in your tenant and specify which accounts are required to use it.

See Steps: Set Up Multifactor Authentication Using Authenticator App.

See Steps: Set Up Multifactor Authentication Using Duo Security.

See Steps: Set Up Multifactor Authentication Using Emailed One-Time Passcode.

See Steps: Set Up Multifactor Authentication Using SMS One-Time Passcode.

2. Register an OAuth 2.0-enabled API client.

Configure these settings:

Option	Value
Client Grant Type	Authorization Grant Code
Support Proof Key for Code Exchange (PKCE)	Enabled
Access Token Type	Bearer
Redirection URI	Enter a valid HTTPS URL.
Scope	In the Custom Objects list, select the functional area for every web service that you'll access.
	In addition select these functional areas:
	ImplementationIntegrationSystemTenant Non-Configurable
	Note: Authentication fails if you omit any relevant web service.
Include Workday Owned Scope	Enabled

Note: Don't select the **Enforce 60 Minute Access Token Expiry** check box. Doing so disables OAuth 2.0 authentication after that period. OAuth 2.0 authentication is also subject to the normal Workday session timeouts configured tenant-wide or for individual accounts.

See Register API Clients.

- **3.** Copy the **Client ID**, **Authorization Endpoint**, and **Token Endpoint** provided by the Register API Client task.
- 4. From the Workday Studio Preferences menu, navigate to Workday > Connections.
- 5. Add a tenant connection and select the OAuth 2.0 credentials tab.
- 6. Paste in the Client ID, Authorization Endpoint, and Token Endpoint.
- 7. Click Get Access Token.

If you receive an Internal Server Error message, the most likely cause is an incorrect Client ID.

8. Enter a username and password for the tenant.

If you're enrolled in Workday Multifactor Authentication, you're prompted to provide a second authentication method.

9. Test the connection.

10.Click Apply and Close.

Related Information Reference

2021R2 What's New Post: Multifactor Authentication in Workday Studio

Integration Configuration

Assign an Integration System User Account to an Integration

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Security domain in the Integration functional area.

Context

Workday Studio integrations require an integration system user (ISU) account for authentication and web service calls.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Assign Integration System User.
- 5. Click Integration System Users.
- **6.** Select an ISU from the right window pane.

Result

You can launch your integration as an ISU.

Next Steps

Launch your integration.

Concept: Integration System Security

In Workday, you can join security groups that enable you to perform specific tasks in your tenant. In Studio, when you connect to your Workday tenant, the **Test Connections** window displays 3 security groups:

- Deploy
- Launch
- Business Process

As a minimum, Studio requires you to be a member of at least 1 of these security groups before you can run an integration.

Related Information Concepts

Concept: Configurable Security

Integration Launching

Launch Integrations from Studio

Prerequisites

- · Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Studio enables you to launch integrations in your Workday tenant.

Steps

- 1. On the **Cloud Explorer** view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.

Result

Your integration launches in your Workday tenant. In Studio, the **Process Monitor** tab displays the status of your integration.

Related Information

Tasks

Deploy Integrations to Workday on page 295

Copy Launch URLs

Prerequisites

Deploy an integration to Workday.

Context

Studio enables you to copy the launch URLs of integrations in your Workday tenant. You can use these URLs to launch integrations from third-party REST-based clients with basic authentication privileges.

- 1. On the **Cloud Explorer** view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Copy Launch URL.
- 5. On the Launch URL window, highlight the launch URL and press Ctrl + C.

Result

Studio copies the launch URL of your integration to your clipboard.

Next Steps

Use the launch URL in REST requests from third-party REST-based clients with basic authentication privileges.

Related Information

Tasks

Deploy Integrations to Workday on page 295

Create Launch Configurations

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Studio enables you to launch integrations in your Workday tenant. You can create launch configurations for your integrations.

Steps

- 1. Select Run > Run Configurations.
- 2. On the left navigation pane, right-click Integration.
- 3. Click New.
- 4. On the right navigation pane, consider:

Option	Description
Name	The name of your launch configuration.
Launch In	The target Workday environment for launching your integration.
Collection	The collection to launch in your integration.
Project	The project to launch in your integration.
Workday-In	The name of the Workday-In transport in your integration.
Launch Parameters	The launch parameters of your integration.

- 5. Click Apply.
- 6. Click Run.

Result

Studio runs your integration with your new launch configuration details.

Related Information

Tasks

Deploy Integrations to Workday on page 295

Edit Launch Configurations

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Studio enables you to launch integrations in your Workday tenant. You can edit the launch configurations of your integrations.

Steps

- Select Run > Run Configurations.
- 2. On the left navigation pane, expand the **Integration** node.
- 3. Select a launch configuration node.
- **4.** On the right navigation pane, consider:

Option	Description
Name	The name of your launch configuration.
Launch In	The target Workday environment for launching your integration.
Collection	The collection to launch in your integration.
Project	The project to launch in your integration.
Workday-In	The name of the Workday-In transport in your integration.
Launch Parameters	The launch parameters of your integration.

- 5. Click Apply.
- 6. Click Run.

Result

Studio runs your integration with your new launch configuration details.

Related Information

Tasks

Deploy Integrations to Workday on page 295

Integration Monitoring and Troubleshooting

Process Monitor

Concept: Integration Event IDs

Workday assigns an ID to all integration events, enabling you to track integration events from launch to completion. When you launch an integration from Workday Studio, the integration event ID displays on the Id column of the Process Monitor view.

Reference: Process Monitor Toolbar Buttons

Button	Description
Refresh	Refreshes the Process Monitor view.
Delete the Process	Deletes a process from the Process Monitor view.
Copy the Process ID to the Clipboard	Copies an integration event ID to your clipboard.
Cancel the Process	Cancels a process.
View Consolidated Report	Opens a consolidated report in the Consolidated Report Viewer.
View Log File	Displays the log file for a process in the View Log File window.
View Request Message	Displays the request message for a process in the View Request Message window.
Import Consolidated Report	Opens the Import Consolidated Report window.
Import Log File	Opens the Import Log File window.
Import Request Message	Opens the Import Request Message window.
Enable Auto Refresh	Enables auto-refresh for the Process Monitor view.
Workday: Process Monitor	Opens the Workday Process Monitor on the Workday tab.
Workday	Opens the Workday view and displays the integration server ESB invocation for your integration.
View Menu	Displays the toolbar options for the Process Monitor view.

Consolidated Report Viewer

Load Consolidated Reports for Integrations

Prerequisites

- · Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

In Studio, the Consolidated Report Viewer tab displays performance information related to the timing, memory usage, and number of calls per step in your integration. Consolidated reports enable you to analyze the process flow of your integrations.

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.

- 4. Select Launch Integration.
- 5. Click Launch.
- 6. On the Process Monitor view, right-click your integration.
- 7. Select View Consolidated Report.

Result

Your consolidated report displays on the Consolidated Report Viewer tab.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Save Consolidated Reports to Your Workspace

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can save consolidated reports to your workspace.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- 6. On the Process Monitor view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. Right-click the consolidated report on the Consolidated Report Viewer tab.
- 9. Select Save As....
- 10.On the Save Consolidated Report window, select a parent folder for your consolidated report.
- 11.Click Finish.

Result

Studio saves your consolidated report to your workspace.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

View Workday Integration Event Details Using Consolidated Reports

Prerequisites

Deploy an integration to Workday.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can view your Workday integration event details using consolidated reports in Studio.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. On the Consolidated Report Viewer tab, select View in Workday.
- 9. On the Workday tab, sign in to your Workday tenant. As you complete the task, consider:

Option	Description
	The username credentials for your Workday tenant.
Password	The password credentials for your tenant.

Result

Your Workday integration event details display on the **Workday** tab in Studio.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

View Request Messages for Integration Events Using Consolidated Reports

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can view the request messages for your integration events using consolidated reports in Studio.

- 1. On the **Cloud Explorer** view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.

8. On the Consolidated Report Viewer tab, select View Request Message.

Result

The request message for your integration event displays on the **View Request Message** window.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Monitor Integrations with the Consolidated Report Viewer Events Log

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can monitor your integrations using the events log in the **Consolidated Report Viewer** tab in Studio.

Steps

- 1. On the **Cloud Explorer** view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. On the Consolidated Report Viewer tab, select Events Log.

Result

The events log for your integration displays on the Consolidated Report Viewer tab.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Monitor Integrations with the Consolidated Report Viewer Profile Log

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can monitor your integrations using the profile log in the **Consolidated Report Viewer** tab in Studio.

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. On the Consolidated Report Viewer tab, select Profile Log.

Result

The profile log for your integration displays on the **Consolidated Report Viewer** tab. The time zone used is PST.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Replay Assembly Executions for Consolidated Reports

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can replay assembly executions for your integrations using consolidated reports in Studio.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- 6. On the Process Monitor view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. On the Consolidated Report Viewer tab, select Replay.

Result

The assembly execution for your integration displays on the Assembly Editor.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Link Consolidated Report Audit Events to Assembly Elements

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can link consolidated report audit events to assembly elements in Studio.

Steps

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.
- 7. Select View Consolidated Report.
- 8. On the Consolidated Report Viewer tab, select Link with editor.

Result

Studio links your consolidated report audit events to assembly elements in your integration. When you select a node on the Consolidated Report Viewer tab, Studio highlights the corresponding assembly element on your assembly diagram.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Display Consolidated Report Annotations on Assembly Diagrams

Prerequisites

- Deploy an integration to Workday.
- Security: Integration Event domain in the Integration functional area.

Context

Consolidated reports enable you to analyze the process flow of your integrations. You can display consolidated report annotations on your assembly diagram in Studio.

- 1. On the Cloud Explorer view, select and expand a cloud server node.
- 2. Select and expand a collection node.
- 3. Right-click an integration node.
- 4. Select Launch Integration.
- 5. Click Launch.
- **6.** On the **Process Monitor** view, right-click your integration.

8. On the Consolidated Report Viewer tab, select Annotate.

Result

Studio displays consolidated report annotations on your assembly diagram in the Assembly Editor.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Concept: Consolidated Report Viewer

In Workday Studio, the **Consolidated Report Viewer** tab displays performance information related to the timing, memory usage, and number of calls per step in your integration. The **Consolidated Report Viewer** tab also summarizes Workday Web Service calls and highlights integration errors.

You can link consolidated reports to assemblies. You can also display consolidated report annotations on each assembly element in your diagram, enabling you to spot issues and errors in your integrations.

The **Consolidated Report Viewer** tab displays as part of the default Workday Studio perspective. If you close it, you can reopen it by selecting **Window** > **Show View** > **Consolidated Report Viewer**.

You can load consolidated reports from within the **Consolidated Report Viewer** tab, or from the **Process Monitor** view for a selected integration process.

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Reference: Consolidated Report Error Messages

Error Message	Example	Description
java.lang.Exception: Win on E2: XSLT job failed	com.capeclear.mediation.M Custom step id=WaitJobComplete, ref=WaitJobCompleteBean - Error while invoking bean, reason: Win on E2: XSLT job failed. The Job with referenceId <referenceid> has failed as it exceeded the maximum number of retry attempts, 1 Root Cause: java.lang.Exception: Win on E2: XSLT job failed.</referenceid>	Displays when your job has ອີຊີ່ເຂື້ອຂໍ້ຕ່ອວ່າ ໃກ້ຮັດກິລັກເກັນໃຫ້ number of retry attempts.
HttpAuthenticationRequiredExce Unauthorized	com.capeclear.mediation.M RetrieveStep id=null encountered a problem sending data	Displays when you have ที่กรนที่เต่อกับกับที่ยี่ต่อใช้ access an attachment.

Error Message	Example	Description
	to endpoint <endpoint>, reason:HttpAuthentication Unauthorized.</endpoint>	RequiredException:
com.workday.esb.blobitory.Blo Tenant wdoms not active	com.capeclear.mediation.Mapplication=bpelEnterpris <version-number> - Failed to store resource in collection eib_xslt_collection in workspace wdoms.</version-number>	
java.lang.OutOfMemoryError: Java heap space.	com.capeclear.mediation.M Custom step id=WaitJobComplete, ref=WaitJobCompleteBean - Error while invoking bean, reason: Win on E2: XSLT job failed. Integration Failed. com.capeclear.mediation.M Xslt step id=transformEIB failed to apply stylesheet mctx:vars/eib.xslt.	
java.xml.transform.TransformC	com.capeclear.mediation.N Custom step id=WaitJobComplete, ref=WaitJobCompleteBean - Error while invoking bean, reason: Win on E2: XSLT job failed. Integration Failed. com.capeclear.mediation.N Xslt step id=transformEIB stylesheet mctx:vars/ eib.xslt located at mctx:vars/eib.xslt is invalid or missing,	
	reason:	formerConfigurationException

Error Message	Example	Description
	well-formed. Root Cause: javax.xml.transform.Tran Failed to compile stylesheet. 1 error detected.	sformerConfigurationException:
com.workday.services.server.ca	com.capeclear.mediation.Napplication=bpelACHTransf- Custom step id=aggregateElement, ref=DocumentElementProce Error while invoking bean, reason: document processor step error Root Cause:	transformer instance. essor er.capeclear.bean.dep.Processir m.TransformerException:
java.io.FileNotFoundException	HIERARCHY_REQUEST_ERR: An attempt was made to insert a node where it is not permitted. com.capeclear.mediation.napplication= <application=< td=""><td>Displays when a keystore file ਜਿਨ੍ਹੇਂ ਤੇ ਜ਼ਿੰਨ੍ਹ ਆਉਂਦੇ ਅੰਦੇ ਇੱਕ ESB</td></application=<>	Displays when a keystore file ਜਿਨ੍ਹੇਂ ਤੇ ਜ਼ਿੰਨ੍ਹ ਆਉਂਦੇ ਅੰਦੇ ਇੱਕ ESB
	<pre>name> - Http Out transport id=retrieveSchemaFromOMS encountered error sending to endpoint <endpoint> Root Cause: java.io.FileNotFoundExce <keystore-file- location=""> (No such file or directory).</keystore-file-></endpoint></pre>	server.
org.jaxen.UnresolvableException	com.capeclear.mediation. Error eval step id=ValidatePaygroup expression=props['myprop	your assembly.
	<pre></pre>	

Error Message	Example	Description	
	<pre>picof:Status/ picof:Pay_Group') Root Cause: org.jaxen.UnresolvableEx Cannot resolve namespace prefix 'picof'.</pre>	cception:	
BadRequestException	<pre>com.capeclear.mediation.M Workday Out transport id=CallGetPos encountered problem sending to endpoint 'https://impl- cc.workday.com/ccx/ service/mycompany/ Staffing/v17' with operation 'Get_Positions_Request'. Details: Code: SOAP- ENV:Client.validationError Reason: Validation error occurred. Invalid ID value. '?' is not a valid ID value for type = 'Position_ID' Root Cause: BadRequestException: Error code: unknown.</pre>	request message.	
java.net.SocketTimeOutExceptio	com.capeclear.mediation.M Transport error in email out transport id=emFailureRecords with endpoint=mailto:	econnect.transport.Transpor	tExceptio

Related Information

Tasks

Deploy Integrations to Workday on page 295 Launch Integrations from Studio on page 301

Create an AUnit Test Skeleton for an Assembly Project

Context

AUnit is a Workday Studio test framework for developing and running unit tests for assemblies. AUnit test skeletons enable you to build test cases for your assemblies.

Steps

- 1. Select File > New > Workday Assembly Project.
- **2.** On the **Project name** field, enter a name for your project. Project names must not contain spaces.
- 3. On the Target Runtime field, select Workday Runtime.
- 4. On the Configurations field, select Assembly (with Java support).
- 5. Click Finish.
- 6. Select File > New > Other > Class.
- 7. On the New Java Class menu, consider:

Option	Description	
Package	Enter a package name.	
Name	Enter a name for the new java class.	
Superclass	Click Browse, and select com.workday.aunit.AssemblyTestCase.	

- 8. Click Finish.
- 9. On the Project Explorer view, right-click the src folder in your project.
- 10. Select Add JUnit Library.

Result

Studio displays your AUnit test skeleton on the java editor.

Next Steps

Run unit tests for your assemblies.

Concept: AUnit Tests

AUnit is a Workday Studio test framework that enables you to develop and run unit tests for assemblies. You can develop AUnit tests in Java using test skeletons that you create in your assembly projects. AUnit test skeletons support these features:

- Actions
- Annotations
- Assertions

You can use these features to build test cases for your assemblies.

Example:

```
package com.workday.training.aunit;
import java.io.InputStream;
```

```
import com.workday.aunit.AssemblyTestCase;
import com.workday.aunit.actions.Action;
import com.workday.aunit.actions.StandardAction;
import com.workday.aunit.annotations.AssemblyTest;
import com.workday.aunit.annotations.AssertAfter;
import com.workday.aunit.annotations.AtComponent;
import com.workday.aunit.annotations.UnitTest;
@AssemblyTest(project = "AUnitTrainer", displayLabel = "Citizens of the
Cloud")
   public class SimpleMediationTest extends AssemblyTestCase {
    @UnitTest(startComponent = "Simple-Mediation")
   public void testSimpleMediation() throws Exception {
        setMessagePart(0, "test/simple-input.xml", "text/xml");
    // Using the @AssertAfter annotation and the assertTrue assertion.
                                                                           //
    @AssertAfter(id = "Simple-Mediation", step="transform")
   public void verifySimpleMediation() throws Exception {
        assertTrue(compare(
            getTestResourceInputStream("test/simple-expected.xml"), "text/
xml",
            (InputStream) getMediationContext().getMessage().getMessagePart(0,
 InputStream.class),
            "text/xml", Comparator.dom));
    @AtComponent(id="Next-Thing")
   public Action handleAfterMediation() throws Exception {
        return new StandardAction(Action.Type.terminate);
}
```

Annotations

All AUnit tests must contain an @AssemblyTest annotation. This annotation identifies your AUnit test and enables you to associate the test with your assembly project. Example:

```
@AssemblyTest(project = "AUnitTrainer")
```

Annotations on test methods define the starting point for a unit test in the assembly processing chain. Example:

```
@UnitTest(startComponent = "Simple-Mediation")
```

Assertions

Assertions define Boolean test conditions. If an assertion fails, AUnit aborts the assembly execution and displays the test result as a failure. If an unexpected exception occurs, AUnit aborts the assembly execution and displays the test result as an error.

Example: The sample below uses an @AssertAfter annotation and an assertTrue assertion to check whether the root message part contains the expected XML after the mediation executes.

```
@AssertAfter(id = "Simple-Mediation", step="transform")
public void verifySimpleMediation() throws Exception {
    assertTrue(compare(
        getTestResourceInputStream("test/simple-expected.xml"), "text/xml",
        (InputStream) getMediationContext().getMessage().getMessagePart(0,
InputStream.class),
```

```
"text/xml", Comparator.dom));
}
```

Actions

Actions define AUnit test behaviors when the assembly execution reaches a component or exit point. Example:

```
@AtComponent(id="Next-Thing")
public Action
    handleAfterMediation() throws Exception {
        return new StandardAction(Action.Type.terminate); }
```

Reference: AUnit Test Annotations

Description	Example
Identifies a test as being an AUnit test and associates it with an assembly.	<pre>@AssemblyTest(project</pre>
Identifies an individual test case.	<pre>@UnitTest(startComponent</pre>
Executes assertions before executing a named assembly component or step.	<pre>@AssertBefore(id="Store- Output") public void verifySummaryDoc() throws Exception { assertEquals("10", evaluateExpression("parts[0].xpasummary/ wd:WorkerSummary)')")); }</pre>
Executes assertions after executing a named assembly component or step.	<pre>@AssertAfter(id = "Simple-Mediation", step="transform") public void verifySimpleMediation() throws Exception { assertTrue(compare(getTestResoursimple-expected.xml"), "text/xml",</pre>
	Identifies a test as being an AUnit test and associates it with an assembly. Identifies an individual test case. Executes assertions before executing a named assembly component or step. Executes assertions after executing a named assembly

Annotation	Description	Example	
		<pre>public void verifySummary() throws Exception { assertEquals("Ace Developer", evaluateExpression("parts wd:WorkerSummary/ wd:Name')")); assertEquals("2010-07-27- evaluateExpression("parts wd:WorkerSummary/ wd:HireDate')")); }</pre>	07:00",
@AssertAfterCompletion	Executes assertions after the assembly has completed.	<pre>@AssertAfterCompletion public void verifyErrorHandling() throws Exception { assertEquals(3, evaluateExpression("props }</pre>	['error.c
@AtComponent	Defines where the test intercepts the assembly to perform verification and defines the test behavior for the named component.	<pre>@AtComponent(id="Get- Workers") public Action handleGetWorkersInvocatio throws Exception { setMessagePart(0, "test/fromworkdayin/ workdayin_workers_response "text/xml"); return new StandardAction(Action.Typ }</pre>	.xml",

Reference: AUnit Test Actions

Actions	Description	Example	
continue_to_next	Continues the AUnit test on the next element in your assembly.	return new StandardAction(Action.Typ	e.continu
invoke	Invokes the endpoint specified by the out-transport of your assembly.	return new StandardAction(Action.Typ	e.invoke)
mock	Simulates a response message returned by the out-transport by specifying an input file containing the response message.	return new StandardAction(Action.Typ	e.mock);
mock_exception	Simulates an exception thrown by the out-transport by specifying an instance of this class: com.capeclear.capeconnect msg)	new StandardAction(Action.Tyrnew BadRequestException("Incl	_

Actions	Description	Example	
terminate	Terminates the test.	return new StandardAction(Action.Tyr	e.termina

Web Service Testing

Test Web Services Using a WSDL File

Context

You can use Workday Studio's Web Service Tester to send sample request messages using any operation described in a WSDL file.

- 1. On the Studio toolbar, click Test Web Service in Tester.
- 2. As you complete the task, consider:

Option	Description
File	Displays the location of the selected WSDL file.
Workspace	Select a WSDL file from your Workspace.
External	Select a WSDL file from an external location.
URL	Select a WSDL file from a URL.
Initialize response endpoint and authentication details for Sandbox environment	 Specifies whether: The tester's Location field is prepopulated with the web service endpoint. The WS-Security Username Token is prepopulated with your Sandbox user login details. This option is selected by default.
Finish	Click when you've selected a WSDL file. Alternatively, click without specifying a file to open the Web Service Tester and enter the location and message of your choice.

- 3. Select a WSDL file from your workspace, an external location, or a URL. Click Finish.
- **4.** Studio opens the Web Service Tester. As you complete the task, consider:

Option	Description
Location	The web service endpoint.
PortType	The WSDL operations exposed by the web service and its associated binding.
Operation	Operations from the WSDL file. When you select one, Studio generates a sample message in the Request pane.
SOAP action	The SOAPAction header in the HTTP request.

Option	Description
Request	The request message that Studio sends to the web service.
<u> </u>	The response message that Studio receives from the web service.

- 5. Modify the XML in the Request pane as required. To add an attachment, click Add Attachment, then click Edit to specify the file location and attachment's Name and Mime type.
- 6. Click Send Request to send the request message to the Web service at the URL specified in the **Location** field. Studio displays the response in the **Response** pane.

Test Web Services Using an XSD File

Context

You can use Workday Studio's Web Service Tester to send sample request messages using any element described in an XSD file.

- 1. On the Studio toolbar, click Test Web Service in Tester.
- 2. As you complete the task, consider:

Option	Description
File	Displays the location of the selected XSD file.
Workspace	Select an XSD file from your Workspace.
External	Select an XSD file from an external location.
URL	Select an XSD file from a URL.
Initialize response endpoint and authentication details for Sandbox environment	 Specifies whether: The tester's Location field is prepopulated with the web service endpoint. The WS-Security Username Token is prepopulated with your Sandbox user login details. This option is selected by default.
Finish	Click when you've selected an XSD file. Alternatively, click without specifying a file to open the Web Service Tester and enter the location and message of your choice.

- 3. Select an XSD file from your workspace, an external location, or a URL. Click Finish.
- **4.** Studio opens the Web Service Tester. As you complete the task, consider:

Option	Description
Location	The web service endpoint. Because the location value isn't available in an XSD, you must enter the location manually.
Elements	Element definitions from the XSD file. When you select one, Studio generates a sample message in the Request pane.

6. Click **Send Request** to send the request message to the Web service at the URL specified in the **Location** field. Studio displays the response in the **Response** pane.

Test Individual Web Services from the Schema Explorer

Prerequisites

Display Workday Web Service WSDLs or XSDs in the Schema Explorer.

Context

You can test individual web services by using the Workday Studio Web Service Tester to create sample SOAP or XML request messages from the **Schema Explorer**.

Steps

- To generate a sample request message for a specific web service, right-click a WSDL or XSD element on the Schema Explorer view. Select either Open request in Web Service Tester or Open SOAP wrapped request in Web Service Tester.
- Studio opens the WS Tester view. The Target section displays the Location of the Web service endpoint.
- 3. From the Content-Type drop-down list, select the message's media type and subtype:

Option	Description
text/plain; charset=utf-8	Specifies plain text, containing no formatting commands or directives.
text/xml; charset=utf-8	Specifies XML text.
application/octet-stream	Specifies an unrecognized type. Example: select this option if you're attaching a binary file to the message.

- **4.** Modify the XML in the **Request** pane as required. To add an attachment, click **Add Attachment**, then click **Edit** to specify the file location and attachment's **Name** and **Mime type**.
- **5.** Click **Send Request** to send the request message to the Web service at the URL specified in the **Location** field. Studio displays the response in the **Response** pane.

Related Information

Tasks

Display Workday Web Service WSDLs on page 248

Test Get Operations and Request Messages Using the Request Builder Wizard

Prerequisites

Display Workday Web Service WSDLs or XSDs in the **Schema Explorer**.

Context

You can use the **Workday Web Service Request Builder Wizard** to simplify testing many Get operations and request messages. Eligible operations and request messages have an arrow decorator in the upper left corner of their icon.

Steps

- 1. Right-click the relevant Get node in the Schema Explorer view, then select Workday Web Service Builder Wizard.
- **2.** Select whether you want to:
 - Use a Reference ID to retrieve specific data.
 - · Retrieve all available records from the web service.
- 3. If you selected to use a Reference ID, enter it.
- **4.** Select the Response Groups you want to include.
- **5.** Select whether you want to:
 - Copy the sample request to the clipboard.
 - Open the sample request in a new WS Tester view.
 - Replace the contents of the current WS Tester view.
- 6. Click Finish.

Configure Web Service Tester Authentication

Prerequisites

Create a web service test.

Context

You can configure a number of security options in Workday Studio's Web Service Tester. The Authentication options enable you specify whether to apply WS-Security or basic authentication to SOAP request messages, or to call the internal cc-authenticate service.

- 1. In the WS Tester view, click Send Options.
- 2. Select the Authentication check box. As you complete the task, consider:

Option	Description
WS-Security UsernameToken	Enables you to specify a username and password for use with WS-Security, without having to select a WS-Security configuration file. Studio inserts a fragment of XML containing the username and password that you specify in the SOAP Header section of request messages that it generates.
Authentication Service	The Web Service Tester calls the internal ccauthenticate service using the username and password that you specify. If the username and password are valid on the server, Workday returns a session ticket which the Web Service Tester adds to the SOAP header when the request is sent. The server processing includes an interceptor that checks that the supplied session ticket is valid.
	By default, a connection to the cc- authenticate service is made once and reused. If you're stopping and starting servers, select Re-connect to the cc-authenticate

Option	Description
	service before each send to create a new connection for each request.
Basic Authentication (pre-emptive)	Enables you to specify a username and password for use with preemptive HTTP Basic Authentication.

Configure Web Service Tester X.509 Authentication

Prerequisites

Create a web service test. Configure an integration system user with a username that corresponds to a key store alias name, but without the @tenant-name suffix. Assign the appropriate user-based group for the web service to the integration system user.

Context

You can configure a number of security options in Workday Studio's Web Service Tester. The X.509 Authentication options enable you to select a key store alias that corresponds to an integration system user and the associated private and public key pair.

Steps

- 1. On the WS Tester view, click Send Options.
- 2. Select the X.509 Authentication check box.
- 3. Select a username from the Username drop-down list. Each username is associated with a key store
- 4. (Optional.) Click Manage Keys to manage existing X.509 keys or generate a new key pair. Studio requests a key store password once per session. As you complete the task, consider:

Option	Description
Generate X.509 key pair	Enables you to generate an X.509 key pair with an associated digital certificate.
Remove key from the key store	Removes the selected key pair.
View the public key (certificate)	Displays the public key for the selected key pair.
Import key pair	Enables you to either:
	 Import a private key and X.509 certificate from a Java key store. Import a private key and X.509 certificate in OpenSSL PEM format.
Rename alias	Enables you to rename key store alias for the selected key pair.

Configure Web Service Tester Advanced WS-Security

Prerequisites

Create a web service test.

Context

You can configure a number of security options in Workday Studio's Web Service Tester. The Advanced WS-Security Configuration options enable the Web Service Tester to read a security configuration file that specifies a sequence of security steps for the request and another sequence of security steps for the response. It applies the security steps to the outgoing request message and removes security encoding from the incoming response message. The server removes security encoding as it receives, and adds security encoding as it responds.

Steps

- 1. On the WS Tester view, click Send Options.
- 2. Select the Advanced WS-Security Configuration check box.
- 3. Provide a Configuration File URL from either a Workspace or External location.
- 4. (Optional.) If the security configuration file has relative locations for values such as the key store location, provide a Configuration Base URL. Studio prepends this URL to the relative locations.
- 5. (Optional.) Select the Re-load the security configuration information before each send check box to reload the file for each request. This option is useful when you're making changes to the configuration file.

Concept: Web Service Testing

The Workday Studio Web Service Tester enables you to create sample SOAP or XML request messages based on the web service description (WSDL) or on a schema definition (XSD). The tool also displays any response messages that the web service returns. It supports HTTP and HTTPS.

This table summarizes the 3 main ways to launch the Web Service Tester:

Method	Notes
From the Studio menu bar.	Enables you to select a WSDL or XSD file for testing from your workspace, a URL, or an external file location. You can also use this option to open the Web Service Tester without reference to any specific file.
From the Schema Explorer view.	Enables you to generate XML requests for a specific WSDL operation or schema element, in either non-SOAP or SOAP envelope-wrapped format.
Using the Workday Web Service Request Builder wizard.	Simplifies testing of specific Get operations and Get request messages.

Reference: Web Service Tester Toolbar Buttons

General

Button	Description
Send Request	Invokes the Web service. The response message is displayed in the Response pane.
· •	Opens the Send Options dialog box, enabling you to configure security options.
Abort Request	Aborts the current request.

Button	Description
Reload the WSDL	Reloads the WSDL driving the Web Service Tester. Useful if the web service has changed.
Choose the XML font via the preferences	Enables you to set font properties for the XML displayed in the Request and Response panes.
Request/Response History	Provides access to a list of previously sent request messages, enabling you to select and resend them.
Request Only	Displays the Request pane only.
Response Only	Displays the Response pane only.
Horizontal Layout	Arranges the layout horizontally.
Vertical Layout	Arranges the layout vertically.
Help	Displays context-sensitive Help for the Web Service Tester.

Request Pane

Button	Description
Save Request	Saves the request message as an XML file.
Load Request	Loads a request message.
Format Request	Applies standard indentation to the request message. Text can exceed the panel width.
Restore original or last sent request	For unsent messages, restores the text to its original unformatted and unwrapped state. Overrides any manual edits. For sent messages, returns the text to its state before the last send action.
Add Attachment	Enables you to add or remove a file attachment. To add an attachment to the request message, click Edit , select a file from the workspace or an external file location, and specify its Name and Mime Type .
	To remove an attachment from a request message, click Remove .
	To save an attachment included in a response message, click Open below the Response pane.
Increase Font	Increases text size in the Request pane.
Decrease Font	Decreases text size in the Request pane.

Response Pane

Button	Description
Save Response	Saves the response message as an XML file.
Load Response	Loads a response message.

Button	Description
Format Response	Applies standard indentation to the response message. Text can exceed the panel width.
Wrap Response	Applies indentation, but also formats the text within the boundaries of the panel width.
Restore Response	For response messages, restores the text to its original unformatted and unwrapped state. For sample responses, removes the loaded file from the text pane. Undoes any manual edits.
Sample Response	Generates a sample response for a SOAP request message generated from a WSDL.
Increase Font	Increases text size in the Response pane.
Decrease Font	Decreases text size in the Response pane.

Assembly Debugging

Debug an Assembly

Prerequisites

- Create an assembly project.
- Security: Integration Debug domain in the Integration functional area.

Context

Workday Studio enables you to detect and debug errors in your assemblies. You can debug assemblies that you've deployed to your Workday server environment. If an assembly contains components or steps that reference a static file, ensure that there are no spaces in the referenced filepath before debugging.

- 1. On the **Project Explorer** view, right-click an assembly project.
- 2. Select Deploy to Workday.
- 3. On the **Deploy to Workday** window, consider:

Option	Description
	Select a target Workday environment for deploying your integration.
Collection being deployed	Select a collection.

- 4. Click Finish.
- 5. On the Cloud Explorer view, select and expand the cloud server node of the target Workday environment to which you deployed your assembly project.
- **6.** Select and expand the collection that you deployed to Workday.
- 7. Right-click an integration node in your collection.

8. Select Debug Integration. On the Debug Integration window, consider:

Option	Description
Launch In	The target Workday environment for launching your debug session.
Collection	The name of the collection you're debugging.
Project	The name of the project you're debugging.
Workday-In	The name of the Workday-In transport in the project you're debugging.
Launch Parameters	The launch parameters of the project that you're debugging.
	To debug with alternative launch parameters, click Select Literal Values and select from the Workday IDs that the CRF returns.
	If you know a specific Workday ID that you want to use as a launch parameter, click Edit Literal Value and enter it in the Value field.

9. Click Debug.

Note: If you encounter problems when the debug runtime begins to start up, consider adjusting the Session Reconnect Retries and Max Startup Wait Iterations values.

Session Reconnect Retries determines how many times Studio tries to connect a debug session to the debug runtime. Max Startup Wait Iterations determines how many times Studio checks whether the debug runtime is ready to receive requests. Try increasing them in increments of 10.

You can adjust these values for an existing launch configuration in the **Debug Configurations** dialog.

To adjust them for future launch configurations, select Window > Preferences > Workday > Assembly Debug > Debug Runtime.

Result

The results of your debug session display on the Console view.

Concept: Assembly Debugger

The Workday Studio Assembly Debugger is a tool for debugging assemblies in the Workday server environment. The Assembly Debugger enables you to:

- Examine the assembly message runtime context.
- · Suspend assembly threads.
- Test MVEL expressions.

If your assembly contains components or steps that reference a static file, ensure that there are no spaces in the referenced filepath before debugging.

Note: You can't debug an assembly in a Production tenant. Use a non-Production environment for debugging.

Setting Breakpoints

Breakpoints enable you to pause the debugging process at specific points in your assemblies. To set breakpoints on assembly elements, right-click an element and select Toggle Assembly Breakpoint. In the main Assembly Editor view, a blue circle displays on the upper right-hand corner of the element to indicate a new breakpoint.

Studio Management

Studio Preferences

Concept: Assembly Editor Preferences

You can specify preferences for your assembly diagrams using the **Assembly Editor** preferences page. To navigate to the preferences page, select **Window** > **Preferences** > **Workday** > **Assembly Editor**. Select one of these nodes to specify the related Assembly Editor preference:

- Color
- Fonts
- Migration
- Modules

Color

The **Diagram Color Preferences** page enables you to specify color preferences for components in your assembly diagram.

Setting	Description
Background Color	Specifies the background color for assembly components.
Line Color	Specifies the line color for assembly components.
Text Color	Specifies the font color for assembly components.
Step Background Color	Specifies the background color for assembly steps.
Header Background Color	Specifies the background color for assembly component headers.

Fonts

The **Diagram Font Preferences** page enables you to specify font preferences for components in your assembly diagram.

Setting	Description
Default	Specifies the standard font type, style, and size for your assembly diagram component ID values.
Step	Specifies the standard font type, style, and size for your assembly step ID values.
Conditional Tooltip Header	Specifies the standard font type, style, and size for tooltip header text displayed in your assembly diagram.
Conditional Tooltip Content	Specifies the standard font type, style, and size for tooltip content displayed in your assembly diagram.

Migration

On the **Migration** page, you can turn migration on or off for legacy assembly projects created using earlier versions of Workday Studio.

If migration is enabled, Workday Studio automatically migrates the assembly configuration for an assembly.xml file to the latest version of Studio when you open the file.

To turn automatic migration off, clear the **Enable legacy assembly migration in the Assembly Editor** check box before opening or saving an assembly.xml file.

Modules

Before you start developing assembly module templates, create a folder to store your assembly modules either in your workspace, or in an external location such as a folder within your Workday Studio installation.

The **Module Library** in the Assembly Editor's assembly tools palette displays only those assembly modules that are selected to load from the modules folder, as specified in the **Window** > **Preferences** > **Workday** > **Assembly Editor** > **Modules page**. Click **Browse Workspace** or **Browse File System** to locate the modules folder and specify the path to this folder. Studio displays all assembly module XMI (XML Metadata Interchange) files that are located in the specified folder in the **Modules** table. Select the check box beside each assembly module that you want to load in the **Module Library**. Studio performs template validation and loads only valid XMI files.

At design time, the **Assembly Module** wizard prompts you to save the module XMI file to a folder in your workspace. If preferred, you can later copy the assembly module XMI files from your workspace folder to the modules folder that you specify here, if different from the workspace folder.

Concept: Connections Preferences

The **Connections** preferences page enables you to set your integration cloud connection credentials. To navigate to the **Connections** preferences page, select **Window** > **Preferences** > **Workday** > **Connections**. You can enter credentials for both **Sandbox** and **Production** environments. You can also add connections to other environments, as well as add groups to your connections.

Concept: Deployment Preferences

On the **Deployment** preferences page, you can specify whether to include project source code in the CLAR when deploying to a Workday environment. To do so, select the **Include source code in deployed CLAR** check box.

To exclude the source code from the CLAR, clear the check box.

If you select the **Include source code in deployed CLAR** option, you can import the source to a project in your workspace. To do so, right-click the collection in the **Cloud Explorer** and select **Import Source**.

Concept: HTTPS Preferences

On the **HTTPS** preferences pane, you can specify whether to enable truststore certificate management in Studio. If you select the **Enable truststore certificate management in Studio** check box, when Studio attempts to connect to Workday over HTTPS, a message is displayed that prompts you to trust the Server certificate for the Sandbox or Production environment. The certificates that you trust are displayed in the **Truststore Certificates** pane, where you can reload, remove all, or delete selected certificates. To open the **Truststore Certificates** pane, expand the **Workday** > **HTTPS** link in the left navigation pane.

Concept: Ivy Preferences

Workday Studio provides an Ivy plugin, which enables you to manage project dependencies with Apache Ivy. To enable the Ivy plugin to resolve resources, you can specify the settings and properties file to use in your project.

You can configure these settings on the **Workday** > **Ivy** preferences page:

• Ivy settings URL: click Browse..., then select the ivysettings.xml file or specify a URL. The settings file defines variables that the Ivy engine can load to resolve resources.

• Ivy properties file: click Browse..., then select the .properties file that the settings file can reference. The properties file contains properties that Ivy loads as variables, in the form:

name=value

Select the **Load ivy.properties file from home directory if present** check box to load the ivy.properties file automatically from your home directory.

Concept: Linking Preferences

The **Linking** preferences page specifies whether to use path variables with absolute paths for linked resources in your workspace. To navigate to the **Linking** preferences page, select **Window > Preferences** > **Workday > Linking**. The **Use PATH variables for linked resource absolute paths** setting is enabled automatically. To disable this setting, clear the check box.

Concept: MVEL Validation Preferences

The **MVEL Validation** preferences page enables you to configure validation for MVEL code. The **Enable MVEL Validation** setting is enabled automatically. To disable this setting, clear the check box.

Concept: Packaged Integrations Preferences

The **Packaged Integrations** preferences page is intended for use by internal Studio developers only for packaged integration deployment purposes. Internal Studio developers, please consult your internal Wiki for more details on support for packaged integrations.

Concept: Runtime Preferences

Workday Studio automatically checks for Workday runtime updates. If any updates are available, Studio downloads them in the background and notifies you upon installation. You can configure your download, installation, and notification preferences on the **Window** > **Preferences** > **Workday** > **Runtime** page.

Concept: Server Preferences

On the **Server** preferences page, you can adjust the **Undeploy Workday collections when they are removed from the Server** setting. This setting is disabled automatically, which means that if a collection is already deployed to the selected Workday environment, and you remove the collection from the **Configured** list, Studio doesn't undeploy the collection. To enable this setting, select the check box. When you click **Finish** on the **Deploy to Workday** wizard, Studio undeploys any collections that are in your workspace, but are no longer in the **Configured** list.

Concept: Splash Screen Login Preferences

At startup, Workday Studio displays an optional splash-screen where you can enter connection details to your Workday environment. If preferred, you can enter your details later in **Connection Details**. To turn off the splash-screen at startup, select the **Don't show the login on startup** check box, then click **Apply** to save your changes.

Concept: Status Bar Preferences

The **Status Bar** preferences page enables you to specify the maximum number of status bar items to store in the Status Bar history list, which is displayed in the bottom right-hand corner of the Studio workspace. In the **Max Status Bar history items** field, enter the maximum number of items you wish to store.

Concept: Update Preferences

Workday Studio supports updates for integrators based in low-bandwidth areas through the Workday Content Delivery Network (CDN). You can enable access to the Workday CDN on the **Window** > **Preferences** > **Workday** > **Install/Update** page.

Note: CDN usage requires unrestricted outbound access on port 443.

Concept: XPath Explorer Preferences

The **XPath Explorer** preferences page enables you to specify namespace-prefix mappings to use when generating XML fragments for the **Evaluate XPath to XML fragment** option.

To add a mapping, click **New...**. The **Add Namespace Prefix Mapping** field is displayed, which enables you to enter **Prefix** and **Namespace** values for the mappings that you require.

To remove an unwanted mapping, select it and click **Remove**. To rearrange the order of the mappings, select a mapping and click **Up** or **Down**, as required.

Reference: Assembly Debug Runtime Preferences

Setting	Description
Hostname	The hostname for launching debug sessions.
HTTP Port	The port number that connects debug sessions to Workday.
Session Connect Retries	The number of times Studio attempts to connect debug sessions to Workday.
Max Startup Wait Iterations	The number of times Studio checks if Workday is ready to receive requests.
Accept All Certificates	Specifies whether Studio accepts unsigned certificates.
Enable HTTPS Proxy Settings for Debugging	Enables HTTPS proxy server settings for debug sessions.
Copy Proxy Settings from Eclipse	Specifies whether to copy the proxy settings for debug sessions from Eclipse.
Proxy Host	The proxy server hostname.
Proxy Port	The port on which the proxy server listens.
Proxy User Name	The username for the proxy server.
Proxy Password	The password for the proxy server.
Wait for preceding BP steps timeout, e.g., Retrieval (seconds)	The timeout period that Studio allocates to related business process integrations before resuming debug sessions.

Reference: Assembly Debug View Preferences

Setting	Description
Auto format root part of XML	Check this box if you want Studio to automatically format the displayed XML for the root part of the message.
Bring the Assembly Debug View to the front when a thread suspends	Check this box if you want Studio to bring the Assembly Debug view to the foreground when a thread suspends during the debug process.
Bring the Exception tab to the front when a thread suspends on an error handler	Check this box if you want Studio to bring the Exception tab in the Assembly Debug view to

Setting	Description
	the foreground when a thread suspends during the debug process.
Automatically retrieve root parts with lengths less than (KB)	Specifies the automatic download threshold, which is the maximum file size for message root parts that the Assembly Debug view can display automatically.
	To view message root parts that exceed the automatic download threshold, you must download the message or save it as a document in the workspace or file system. To do so, use the Assembly Debug view toolbar buttons.
Truncate messages downloaded to the Assembly Debug View when lengths exceed (KB)	Truncates messages that exceed the specified file size when displaying in the Assembly Debug view after download.

Reference: Cloud Explorer Preferences

Setting	Description
Ask for confirmation when deleting a collection	If this feature is enabled, you're prompted to confirm your choice before you can delete a collection from the Cloud.
Show annotations in the Cloud Explorer	If this feature is enabled, annotations are displayed on nodes in the Cloud Explorer .
Show Workday connector content	If this feature is enabled, the Cloud Explorer displays content for the workday-in transport such as launch parameters, attributes, and maps.

Reference: Consolidated Report Viewer Preferences

Profile Log Column	Description
Calls	The number of calls the component receives during the integration event.
Avg Time	The average processing time of the component.
Max Time	The maximum processing time of the component.
Min Time	The minimum processing time of the component.
Std Deviation Time	The standard deviation from the average processing time of the component.
Total Time	The total processing time of the component.
Avg Req Size	The average request size of the component.
Max Req Size	The maximum request size of the component.
Min Req Size	The minimum request size of the component.
Std Deviation Req Size	The standard deviation from the average request size of the component.

Reference: Java Project Settings Preferences

Available Memory

Setting	Description
Enforce compatibility with only the current workbench default JRE	By default, any Java code that Studio generates is compatible with any installed JRE. However, by selecting this check box, you can enforce Java web service projects to be compatible with only a specific JRE, that is, the default Workbench JRE.
Respect export settings for classpath entries in referenced projects	Select this check box to include only exported resources from referenced projects when exporting a WSAR or deploying a web service project.

The available memory usage of the component.

Reference: Notification Preferences

Setting	Description
Enable notifications	Studio automatically enables this setting. Clear this check box to disable the display of notifications on the Studio screen.
Fade out delay	Enter a value in milliseconds to specify the length of time that notifications remain displayed before fading out.

Reference: Process Monitor Preferences

Setting	Description
	Automatic refreshing of the Process Monitor view is enabled by default. To disable this feature, clear the check box.
Refresh interval in seconds	Enter a value (in seconds) to specify the length of time between automatic refreshes. Use the scroll buttons on the right to increase or decrease the value.

Reference: Web Service Tester Preferences

Setting	Description
Request and response XML display	Specifies the font size and style used to display the request and response XML data. The open editor updates immediately when you change the font details.
Do not display messages larger than:	Specifies the maximum size of messages to be displayed in the Web Service Tester's Response panel. The standard value is 1024 KB. Any message larger than the value specified is saved as an attachment. You can save the attachment locally.

Studio Updates

Update Studio

Context

Just as there's only 1 version of the Workday application that's used by all customers, there's only ever 1 valid release of Workday Studio. Your Studio installation must be up-to-date to interact with your Sandbox or Production environment.

Steps

 If an update is available, Studio notifies you when you enter your tenant credentials, either at startup or later. Confirm that you would like to update, then follow the steps in the Update Workday Studio wizard.

Note: Don't update the underlying Eclipse platform independently of the Studio update schedule. Doing so can cause your integrations to fail.

2. If you choose not to update immediately, Studio displays a red arrow in the status bar to act as a reminder. You can still develop assemblies locally while an update remains uninstalled. However, you're prevented from connecting to your Sandbox or Production tenants. To update later, select Workday > Update Workday Studio.

Note: Studio includes a lightweight version of the Workday Runtime to enable you to test and debug your integrations. To ensure that you always have access to the same Runtime that's available in your

production tenant, Studio checks for a Runtime update on start-up. If one is available, it's downloaded it in the background. To adjust this behavior, select **Window** > **Preferences** > **Runtime** > **Automatic Updates**.

Workday Assembly Runtime Changes

Concept: Assembly Versions

Assembly version-management allows the Workday Enterprise Service Bus (ESB) server and Studio development teams to evolve assemblies within the Workday Runtime programming model over time without affecting existing users. For example, assembly version-management enables Workday to:

- Deprecate features
- · Introduce new features
- · Modify the semantics of existing features

All assemblies have a version attribute. By default, when you create a new assembly project, Workday Studio sets the version attribute value for the assembly element in the assembly.xml file to the most current version of the Workday Runtime. The format is year.drop-number, where drop-number corresponds to the week number. Example: 2016.11.

Studio displays this number next to the Assembly folder in the Project Explorer.

When changes are introduced to existing runtime features, Workday ensures that they are backwards compatible. This means that all existing assemblies operate as before, according to their version number. However, by default, new assemblies have the behavior that corresponds to the current version number. Typically, when Workday introduces a change, we define a new attribute on an assembly step or component. Older assemblies do not have this attribute, so we introduce a rule based on the version number to default the value for older assemblies. We also introduce a rule to default a different value for newer assemblies. As a developer, if you want to uptake new features in older assemblies, you have several options. You can:

- Keep the older version and accept the default that the Workday Runtime assigns.
- Keep the older version and set an explicit value for the new attribute, depending on your requirements.
- Migrate to a newer version and accept the new default.
- Migrate to a newer version and set an explicit value for the new attribute.

Reference: Version Changes at the Schema Level

This table summarizes schema-level changes that have occurred for each version update.

Version	Component	Attribute/Property	Change Description
8.0	async-mediation and sync-mediation	handle-downstream- errors	Default changed from true to false
	components		A value of false means local error handlers in this component only deal with errors occurring in this component's steps.
			A value of true means local error handlers in this component can deal with downstream errors.
9.0	write	output-mime-type	Default changed from text/plain to text/

Version	Component	Attribute/Property	Change Description
			xml, in line with other steps.
11.0	xmldiff step	copy-to-output	Default changed to true.
			A value of true means the step copies the output to the mediation message.
			A value of false means the step copies the output to a variable.
12.0	http-in transport	secure	Default changed from false to null, meaning the endpoint is available over HTTP and HTTPS unless otherwise specified.
	http-out transport	error-as-response	Default changed from false to true.
			A value of true means that when the runtime encounters an error in the transport, it sets the error in the current message. Previously, the error was available only through a BadRequestException on the MediationContext.
	local-out, http-out, ftp-out, ftps-out, sftp-out,	ignore-dynamic- endpoints	Default changed from false to true.
	xmpp-out, custom-out, email-out transports		A value of true means the transport ignores the dynamic WS-Addressing (WSA) value in the incoming message's header.
			A value of false means the transport uses the WSA value to override the value in its Endpoint property.
13.0	store	schema	Default changed from urn:com.workday/ bsvc/blob to [http://

Version	Component	Attribute/Property	Change Description
			www.w3.org/2005/ Atom].
			The PutIntegrationMessage subassembly can directly consume the Atom when adding documents to the current integration event.
	async-mediation and sync-mediation components	continue-after-error	Default changed from recover to rewind. A value of rewind means that processing continues from the previous component in the assembly when an error is cleared.
			The previous default, recover, is now deprecated.
	local-out transport	unset-properties	Default changed from false to true.
			A value of true means the transport's properties reset after it calls a subassembly.
	on-error error handler component	rethrow-error	Default changed from true to false.
			A value of false means the runtime clears the error when the error handler fires.
			A value of true means the error handler must clear the error itself.
14.0	workday-out-soap	replace-with-soap-fault	Default changed from false to true.
			A value of true means the transport replaces the current message with the SOAP fault when one is returned.
	local-in	access	Default changed from public to private. A value of private means only a local-

Version	Component	Attribute/Property	Change Description	
			out in the same assembly can call the transport.	
			A value of public means any assembly can call the transport.	
	The aggregator component's message-content-collater strategy.	output-mimetype	Default changed from application/octet-stream to text/plain.	
			Custom collaters that implement the AggregationCollater interface still default to application/octetstream.	
18.0	store	immutable	New property that specifies whether the binary data that the blob references can be modified directly. Defaults to true.	
			A value of true means the blob is immutable and can't be modified.	
			A value of falsemeans the blob is mutable and can be modified.	
			Note: In Workday 18, the server runtime migrates all store steps on existing assemblies with old version numbers to use this new default setting, which makes blobs immutable. If your assembly needs to update a blob, make sure that you set immutable to false.	
2016.45	PagedGet	is.paged.get.version	Default changed from	7 111.1011
Note: After version 27, Workday introduced a new naming scheme in the form year.week			util.assemblyVersio	nAswwsvers
2019.30	PagedGet	As_Of_Effective_Date As_Of_Entry_DateTime	If no values are provided for these properties, they	

Version	Component	Attribute/Property	Change Description
			default to the current date and time (PST).
2020.09	ftp-out, ftps-out, sftp-out		Workday now uses JSCAPE version 9.3, which supports a wider set of encryption ciphers.
2020.09	PrismAnalytics	wd.prism.component.api.h	Stundimeow calls v2 of the Prism Analytics REST API.
			The component name has changed from PrismConnector to PrismAnalytics.

Related Information Reference

FAQ: Encryption, Certificates, and Ciphers for Integrations

Reference: Version Changes at the XML Level

This table below summarizes XML-level changes that have occurred for each version update.

Version	Previous XML element/ attribute	Replaced by	Meaning/Reason for change
11.0 (These changes all concern changes to integration-system definitions in the workday-in transport component.)	simple-type- reference	simple-type	The item's type is being declared, not referred to.
	type-reference	class-report-field	The new element name better represents the meaning.
	service	service-reference	The item is not being defined, it is being referred to. Removed the defined-by attribute, which is no longer used.
	integration- system/@template	Removed	No longer applies.
	param/@required	param/@option	Changed the boolean required attribute to an option attribute with a value of required, where true.
	cloud/name	cloud/@name	Less verbose.
	integration/name	in-connector/@id	Less verbose.
	in-connector/id	private-key	private-key

Version	Previous XML element/ attribute	Replaced by	Meaning/Reason for change
12.0	key-file	private-key	Affects sftp-out and ftps-out transports. Renamed the attribute to better reflect the meaning.
	public-key- properties	private-key- properties	Renamed to better reflect the meaning.
	aggregator/ @spawn-aggregated- processing	Removed	This feature allowed an aggregator to create a new task or thread to handle an aggregated message. This functionality was not used in Workday integrations and was not suitable for public Workday Studio, so it was removed.
	store/@compress store/@encrypt	Removed	Previously allowed fine- grained control over the store step. However, Workday policy on integrations is to always compress and encrypt, so they were removed.
	ftp-out/@tmp-directory sftp-out/@tmp-directory ftps-out/@tmp-directory	Removed	Previously these transports managed their own temp files, but were refactored to use common FileBackedManagedData (FBDM) capability, so these options were removed.
14.0	delivery-service/ child::*	Removed	Sub-elements of the delivery service defined the allowed transports. Such constraints should not be defined at design time. This is a runtime configuration task, so they were removed from the design time development stage.

Reference: Saxon XSLT Processor Changes

The following table summarizes Workday support for various versions of Saxon and XSLT. Note that after version 27, Workday introduced a new naming scheme in the form year.week.

Workday Version	Supported Saxon Version	Supported XSLT Version	Notes
<20	9.1	1.0, (2.0)	Limited support for XSLT version 2.0.
20-2017.05	9.4	2.0, (3.0)	Limited support for XSLT version 3.0.
2017.05-	9.7	3.0	Support for XSLT streaming.

Note: Studio displays a warning message if you create a collection containing assemblies with different version numbers. This is because differently versioned assemblies can require conflicting versions of Saxon, leading to class loading errors at runtime. Best practice is to use the latest assembly versions for all of your integrations.

Note the following:

- The XPath methods that are available in MVEL for accessing message parts and variables support XPath 3.0.
- The mctx URL protocol allows XSL developers to write to message parts and variables, for example:

```
<xsl:result-document href="mctx:vars/var1">...</xsl:result-document>
```

- Although there is no direct assembly support for XQuery, you can add custom steps to call XQuery scripts.
- In assemblies versioned 2022.46 or earlier, Saxon is set as the default transformer only when the use.saxon.transformer property is set to true in the mediation context. In assemblies versioned 2022.47 or later, Saxon is set as the default if that property is set to true or if it's not present.

Note: XSLT 2.0 and XSLT 3.0 are strongly typed. For example, they do not allow xs:string to be evaluated for equality in XPath expressions. The following expression, in which stringParam is an XSL parameter, results in a Saxon runtime error:

```
$stringParam = true()
```

The XSL compiler will not encounter the issue at deploy time, because it cannot predict what type the parameter will have in advance.

Your existing XSL documents and Workday Studio integrations will not be impacted by this strong typing issue, unless you choose to enable XSLT 3.0 by changing the version attribute value in your XSL documents to 3.0. If you encounter these runtime errors, which result from the XSLT that you deploy with your integration, you must take action to fix them.

Note: The following error relating to the Saxon upgrade has been observed in legacy XSL for business forms printing:

```
Failed to compile stylesheet. Xerrors detected. Invalid value for @case-order. Value must be one of (lower-first|upper-first).
```

If you encounter this error, check whether your XSL contains the following attribute setting on a sort element:

```
case-order="#default"
```

This optional case-order attribute determines whether the sort lists upper or lower case letters first in the sort. The default is to list upper case first. The Saxon parser accepts only these values for case-order:

upper-first

• lower-first

To fix this error, do one of the following:

- Remove the existing case-order attribute from the sort element, because it is an optional setting.
- Set the case-order value explicitly to upper-first.
- Set the case-order value explicitly to lower-first.

Sample Assemblies

Example: Run the Hello Cloud Sample Assembly

Context

Workday Studio enables you to deploy and launch integrations in Workday. This example demonstrates how to run a basic sample integration.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

Steps

- 1. On the Studio toolbar, select **Help** > **Welcome** > **Samples** > **Hello Cloud**.
- 2. On the Project Names window, click Finish.
- 3. On the Project Explorer view, expand the HelloCloud folder and double-click the Assembly folder.
- 4. On the Assembly Editor toolbar, click Show annotations.
- 5. On the Cloud Explorer view, click Connection Details.
- Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the Project Explorer view, right-click the HelloCloud folder and select Deploy to Workday.
- 9. On the Deploy to Workday window, select the Sandbox environment. Click Finish.
- 10.On the Cloud Explorer view, expand these nodes: Sandbox > HelloCloudCollection > HelloCloud.
- 11. Right-click the **StartHere** integration node and select **Launch Integration**.
- 12.Click Launch.

Result

The integration launches in your Workday tenant. The **Process Monitor** view in Studio displays the status of the integration.

Next Steps

Sign in to Workday and access the **Process Monitor** task to display the integration event details for the sample assembly.

Example: Run the Hello Workday Web Services Sample Assembly

Context

Workday Studio enables you to connect to Workday Web Services. This example demonstrates the SOAP web service request message <code>Get_Workers_Request</code>. It uses XSLT 3.0 streaming to process the request.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

Steps

- 1. On the Studio toolbar, select Help > Welcome > Samples > Hello Workday Web Services.
- 2. On the Project Names window, click Finish.
- 3. On the Project Explorer view, expand the HelloWWS folder and double-click the Assembly folder.
- 4. On the Assembly Editor toolbar, click Show annotations.
- 5. On the Cloud Explorer view, click Connection Details.
- 6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the Project Explorer view, right-click the HelloWWS folder and select Deploy to Workday.
- 9. On the Deploy to Workday window, select the Sandbox environment and click Finish.
- 10.On the Cloud Explorer view, expand these nodes: Sandbox > HelloWWSCollection > HelloWWS.
- 11.Right-click the HelloWWS_EntryPoint integration node and select Launch Integration.
- 12.Click Launch.

Result

The integration launches in your Workday tenant. The **Process Monitor** view in Studio displays the status of the integration.

Next Steps

Sign in to Workday and access the **Process Monitor** task to display the integration event details for the sample assembly.

Context

This example demonstrates some common integration design patterns. It contains multiple separate processing chains, each of which illustrates a different pattern.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

- 1. On the Studio toolbar, select **Help** > **Welcome** > **Samples** > **Common Usage Patterns**.
- 2. On the Project Names window, click Finish.
- 3. On the **Project Explorer** view, expand the **CommonUsagePatterns** folder and double-click the **Assembly** folder.
- **4.** On the Assembly Editor toolbar, click **Show annotations**.
- 5. On the Cloud Explorer view, click Connection Details.
- 6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the **Project Explorer** view, right-click the **CommonUsagePatterns** folder and select **Deploy to Workday**.
- 9. On the Deploy to Workday window, select the Sandbox environment and click Finish.
- **10.**On the **Cloud Explorer** view, expand these nodes: **Sandbox** > **CommonUsagePatterns** > **CommonUsagePatterns**.
- **11.**Right-click the **Conditional-Processing** integration node and select **Launch Integration**.
- 12.Click Launch.

13.Launch each of these integration nodes:

- Enriching
- Global-Error-Handling
- Local-Error-Handling
- Looping
- · Request-Response-Processing-Chain
- · Response-Chaining
- Routing
- Scalable-Message-Processing
- Simple-Processing-Chain
- SubRoutines
- Variables

The Request-Response-Processing-Chain and Response-Chaining integrations have an additional launch parameter: Employee ID. Click Select literal value to configure it.

Result

The integration launches in your Workday tenant. The **Process Monitor** view in Studio displays the status of the integration.

Next Steps

Sign in to Workday and access the **Process Monitor** task to display the integration event details for the sample assembly.

Example: Run the Debugging Sample Assembly

Context

Workday Studio enables you to detect and debug errors in your integrations. This example demonstrates how to debug a sample integration.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Debug
- Integration Event

- On the Studio toolbar, select Help > Welcome > Samples > Assembly Debugger.
- 2. On the Project Names window, click Finish.
- **3.** On the **Project Explorer** view, expand the **AssemblyDebug** folder and double-click the **Assembly** folder.
- 4. On the Assembly Editor, right-click each of these assembly elements and select Toggle Assembly Breakpoint:
 - create-get-workers-request
 - store-summary-doc
- 5. On the Cloud Explorer view, click Connection Details.

6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the Project Explorer view, right-click the AssemblyDebug folder and select Deploy to Workday.
- 9. On the Deploy to Workday window, select the Sandbox environment and click Finish.
- 10.On the Cloud Explorer view, expand these nodes: Sandbox > AssemblyDebug > AssemblyDebug.
- **11.**Right-click the **Start-Here** integration node and select **Debug Integration**.
- 12.Click Debug.
- 13.On the Confirm Perspective Switch window, click Yes.
- 14.On the Assembly Debug view, select the Message Root Part tab and click Save the message or attachment to a document in the workspace.
- **15.**On the **Save** window, enter these values:

Option	Description
Parent Folder	AssemblyDebug
File name	rootpart.xml

- **16.**On the **Debug** view, right-click the **Create-Request create-get-workers-request** breakpoint and select **Resume**.
- 17.On the Assembly Debug view, select the Message Root Part tab and click Save the message or attachment to a document in the workspace.
- **18.**On the **Save** window, enter these values:

Option	Description
Parent Folder	AssemblyDebug
File name	rootpart1.xml

19.On the Debug view, right-click the Store - store-summary-doc breakpoint and select Terminate.

Result

Studio saves the XML breakpoint files to the **AssemblyDebug** project folder. You can use these files to troubleshoot bugs in your assembly.

Next Steps

Open the XML breakpoint files for your assembly.

Example: Run the Workday-In Features Sample Assembly

Context

The **workday-in** transport component is represented in Workday as an integration system. This sample demonstrates how you can use MVEL expressions in a Workday Studio assembly to reference the integration system's services and launch parameters. It contains 3 separate processing chains.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

- 1. On the Studio toolbar, select **Help** > **Welcome** > **Samples** > **Workday-In Features**.
- 2. On the Project Names window, click Finish.
- **3.** On the **Project Explorer** view, expand the **WorkdayInFeatures** folder and double-click the **Assembly** folder.
- **4.** On the Assembly Editor toolbar, click **Show annotations**.
- 5. On the Cloud Explorer view, click Connection Details.
- 6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- **8.** On the **Project Explorer** view, right-click the **WorkdayInFeatures** folder and select **Deploy to Workday**.
- 9. On the **Deploy to Workday** window, select the **Sandbox** environment and click **Finish**.
- **10.**For each of the individual integrations, consider:

Integration	Note
AttributesAndMaps	After deployment, you can adjust the attribute and map values in Workday.
	 a. Access the View Integration System report and select WorkdayInFeatures-attr-maps. b. From the related actions menu of the ExampleAttrMapService integration service, select Integration Generic Service > Configure Integration Attributes or Integration Generic Service > Configure Integration Maps. c. Adjust the attribute and map values as required.
LaunchParameters	On the Cloud Explorer view in Studio, expand these nodes: Sandbox > WorkdayInFeatures > WorkdayInFeatures.
	 a. On the referenceParam field, click Select literal values and select an employee. b. Enter password in the passwordParam field.
SequenceGenerator	After deployment, you can configure the Sequence Generator service in Workday:

12.Right-click a workday-in transport node and select **Launch Integration**. Example: **AttributesAndMaps**. **13.**Click **Launch**.

Result

The integration launches in your Workday tenant. The **Process Monitor** view in Studio displays the status of the integration.

Next Steps

Sign in to Workday and access the **Process Monitor** task to display the integration event details for the sample assembly.

Example: Run the Error Handling Sample Assembly

Context

This example demonstrates several approaches to error handling in Workday Studio. It contains 6 different processing chains, each of which illustrates a different pattern.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

- 1. On the Studio toolbar, select **Help > Welcome > Samples > Error Handling**.
- 2. On the Project Names window, click Finish.
- On the Project Explorer view, expand the ErrorHandling101 folder and double-click the Assembly folder.
- On the Assembly Editor toolbar, click Show annotations.
- 5. On the Cloud Explorer view, click Connection Details.

^{11.}On the Cloud Explorer view, expand these nodes: Sandbox > WorkdayInFeatures > WorkdayInFeatures.

6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the Project Explorer view, right-click the ErrorHandling folder and select Deploy to Workday.
- 9. On the Deploy to Workday window, select the Sandbox environment and click Finish.
- 10.On the Cloud Explorer view, expand these nodes: Sandbox > ErrorHandling > ErrorHandling.
- 11.Right-click a workday-in transport node and select Launch Integration. Example: All-Or-Nothing.
- 12.Click Launch.

Result

The integration launches in your Workday tenant. The **Process Monitor** view in Studio displays the status of the integration.

Next Steps

Sign in to Workday and access the **Process Monitor** task to display the integration event details for the sample assembly.

Example: Run the AUnit Sample Tests

Context

AUnit is a Workday Studio test framework that enables you to perform unit tests on your assemblies. This example demonstrates how to run AUnit tests. It contains 8 separate processing chains.

Steps

- On the Studio toolbar, select Help > Welcome > Samples > AUnit Tests.
- 2. On the Project Names window, click Finish.
- 3. On the Project Explorer view, expand the AUnit 101 folder and double-click the Assembly folder.
- 4. On the Assembly Editor toolbar, click Show annotations.
- 5. Run the AUnit 101 sample tests.
 - a) On the Project Explorer view, expand the src folder.
 - b) Right-click the **com.workday.example.aunit** folder.
 - c) Select Run As > AUnit Test.

Result

Studio displays the results of the sample tests on the **Console** view.

Next Steps

Navigate to the **JUnit** view to display a detailed summary of the results.

Context

Workday Studio enables you to generate PDF files in the output of your integrations. This example demonstrates how to generate basic PDF documents. It contains 3 separate processing chains.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

Steps

- 1. On the Studio toolbar, select Help > Welcome > Samples > FOP Step.
- 2. On the Project Names window, click Finish.
- 3. On the **Project Explorer** view, expand the **FOPStep** folder and double-click the **Assembly** folder.
- 4. On the Cloud Explorer view, click Connection Details.
- 5. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 6. Click Apply and Close.
- 7. On the Project Explorer view, right-click the FOPStep folder and select Deploy to Workday.
- 8. On the Deploy to Workday window, select the Sandbox environment. Click Finish.
- 9. On the Cloud Explorer view, expand these nodes: Sandbox > FOPStep > FOPStep.
- 10. Right-click the Simple-Start integration node and select Launch Integration.
- 11.Click Launch.
- **12.**On the **Process Monitor** view, right-click the integration and select **Workday: Integration ESB Invocation**.
- 13.On the Workday view, enter these values:

Option	Description
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- **14.**On the **View Background Process** window, select the **Output Files** tab.
- **15.**On the **File** column of the **Reports and Other Output Files** table, double-click the PDF file.
- **16.**Launch the **Invoice-Start** and **Kanji-Start** integration nodes.

Result

Workday displays the newly generated PDF files.

Download and save the PDF files.

Example: Run the Extract Organization Data for a Worker Sample Assembly

Context

Workday enables you to categorize workers into groups using organization types. This example demonstrates how to run an integration that extracts the organization type and employee id values of a worker from Workday.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

- 1. On the Studio toolbar, select Help > Welcome > Samples > Extract Organization Data for a Worker.
- 2. On the Project Names window, click Finish.
- On the Project Explorer view, expand the OrgDataForWorkerForOrgType folder and double-click the Assembly folder.
- **4.** On the Assembly Editor toolbar, click **Show annotations**.
- 5. On the Cloud Explorer view, click Connection Details.
- 6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- **8.** On the **Project Explorer** view, right-click the **OrgDataForWorkerForOrgType** folder and select **Deploy to Workday**.
- 9. On the Deploy to Workday window, select the Sandbox environment. Click Finish.
- 10.On the Cloud Explorer view, expand these nodes: Sandbox > OrgDataForWorker > OrgDataForWorkerForOrgType.
- 11.Right-click the StartGetOrgForOrgType integration node and select Launch Integration.
- 12.On the Launch Integration window, navigate to the Launch Parameters section.
- 13.On the OrgType field, click Select literal values.
- 14.On the Select Class Report Field window, click Next.
- **15.**On the **CRF** window, select an organization type. As you complete the task, consider:

Option	Description
Name	The name of the organization type.
WID	The Workday ID of the organization type.

- 16.Click Finish.
- 17.On the EmployeeID field, click Select literal values.
- 18.On the Select Class Report Field window, click Next.
- 19. On the CRF window, select an employee. As you complete the task, consider:

Option	Description
Name	The name of the employee.
WID	The Workday ID of the employee.

- 20.Click Finish.
- 21.Click Launch.
- **22.**On the **Process Monitor** view, right-click your integration.
- 23. Select Show Details View.
- 24.On the Process Details view, expand the OrgType and EmployeeID launch parameter fields.

Result

Studio displays the organization type and employee id values of the worker on the Process Details view.

Example: Run the PrismAnalytics Sample Assembly

Context

This example demonstrates how to use the **PrismAnalytics** component to send CSV data to Workday Prism Analytics. Source CSV files are provided in the assembly project. For the purposes of this example, copy these files to an SFTP server for retrieval by the sample assembly.

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

- Register a Prism API client and copy values that the PrismAnalytics component requires.
 - a) In Workday, access the Register API Client for Integrations task.
 - b) Register an API client with **Prism Analytics** as its **Scope (Functional Area)**. Select the **Include Workday Owned Scope** check box.
 - c) Copy the Client ID and Client Secret values.
 - d) From the related actions menu, select API Client > Manage Refresh Tokens for Integrations.
 - e) Select a **Workday Account** to associate with the refresh token. The account must have permission to create Prism tables in Workday.
 - f) Generate a refresh token and copy the value.
- 2. Obtain Workday REST API Endpoint.
 - a) Access the View API Clients report.
 - b) Copy the **Workday REST API Endpoint** value. Delete the https:// at the beginning and the / ccx/api/v1/<tenant_name> at the end.
- 3. On the Studio toolbar, select Help > Welcome > Samples > PrismAnalytics.
- 4. On the Project Names window, click Finish.

- On the Project Explorer view, expand the PrismAnalytics folder and double-click the Assembly folder.
- 6. Copy the provided sample CSV files to your SFTP server.
 - a) In the PrismAnalytics project folder, expand ws > WSAR-INF > PrismAnalytics Sample CSVs.
 - b) Copy these files to your SFTP server:
 - states.csv
 - states2.csv
 - states3.csv
 - states4.csv
 - states5.csv
- 7. On the Assembly Editor toolbar, click Show annotations.
- 8. On the Cloud Explorer view, click Connection Details.
- 9. Select the **Sandbox** environment and enter these values on the **Connections** window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 10. Click Apply and Close.
- 11.On the Project Explorer view, right-click the PrismAnalytics folder and select Deploy to Workday.
- 12.On the Deploy to Workday window, select the Sandbox environment and click Finish.
- **13.**On the **Cloud Explorer** view, launch 1 of the integrations in this sample.
 - a) Expand the Sandbox node.
 - b) Expand the **PrismAnalyticsCollection** collection node.
 - c) Expand the **PrismAnalytics** project node.
 - Right-click a workday-in transport node and select Launch Integration. Example: SingleCSV.
- 14.Click Launch.

Result

Workday Prism Analytics creates a table using the CSV data you supplied.

Third-Party Payroll Interface Sample

Steps: Run the Payroll Interface Sample

Context

In this example, an integration called **PayData Extract** extracts data relating to one-time payments for a pay group. A second Studio integration cycles through the integration event documents and uses XSLT 3.0 streaming to process them.

Steps

1. Create the Payroll Interface Security Group on page 353.

Create a security group with access to the domains required by the payroll interface sample.

2. Access the Create Integration System User task.

Create an integration system user for the PayData Extract integration. Example: PayData Extract ISU.

Select **Security Profile** > **Assign Integration System Security Groups** from the related actions menu of the integration system user. On the **Integration System Security Group to Assign** prompt, select *Payroll Interface Security*.

Security: Integration Security domain in the Integration functional area.

3. Create the PayData Extract Integration System on page 354.

Create an integration in Workday that extracts one-time payment data for a pay group.

- Test the PayData Extract Integration System on page 355.
- 5. Deploy the Studio PayData Integration on page 356.

Deploy a Studio integration that cycles through the **PayData Extract** integration event documents and uses XSLT 3.0 streaming to process them.

6. Access the Create Integration System User task.

Create an integration system user for the PayData integration. Example: PayData ISU.

Security: Integration Security domain in the Integration functional area.

- 7. Assign an Integration System User to the PayData Integration on page 356.
- 8. Link the PayData Extract and PayData Integrations on page 357.
- **9.** Launch the Linked Integrations on page 358.

Create the Payroll Interface Security Group

Prerequisites

Security: Security Configuration domain in the System functional area.

Context

Before you can run the payroll interface sample in Studio, you need to create a security group in Workday.

Steps

- 1. Sign in to your Workday test environment.
- 2. Access the Create Security Group task. As you complete the task, consider:

Option	Description
1 * * * * * * * * * * * * * * * * * * *	Integration System Security Group (Unconstrained)
Name	Payroll Interface Security

- 3. Access the View Security Group report.
- **4.** Select *Payroll Interface* Security from the **Security Group** prompt.
- 5. From the related actions menu of the security group, select **Security Group > Maintain Domain Permissions for Security Group**.
- 6. Select these domains from the Domain Security Policies permitting Get access prompt:
 - Payroll Interface
 - Manage: Organization Integration
 - Worker Data: Public Worker Reports
 - Worker Data: Compensation by Organization

Workday alerts you that you must activate your security policy changes.

- 7. Access the Activate Pending Security Policy Changes task and enter a comment.
- 8. Select the Confirm check box.

Result

Workday adds your new security group to the domain security policies of each relevant functional area.

Next Steps

Create an integration system user to run the PayData Extract integration.

Create the PayData Extract Integration System

Prerequisites

Security: Integration Build and Integration Configure domains in the Integration functional area.

Context

Create an integration in Workday that extracts one-time payment data.

Steps

- 1. Sign in to your Workday test environment.
- 2. Access the Create Integration System task.
- 3. As you complete the Create Integration System task, consider:

Option	Description
System Name	PayData Extract
New Using Template	Payroll Interface

- **4.** On the **Configure Integration Services** page, select the **Enabled** check box for these integration services:
 - Payroll Interface/PI Change Detection Launch Parameters
 - Payroll Interface/PI Pay Data Section Fields
 - Payroll Interface/PI Filename

Workday alerts you that you must assign values to some Integration Attributes and configure a Sequence Generator for the integration system.

- On the related actions menu for the PayData Extract integration system, select Workday Account > Edit.
- **6.** On the **Workday Account** prompt, enter the name of the integration system user for the **PayData Extract** integration system.
- 7. On the Edit Account for Integration System page, click OK.
- 8. On the related actions menu for the **PayData Extract** integration system, select **Integration System > Configure Integration Attributes**. As you complete the task consider:

Option	Description
Version	Add a row and select the value 25.
Output Document Tags	Add a row, select Create Document Tag , and enter the Document Tag Name <i>PICOF</i> .
Primary Payroll Integration	Add a row.
Payroll Vendor	Add a row and select any vendor.

On the related actions menu for the PayData Extract integration system, select Integration System >
 Configure Integration Field Attributes.

10.In the Field Configuration section, select the Include in Output check box for these fields:

- Code
- Date
- Earning or Deduction
- Amount
- 11.On the related actions menu for the **PayData Extract** integration system, select **Integration System > Configure Integration Sequence Generators**.
- **12.**On the **Configure Integration Sequence Generators** page, consider:

Option	Description
Increment by	1
Format/Syntax	Payrollinterface-paydata-[Seq].xml

Result

Workday configures the PayData Extract integration system.

Next Steps

Test the **PayData Extract** integration system.

Test the PayData Extract Integration System

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

Context

Before you can run the payroll interface sample in Studio, you need to test the integration system for it in Workday.

- 1. Sign in to your Workday test environment.
- Access the View Integration System task.
- 3. On the Integration System prompt, enter PayData Extract.
- **4.** On the related actions menu for the **PayData Extract** integration system, select **Integration > Launch/ Schedule**.
- **5.** On the **Schedule an Integration** page, enter these values in the **Value** column:

Option	Description
Pay Group	Select any pay group that has one-time payments.
Pay Period Selection Option	Use Pay Period for Current Date.
Last Successful Run	Select a date after which there have been new one-time payments.

6. Launch the integration and refresh until it completes.

Result

The PayData Extract integration system launches in Workday.

Next Steps

Deploy the PayData integration to Workday from Studio.

Deploy the Studio PayData Integration

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure

Context

The Studio **PayData** integration cycles through the **PayData Extract** integration event documents and uses XSLT 3.0 streaming to process them. Before you can launch it, you must deploy it to Workday.

Steps

- 1. On the Studio toolbar, select **Help** > **Welcome** > **Samples** > **Payroll Interface**.
- 2. On the Project Names window, click Finish.
- 3. On the **Project Explorer** view, expand the **PayData** folder and double-click the **Assembly** folder.
- 4. On the Assembly Editor toolbar, click Show annotations.
- 5. On the Cloud Explorer view, click Connection Details.
- 6. Select the Sandbox environment and enter these values on the Connections window:

Option	Description
Tenant	The name of your tenant.
Username	The username credentials for your tenant.
Password	The password credentials for your tenant.

- 7. Click Apply and Close.
- 8. On the Project Explorer view, right-click the PayData folder and select Deploy to Workday.
- 9. On the Deploy to Workday window, select the Sandbox environment. Click Finish.

Result

Studio deploys the **PayData** sample integration to Workday.

Next Steps

Create an integration system user to run the **PayData** integration.

Assign an Integration System User to the PayData Integration

Prerequisites

Security: Integration Configure domain in the Integration functional area.

Context

Assign an integration system user to the PayData integration system in Workday.

Steps

- 1. On the Cloud Explorer view, expand these nodes: Sandbox > PayData > PayData.
- **2.** Right-click the **StartHere** integration node.
- 3. Select Workday: Integration System.
- 4. On the Workday view, consider:

Option	Description
	The username credentials for your Workday tenant.
Password	The password credentials for your tenant.

- 5. On the related actions menu for the PayData integration system, select Workday Account > Edit.
- **6.** On the **Workday Account** prompt, enter the name of the integration system user for the **PayData** integration system.
- 7. On the Edit Account for Integration System page, click OK.

Result

Workday assigns an integration system user to the PayData integration system.

Next Steps

Link the PayData Extract and PayData integrations.

Link the PayData Extract and PayData Integrations

Prerequisites

Security: Integration Configure domain in the Integration functional area.

Context

Link the PayData Extract and PayData integrations in Workday.

Steps

- **1.** Sign in to your Workday test environment.
- 2. Access the View Integration System task.
- **3.** On the **Integration System** prompt, enter *PayData Extract*.
- 4. On the related actions menu for the **PayData Extract** integration system, select **Business Process** > **Create**, **Copy**, **or Link Definition**.
- **5.** Click **OK** to create a new business process definition.
- 6. On the Business Process Steps tab of the Edit Business Process Integration Process Event for PayData Extract (TOP LEVEL) page, click Add Row. On the new row, consider:

Option	Description
Order	С
Туре	Integration

Workday warns you that configuration isn't yet complete.

- 7. Click Configure Integration System.
- 8. On the Integration prompt, select PayData.
- 9. On the Integration Attributes tab of the Configure Integration Step page, consider:

Option	Description
Value Type	Determine Value at Runtime
Value	Deliverable Documents

Result

Workday links the PayData Extract and PayData integrations together to deliver the required output.

Next Steps

Launch the linked PayData Extract and PayData integrations in Workday.

Launch the Linked Integrations

Prerequisites

Security: These domains in the Integration functional area:

- Integration Build
- Integration Configure
- Integration Event

Context

Launch the PayData Extract integration that is now linked to the PayData integration.

- 1. Sign in to your Workday test environment.
- 2. Access the View Integration System task.
- 3. On the Integration System prompt, enter PayData Extract.
- On the related actions menu for the PayData Extract integration system, select Integration > Launch/ Schedule.
- **5.** On the **Schedule an Integration** page, enter these values in the **Value** column:

Option	Description
Pay Group	Select any pay group that has one-time payments.
Pay Period Selection Option	Use Pay Period for Current Date.
Last Successful Run	Select a date after which there have been new one-time payments.

- **6.** Launch the integration and refresh until it completes.
- **7.** On the **Event Documents** section, note the CSV file that Workday produced. Example: payrollinterface-paydata-1.csv.