# Linkmodel: sn (EXPERIMENTAL)

#### **Parametrization**

This is the link that map  $p \in (0,1)$  into  $x \in \Re$ , where

$$F_a(x) = p$$

and  $F_a$  is the cumulative distribution function for the skew-normal distribution,

$$2\phi(x)\Phi(a^{1/3}x)$$

which is renormalized to have zero mean and unit variance (expression omitted).

### **Hyperparameters**

The parameter a represented using the (standarized) skewness s (expression omitted) where

$$s = s_{\max} \left( 2 \frac{\exp(\theta)}{1 + \exp(\theta)} - 1 \right)$$

 $s_{\text{max}} = 0.988$ , and the prior is defined on  $\theta$ . There is a PC prior available for  $\theta$ . The PC-prior is corrected for this bound, whereas the pc-prior in the R-functions inla.pc. $\{r,p,q,d\}$ sn does not define a such bound (but use the bound defined by the Skew-Normal itself, 0.99527...).

### Specification

Use model="sn" within control.link.

#### Hyperparameter spesification and default values

doc Skew-normal link

hyper

#### theta1

hyperid 49031

name skewness

short.name skew

initial 0.00123456789

fixed FALSE

prior pc.sn

param 10

to.theta function(x, skew.max = 0.988) log((1 + x / skew.max) / (1 - x / skew.max))

from.theta function(x, skew.max = 0.988) skew.max \* (2 \* exp(x) / (1 + exp(x)) - 1)

#### theta2

hyperid 49032

name intercept

short.name intercept

initial 0

fixed FALSE

prior linksnintercept

```
param 0 0
to.theta function(x) log(x / (1 - x))
from.theta function(x) exp(x) / (1 + exp(x))
```

 $\mathbf{pdf}$  linksn

## Example

## Notes

- The link-function is also available as R-functions inla.link.sn and inla.link.invsn
- This link-model is experimental for the moment.
- Setting the initial value for the hyperparameter "intercept" to infinity, will remove the intercept from the link-model.