General Configuration

Outline:

- Introduction
- · Waldur Core settings
- · Admin dashboard configuration
- Custom templates configuration
- · Local time zone configuration

Introduction

Waldur is a Django-based application, so configuration is done by modifying settings.py file.

If you want to configure options related to Django, such as tune caches, database connection, configure custom logging, etc, please refer to Django documentation.

Configuration for Waldur Core is namespaced inside a single Django setting, named WALDUR_CORE. Usually each plugin's settings are namespaced, so please refer to plugin documentation for details.

Basic configuration might look like this:

```
WALDUR_CORE = {
   'ENABLE_GEOIP': True,
   'EXTENSIONS_AUTOREGISTER': True,
   'GOOGLE_API': {
        'Android': {
            'server_key': 'AIzaSyA2_7UaVIxXfKeFvxTjQNZbrzkXG90TCkg',
        'iOS': {
             'server_key': 'AIzaSyA34zlG_y5uH0e2FmcJKwfk2vG-3RW05vk',
    'SHOW_ALL_USERS': False,
    'OWNER_CAN_MANAGE_CUSTOMER': False,
    'CREATE_DEFAULT_PROJECT_ON_ORGANIZATION_CREATION': False,
    'TOKEN_KEY': 'x-auth-token',
   'TOKEN_LIFETIME': timedelta(hours=1),
   'SITE_NAME': 'Waldur MasterMind',
    'COUNTRIES': ['EE', 'LV', 'LT'],
    'NOTIFICATIONS_PROFILE_CHANGES': {
        'ENABLED': True,
       'FIELDS': ('email', 'phone_number', 'job_title')
   },
```

Waldur will send notifications from email address specified in <code>DEFAULT_FROM_EMAIL</code> variable. for example,

```
DEFAULT_FROM_EMAIL = 'noreply@example.com'
```

Waldur Core settings

- ALLOW_SIGNUP_WITHOUT_INVITATION is disabled by default. Set to True to enable signup by invitation only.
- AUTHENTICATION_METHODS is a list of enabled authentication methods. It allows you to restrict enabled authentication methods.
- BACKEND_FIELDS_EDITABLE allows to control /admin writable fields. If this flag is disabled, it is impossible to edit any field that corresponds to backend value via /admin. Such restriction allows to save information from corruption. Flag is enabled by default.
- COMPANY_TYPES specifies list of available company types, it is used in organization creation dialog. By default *Ministry*, *Private company*, *Public company*, *Government owned company* are available.
- COUNTRIES list is used in organization creation dialog in order to limit country choices to predefined set.
- CREATE_DEFAULT_PROJECT_ON_ORGANIZATION_CREATION enables generation of the first project on organization creation.

- CURRENCY_NAME is used in marketplace order details and invoice for currency formatting.
- ENABLE_ACCOUNTING_START_DATE allows to enable accounting only for organizations using value of accounting_start_date field. Disabled by default.
- ENABLE_GEOIP indicates whether geolocation is enabled (boolean). Enabled by default.
- EXTENSIONS_AUTOREGISTER defines whether extensions should be automatically registered (boolean).
- GOOGLE_API is settings dictionary for Google Cloud Messaging:
 - Android specifies settings for Android devices. server_key is Google Cloud messaging server key.
 - IOS specifies settings for IOS devices. server_key is Google Cloud messaging server key.
- NOTIFICATION_TITLE is string to be displayed in the notification pop-up title.
- INITIAL_CUSTOMER_AGREEMENT_NUMBER allows to tweak initial value of agreement number (4000 by default). It is assumed that organization owner should accept terms of services when organization is registered via Waldur HomePort.
- INVITATION_LIFETIME defines for how long invitation remains valid. Default value 1 week.
- INVITATIONS_ENABLED allows to enable invitations feature. Enabled by default.
- NATIVE_NAME_ENABLED allows to render native name field in customer and user forms. Disabled by default.
- NOTIFICATIONS_PROFILE_CHANGES allows enabling notifications about profile changes of organization owners and allows selecting, which fields of profile should be tracked.
- OWNER_CAN_MANAGE_CUSTOMER enables organization owners to create an organization (boolean).
- OWNERS_CAN_MANAGE_OWNERS enables organization owners to manage other organization owners, enabled by default.
- ONLY_STAFF_MANAGES_SERVICES allows to restrict provider management only to staff users, disabled by default. Please also note, that if this flag is enabled, OpenStack tenant provision & modification would be available for staff users only. It means that organization owners wouldn't be able to manage virtual private clouds.
- SELLER_COUNTRY_CODE specifies seller legal or effective country of registration or residence as an ISO 3166-1 alpha-2 country code. It is used for computing VAT charge rate.
- SHOW_ALL_USERS indicates whether user can see all other users in api/users/ endpoint (boolean).
- SITE_NAME is used in email notifications in order to refer to the current deployment in user-friendly way.

- SITE_ADDRESS is used in marketplace order header.
- SITE_EMAIL is used in marketplace order header.
- SITE_PHONE is used in marketplace order header.
- SITE_L0G0 is used in marketplace order header.
- TOKEN_KEY is header for token authentication. For example, 'x-auth-token'.
- TOKEN_LIFETIME defines for how long user token should remain valid if there was no action from user (timedelta value, for example timedelta(hours=1)).
- VALIDATE_INVITATION_EMAIL allows to ensure that invitation and user emails match. Disabled by default.

Admin dashboard configuration

An admin dashboard supports custom links on Quick access panel. For instance, a panel below was configured with one additional link to https://waldur.com:



Configuration of custom links is stored under FLUENT_DASHBOARD_QUICK_ACCESS_LINKS settings key and for current example has following structure:

Here is a short description of link parameters:

Name	Туре	Required	Description
description	string	No	Tool tip on the link
external	boolean	No	Specifies whether additional icon indicating an external URL has to be added
url	URL	Yes	A URL of the link
title	string	Yes	A title of the generated link
attrs	dict	No	A dictionary of anchor attributes to be added to generated element

It is also possible to omit optional fields and add links by specifying only a title and a URL to the generated link.

```
FLUENT_DASHBOARD_QUICK_ACCESS_LINKS = [
  ['[Custom] Waldur - Cloud Service', 'https://waldur.com'],
  ['Find us on GitHub', 'https://github.com/opennode/waldur-core'],
]
```

Custom templates configuration

To overwrite default templates you should use django-dbtemplates. It allows creation of templates through /admin.

Local time zone configuration

Set TIME_ZONE setting in /etc/waldur/override.conf.py to use local time zone. By default it is set to UTC. See the list of time zones for possible options.