How to setup JumpCloud LDAP Service for Synology NAS


Preparation	3
Create Users	4
Create Groups	6
File Sharing with NT-Password	8
Reference	12

Preparation


- 1. Register account in the jump cloud website
- https://console.jumpcloud.com/
- 2. Login

Create Users


1. At page USERS, click the "+" to add user




- 2. We want to add user "testuser1"
- Because we want to allow user to bind LDAP
- => Enable the option [Enable as LDAP Bind DN]




- it will show alert message, and click [continue]



3. Select groups to join




4 Select Directory here




- click [save user] to apply Setting

Create Groups


1. At page GROUPS, choose [Create Group of Users]




- 2. Add group name "testgroup1"
- because Synology need attribute objectClass: posixGroup
- => Enable the option [Create Linux group for this user group]
- You **can't** use the same name "testgroup1" as GROUP NAME, so we rename it "tg1" and give an arbitrary number for GID



3. Select users to join the group



4. Select directory to user



5. click [save group] to apply setting


File Sharing with NT-Password

If you don't want to use File Sharing with plain text password, you have to enable Samba Schema in the JumpClound LDAP Service


- 1. Login your DS with SSH
- 2. Use command to get SAMBA SID
- >> net getlocalsid

SID for domain xxxx is: **S-1-5-21-1413691194-1125850329-771830121**

- 3. Modify setting from [DIRECTORIES]
- click to edit [JumpCloud LDAP]



- 4. Enable option [Configure Samba Authentication]
- WORKGROUP: same as the setting in the DSM Control Panel




- SID: copy the result from Step 2


- SAMBA SERVICE ACCOUNT: select the user you used to bind jumpcloud in the Synology NAS, e.g. testuser1



- 5. Click [save] to apply setting
- 6. You can check the status from [DIRECTORIES] -> [JumpCloud LDAP] -> [USERS]




7. Login DSM, and go to [Control Panel] -> [Domain/LDAP] -> [LDAP]




8. Setup LDAP Client

- Server address: Idap.jumpcloud.com
- Encryption: must be SSL/TLS or STARTTLS
- Base DN: ou=Users,o=YOUR_ID,dc=jumpcloud,dc=com
 - you can find YOUR_ID in the JumpCloud



9. Click [Apply] to save change

- you have to enter the Bind DN and Password



- 10. Check User/Group List
- you can find user list in the LDAP Users
- you can find group list in the LDAP Group



11. Done!! You can use File Sharing with NT-Password now.

Reference

[1]

https://support.jumpcloud.com/customer/en/portal/topics/947955-getting-started/articles

[2]

https://support.jumpcloud.com/customer/en/portal/articles/2440742-configuring-a-synology-nas-to-use-jumpcloud-s-ldap-as-a-service

[3]

https://support.jumpcloud.com/customer/portal/articles/2873709