Linux系统编程之-read与write使用

Linux系统编程之-read与write使用 概述 系统调用open()打开文件 open基本使用 inode结构 系统调用read()读取文件 系统调用write()读取文件

概述

Linux哲学"一切皆文件",我们也知道,文件操作中最基本的就是打开(open)、读(read)、写(write),内核会为每个进程维护一个打开文件的列表,该列表称为文件表。文件表由一些非负整数进行索引,这些非负整数称为文件描述符(file descriptors,简称为fds)。列表的每一项是一个打开文件的信息,包括指向该文件的索引节点(inode),其中inode中保存除了文件名以外的元数据信息。内核空间和用户空间都使用文件描述符作为唯一cookies,即**打开文件会返回文件描述符,而后续的操作都会将文件描述符作为基本的参数**。它包含以下要点:

- 内核会为每个进程维护一个文件表,而该文件表通过非负整数索引,我们把这个 非负整数称为文件描述符 (fds)
 - 。 fds用整数来表示
 - 。fds存在最大的上限,默认情况下为1024
 - 。 负数表示文件操作函数返回错误
 - 。 因此,文件操作的返回值在Linux中应该是ssize_t (signed size_t)类型

系统调用open()打开文件

open基本使用

```
#include <sys/types.h> // It is finded in the
/usr/include/sys/types.h.
#include <sys/stat.h> //It is finded in the
/usr/include/sys/stat.h.
```


```
#include <fcntl.h> //fcntl means file control. It defines the file
   control operate.
4 #include <stdio.h> //It includes perror(const char *str)
5 #include <unistd.h> //It includes read(int fd, void* buf, size_t
   len)
6 #include <errno.h>
  #include <string.h> //It includes memset(void *str, int value,
   size_t __n)
  #define BUFFER_SIZE 4096
8
9
10 | int main (int argc,char *argv[]){
     int fd; // It is the File Description which is used int the Linux
   System.
12
     fd = open("/home/os/Papers/Technical-
   Documents/OS/linux_system_programming/code/file/testRead.c",O_RDONLY)
     if (fd == -1){
13
       perror("main");
14
     }else{
15
       printf("Success!\n");
16
17
     }
18
     ssize_t ret; // signed size_t, the negative numbers mean error
19
20
     char buf[BUFFER_SIZE]; //It means the buffer for the reading
21
   operating.
22
     memset(&buf,0,BUFFER_SIZE); //It means the initial value for every
   value in the buffer
23
24
     while ((ret = (read(fd,&buf,BUFFER_SIZE))) != 0){
       if (ret == -1){
25
          if (errno == EINTR) //It means interupts
26
27
              continue;
          perror("main");
28
          break;
29
       }
30
       for (int i = 0; i < BUFFER_SIZE; i++){</pre>
31
         printf("%c",buf[i]);
32
33
       }
34
     }
     if (close(fd) == -1){
35
       perror("fd_close:");
36
```

```
37  }
38  return 0;
39 }
```

需要注意:使用open系统调用打开文件后,会返回对应文件的文件描述符fd,该文件描述符将作为后续read、write、close系统调用的输入参数。open的详细介绍参见: http://man7.org/linux/man-pages/man2/open.2.html。

inode结构

假设当前文件分配到的inode为4,在这个inode中记录了该文件实际存放的物理块的位置,还包括文件的权限、用户、组等信息(但不包括文件名,文件名仅仅是方便用户管理,系统管理中不用文件名管理),在本例中,它们分别为2,7,13,15。通过"文件名"查找到相应的inode编号,则可以直接读取文件内容。用户在操作Linux时,使用文件名查找文件,实际上系统会查找"文件名与inode索引之间的映射",在系统内部不使用文件名,仅仅使用inode来标识文件,在inode中也不存在任何与文件名相关的字段。在Linux中采用索引式文件系统(indexed allocation),即inode(index node)机制。



系统调用read()读取文件

函数原型: ssize_t read(int fd, void *buf, size_t count);

该函数原型有三个参数: fd表示文件描述符,使用open函数打开文件后,会返回该值; buf用于存放读到的数据; count表示读取的字节数。该函数原型的返回值为 ssize_t,当它大于0时,表示读取到buf中的字节数;当它小于0时,表示返回错误;当它为0时,表示读取到文件的末尾即EOF。

```
1 #include <sys/types.h> // It is finded in the
   /usr/include/sys/types.h.
2 #include <sys/stat.h> //It is finded in the
   /usr/include/sys/stat.h.
3 #include <fcntl.h> //fcntl means file control. It defines the file
   control operate.
4 #include <stdio.h> //It includes perror(const char *str)
5 #include <unistd.h> //It includes read(int fd, void* buf, size_t
   len)
6 #include <errno.h>
7 | #include <string.h> //It includes memset(void *str, int value,
   size_t __n)
8 #define BUFFER_SIZE 4096*2
  // #define BUFFER_SIZE 20 // extreme case. The buffer size is
   common 4096 * n
int main (int argc,char *argv[]){
    int fd; // It is the File Description which is used int the Linux
11
   System.
   //fd = open("/home/os/Papers/Technical-
   Documents/OS/linux_system_programming/code/file/testRead.c",O RDONLY)
       //example 1: reading the testRead.c file
    //fd = open("/home/os/Papers/Technical-
   Documents/OS/linux_system_programming/code/file/input_not_null",O_RDO
   NLY); //example 2: reading the input file
    fd = open("/home/os/Papers/Technical-
   Documents/OS/linux_system_programming/code/file/input_null",O_RDONLY)
   ; //example 3: reading the null input file
     if (fd == -1){
15
     perror("main");
16
17
     }else{
       printf("Success!\n");
18
19
     }
20
21
     ssize t ret; // signed size t, the negative numbers mean error
     char buf[BUFFER_SIZE]; //It means the buffer for the reading
22
   operating.
     memset(&buf,0,BUFFER SIZE); //It means the initial value for every
23
   value in the buffer
24
     while ((ret = (read(fd,&buf,BUFFER_SIZE))) != 0){
25
       if (ret == -1){
26
```

```
27
          if (errno == EINTR) //It means the program encounts
   interupts, for software interupts and so on.
               continue;
28
          perror("main");
29
30
          break;
       }
31
       for (size_t i = 0; i < BUFFER_SIZE; i++){</pre>
32
         printf("%c",buf[i]);
33
34
       }
35
     }
     if (close(fd) == -1){
36
       perror("fd_close:");
37
38
     }
39
     return 0;
40 }
```

系统调用write()读取文件

函数原型: ssize_t write(int fd, void *buf, size_t count);

该函数原型的参数个数与参数含义与read()函数一样,其返回值也表示写入到buf中的字节数,如果返回值小于0,表示返回错误;当返回值为0时,仅仅表示写入0个字节,并无任何其它的含义。

```
#include <sys/types.h>
1
2
   #include <sys/stat.h>
3
4
   #include <unistd.h>
5
6
7
   #include <fcntl.h>
8
   #include <stdio.h>
9
10
  #include <string.h>
11
12
13 #include <errno.h>
14
15 #define BUFFER SIZE 4096
16
```

```
17
    int main (int argc, char *argv[]){
18
19
20
      ssize_t fd_input = open("/home/os/Papers/Technical-
21
   Documents/OS/linux_system_programming/code/file/testRead.c",O_RDONLY
   );
22
23
     if (fd_input == -1){
24
        perror("input:");
25
26
27
     }
28
29
30
31
      ssize_t fd_output = open("/home/os/Papers/Technical-
   Documents/OS/linux_system_programming/code/file/output",O_WRONLY |
   O_APPEND);
32
33
     if (fd_output == -1){
34
        perror("output:");
35
36
37
     }
38
39
40
     char buffer[BUFFER_SIZE];
41
42
     memset(&buffer,0,BUFFER_SIZE);
43
44
45
46
47
      ssize_t ret_read;
48
49
      ssize_t ret_write;
50
     while((ret_read = read(fd_input,&buffer,BUFFER_SIZE)) != 0){
51
52
        if(ret_read == -1){
53
54
```

```
55
          if (errno == EINTR){
56
57
             continue;
58
          }
59
60
          perror("read:");
61
62
63
          break;
64
       }
65
66
67
        ret_write = write(fd_output,&buffer,(ssize_t)ret_read);
68
       if (ret_write == -1){
69
70
71
          if(errno == EINTR){
72
73
            continue;
74
          }
75
76
          perror("write:");
77
78
79
          break;
80
81
       }
82
83
     }
84
85
     int ret = fdatasync(fd_output);
86
87
     printf("sync:%d\n",ret);
88
89
     if (close(fd_output) == -1){    //The fd_output is closed that is
   input file desctiptor. It is the second for the open sort.
90
       perror("fd_outpt:");
91
92
93
     }
94
     if (close(fd_input) == -1){
95
```

```
96
97    perror("fd_input:");
98
99    }
100    return 0;
101 }
```