# PARTIAL DIFFERENTIAL EQUATIONS

A Quick Guide

Huan Q. Bui

Colby College Physics & Statistics Class of 2021

February 17, 2019

# Preface

Greetings,

Partial Differential Equations: A Quick Guide is based on my lecture notes from MA411: Topics in Differential Equations - Partial Differential Equations with professor Evan Randles at Colby. The contents are somewhat based on Farlow's Partial Differential Equations for Scientists and Engineers.

Enjoy!

# Contents

	Pref	ace	1
L	Ove 1.1 1.2 1.3 1.4 1.5 1.6 1.7	What in the world is a PDE? Some notable examples Vocabulary Our goals Our plan Classification Types of second order linear PDE Lesson 1: Selected Problems & Solutions	3 3 3 4 4 5 5 6 8
2	Diff	fusion-type problems (parabolic equations): A study of the	•
		t equation	10
	2.1	An experiment	10
	2.2	The Mathematical Model	10
	2.3	Boundary Conditions	11
	2.4	Initial Conditions	12
	2.5	A Couple of Variants	12
	2.6	2.5.1 Lateral Heat Loss 2.5.2 Internal Heat Source 2.5.3 Diffusion-convection Equation 2.5.4 Variable-coefficients case Other types of Boundary Conditions 2.6.1 Type 1 2.6.2 Type 2 (more realistic) 2.6.3 Type 3: Flux specified - including isolated boundaries	12 12 13 13 13 13
		2.6.4 Type 4: Mixed	14
	2.7	Derivation of the Heat Equation	14
3	<b>Sep</b> 3.1	aration of Variables - First method of solution  Example: The heat equation	1 <b>7</b> 17
1	Pro	blems and Solutions	20
_	4.1	Problem set 1	20
	4.2	Problem set 2	30
	4.3	Problem set 3	31
		Problem set 4	32

## 1 Overview and Classification

#### 1.1 What in the world is a PDE?

We shall begin with what PDEs are.

**Definition 1.1.** A partial differential equation (PDE) is an equation relating a function of several variables  $\psi(t, \vec{x})$  to its partial derivatives:  $\partial_{x_1} \psi$ ,  $\partial^2_{x_1 x_2} \psi$ , etc.

A note on notation:

$$\frac{\partial^2 \psi}{\partial x_1 \, \partial x_2} \equiv \partial_{x_1 x_2}^2 \psi \equiv \partial_{x_1} \partial_{x_2} \psi.$$

#### 1.2 Some notable examples

Let us look at a couple of famous PDEs:

Example 1.1. Laplace Equation:

$$\Delta \psi = \nabla^2 \psi = \frac{\partial^2 \psi}{\partial x^2} + \frac{\partial^2 \psi}{\partial y^2} + \frac{\partial^2 \psi}{\partial z^2} = 0.$$

Example 1.2. Poisson's Equation:

$$\Delta \psi = \nabla^2 \psi = F(x, y, z)$$

We take note of the Laplacian or the Laplacian operator:

$$\Delta \psi \equiv \nabla^2 \psi = \frac{\partial^2 \psi}{\partial x^2} + \frac{\partial^2 \psi}{\partial y^2} + \frac{\partial^2 \psi}{\partial z^2}$$

The Laplacian operator takes a function  $\psi$  linearly to another function  $\nabla^2 \psi$ . The Laplacian is one of the most important objects in mathematics, as it touches probability theory, potential theory, partial differential equations, mathematical physics, harmonic analysis, number theory, etc.

Another note on notation: the symbols  $\Delta$  and  $\nabla^2$  will be used interchangeably in this text. The  $\nabla^2$  represents the divergence of the gradient.

Let us look at some more examples to see the ubiquity of the Laplacian in PDEs:

Example 1.3. The heat equation:

$$\frac{\partial \psi}{\partial t} = \nabla^2 \psi.$$

The heat equation describes heat transfer over time. But there is also a connection between the heat equation and probability theory. In particular, the Gaussian function:

$$\frac{1}{\sqrt{4\pi t}}e^{-\frac{x^2}{4t}}$$

solves the heat equation.

#### Example 1.4. The wave equation:

$$\frac{\partial^2 \psi}{\partial t^2} = \nabla^2 \psi.$$

The wave equation describes physical vibrations. The second t-derivative in the equation is strongly correlated to Newton's second law of motion.

#### Example 1.5. The Schrödinger equation:

$$i\hbar \frac{\partial \psi}{\partial t} = -\frac{\hbar^2}{2m} \nabla^2 \psi + V(t, \vec{x}) \psi.$$

One can hardly talk about PDEs without mentioning the Schrödinger equation. There is a strong resemblance between the Schrödinger equation and the wave equation. Of course, this is no coincidence, as the Schrödinger equation is postulated based on a description of a harmonic oscillator.

Our next example does not include the Laplacian operator.

#### Example 1.6. The telegraphic equation:

$$\frac{\partial^2 \psi}{\partial t^2} = \frac{\partial^2 \psi}{\partial x^2} + \alpha \frac{\partial \psi}{\partial t} + \beta \psi.$$

The telegraphic equation describes the transfer of information.

#### 1.3 Vocabulary

- $\bullet$  The function  $\psi$  appearing in a given PDE is called the "dependent variable."
- The variables  $t, x_1, x_2, \ldots$  are called "independent variables."

#### 1.4 Our goals

Our goal is, given a PDE, to find a sufficiently differentiable function which satisfies it that is subject to **boundary** and **initial** conditions.

## 1.5 Our plan

Here are the key concepts we will explore in this text:

- Modeling: Formulate same physical problem in terms of PDEs.
- Learn how to solve (some) PDEs, subjection to initial conditions and boundary conditions. This means we will be looking at ideas like:
  - Separation of variables, in order to reduce a PDE into a system of ODEs.
  - Integral transforms, in order to reduce the number of independent variables.
  - Change of coordinates, in order to change a complicated PDE into another one which is easier to solve.
  - Eigenfunction expansion, which generally goes under the Sturm-Liouville theory.
  - Numerical methods, as most PDEs cannot be solved analytically.

#### 1.6 Classification

• The order of a PDE is the highest order of partial derivatives appearing (non-trivially) in the PDE.

#### Example 1.7.

$$\frac{\partial \psi}{\partial t} = \nabla^2 \psi$$

is a second-order PDE.

#### Example 1.8.

$$\frac{\partial \psi}{\partial t} = \partial_x^4 \psi$$

- the biharmonic heat equation, is a fourth-order PDE.
- Linearity: A PDE is linear if the function  $\psi$  and its derivatives appear in a linear way.

**Example 1.9.** All second-order linear PDEs in 2 variables are of the form:

$$\boxed{A\frac{\partial^2 \psi}{\partial x^2} + B\frac{\partial^2 \psi}{\partial x \, \partial y} + C\frac{\partial^2 \psi}{\partial y^2} + D\frac{\partial \psi}{\partial x} + E\frac{\partial \psi}{\partial y} + F\psi = G}$$

Note: define

$$L[\psi](x,y) = A\frac{\partial^2 \psi}{\partial x^2} + B\frac{\partial^2 \psi}{\partial x \partial y} + C\frac{\partial^2 \psi}{\partial y^2} + D\frac{\partial \psi}{\partial x} + E\frac{\partial \psi}{\partial y} + F\psi$$

then we get

$$L[u] = G.$$

We get a linear map  $L: \psi \to L[\psi]$ . So, for  $\gamma, \sigma \in \mathbb{R}$ 

$$L[\gamma u + \sigma v)] = \gamma L[u] + \sigma L[v].$$

This observation justifies the moniker "linear." Next, we say that  $L[\psi] = G$  is **homogeneous** if G = 0. The equation is **inhomogeneous** if  $G(x, y) \neq 0$  for some x, y.

If A, B, C, D, E, F are constants, then  $L[\psi] = G$  is said to be a **constant-coefficient** equation. Otherwise (at least one of A, B, C, D, E, F is a function of x, y in some non-trivial way), it is said to have **variable coefficients**.

**Example 1.10.** Classify:  $u_t = \sin t u_{xx}$ .

It is a linear PDE,  $A = \sin t$ , B = C = D = F = 0, E = -1, G = 0, variable coefficient, and homogeneous.

**Example 1.11.** Classify:  $u_{xx} - \sin u = 0$ .

Not linear.

**Example 1.12.** Classify:  $xu_x - yu_y = 0$ .

First-order homogeneous linear PDE with variable coefficients.

Note: Linear PDEs are quite well understood. Notable mathematicians who established theories of linear PDEs: Ehenpres(?), Hille, Browder, Soboher, Nash, Nierenburd, Friedmann, Schwartz, Hormander (Fields, 1962), Gardiy.

Note: Constant coefficient equations are **much easier** to solve than variable coefficient equations, because Fourier analysis makes a lot of the constant coefficient problems easy.

Note: Non-linear equations are really hard, and there is no general theory. Each type of non-linear problem demands its own special techniques (well, if they exist at all).

# 1.7 Types of second order linear PDE

**Parabolic:**  $L[\psi] = G$  is said to be parabolic if  $B^2 - 4AC = 0$  (A, B, C don't have to be constant coefficients - so the PDE can be parabolic in some region and not elsewhere).

Example 1.13. The heat equation

$$u_t = u_{xx}$$

is a parabolic equation, because A = 1, E = -1, B = C = 0.

**Elliptic:**  $L[\psi] = G$  is elliptic if  $B^2 - 4AC < 0$ .

Example 1.14. Laplace's equation

$$\delta u = u_{xx} + u_{yy} = 0$$

is elliptic, because A = C = 1, B = 0.

**Hyperbolic:** if  $B^2 - 4AC > 0$ .

**Example 1.15.** The wave equation:

$$u_{tt} = u_{xx}$$

is hyperbolic, because B = 0, A = 1, C = -1.

#### 1.8 Lesson 1: Selected Problems & Solutions

**Problem (3).** If  $u_1(x,t)$  and  $u_2(x,t)$  satisfy L[u] = G, then is it true that the sum satisfies it? If yes, show.

**Solution** (3). Yes. We have established, in class, that if we define  $L: u \to L[u]$  where

$$L[u] = Au_{xx} + Bu_{xt} + Cu_{tt} + Du_x + Eu_t + Fu = G,$$

then L[u] is a linear map, which can be readily shown:

$$L[\mu u_1 + \nu u_2] = \mu (Au_{1xx} + Bu_{1xt} + Cu_{1tt} + Du_{1x} + Eu_{1t} + Fu_1)$$
  
+  $\nu (Au_{2xx} + Bu_{2xt} + Cu_{2tt} + Du_{2x} + Eu_{2t} + Fu_2)$   
=  $\mu L[u_1] + \nu L[u_2].$ 

So, the sum of  $u_1$  and  $u_2$  also satisfies L[u] = G.

**Problem (4).** Probably the easier of al PDEs to solve is the equation

$$\frac{\partial u(x,y)}{\partial x} = 0.$$

Can you solve this equation? Find all functions u(x,y) that satisfy it.

**Solution** (4). The PDE suggests that u does not depend on x. This means that u(x,y) is just some function of y, i.e.  $u(x,y) = \tilde{u}(y)$ .

**Problem (5).** What about the PDE

$$\frac{\partial^2 u(x,y)}{\partial x \, \partial y} = 0?$$

Can you find all solutions u(x,y) to this equation? How many are there? How does this compare with an ODE like

$$\frac{d^2y}{dx^2} = 0$$

insofar as the number of solutions is concerned?

**Solution** (5). This PDE is a first-order, linear, homogeneous PDE with B = 1, A = C = D = E = F = 0. Since  $B^2 - 4AC = 1 > 0$ , the PDE is **hyperbolic**. The PDE suggests that  $u_y$  has no x-dependence. From the previous problem, we know that  $u_y = f'(y)$ . Taking the antiderivative with respect to y, we get

$$u(x,y) = \int f'(y) dy = f(y) + g(x).$$

Since the variables x, y are exchangeable (by the equality of mixed partials), following the same argument starting with  $u_x$  gives the same form for u(x, y).

The ODE  $D^2[y] = y''(x) = 0$  is a second-order, linear, homogeneous ODE. We know that the solution space has dimension of 2:


$$\ker(D^2) = \{1, x\}.$$

So while there are infinitely many solutions, only **two** linearly independent solutions are sufficient to generate all solutions. Whereas there are infinitely many linearly independent solutions to the PDE. We can simply generate a new (linearly independent from f(y) + g(x)) solution by multiplying f(y) by y or g(x) by x.

# 2 Diffusion-type problems (parabolic equations): A study of the heat equation

## 2.1 An experiment

We consider a copper rod of length L, which allows heat to transfer along the rod, but is insulated in such a way that heat does not transfer laterally across/out of the rod.



At time t = 0, the temperature in the rod is known.

$$u(0,x) = T_0$$

The ends of the rod are placed in thermal baths which hold their temperatures fixed. So, at x = 0,  $u(t, 0) = T_1$  and at x = L,  $u(t, L) = T_2$  for all t > 0.

#### 2.2 The Mathematical Model

This behavior is modeled by the heat equation.

$$u_t = \alpha^2 u_{xx},$$

where  $\alpha \in \mathbb{R}$ , determined by the thermo-character of the rod.  $u_t$  is the rate of change of temperature in time, and  $u_{xx}$  is the concavity profile in space.

Some justification for the heat equation: we look at the spatial difference

quotient. For small change in x,  $\Delta x$ :

which For small change in 
$$x$$
,  $\Delta x$ : 
$$u_{xx} \approx \frac{u_x(t, x + \Delta x) - u_x(t, x)}{\Delta x}$$

$$\approx \frac{(u(t, x + \Delta x) - u(t, x))/\Delta x - (u(t, x) - u(t, x - \Delta x))/\Delta x}{\Delta x}$$

$$\approx \frac{1}{\Delta x^2}(u(t, x + \Delta x) + u(t, x - \Delta x) - 2u(t, x))$$

$$\approx \frac{2}{\Delta x^2} \left(\frac{u(t, x + \Delta x) + u(t, x - \Delta x)}{2} - u(t, x)\right)$$

So,  $u_{xx} \propto$  the difference between the average temperatures among neighboring points and the temperature at x.



FIGURE 2.2 Arrows indicating change in temperature according to  $u_t = \alpha^2 u_{\rm sc}$ 

Assume that  $u_t = \alpha^2 u_{xx}$ , then if  $u_{xx} < 0$ , then  $u_t < 0$ , i.e. temperature decreases in time. If  $u_{xx} > 0$ , then  $u_t > 0$ , i.e. temperature increases in time. If  $u_{xx} = 0$ , the temperature stays fixed.

#### 2.3 Boundary Conditions

In contrast to ODEs, PDE have different types of constraints which are combined with the PDE to form well-posed problems, where "well-posed" means that a unique solution exists. Our conditions are often (and will almost always) be physically motivated.

Let us revisit the heat equation.

$$u_t = \alpha^2 u_{xx}, t > 0, 0 \le x \le L.$$

The temperatures at the ends x = 0 and x = L are fixed  $T_1$  and  $T_2$  by the thermal baths, so the boundary conditions are

$$BCs = \begin{cases} u(0,t) = T_1 \\ u(L,t) = T_2 \end{cases} \forall t > 0.$$

Here "boundary" refers to the boundary of [0, L].

#### 2.4 Initial Conditions

Our problem also involves evolution in time, we have an initial condition of the form

$$u(x,0) = T_0 \text{ or } u(x,0) = u_0(x) \forall x \in [0,L]$$

where  $T_0$  is the initial constant temperature of the rod and  $u_0(x)$  is the initial temperature which is allowed to vary (some spatial distribution). All together, we form an initial boundary value problem, an IBVP of the form

$$\begin{cases} u_t = \alpha^2 u_{xx}, t > 0, x \in [0, L] \\ u(0, t) = T_1, \forall t > 0 \\ u(L, t) = T_2, \forall t > 0 \\ u(x, 0) = T_0, \forall x \in [0, L] \end{cases}$$

## 2.5 A Couple of Variants

#### 2.5.1 Lateral Heat Loss

This allows for heat to be transferred laterally into the rod according to Newton's law of cooling. So the new heat equation is

$$u_t = \alpha^2 u_{xx} - \beta(u - u_0), \beta > 0$$

where  $u_0$  is the outside temperature.

#### 2.5.2 Internal Heat Source

If, by some non-diffusive heat source, heat is added into the rod at (t, x), the equation is

$$u_t = \alpha^2 u_{xx} + f(x, t)$$

where f(x,t) is the heat added to the rod, internally. This PDE is *inhomogeneous*.

#### 2.5.3 Diffusion-convection Equation

$$u_t = \alpha^2 u_{xx} - v u_x$$

If u describes the amount (not heat) pollutant, then the term  $-vu_x$  describes the flow of additional pollutant introduced by the moving particles.

#### 2.5.4 Variable-coefficients case

When the thermal make up of the rod (its thermal character) is allowed to vary according to a variable diffusivity coefficient, i.e.  $\alpha \to \alpha(x)$ , then the relevant heat equation is

$$u_t = \alpha^2(x)u_{xx}.$$

So, let's say

$$\alpha(x) = \begin{cases} \alpha_{Copper}, x \in [0, L/2] \\ \alpha_{Bronze}, x \in [L/2, L] \end{cases}$$

## 2.6 Other types of Boundary Conditions

#### 2.6.1 Type 1

Let's revisit the original heat equation:  $u_t = \alpha^2 u_{xx}$ . If we force the rod ends to have time-dependent temperatures:  $g_1(t)$  and  $g_2(t)$  at x = 0 and x = L respectively, then our boundary conditions are

$$BCs = \begin{cases} u(0,t) = g_1(t) \\ u(L,t) = g_2(t) \end{cases} \forall t > 0.$$

If instead we're studying the heat flow on a circular plate, i.e., where  $u = u(t, t, \theta)$ , and the heat EQ is

$$u_t = \alpha^2 \nabla^2 u = \alpha^2 \left( u_{rr} + \frac{1}{r} u_r + \frac{1}{r^2} u_{\theta\theta} \right).$$

Here, the boundary conditions look like  $u(t, r_0, \theta) = g(t, \theta)$ , i.e. we force the disk to have temperature  $g(t, \theta)$  along the boundary.

#### 2.6.2 Type 2 (more realistic)

We take into account heat transfer to rod ends via thermal bath. Suppose that our rod is placed in bath (liquid) at each end of temperature  $g_1(t)$  and  $g_2(t)$  respectively.

In view of Newton's law of cooling, the heat flux at a rod end is  $h(u(t,0) - g_1)$  at x = 0 and  $h(u(t,L) - g_2(t))$  at x = L, and h is some constant. Next, we introduce Fourier's law of heat flux (empirical):

$$\frac{\partial u}{\partial n} = k \times \text{Heat flux}$$

where n is the *inward normal* direction to the boundary, and  $k \in \mathbb{R}$ . At x = 0:

$$\begin{cases} \frac{\partial u}{\partial n} = u_x(t,0) = kh(u(t,0) - g_1(t)), x = 0\\ \frac{\partial u}{\partial n} = -u_x(t,L) = kh(u(t,L) - g_2(t)), x = L \end{cases}.$$




FIGURE 3.3 Convection cooling at the boundaries.

So, the BC for Type 2 is the following

$$\begin{cases} u_x(t,0) = kh(u(t,0) - g_1(t)) \\ u_2(t,L) = -kh(u(t,L) - g_2(t)) \end{cases}$$

The 2-D plate analogue is the following. We require (since r is outward)

$$-\frac{\partial u}{\partial r} = -kh(u(t, r_0, \theta) - g(t, \theta))$$

where  $g(t,\theta)$  is the temperature of the bath surrounding the plate.

#### 2.6.3 Type 3: Flux specified - including isolated boundaries

The rod ends are insulated, i.e., no heat flows in or out of the rod ends. So the boundary conditions are

$$u_x(0,t) = u_x(L,t) = 0 \forall 0 < t < \infty.$$

In two variables (a disk), the analogous BC is

$$u_r(t, r_0, \theta) = 0 \forall 0 < t < \infty, 0 < \theta < 2\pi.$$

#### 2.6.4 Type 4: Mixed

We can mix BCs. Suppose that one end of the rod has zero flux condition (type 3) and the other end is submerged in a liquid (type 2).

So, the IBVP is

$$\begin{cases} u_t = \alpha^2 u_x x \\ u_x(t, L) = 0 \\ u_x(t, 0) = -\lambda (u(t) - g_1(t)) \forall t > 0 \\ u(0, x) = u_0(x) \forall 0 \le x \le L \end{cases}$$

## 2.7 Derivation of the Heat Equation

Main idea: Conservation of (Heat) Energy. Assumptions:




FIGURE 3.6 Initial-boundary-value problem.



FIGURE 4.3 Thin conducting rod

- 1. The rod is a thermally homogeneous material
- 2. The temperature is constant across all cross-sections
- 3. The rod is laterally insulated (no heat loss laterally)

Using conservation of energy, we have the following: the change in thermal energy in the cross section x to  $x + \Delta x$  should be equal to the flux of the heat through the "ends" at x and  $x + \Delta x$  plus any external heat produced by some source (e.g. heat element). Some physical constants:

- 1. C: thermal capacity of the rod
- 2.  $\rho$ : density of the material of the rod
- 3. A: area of cross section
- 4. k: thermal conductivity

Total heat inside is

$$\int_{x}^{\Delta x+x} c\rho Au(s,t) \, ds.$$

The flux through the ends is

$$kA(u_x(x+\Delta x,t)-u_x(x,t)).$$

The external energy is

$$A \int_{x}^{x+\Delta x} f(t,s) \, ds$$

where f(t,s) is the energy added at time t and  $x \leq s \leq x + \Delta x$ . All together

$$\frac{d}{dt} \int_x^{\Delta x + x} c \rho A u(s,t) \, ds = k A (u_x(x + \Delta x, t) - u_x(x,t)) + A \int_x^{x + \Delta x} f(t,s) \, ds.$$

Assuming that u is nice enough, that

$$\frac{d}{dt} \int_{x}^{\Delta x + x} c\rho Au(s, t) \, ds = \int_{x}^{\Delta x + x} c\rho Au_{t}(s, t) \, ds.$$

Also, the MVT for integrals says that if G is continuous on the interval [a,b] then  $\exists c \in [a,b]$  such that

$$\int_{a}^{b} G(s) ds = G(c)(b-a).$$

Therefore  $\exists \chi \in [x, \Delta x]$  such that

$$\int_{T}^{\Delta x + x} c\rho A u_t(s, t) \, ds = c\rho A u_t(t, \chi) \Delta x$$

and  $\exists \eta \in [x, \Delta x]$  such that

$$A \int_{x}^{x+\Delta x} f(t,s) \, ds = A f(t,\eta) \Delta x.$$

Combining all of these gives  $\forall t > 0, \exists \chi, \eta \in [x, \Delta x]$  such that

$$c\rho A u_t(t,\chi) \Delta x = kA(u_x(t,x+\Delta x) - u_x(t,x)) + Af(t,\eta) \Delta x$$
$$u_t(t,\chi) = \frac{k}{\rho c} \frac{u_x(t,x+\Delta x) - u_x(t,x)}{\Delta x} + \frac{1}{c\rho} f(t,\eta).$$

As  $\Delta x \to 0$ ,  $\eta, \chi \to x$ 

$$u_t(t,x) = \frac{k}{\rho c} u_{xx}(x,t) + \frac{1}{c\rho} f(t,x)$$
$$u_t(t,x) = \frac{k}{\rho c} u_{xx}(x,t) + F(t,x)$$
$$u_t(t,x) = \alpha^2 u_{xx}(x,t) + F(t,x),$$

where

$$\alpha^{2} = \frac{k}{\rho c}$$

$$F(t, x) = \frac{1}{c\rho} f(t, x).$$

# 3 Separation of Variables - First method of solution

Main idea: If the IBVP is posed on a rectangle, e.g.  $t > 0, x \in [0, L]$ , and the PDE is linear, it is often the case that this method reduces the PDE into ODEs.

# 3.1 Example: The heat equation

$$u_t = \alpha^2 u_{xx}, t > 0, x \in [0, 1]$$

We shall accompany this with so-called linear homogeneous BCs:

$$\alpha u(t,0) + \beta u_x(t,0) = 0$$
  
$$\gamma u(t,1) + \delta u_x(t,1) = 0.$$

In fact, we specify further to assume

$$u(t,0) = 0 = u(t,1) \forall t > 0.$$

We make an ansatz that solutions are of the form

$$u(t,x) = T(t)X(x).$$

(Maybe not solutions but builidng blocks of solutions). Plug into the PDE, we get

$$u_t(t,x) = T'(t)X(x) = \alpha^2 \partial_x^2 (u(t,x)) = \alpha^2 T(t)X''(x).$$

Separating variables gives

$$\frac{T'(t)}{\alpha^2 T(t)} = \frac{X''(x)}{X(x)} \forall t > 0, x \in [0, 1].$$

For this equation to hold for all independent t and x, we must have that

$$\frac{T'(t)}{\alpha^2 T(t)} = \frac{X''(x)}{X(x)} = \mathrm{Const} \forall t > 0, x \in [0,1].$$

This immediately gives two ODEs connected by a constant k:

$$\begin{cases} T(t) = \alpha^2 k T(t) \\ X''(x) = k X(x) \end{cases}.$$

By solving these equations, we hope to learn something aboaut k. The solution to the first solution is obvious:

$$K(t) = Ae^{\alpha^2kt} \forall t > 0.$$

For physically reasonable solutions, we expect that the limit as  $t \to \infty$  of u(t,x) = 0 and so,  $T(t) \not\to \infty$  as  $t \to \infty$ , this forces k < 0. Thus, we write  $k = -\lambda^2$ ,  $\lambda \in \mathbb{R}$ , and denote

$$u_{\lambda}(t,x) = T(t)X(x) = X(x)Ae^{-\alpha^2\lambda^2t}$$
.

Next, the spatial ODE gives

$$X''(x) + \lambda^2 X(x) = 0.$$

A general solution for this equation is

$$X(x) = A\sin(\lambda x) + B\cos(\lambda x).$$

By absorbing multiplicative constants

$$u_{\lambda}(t,x) = e^{-\alpha^2 \lambda^2 t} \left( A \sin(\lambda x) + B \cos(\lambda x) \right).$$

Though we still don't know what  $\lambda$  is, let us force this solution to satisfy the boundary conditions to learn more. Since the boundary conditions require that u(t,0) = 0 = u(t,1), we require that

$$\begin{cases} B = 0 \\ \lambda = \pm n\pi \end{cases}$$

where  $n \in \mathbb{N}$ , for non-trivial solutions (where  $A \neq 0$ ). Thus, with separation of variables, we find that

$$u_n(t,x) = A_n e^{-(n\alpha\pi)^2} \sin(n\pi x).$$

This is a solution for any  $n \in \mathbb{N}$  and  $A_n \in \mathbb{R}$ . Just to be sure that we haven't made an error, we can readily verify this solution. This is left as an exercise to the reader.

Note that we still have some "degrees of freedom" -  $A_n$  and n. So, we have established the existence of many solutions, for each  $n \in \mathbb{N}$  and  $A_n \in \mathbb{R}$ . Now, we make use of the principle of superposition to generate more solutions. The principle of superposition (works for linear DEs) says that all convergent sums of solutions are solutions. More generally, for any collection  $\{A_n\} \subseteq \mathbb{R}$ ,

$$u(t,x) = \sum_{n=1}^{\infty} A_n e^{-(n\pi\alpha)^2} \sin(n\pi x)$$

is also a solution. But divergence could be a problem here. It might be that u(t,x) fails to exist, or differentiation might not work. But worry not, since the presence of the term  $e^{-(n\pi\alpha)^2}$  makes this series always converge. And so, we have that for any sequence  $\{A_n\}$ , u(t,x) defined in this way solves the DE  $u_t = \alpha^2 u_{xx}$  and satisfies the boundary conditions u(t,0) = 0 = u(t,1). The

problem of satisfying the initial condition  $u(0,x)=u_0$  becomes one of finding the "right" constants  $A_n$  so that

$$u(0,x) = \sum_{n=1}^{\infty} A_n \sin(n\pi x) = u_0(x).$$

The term on the left hand side is called the trigonometric series.

## 4 Problems and Solutions

#### 4.1 Problem set 1

Exercise 4.1.

**Problem.** 2, Lesson 2. The heat equation is

$$u_t = \alpha^2 u_{xx} + 1$$
, with  $0 < x < 1$ .

Suppose u(0,t) = 0 and u(1,t) = 1. What is the steady-state temperature of the rod?

**Solution.** Stead-state temperature can be found by setting  $u_t(x,t) = 0$  for 0 < x < 1. It follows that  $\alpha^2 u_{xx}(x,t) + 1 = 0$ . In addition, the temperature profile is no longer time-dependent, so  $u(x,t) \to u(x)$ . These conditions give

$$u_{xx}(x) = -\frac{1}{\alpha^2}$$
$$u(x) = -\frac{1}{2\alpha^2}x^2 + Cx + D.$$

Applying the boundary conditions u(0,t)=0 and u(1,t)=1, we can find C and D:

$$\begin{cases} u(0) = 0 = D \\ u(1) = -\frac{1}{2\alpha^2} + C = 1 \end{cases}.$$

So,  $C = 1 + 1/s\alpha^2$ . The temperature profile of the rod is then

$$u_{\text{steady-state}}(x) = -\frac{1}{2\alpha^2}x^2 + \left(1 + \frac{1}{2\alpha^2}\right)x.$$

**Problem.** 3, Lesson 2. The heat equation is

$$u_t = \alpha^2 u_{xx} - \beta u$$
, with  $0 < x < 1$ .

Suppose the BC is u(0,t) = 1 and u(1,t) = 1. What is the steady-state temperature of the rod?

**Solution.** Again, we set  $u_t = 0$  to find the steady-state temperature profile. This forces  $\alpha^2 u_{xx} - \beta u = 0$ , i.e.,  $\alpha^2 u_{xx} = \beta u$ . Next, since the temperature is no longer time-dependent, we can let  $u(x,t) \to u(x)$ . Now, because  $\beta$  and  $\alpha^2$  are both positive numbers, the solution to this ODE has the form

$$u_{\text{steady-state}} = u(x) = Ce^{-\sqrt{\frac{\beta}{\alpha^2}}x} + De^{\sqrt{\frac{\beta}{\alpha^2}}x}.$$

Let us denote  $\sqrt{\beta/\alpha^2}$  as  $\phi$ . To find the coefficients C and D, we apply the boundary condition:

$$\begin{cases} u(0) = C + D = 1 \\ u(1) = Ce^{-\phi} + De^{\phi} = 1. \end{cases}$$

Solving this linear system of equation in Mathematica we find

$$C = \frac{e^{\phi}}{1 + e^{\phi}}$$
$$D = \frac{1}{1 + e^{\phi}}.$$

So, the steady-state temperature profile is

$$u_s(x) = \frac{e^{\phi}}{1 + e^{\phi}}e^{-\phi x} + \frac{1}{1 + e^{\phi}}e^{\phi x} = \frac{1}{1 + e^{\phi}}\left(e^{\phi(1-x)} + e^{\phi x}\right),$$

where

$$\phi = \sqrt{\frac{\beta}{\alpha^2}}.$$

Mathematica code and graph of steady-state temperature distribution:



#### Exercise 4.2.

**Problem.** 1, Lesson 3. Sketch the solution to the IBVP (Farlow, 3.6) for different values of time. Check if they agree with the boundary conditions. What is the steady-state temperature of the rod? Is this obvious?

The IBVP:

$$\begin{cases} PDE: u_t = \alpha^2 u_{xx}, x \in (0, 200), t \in (0, \infty) \\ BC_1: u_x(0, t) = 0, t \in (0, \infty) \\ BC_2: u_x(200, t) = -\frac{h}{k} [u(200, t) - 20], t \in (0, \infty) \\ IC: u(x, 0) = 0, x \in [0, 200] \end{cases}$$

Solution 4.1. Sketches:

Intuitively, the steady-state temperature of the rod is just 20°C, since the rod in the problem, which is initially at 0°C, is simply being warmed up by the 20°C water. We can of course show this mathematically. By the steady-state condition,  $u_t = 0 = u_{xx}$ . This forces  $u_{xx} = Cx + D$ . But by the first boundary condition  $u_x(0,t) = 0$ , require that C = 0. The second boundary condition requires that  $u_{s,x} = C = 0 = (-h/k)[u(200,t)-20] = (-h/k)[200C + D - 20]$ , which means D = 20. So, the steady-state temperature profile, not surprisingly, is 20°C uniform along the length of the rod.

**Problem.** 2, Lesson 3. Interpret the IBVP:

$$\begin{cases} PDE : u_t = \alpha^2 u_{xx}, x \in (0,1), t \in (0,\infty) \\ BC_1 : u(0,t) = 0, t \in (0,\infty) \\ BC_2 : u_x(1,t) = 1, t \in (0,\infty) \\ IC : u(x,0) = \sin(\pi x), x \in [0,1] \end{cases}$$

#### Solution 4.2.

Interpretation: The PDE suggests that we are dealing with heat flow in one dimension, so we can imagine a rod of length 1 with no laterally heat transfer. The first boundary condition suggests that the temperature is held fixed at 0 at x=0 for all t. The second boundary condition suggests that temperature is increasing (at a constant rate) at x=1 end. The initial condition tells us that initially, the temperature profile of the rod has a sinusoidal distribution across the rod's length, with the ends having temperature of  $0 (\sin(0) = \sin(\pi) = 0)$  and the middle x=1/2 having the highest temperature of 1.

Steady-state? The steady-state condition requires that  $u_{xx}=0$ , so again, we have  $u_s(x)=Cx+D$ , where C,D are real constants. The first boundary condition requires D=0. The second boundary condition requires that  $u_x(1)=C\times 1=C=1$ . Therefore, in the long run,  $u_s(x)=x$ . So, the stead-state temperature at each point of the rod has the same value as the position (from the 0 degree end) of that point on the rod.

Sketches:

**Problem.** 3, Lesson 3. Interpret the following IBVP:

$$\begin{cases} PDE: u_t = \alpha^2 u_{xx}, x \in (0,1), t \in (0,\infty) \\ BC_1: u_x(0,t) = 0, t \in (0,\infty) \\ BC_2: u_x(1,t) = 0, t \in (0,\infty) \\ IC: u(x,0) = \sin(\pi x), x \in [0,1] \end{cases}$$

#### Solution 4.3.

Interpretation: The PDE suggests that we are dealing with heat flow in one dimension, so we can imagine a rod of length 1 with no laterally heat transfer. The boundary conditions suggest that there are no temperature gradients at the ends of the rod. So we imagine the rod being insulated at the ends. The initial condition is like that in the previous problem where the temperature profile of the rod has a sinusoidal distribution across the rod's length, with the ends being at zero degrees  $(\sin(0) = \sin(\pi) = 0)$  and the middle x = 1/2 having the highest temperature of 1.

Steady-state: The steady-state condition requires that  $u_{xx}=0$ , i.e.,  $u_s(x)=Cx+D$ , where C,D are real constants. Since the temperatures are fixed at the end points,  $u_{s,x}=C=0$ . So the steady state temperature is D, which takes some value between 0 and 1 as  $t\to\infty$ . The steady-state temperature profile is the same along the length of the rod.

Sketches:

#### Exercise 4.3.

**Problem.** 3, Lesson 4. Derive the heat equation

$$u_t = \frac{1}{c\rho} \partial_x [k(x)u_x] + f(x,t)$$

for the situation where the thermal conductivity k(x) depends on x.

**Solution.** We can start the derivation from step (4.2) in Farlow's, modify  $k \to k(x)$ . The conservation of energy gives:

$$c\rho A \int_x^{x+\Delta x} u_t(s,t)\,ds = A\left(k(x+\Delta x)u_x(x+\Delta x,t) - k(x)u_x(x,t) + \int_x^{x+\Delta x} f(s,t)\,ds\right).$$

By the MVT, there exists  $\zeta \in (x, x + \Delta x)$  such that

$$c\rho u_t(\zeta, t)\Delta x = k(x + \Delta x)u_x(x + \Delta x, t) - k(x)u_x(x, t) + f(\zeta, t)\Delta x,$$

i.e.,

$$u_t(\zeta,t) = \frac{1}{c\rho} \left\{ \frac{k(x + \Delta x)u_x(x + \Delta x, t) - k(x)u_x(x, t)}{\Delta x} \right\} + \frac{1}{c\rho} f(\zeta,t)$$

Letting  $\Delta x \to 0$ , we turn the term with  $\Delta x$  into a derivative of a composition defined as  $UK(x,t) = k(x)u_x(x,t)$ . The result is

$$u_t(x,t) = \frac{1}{c\rho} \partial_x (k(x)u_x(x,t)) + f(x,t),$$

where we simply let f(x,t) absorb the constant  $(c\rho)^{-1}$ . We have obtained the heat equation with x-dependent thermal conductivity.

#### Exercise 4.4.

**Problem.** 1, Lesson 5. Show that

$$u(x,t) = e^{-\lambda^2 \alpha^2 t} (A \sin \lambda x + B \cos \lambda x)$$

satisfies the PDE  $u_t = \alpha^2 u_{xx}$  for  $A, B, \lambda \in \mathbb{R}$ .

**Solution.** We can compute the partial derivatives and verify that u(x,t) solves the PDE "by inspection." The t-derivative gives the same u(x,t), multiplied by a factor of  $-\lambda^2\alpha^2$ , while the x-second derivative also gives u(x,t), but multiplied by factor of  $\lambda^2$ . So, these expressions differ by a factor of  $\alpha^2$ . Mathematically:

$$u_t = -\lambda^2 \alpha^2 u(x, t) = \alpha^2 u_{xx}.$$

Hence, u(x,t) solves the given PDE.

**Problem.** 2, Lesson 5. Let  $\delta_n^m$  denotes the Kronecker delta, where m,n are non-negative whole numbers. Show

$$\int_0^1 \sin(\pi mx) \sin(\pi nx) \, dx = \frac{1}{2} \delta_n^m$$

Solution. Applying the hinted trigonometric identity, we have

$$\int_0^1 \sin(\pi m x) \sin(\pi n x) dx = \frac{1}{2} \int_0^1 \cos[(m-n)\pi x] - \cos[(m+n)\pi x] dx$$
$$= \frac{1}{2} \int_0^1 \cos[(m-n)\pi x] dx - \frac{1}{2} \int_0^1 \cos[(m+n)\pi x] dx$$

At this point, we can argue why the equality given by the problem is true without much computation. The argument goes as follows. If m=n, then the second integral vanishes because  $\cos(xk\pi)$ , where k is an even number and  $x \in [0,1]$ , is symmetric about x=1/2 and y=0. If  $m \neq n$ , then m-n and m+n are either odd or even. If they are even (and positive), then both integrals on the right hand side vanish. If they are odd, then we can assume (without loss of generality) that m is odd and n is even. This makes  $\sin(\pi mx)\sin(\pi nx)$  symmetric about x=1/2 and y=0, so the integral also vanishes over  $x \in [0,1]$ .

**Problem.** 5, Lesson 5. What is the solution to problem 4 in Farlow, Lesson 5 (which also requires doing 3) if the initial condition is changed to

$$u(x,0) = \sin(2\pi x) + \frac{1}{3}\sin(4\pi x) + \frac{1}{5}\sin(6\pi x)$$

**Solution.** We should quickly do problem 3 first. If  $\Phi(x) = 1$ ,  $x \in [0,1]$ . Applying the formula for the coefficients  $A_n$ :

$$A_n = 2 \int_0^1 \Phi(x) \sin(n\pi x) \, dx = 2 \int_0^1 \sin(n\pi x) \, dx = \frac{2}{n\pi} (1 - \cos(n\pi x)) = \begin{cases} \frac{4}{n\pi}, n \text{ odd} \\ 0, n \text{ even} \end{cases}$$

So, the Fourier expansion for  $\Phi(x) = 1$  is

$$\Phi(x) = 1 = \frac{4}{\pi} \left[ \sin(\pi x) + \frac{1}{3} \sin(3\pi x) + \frac{1}{5} \sin(5\pi x) + \dots \right].$$

In problem 4, the boundary and initial conditions suggests using  $\Phi(x)$  from problem 3. So, given the formula for u(x,t), we simply substitute in the coefficients to generate a Fourier expansion for u(x,t):

$$u(x,t) = \sum_{n=1}^{\infty} A_n e^{-(n\pi)^2 t} \sin(n\pi x)$$
  
=  $\frac{4}{\pi} \left[ e^{-(\pi)^2 t} \sin(\pi x) + \frac{1}{3} e^{-(3\pi)^2 t} \sin(3\pi x) + \frac{1}{5} e^{-(5\pi)^2 t} \sin(5\pi x) + \dots \right].$ 

Back to problem 5, if the initial condition is given as u(x,0) above, then we might think we have to re-do and find a new Fourier expansion. But by inspecting the form of u(x,0), we can see that it is just a truncated Fourier expansion. So there is no need to find the coefficients  $A_n$  since they are already given to us. So, carefully picking out the coefficients, we get the new solution

$$u(x,t) = e^{-(2\pi)^2 t} \sin(2\pi x) + \frac{1}{3} e^{-(4\pi)^2 t} \sin(4\pi x) + \frac{1}{5} e^{-(6\pi)^2 t} \sin(6\pi x).$$

# 4.2 Problem set 2

# 4.3 Problem set 3

# 4.4 Problem set 4