# Assignment 2 Notes

## Hyungmo Gu

### November 5, 2020

## 1 Read and Writer

- Reader don't modify the data so we can have multiple readers, but only one writer
- Are examples of a common computing problem in concurrency
- Is a part of semaphore problem

# 2 Product/Consumer

- Is essentially how pipes () are implemented
- Has bounded buffer as a shared variable
  - Bounded buffer is also used when piping the output of one program into another

#### Example

```
grep foo file.txt | wc -l
  * grep
```

- · searches the input files for lines containing a match to a given pattern lis
- · when it finds a match in a line, it copies the line to standard output (by default)
- \* wc -1
  - $\cdot$  stands for word count
  - · is used to find the number of lines (in this case)
- \* grep is the producer
- \* wc is the consumer
- Single buffer producer/consumer solution

- Is to use two different conditial variables
  - \* Is nice, trouble free and simple

```
cond_t empty, fill;
  mutex_t mutex;
   void *producer(void *arg) {
       int i;
       for (i = 0; i < loops; i++) {
           Pthread_mutex_lock(&mutex);
           while (count == 1)
               Pthread_cond_wait (&empty,
                                           &mutex);
10
           put(i);
11
           Pthread_cond_signal(&fill);
           Pthread_mutex_unlock(&mutex);
12
13
14
  }
                                              Conditional variable 1
15
16
   void *consumer(void *arg) {
       int i;
17
       for (i = 0; i < loops; i++) {
                                              Conditional variable 2
18
           Pthread_mutex_lock(&mutex);
           while (count == 0)
20
               Pthread_cond_wait (&fill,
                                          &mutex);
21
           int tmp = get();
22
           Pthread_cond_signal(&empty);
23
           Pthread_mutex_unlock(&mutex);
25
           printf("%d\n", tmp);
26
                          YES
   int loops;
    cond_t cond;
    mutex_t mutex;
    void *producer(void *arg) {
        int i;
        for (i = 0; i < loops; i++) {
             Pthread_mutex_lock(&mutex);
                                                       // p1
             while (count == 1)
                                                       // p2
                                             &mutex); // p3
                 Pthread_cond_wait (&cond,
                                                       // p4
             put(i);
11
                                                       // p5
12
             Pthread_cond_signal(&cond)
             Pthread_mutex_unlock(&mutex)
                                                       // p6
14
        }
15
   }
                                                 Same conditional
14
                                                 variable
    void *consumer(void *arg) {
17
18
        int i;
19
        for (i = 0; i < loops; i++) {
             Pthread_mutex_lock(&mutex);
                                                       // c1
20
                                                       // c2
             while (count == 0)
21
                 Pthread_cond_wait (&cond,
                                             &mutex); // c3
             int tmp = get();
                                                       // c4
23
             Pthread_cond_signal(&cond);
                                                       // c5
            Pthread_mutex_unlock(&mutex);
                                                      // c6
             printf("%d\n", tmp);
26
27
        -}
   }
28
```

NONO

• The general correct producer/consumer solution

```
int buffer[MAX];
   int fill_ptr = 0;
   int use_ptr = 0;
   int count
   void put(int value) {
       buffer[fill_ptr] = value;
                                                             Changes made
       fill_ptr = (fill_ptr + 1) % MAX;
                                                             to make solution
       count++;
10
                                                             general
11
12
   int get() {
13
       int tmp = buffer[use_ptr];
       use_ptr = (use_ptr + 1) % MAX;
14
       count--;
15
16
       return tmp;
   cond_t empty, fill;
   mutex_t mutex;
   void *producer(void *arg) {
       int i:
       for (i = 0; i < loops; i++) {
           Pthread_mutex_lock(&mutex);
           while (count == MAX)
               Pthread_cond_wait(&empty, &mutex); // p3
           put(i);
           Pthread_cond_signal(&fill);
                                                    // p6
           Pthread_mutex_unlock(&mutex);
12
13
  }
15
   void *consumer(void *arg) {
16
      int i;
       for (i = 0; i < loops; i++) {
18
          Pthread_mutex_lock(&mutex);
                                                    // c1
19
           while (count == 0)
               Pthread_cond_wait(&fill, &mutex);
           int tmp = get();
                                                    // c4
                                                   // c5
// c6
           Pthread_cond_signal(&empty);
           Pthread_mutex_unlock(&mutex);
           printf("%d\n", tmp);
26
```

# 3 Condtional Variable

```
lock_acquire(lock);
while(condition not true) {
    cv_wait(cond, lock);
}
... // do stuff
    Conditional variable
cv_signal(cond); //or cv_broadcast(cond)
lock_release(lock);
```

• is a queue of waiting threads

- has two operations associated with it:
  - 1. cv\_wait(struct cv \*cv, struct lock \*lock)
    - Is executed when a thread wishes to put itself to sleep
    - Releases lock, waits, re-acquires lock before return
      - \* Is to prevent race condtions from occuring when a thread is trying to put itself to sleep
  - 2. cv\_signal(struct cv \*cv, struct lock \*lock)
    - Wakes <u>one</u> enqueued thread
  - 3. cv\_broadcast(struct cv \*cv, struct lock \*lock) [from notes]
    - Wakes all enqueued threads
- If no one is waiting, signal or broadcast has no effect
- has rules
  - always use with while loops
    - \* on waking up, tread checks for condition in while loop
    - \* if condition is true, then thread goes back to sleep
- is always used together with locks

# 3.1 Example 1: Read/Writer Problem (Using CV)

```
//number of readers
int readcount = 0;

/* Readers don't modify any
data */
Reader {

// Only one writer allowed.
/* No reader while writer is
writing*/

Writer {

Read;

Read;
```

• The problem is about updating and checking the value


#### Example

Updating values or reading values in database

- Goals
  - Want only one writer at a time so the writing data is always correct
    - \* One reader + One writer or multiple writer creates a problem (race condition)
  - Want many readers at a time because they don't get each other in the way
- Is complex
  - Lots of overhead
- Steps (from lectures)

## Step 1

- is about making sure only one thread in writer can enter at a time
- symmetric locks in reader are made for now



### Step 2

- is about making sure we are not holding the lock while we are reading
- symmetric locks in writer are made for now

```
int readcount = 0
lock mutex = MUTEX_INIT
                                                                      Lock allows mutual exclusion -
                                                                      only one thread can read critical section
                                                                      at a time
                                          Reader {
Writer {
                                             lock(&mutex)
  lock(&mutex);
                                                                        We want to make sure
                                                                        lock is not held when reading
                                             readcount++
  unlock(&mutex)
                                             unlock(&mutex)
  Write
                                             Read
  lock(&mutex)
                                             lock(&mutex)
                                             readcount--
  unlock(&mutex)
                                             unlock(&mutex)
```

#### Step 3

- is about making sure write doesn't proceed when read is in process

```
int readcount = 0
                              lock mutex = MUTEX_INIT
of readcount to make sure
                              CV turn = MUTEX INIT
thread-to-write goes to sleep
                                                                      Reader {
when reading is in progress
                              Writer {
                                                                         lock(&mutex)
                                lock(&mutex);
                                while(readcount){
                                   cv_wait(&turn, &mutex)
                                                                         readcount++
                                unlock(&mutex)
                                                                         unlock(&mutex)
                                Write
                                                                         Read
                                lock(&mutex)
                                                                         lock(&mutex)
                                                                         readcount--
                                                                         cv signal(&turn)
                                unlock(&mutex)
                                                                         unlock(&mutex)
                                                                                                        perform signal to wake the thread in writer
```

 We can use mutex in reader before critical section because lock in write is released under cv\_wait(...)

#### **Step 3.5**

- suppose we try to remove inner lock (to remove extra overhead)
  - \* then we hold lock longer than necessary (Not what we want!!)
    - · we don't want to hold lock longer than necessary

```
we don't want to hold lock
int readcount = 0
                                      longer than necessary
lock mutex = MUTEX_INIT
CV turn = MUTEX_INIT
                                    Reader {
Writer {
 lock(&mutex);
                                      lock(&mutex)
  while(readcount){
   cv_wait(&turn, &mutex)
                                      readcount++
  unlock(&mutex)
                                      unlock(&mutex)
  Write
                                      Read
 lock(&mutex)
                                      lock(&mutex)
                                      readcount--
                                      cv_signal(&turn)
  unlock(&mutex)
                                      unlock(&mutex)
```

NoNo


## Step 4

```
int readcount = 0
int writing = 0
lock mutex = MUTEX_INIT
CV turn = MUTEX_INIT
                                  Reader {
Writer {
                                    lock(&mutex)
 lock(&mutex);
                                    while(writing) {
  while(readcount || writing){
                                      cv_wait(&turn, &mutex)
   cv_wait(&turn, &mutex)
  writing++
                                    readcount++
  unlock(&mutex)
                                    unlock(&mutex)
  Write
  lock(&mutex)
                                    lock(&mutex)
  writing--
                                    readcount--
  cv broadcast(&turn)
                                    cv signal(&turn)
  unlock(&mutex)
                                    unlock(&mutex)
```


# 4 Semaphore

```
Wait(Sem) {
   while(Sem <= 0);
   Sem--;
}</pre>
Signal(Sem) {
   Sem++;
}
```

- Was first invented by Dijkstra
- Is abstract data types that provide synchronization



- Has two atomic operations
  - wait
    - \* Is also called P or decrement
    - \* waits if value of count is negative
  - signal
    - \* increments the variable, unblock a waiting thread if there are any
    - \* wakes one thread if there are one or more threads waiting
- Has two types
  - 1. Binary semaphore (count = 0 or 1)
    - Has single access to a resource
    - Can be used like a lock
      - \* Provides mutual exclusion to a critical section
    - Needs to have initial value of 1
      - \* Is for decrementation of count in sem\_wait()



#### 2. Counting semaphore

- Resource with many units available
- Is resource that allows certain kinds of unsynchronized concurrent access (e.g. reading)
- Mutex has count = 1, counting has <math>count = N
- 3. Implementation Tips
  - Implement as few constraints as possible (e.g. how many semaphores do you need to solve the problem?)

\_

## 4.1 Example 1: Producer/Consumer (Using semaphore)

```
void *producer(void *arg) {
       int i;
       for (i = 0; i < loops; i++) {
                                    // Line P0 (NEW LINE)
           sem_wait(&mutex);
                                    // Line P1
           sem_wait(&empty);
           put(i);
                                    // Line P2
           sem_post(&full);
                                    // Line P3
                                    // Line P4 (NEW LINE)
           sem_post(&mutex);
10
11
   void *consumer(void *arg) {
12
13
       int i;
       for (i = 0; i < loops; i++) {
           sem_wait(&mutex);
                                    // Line CO (NEW LINE)
15
                                    // Line C1
           sem_wait(&full);
                                    // Line C2
           int tmp = get();
17
                                    // Line C3
           sem_post(&empty);
                                    // Line C4 (NEW LINE)
           sem_post(&mutex);
           printf("%d\n", tmp);
```