Dookug Template Modul DB repo documentation

Table of Contents

1. Overview . . . 1
2. Schemas . . . 1
   2.1. dookug . . . 1
      2.1.1. ERD: . . . 2
      2.1.2. Tables: . . . 2
      2.1.3. Permissions . . . 12
3. Configurations . . . 12
4. Installation, Release, Deployment . . . 14
5. Release notes . . . 19

1. Overview

- Brief overview:
  - Document generation module based on templates, which
    - can handle templates in different formats and inject parameter lists into them, then generate the finished document.
    - The module is designed to generate output documents (PDF, XLSX, HTML, TXT, ...) from various template formats with identifiers (TXT, HTML, object, JRXML, ...) by inserting the received parameter(s) into the received template.
    - The solution is based on a microservice architecture.
- Technologies:
  - Components and their versions:
    - Included local Postgres: 14.8-bullseye
    - Included local Oracle: 21.3.0-xe
    - Liquibase: 4.21
    - The latest final PGTools version: 0.10.0

2. Schemas

2.1. dookug

2.1.1. ERD:

[Dookug schema ERD] | *dookug_erd.png*

2.1.2. Tables:

Table 1. document

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	PK → unique identifier
template_id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		No	TEMPLATE identifier
status	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Document status
format	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Document format
filename	Oracle: VARCHAR2(100 CHAR) Postgres: VARCHAR(100)		No	Document filename
error_message	Oracle: VARCHAR2(512 CHAR) Postgres: VARCHAR(512)		No	Error message during process

Field	Type	Default Value	Required?	Description
storage_type	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Storage type
storage_id	Oracle: VARCHAR2(128 CHAR) Postgres: VARCHAR(128)		No	Unique invoice identifier in the calling system
parameters	Oracle: BLOB Postgres: BYTEA		No	Parameter key-value pairs json
parameter_data	Oracle: BLOB Postgres: BYTEA		No	Parameter data structure json
config	Oracle: CLOB Postgres: TEXT		No	Configuration
x__insdate	TIMESTAMP(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	TIMESTAMP(6)		No	Modification timestamp, null at insertion
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: NUMBER Postgres: INT	0	Yes	Change versioning

Table 2. document constraints and indexes

Field	Type	Value	Related Field	Referenced Field
pk_document	primary key		x__id	
pk_document	unique index		x__id	

Table 3. document_content

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Generated primary key (PK)
document_id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	DOCUMENT unique identifier
content	Oracle: BLOB Postgres: BYTEA		Yes	Document content (gzip)
expiry	Oracle: TIMESTAMP(6) Postgres: TIMESTAMP(6)		No	Expiration date
x__insdate	timestamp(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	timestamp(6)		No	Modification timestamp, null at insertion

Field	Type	Default Value	Required?	Description
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: number Postgres: int	0	Yes	Change versioning

Table 4. document_content constraints and indexes

Field	Type	Value	Related Field	Referenced Field
pk_document_content	primary key		x__id	
fk_document_content_document	foreign key constraint		document_id	document.x__id
ix_document_content_document_id	index		document_id	
pk_document_content	unique index		x__id	

Table 5. template

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Generated primary key (PK)
name	Oracle: VARCHAR2(255 CHAR) Postgres: VARCHAR(255)		Yes	Template name
description	Oracle: VARCHAR2(1024 CHAR) Postgres: VARCHAR(1024)		Yes	Description

Field	Type	Default Value	Required?	Description
template_engine	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Template engine. Possible values: HANDLEBARS, NONE
generator_engine	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Document generation engine. Possible values: PDF_BOX, NONE
language	Oracle: VARCHAR2(30 CHAR) Postgres: varchar(30)		No	Template language
validity_start	Oracle: TIMESTAMP(6) Postgres: TIMESTAMP(6)	Oracle: sysdate Postgres: now()	Yes	Validity start
validity_end	Oracle: TIMESTAMP(6) Postgres: TIMESTAMP(6)		No	Validity end
x__insdate	timestamp(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	timestamp(6)		No	Modification timestamp, null at insertion

Field	Type	Default Value	Required?	Description
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: number Postgres: int	0	Yes	Change versioning

Table 6. template constraints and indexes

Field	Type	Value	Related Field	Referenced Field
ck_template_generator_engine	check constraint	PDF_BOX, NONE, SAXON	generator_engine	
ck_template_template_engine	check constraint	HANDLEBARS, NONE	template_engine	
pk_template	primary key		x__id	
pk_template	unique index		x__id	

Table 7. template_part

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Generated primary key (PK)
key	Oracle: VARCHAR2(255 CHAR) Postgres: VARCHAR(255)		Yes	Template key. For template engine.
description	Oracle: VARCHAR2(1024 CHAR) Postgres: VARCHAR(1024)		Yes	Description

Field	Type	Default Value	Required?	Description
template_engine	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Template engine. Possible values: HANDLEBARS, NONE
generator_engine	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Document generation engine. Possible values: PDF_BOX, NONE
template_part_type	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Template type. Possible values: HEADER, CONTENT, FOOTER, MAIN, OTHER
x__insdate	timestamp(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	timestamp(6)		No	Modification timestamp, null at insertion
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: number Postgres: int	0	Yes	Change versioning

Table 8. template_part constraints and indexes

Field	Type	Value	Related Field	Referenced Field
ck_template_part_generator_engine	check constraint	PDF_BOX, NONE	generator_engine	
ck_template_part_template_engine	check constraint	HANDLEBARS, NONE	template_engine	
ck_template_part_template_part_type	check constraint	HEADER, CONTENT, FOOTER, MAIN, OTHER	template_part_type	
pk_template_part	primary key		x__id	
pk_template_part	unique index		x__id	

Table 9. template_part_content

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Generated primary key (PK)
template_part_id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	TEMPLATE unique identifier
content	Oracle: BLOB Postgres: BYTEA		Yes	Template content
compressed	Oracle: NUMBER Postgres: INT		Yes	Is template content compressed
validity_start	Oracle: TIMESTAMP(6) Postgres: TIMESTAMP(6)	Oracle: sysdate Postgres: now()	Yes	Validity start
validity_end	Oracle: TIMESTAMP(6) Postgres: TIMESTAMP(6)		No	Validity end

Field	Type	Default Value	Required?	Description
x__insdate	timestamp(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	timestamp(6)		No	Modification timestamp, null at insertion
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: number Postgres: int	0	Yes	Change versioning

Table 10. template_part_content constraints and indexes

Field	Type	Value	Related Field	Referenced Field
pk_template_part_content	primary key		x__id	
ix_template_part_content_template_part_id	index		template_part_id	
fk_template_part_content_template_part	Foreign key constraint		template_part_id	template_part.x__id
pk_template_part_content	unique index		x__id	

Table 11. template_template_part

Field	Type	Default Value	Required?	Description
x__id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	Generated primary key (PK)
template_id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	TEMPLATE unique identifier
template_part_id	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)		Yes	TEMPLATE_PART unique identifier
x__insdate	timestamp(6)	Oracle: sysdate Postgres: now()	Yes	Insertion timestamp
x__insuser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	Yes	Not used, default value 0
x__moddate	timestamp(6)		No	Modification timestamp, null at insertion
x__moduser	Oracle: VARCHAR2(30 CHAR) Postgres: VARCHAR(30)	'0'	No	Not used, default value 0
x__version	Oracle: number Postgres: int	0	Yes	Change versioning

Table 12. template_template_part constraints and indexes

Field	Type	Value	Related Field	Referenced Field

pk_template_template_part	primary key		x__id	
fk_template_template_part_template	foreign key constraint		template_id	template.x__id
fk_template_template_part_template_part	foreign key constraint		template_part_id	template_part.x__id
ix_template_template_part_template_id	index		template_id	
ix_template_template_part_template_part_id	index		template_part_id	
pk_template_template_part	unique index		x__id	

2.1.3. Permissions

Table 13. Postgres permissions

Users	Permissions
dookug	SELECT, INSERT, UPDATE, DELETE
dookug_del	DELETE, TRUNCATE
dookug_mod	INSERT, UPDATE
dookug_sel	SELECT
dookug_full	SELECT, INSERT, UPDATE, DELETE
dookug_service	SELECT, INSERT, UPDATE, DELETE

Table 14. Oracle permissions

Users	Permissions
DOOKUG_WRITE	INSERT, UPDATE, DELETE
DOOKUG_READ	SELECT
DOOKUG_EXEC	NOTEEFLY_READ, NOTEEFLY_WRITE

3. Configurations

- ENV variables:
  - **DOCKER_REPOSITORY**: Root location of images (*default value: DOCKER_REPOSITORY_*).
  - **DOCKER_LIQUIBASE_DOOKUG**: Indicates the image location (*schema1 default value: ${DOCKER_REPOSITORY}/liquibase/modules/dookug_db*).

- **DBDWH_IMAGE_VERSION**: used version of liquibase, postgres, partman images (*default value: 0.10.0*)
- **VERSION**: Project version, this is set automatically.

- Compose variables:
  - **LIQUIBASE_BASE_IMAGE**: central, corporate base liquibase image with version, used by dockerfile (*default value: DOCKER_REPOSITORY/db-base-liquibase:${DBDWH_IMAGE_VERSION}*).
  - **liquibase-release/LIQUIBASE_INSTALL_DIR**: local liquibase directory, used by dockerfile (*schema1 default value: ./liquibase/dookug*).
  - **LIQUIBASE_INSTALL_COMMON_DIR**: local liquibase/common directory, used by dockerfile (*default value: ./liquibase/common*).
- Before Liquibase variables:
  - **S2_SCHEMA_NAME**: Step 2 schema name, with default value, can be overridden externally (*default value: dookug*).
  - **CREATE_DATABASE**: PostgreSQL DB. If the current DB needs to be embedded in another DB (*under a specific schema*), this variable prevents an empty DB from being created. Default value is TRUE in the before-liquibase file, can be overridden externally.
- Properties variables:
  - Properties file: File belonging to the given DB that provides data for local db access and maps the liquibase changelog file to the given step compose file.
  - **URL**: URL of the DB to be installed, by default local DB access is specified, can be overridden externally.
    - Oracle DB: (default value: *jdbc:oracle:thin:@module-dookug-oracle:1521/xepdb1*).
    - Postgres DB/step1: (default value: *jdbc:postgresql://module-dookug-postgredb:5432/postgres*).
    - Postgres DB/step2: (default value: _jdbc:postgresql://module-dookug-postgredb:5432/dookug_db).
    - Postgres DB/step3: (default value: *jdbc:postgresql://module-dookug-postgredb:5432/postgres*).
    - Postgres DB/step4: (default value: _jdbc:postgresql://module-dookug-postgredb:5432/dookug_db).
  - **USERNAME**: Username for the DB to be installed, by default local DB access is specified, can be overridden externally.
    - Oracle DB/step1: (default value: *system*).
    - Oracle DB/step2: (schema2 default value: dookug).
    - Oracle DB/step4: (schema4 default value: dookug).
    - Postgres DB: (default value: *postgres*).
  - **PASSWORD**: Password for the DB to be installed, by default local DB access is specified, can be overridden externally.

    - Oracle DB: (default value: *developer*).
    - Postgres DB: (default value: *postgres*).
  - **CHANGELOGFILE**: Name of the liquibase changelog file, by default local changelog file access for the given DB step is specified.
    - step1: DB installation, users, permissions, etc. (default value: *liquibase-install-step-01.xml*).
    - step2: Liquibase installation, DB objects (default value: *liquibase-install-step-02.xml*).
    - step3: ONLY PostgreSQL - CRON scheduler entry (default value: *liquibase-install-step-03.xml*).
    - step4: Optional! Default (test/dev) template loading (default value: *liquibase-install-step-04.xml*).

4. Installation, Release, Deployment

▼ *Local Postgres (click here)*

```
#=====================
#Full install
#=====================
docker run -it --rm \
  --network=dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  icellmobilsoft/dookug_db:1.1.0
```

```
#=====================
#Step by step:
#=====================
#---------------------
#STEP1 DB init
#---------------------
docker run -it --rm \
  --network=dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_STEP=STEP_1 \
  icellmobilsoft/dookug_db:1.1.0 && \
#---------------------
#PG Tools (partman) install:
#---------------------
docker run -it --rm \
  --network dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S1=jdbc:postgresql://module-dookug-postgredb:port_num/postgres \
  -e INSTALL_URL_S2=jdbc:postgresql://module-dookug-postgredb:port_num/dookug_db \
  --name module-dookug-pg_tools-step-01B \
  icellmobilsoft/pg_tools:0.10.0 && \
#---------------------
```

```
#STEP2 - Liqui install:
#---------------------
docker run -it --rm \
  --network=dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_STEP=STEP_2 \
  icellmobilsoft/dookug_db:1.1.0 && \
#---------------------
#STEP3 - register in CRON scheduler:
#---------------------
docker run -it --rm \
  --network=dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_STEP=STEP_3 \
  icellmobilsoft/dookug_db:1.1.0 && \
#---------------------
#STEP4 - Load default (test/dev) templates:
#---------------------
docker run -it --rm \
  --network=dookug-local-network \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_STEP=STEP_4 \
  icellmobilsoft/dookug_db:1.1.0
```

- How "embed" Dookug DB into other "host" DB (*install Dookug-db dookug schema into other DB*):

▼ *Embed Postgres in to other DB locally (click here)*

```
#---------------------
#Postgres and Linux:
#---------------------
# The Step4 in DookuG DB contains loading of default templates, therefore the
"embedding" installer script format is different for this DB.
# For all host (parent) DBs, the corresponding environment variables need to be
rewritten accordingly.
# If you don't need default templates, then STEP_4 can be omitted.
#---------------------
    docker run -it --rm \
      --network=host-local-network \
      -e AUTO_INSTALL=postgresql \
      -e DATABASE_NAME=host_db \
      -e INSTALL_URL_S1=jdbc:postgresql://local_host_db-postgredb:port_num/postgres
\
      -e CREATE_DATABASE=false \
      -e INSTALL_STEP=STEP_1 \
      -e INSTALL_SCHEMA=dookug \
    icellmobilsoft/dookug_db:1.1.0 && \
    docker run -it --rm \
      --network=host-local-network \
      -e AUTO_INSTALL=postgresql \
      -e DATABASE_NAME=host_db \
```

```
      -e INSTALL_URL_S1=jdbc:postgresql://local_host_db-postgredb:port_num/postgres
\
      -e CREATE_DATABASE=false \
      -e INSTALL_URL_S2=jdbc:postgresql://local_host_db-postgredb:port_num/host_db \
      -e INSTALL_SCHEMA=dookug \
      --name module-dookug-pg_tools-step-01B \
    icellmobilsoft/pg_tools:0.10.0 && \
    docker run -it --rm \
      --network=host-local-network \
      -e AUTO_INSTALL=postgresql \
      -e DATABASE_NAME=host_db \
      -e INSTALL_URL_S2=jdbc:postgresql://local_host_db-postgredb:port_num/host_db \
      -e CREATE_DATABASE=false \
      -e INSTALL_STEP=STEP_2 \
      -e INSTALL_SCHEMA=dookug \
      icellmobilsoft/dookug_db:1.1.0  && \
    docker run -it --rm \
      --network=host-local-network \
      -e AUTO_INSTALL=postgresql \
      -e DATABASE_NAME=host_db \
      -e INSTALL_URL_S3=jdbc:postgresql://local_host_db-postgredb:port_num/postgres
\
      -e CREATE_DATABASE=false \
      -e INSTALL_STEP=STEP_3 \
      -e INSTALL_SCHEMA=dookug \
      icellmobilsoft/dookug_db:1.1.0
#-------------------------
#This 4th step is needed because the Step4 in Dookug DB contains loading of default
templates.
#If you don't need default templates, then STEP_4 can be omitted.
#-------------------------
    docker run -it --rm \
      --network=host-local-network \
      -e AUTO_INSTALL=postgresql \
      -e DATABASE_NAME=host_db \
      -e INSTALL_URL_S4=jdbc:postgresql://local_host_db-postgredb:port_num/host_db \
      -e CREATE_DATABASE=false \
      -e INSTALL_STEP=STEP_4 \
      -e INSTALL_SCHEMA=dookug \
      icellmobilsoft/dookug_db:1.1.0
```

▼ *Local Oracle (click here)*

- Locale Oracle install:

```
#=====================
#Full local install
#=====================
docker run --rm \
  --network dookug-local-network \
  -e AUTO_INSTALL=oracle \
```

```
    icellmobilsoft/dookug_db:1.1.0
```

```
#=====================
#Step by step:
#=====================
#---------------------
#STEP1 DB init
#---------------------
docker run --rm \
  --network dookug-local-network \
  -e AUTO_INSTALL=oracle \
  -e INSTALL_STEP=STEP_1 \
  icellmobilsoft/dookug_db:1.1.0
#---------------------
#STEP2 - Liqui install:
#---------------------
docker run --rm \
  --network dookug-local-network \
  -e AUTO_INSTALL=oracle \
  -e INSTALL_STEP=STEP_2 \
  icellmobilsoft/dookug_db:1.1.0
#---------------------
#STEP4 - Load Default (test/dev) templates - optional:
#---------------------
docker run --rm \
  --network dookug-local-network \
  -e AUTO_INSTALL=oracle \
  -e INSTALL_STEP=STEP_4 \
  icellmobilsoft/dookug_db:1.1.0
```

▼ *Embed Oracle into other Oracle DB locally (click here)*

```
#---------------------
#Oracle and Linux:
#---------------------
    docker run --rm \
      --network host-local-network \
      -e AUTO_INSTALL=oracle \
      -e INSTALL_URL=jdbc:oracle:thin:@local_host_db-oracle:port_num/xepdb1 \
      icellmobilsoft/dookug_db:1.1.0
```

▼ *Server install (click here)*

- The installation process is the same as the local one, however,
  - if the DB is already installed on the server, then STEP1 and/or pg_tools are probably not needed.
  - some environment variables need to be set with different values:
    - USERNAME=user_name

    - PASSWORD=passw
    - INSTALL_URL_S1=jdbc:postgresql://host:port_num/postgres
    - INSTALL_URL_S2=jdbc:postgresql://host:port_num/schema_name
    - INSTALL_URL_S3=jdbc:postgresql://host:port_num/postgres
    - INSTALL_URL_S4=jdbc:postgresql://host:port_num/schema_name
    - There is a possibility to change the password of the Service User from outside: e.g.: -e DB_SERVICE_USER_PASSWORD=new_service_passw, this can only be changed externally on the new installation, so it is only in step 1!
  - Other environment variables are explained in the Configuration section.

```
docker run -it --rm \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S1=jdbc:postgresql://host:port_num/postgres \
  -e INSTALL_STEP=STEP_1 \
  -e USERNAME=postgres \
  -e PASSWORD=postgres \
  icellmobilsoft/dookug_db:1.1.0 && \
docker run -it --rm \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S1=jdbc:postgresql://host:port_num/postgres \
  -e INSTALL_URL_S2=jdbc:postgresql://host:port_num/dookug_db \
  --name module-dookug-pg_tools-step-01B \
  icellmobilsoft/pg_tools:0.10.0 && \
docker run -it --rm \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S2=jdbc:postgresql://host:port_num/dookug_db \
  -e INSTALL_STEP=STEP_2 \
  icellmobilsoft/dookug_db:1.1.0
docker run -it --rm \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S3=jdbc:postgresql://host:port_num/postgres \
  -e INSTALL_STEP=STEP_3 \
  icellmobilsoft/dookug_db:1.1.0
docker run -it --rm \
  -e AUTO_INSTALL=postgresql \
  -e INSTALL_URL_S4=jdbc:postgresql://host:port_num/dookug_db \
  -e INSTALL_STEP=STEP_4 \
  icellmobilsoft/dookug_db:1.1.0
#---------------------
#ORACLE server run - in default schema:
#---------------------
docker run --rm \
  -e AUTO_INSTALL=oracle \
  -e INSTALL_URL_S2=jdbc:oracle:thin:@host:port_num/db_name \
  -e CREATE_DATABASE=false \
  -e INSTALL_STEP=STEP_2 \
  -e INSTALL_USERNAME=vdr_dookug \
```

```
  -e INSTALL_PASSWORD=passw \
  icellmobilsoft/dookug_db:1.1.0
#---------------------
#ORACLE server run - in NOT default schema:
#---------------------
docker run --rm \
  -e AUTO_INSTALL=oracle \
  -e INSTALL_URL_S2=jdbc:oracle:thin:@host:port_num/db_name \
  -e CREATE_DATABASE=false \
  -e INSTALL_SCHEMA=vdr_dookug \
  -e INSTALL_STEP=STEP_2 \
  -e INSTALL_USERNAME=vdr_dookug \
  -e INSTALL_PASSWORD=passw \
  icellmobilsoft/dookug_db:1.1.0
#---------------------
#If the DookuG DB is already installed on the server, then only the 2. step,
liquibase install is needed.
#---------------------
  docker run --rm \
    -e AUTO_INSTALL=oracle \
    -e INSTALL_URL=jdbc:oracle:thin:@host:port/db_name \
    -e INSTALL_STEP=2 \
    icellmobilsoft/dookug_db:1.1.0
```

#on windows: the "\" needs to be changed to "`"!

[DookuG is embedded in to Taxi] | *embedded_dookug_db_into_taxi_db.png*

[DookuG Service register in CRON] | *embedded_dookug_db_in_cron_jobs.png*

- optional environment variable, only needed during password change:

```
  -e DB_SERVICE_USER_PASSWORD=<service user passw> \
```

5. Release notes

- 0.1.0 Changes:
  - Dookug db install
  - Templates install
  - Documentation
- 1.0.0 Changes:
  - DATE type has been replaced with Timestamp(6) in Common.dtd file.
  - DKG-228 - Insert a new flexible template into the boards.
  - DKG-217 - Replacing new date types in the boards.
  - DKG-233 - Hash Fix

    - DKG-231 - Convert documentation
    - DKG-238- Load default templates in Step 4.
    - DKG-245 - Improvement of Dookug Vader Installation Error
- 1.0.3 Changes:
    - DKG-246 - Template Content Fix
    - DKG-261 - Repair of Readme adoc.
    - DKG-261 - Repair of Install.adoc.
- 1.1.0 Changes:
    - DKG-265 - open source changes