Icellmobilsoft base dockerimage

Table of Contents

1. Általános	2
2. Architecture	2
3. Projekt struktúra	3
3.1./dockerfile	3
3.1.1. base images - /dockerfile/bases	4
base	4
base-alpine	4
curl	5
java11jre	5
java17jre	5
java21jre	6
3.1.2. builder images - /dockerfile/builder	6
alpine-runner	6
builder/java11-maven	7
builder/java17-maven	8
builder/java21-maven	8
builder/java11-galleon	9
builder/java17-galleon	10
builder/java21-galleon	10
builder/nexus-download	11
dind	12
icellmobilsoft/builder-java17-maven-sonar	13
3.2. /script	13
3.2.1. Artifact download	13
artifact/maven-search-download.sh	13
artifact/sonatype-download.sh (Nexus 2)	13
artifact/common-nexus-download.sh (Nexus 3)	14
4. Release notes	14
4.1. v1.0.0	14
4.2. v1.1.0	15
4.3. v1.2.0	15
4.4. v1.3.0	16
4.5. v1.4.0	16
4.6. v1.5.0	17
4.7. v1.6.0	17

1. Általános


A repository az icellmobilsoft-ban használt base docker image-k gyűjtését szolgálja, hogy azonos alapon működjenek a projektek és azok buildjei.

A projekt több részre osztható, egymást kiegészítik. Alapvetően 2 csoportra oszthatóak az image-k:

- parent (base image) ezek azok az docker imagek, melyeket a cél termékeknél base image-nek használunk. Csak a feltétlenül szükséges funkció és tartalom lehet bennük.
- builder tartalom hordozásra használjuk őket,ű sosem szabad base image-re használni. A funkciója a multi-stage dockerfile-ban van, ahol például driver tárhelyként van felhasználva.

2. Architecture

Base images



3. Projekt struktúra

3.1./dockerfile

Detailed description of the created Docker image.

3.1.1. base images - /dockerfile/bases

base

- Image: icellmobilsoft/base
- Base: https://hub.docker.com/_/debian official LTS release
- Purpose: Running production applications
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value.
 - USER_GID The GID (Group ID) of the created user group (default 101)
 - USER_UID The UID (User ID) of the created user (default 101)
 - **SYSTEM_USER_DEFAULT** The name of the created user (default icellmobilsoft)
 - SYSTEM_USER_GROUP_DEFAULT The name of the created user group (default icellmobilsoft)
- Added ENV:
 - \$SYSTEM_USER Non 'root' user with which the image runs (default: icellmobilsoft)
 - \$SYSTEM_USER_GROUP The Linux group of the SYSTEM_USER (default: icellmobilsoft)
 - **\$HOME** The home directory of the SYSTEM_USER (WORKDIR \$HOME)
- Installed programs: -

The purpose of the image is to create a system user who runs the image by default.

base-alpine

- Image: icellmobilsoft/base-alpine
- Base: https://hub.docker.com/_/alpine official release
- Purpose: A base image containing a toolset for various stages of development
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value
 - USER_GID The GID (Group ID) of the created user group (default 101)
 - USER_UID The UID (User ID) of the created user (default 101)
 - SYSTEM_USER_DEFAULT The name of the created user (default icellmobilsoft)
 - SYSTEM_USER_GROUP_DEFAULT The name of the created user group (default icellmobilsoft)
- Added ENV:
 - \$SYSTEM USER Non 'root' user with which the image runs (default: icellmobilsoft)
 - \$SYSTEM_USER_GROUP The Linux group of the SYSTEM_USER (default: icellmobilsoft)
 - **\$HOME** The home directory of the SYSTEM USER (WORKDIR \$HOME)

The purpose of the image is to create a system user who runs the image by default.

curl

• Image: icellmobilsoft/base-curl

• Base: icellmobilsoft/base

• Purpose: To run live applications

• Used argument:

- BASE_IMAGE Specifies the base image, it has no default value
- Added ENV: -
- Installed programs:
 - curl

The image uses and extends the above base image with curl.

java11jre

- Image: icellmobilsoft/base-java11jre
- Base: icellmobilsoft/base-curl
- Purpose: Running applications on Java 11 LTS version
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value
 - JRE_TEMURIN_IMAGE A Temurin Java image, from which the JRE parts are copied into the final image
- Added ENV:
 - JAVA_HOME The location of the java directory in the original JRE image (default /opt/java/openjdk) The JAVA_HOME defined in the Temurin image
 - PATH Appending the PATH with JAVA_HOME/bin to make the commands provided by JRE usable
- Installed programs:
 - fontconfig
 - · fonts-dejavu

The image uses and extends the above curl image with jre11.

java17jre

- Image: icellmobilsoft/base-java17jre
- Base: icellmobilsoft/base-curl
- Purpose: Running applications on Java 17 LTS version
- Used argument:

- BASE_IMAGE Specifies the base image, it has no default value
- JRE_TEMURIN_IMAGE A Temurin Java image, from which the JRE parts are copied into the final image

• Added ENV:

- JAVA_HOME The location of the java directory in the original JRE image (default /opt/java/openjdk) The JAVA_HOME defined in the Temurin image
- PATH Appending the PATH with JAVA_HOME/bin to make the commands provided by JRE usable
- Installed programs:
 - fontconfig
 - fonts-dejavu

The image uses and extends the above curl image with jre17.

java21jre

- Image: icellmobilsoft/base-java21jre
- Base: icellmobilsoft/base-curl
- Purpose: Running applications on Java 21 LTS version
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value
 - JRE_TEMURIN_IMAGE A Temurin Java image, from which the JRE parts are copied into the final image
- Added ENV:
 - JAVA_HOME The location of the java directory in the original JRE image (default /opt/java/openjdk) The JAVA_HOME defined in the Temurin image
 - PATH Appending the PATH with JAVA_HOME/bin to make the commands provided by JRE usable
- Installed programs:
 - fontconfig
 - fonts-dejavu

The image uses and extends the above curl image with jre21.

3.1.2. builder images - /dockerfile/builder

alpine-runner

- Image: icellmobilsoft/builder-alpine-runner
- Base: icellmobilsoft/base-alpine
- Purpose: A base image containing a toolset for various stages of development

- Used **argument**:
 - BASE_IMAGE Specifies the base image, it has no default value
 - **USER GID** The GID (Group ID) of the created user group (default 101)
 - **USER_UID** The UID (User ID) of the created user (default 101)
 - SYSTEM_USER_DEFAULT The name of the created user (default icellmobilsoft)
 - SYSTEM_USER_GROUP_DEFAULT The name of the created user group (default icellmobilsoft)
 - \$SYSTEM_USER Non 'root' user with which the image runs (default: icellmobilsoft)
 - \$SYSTEM_USER_GROUP The Linux group of the SYSTEM_USER (default: icellmobilsoft)
 - **\$HOME** The home directory of the SYSTEM_USER (WORKDIR \$HOME)
- Installed programs:
 - bash
 - git
 - openssh
 - curl
 - libxml2-utils
 - jq

builder/java11-maven

- Image: icellmobilsoft/builder-java11-maven
- Base: icellmobilsoft/base-curl
- Purpose: Building a project with Maven based on Java 11 foundations
- Used **argument**:
 - BASE_IMAGE Specifies the base image, it has no default value
 - **JRE_TEMURIN_IMAGE** A Temurin Java image, from which the JRE parts are copied into the final image
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
 - SHA SHA of the Maven file to be downloaded (default: SHA of the current version from the website)
 - MAVEN_DOWNLOAD_URL Donwload URl of Maven (default: https://archive.apache.org/ dist/maven/maven-3/\${MAVEN_VERSION}/binaries)
- Added ENV:
 - MAVEN_VERSION Version number of the Maven used
 - DOWNLOAD_DIR Used in scripts (default \$DOWNLOAD_DIR_DEFAULT\$)
 - MAVEN_HOME Environment variable of MAVEN_HOME for Maven (default \$HOME/maven=/home/icellmobilsoft/maven)

- MAVEN_CONFIG Maven configuration (default \$HOME/.m2=/home/icellmobilsoft/.m2)
- Installed programs:
 - maven Extracted into \$MAVEN HOME
 - jdk Extracted into /opt/java/openjdk
 - git
 - libxml2-utils
 - jq

builder/java17-maven

- Image: icellmobilsoft/builder-java17-maven
- Base: icellmobilsoft/base-curl
- Purpose: Building a project with Maven based on Java 17 foundations
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value
 - JRE_TEMURIN_IMAGE A Temurin Java image, from which the JRE parts are copied into the final image
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
 - **SHA** SHA of the Maven file to be downloaded (default: SHA of the current version from the website)
 - MAVEN_DOWNLOAD_URL Donwload URl of Maven (default: https://archive.apache.org/dist/maven/maven-3/\${MAVEN_VERSION}/binaries)
- Added ENV:
 - MAVEN VERSION Version number of the Maven used
 - DOWNLOAD_DIR Used in scripts (default \$DOWNLOAD_DIR_DEFAULT\$)
 - **MAVEN_HOME** Environment variable of MAVEN_HOME for Maven (default \$HOME/maven=/home/icellmobilsoft/maven)
 - MAVEN_CONFIG Maven configuration (default \$HOME/.m2=/home/icellmobilsoft/.m2)
- Installed programs:
 - maven Extracted into \$MAVEN_HOME
 - jdk Extracted into /opt/java/openjdk
 - git
 - libxml2-utils
 - jq

builder/java21-maven

• Image: icellmobilsoft/builder-java21-maven

- Base: icellmobilsoft/base-curl
- Purpose: Building a project with Maven based on Java 21 foundations
- Used argument:
 - BASE_IMAGE Specifies the base image, it has no default value
 - JRE_TEMURIN_IMAGE A Temurin Java image, from which the JRE parts are copied into the final image
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
 - **SHA** SHA of the Maven file to be downloaded (default: SHA of the current version from the website)
 - MAVEN_DOWNLOAD_URL Donwload URl of Maven (default: https://archive.apache.org/ dist/maven/maven-3/\${MAVEN_VERSION}/binaries)
- Added ENV:
 - MAVEN_VERSION Version number of the Maven used
 - DOWNLOAD_DIR Used in scripts (default \$DOWNLOAD_DIR_DEFAULT\$)
 - MAVEN_HOME Environment variable of MAVEN_HOME for Maven (default \$HOME/maven=/home/icellmobilsoft/maven)
 - MAVEN_CONFIG Maven configuration (default \$HOME/.m2=/home/icellmobilsoft/.m2)
- Installed programs:
 - maven Extracted into \$MAVEN_HOME
 - jdk Extracted into /opt/java/openjdk
 - git
 - libxml2-utils
 - jq

builder/java11-galleon

- Image: icellmobilsoft/builder-java11-galleon
- Base: icellmobilsoft/builder-java11-maven
- Purpose: Building WildFly with Galleon using Maven support on Java 11 foundations
- Used argument:
 - BASE_BUILDER_IMAGE Specifies the base image, it has no default value
 - GALLEON_VERSION Version number of Galleon
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
- Added ENV:
 - **GALLEON_HOME** Directory of Galleon (default \$HOME/galleon=/home/icellmobilsoft/galleon)

- GALLEON_VERSION Used in scripts (default GALLEON_VERSION argumentum)
- DOWNLOAD_DIR Download directory where Galleon will be downloaded (default \$HOME/download=/home/icellmobilsoft/download)
- Installed programs:
 - galleon Extracted into \$GALLEON_HOME

builder/java17-galleon

- Image: icellmobilsoft/builder-java17-galleon
- Base: icellmobilsoft/builder-java17-maven
- Purpose: Building WildFly with Galleon using Maven support on Java 17 foundations
- Used argument:
 - BASE_BUILDER_IMAGE Specifies the base image, it has no default value
 - GALLEON_VERSION Version number of Galleon
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
- Added ENV:
 - **GALLEON_HOME** Directory of Galleon (default \$HOME/galleon=/home/icellmobilsoft/galleon)
 - GALLEON_VERSION Used in scripts (default GALLEON_VERSION argumentum)
 - DOWNLOAD_DIR Download directory where Galleon will be downloaded (default \$HOME/download=/home/icellmobilsoft/download)
- Installed programs:
 - galleon Extracted into \$GALLEON_HOME

builder/java21-galleon

- Image: icellmobilsoft/builder-java21-galleon
- Base: icellmobilsoft/builder-java21-maven
- Purpose: Building WildFly with Galleon using Maven support on Java 21 foundations
- Used argument:
 - BASE_BUILDER_IMAGE Specifies the base image, it has no default value
 - GALLEON_VERSION Version number of Galleon
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
- Added ENV:
 - **GALLEON_HOME** Directory of Galleon (default \$HOME/galleon=/home/icellmobilsoft/galleon)
 - GALLEON_VERSION Used in scripts (default GALLEON_VERSION argumentum)

- DOWNLOAD_DIR Download directory where Galleon will be downloaded (default \$HOME/download=/home/icellmobilsoft/download)
- Installed programs:
 - galleon Extracted into \$GALLEON_HOME

builder/nexus-download

- Image: icellmobilsoft/builder-nexus-download
- Base: icellmobilsoft/base-curl
- Purpose: Downloading artifacts from the company's Nexus or central repository
- Used argument:
 - BASE_BUILDER_IMAGE Specifies the base image, it has no default value
 - DOWNLOAD_DIR_DEFAULT Default download directory (where the Maven tar.gz is downloaded) (default: \$HOME/download = /home/icellmobilsoft/download)
 - NEXUS_USER Nexus user
 - NEXUS_PASSWORD Nexus user password (plain text)
 - NEXUS_REPOSITORY_URL Nexus repository url
 - NEXUS_REPOSITORY Nexus repository within Nexus (e.g.: public)
 - NEXUS_OBJECT_GROUP_ID The groupId of the artifact object
 - $\circ~$ NEXUS_OBJECT_ARTIFACT_ID The artifact of the artifact object
 - NEXUS_OBJECT_EXTENSION The extension of the artifact object (e.g.: jar)
 - NEXUS_OBJECT_VERSION The version of the artifact object
 - NEXUS_OBJECT_CLASSIFIER The classifier of the artifact object
 - NEXUS_DOWNLOAD_OUTPUT_FILE_NAME Output name of the file to be downloaded
 - NEXUS_DOWNLOAD_OUTPUT_FILE_NAME_SHA1 SHA1 of the file to be downloaded
 - **SONATYPE_URL** Sonatype base url (default https://oss.sonatype.org)
 - **SONATYPE_REPOSITORY** The name of the repository from which we want to download the file (default releases)
 - **DEBUG** If set to true (or any value), the commands issued in the download scripts will be printed to the terminal (default is empty)

Added ENV:

- DOWNLOAD_DIR Download directory where Galleon will be downloaded (default \$HOME/download=/home/icellmobilsoft/download)
- NEXUS_USER Nexus username from argument (default \$NEXUS_USER)
- NEXUS_PASSWORD Nexus user password from argument (default \$NEXUS_PASSWORD)
- NEXUS_REPOSITORY_URL Nexus repository URL from argument (default \$NEXUS_REPOSITORY_URL)
- NEXUS_REPOSITORY Nexus repository within Nexus from argument (default

\$NEXUS REPOSITORY)

- NEXUS_OBJECT_GROUP_ID Artifact object's groupId from argument (default \$NEXUS_OBJECT_GROUP_ID)
- **NEXUS_OBJECT_ARTIFACT_ID** AArtifact object's artifactId from argument (default \$NEXUS_OBJECT_ARTIFACT_ID)
- **NEXUS_OBJECT_EXTENSION** Artifact object's extension from argument (default \$NEXUS_OBJECT_EXTENSION)
- NEXUS_OBJECT_VERSION Artifact object's version from argument (default \$NEXUS_OBJECT_VERSION)
- **NEXUS_OBJECT_CLASSIFIER** Artifacet objektum classifier from argument (default \$NEXUS_OBJECT_CLASSIFIER)
- NEXUS_DOWNLOAD_OUTPUT_FILE_NAME Output name of the file to be downloaded from argument (default \$NEXUS_DOWNLOAD_OUTPUT_FILE_NAME)
- **NEXUS_DOWNLOAD_OUTPUT_FILE_NAME_SHA1** SHA1 of the file to be downloaded from argument (default \$NEXUS_DOWNLOAD_OUTPUT_FILE_NAME_SHA1)
- **SONATYPE_URL** Sonatype base url (default https://oss.sonatype.org)
- **SONATYPE_REPOSITORY** The name of the repository from which we want to download the file (default releases)
- **DEBUG** If set to true (or any value), the commands issued in the download scripts will be printed to the terminal (default is empty)
- **NEXUS_REPOSITORY_TYPE** Set it to **central** in your Dockerfile before running the **sonatype-download.sh** script to download artifacts from the Central Portal (default is empty). **SONATYPE REPOSITORY** and **SONATYPE URL** parameters will be ignored.
- Installed programs: -

NOTE The downloaded artifact will be located in the DOWNLOAD_DIR.

dind

- Image: icellmobilsoft/builder-dind-runner
- Base: docker:28.0.0-dind
- Purpose: A base image containing a toolset for various stages of development
- Used **argument**:
 - BASE_IMAGE Specifies the base image, it has no default value
- Installed programs:
 - bash
 - git
 - openssh
 - curl

- libxml2-utils
- jq

icellmobilsoft/builder-java17-maven-sonar

- Image: icellmobilsoft/icellmobilsoft/builder-java17-maven-sonar
- Base: icellmobilsoft/builder-java17-maven
- Purpose: Run SonarQube with maven and java in one image to analys maven project with local sonar.
- Used argument:
 - MAVEN_BUILD_BASE_IMAGE Specifies the base image, it has no default value
- Added ENV:
 - **SONAR_VERSION** Sonarqube version (default 9.9.8.100196)
 - SONAR_HOME Sonarqube home directory (default /opt/sonarqube)
- Installed programs:
 - sonarqube
 - wget
 - unzip
 - procps
- Expose port:
- 9000 (sonar default http port)

3.2. /script

Itt gyülekeznek azok a scriptek melyeket a dockerimage-k felhasználnak.

3.2.1. Artifact download

Maven central/Sonatype artifact lehúzására szolgáló scriptek

artifact/maven-search-download.sh

Célja a központi maven public repository-ból (https://search.maven.org/ az oldala) artifact lehúzása API-n keresztül (https://central.sonatype.org/search/example-urls/) Az objektum útvonalának van egy standardizált képzési algoritmusa, ami a maven package rendszere állít elő.

artifact/sonatype-download.sh (Nexus 2)

A Sonatype Nexus 2 szervernek (public vagy privát) van saját API-ja, ahol szintén le lehet kérdezni az artifactokat. Így nem szükséges a maven dependency plugin használata (önmagában kell hozzá java és sok maven dependency) és közvetlen, gyorsan, egyszerű http hívásokkal lehúzható az a artifact ami kell. A struktúra a maven G-A-V alapon működik.

artifact/common-nexus-download.sh (Nexus 3)

A Sonatype Nexus 3 új API-ja (https://stackoverflow.com/questions/47653338/sonatype-nexus-3-rest-api-backward-compatibility), ahol többek között le is lehet kérdezni az artifactokat. Így nem szükséges a maven dependency plugin használata (önmagában kell hozzá java és sok maven dependency) és közvetlen, gyorsan, egyszerű http hívásokkal lehúzható az a artifact ami kell. A struktúra a maven G-A-V alapon működik. A script konkrétan a https://help.sonatype.com/repomanager3/integrations/rest-and-integration-api/search-api#SearchAPI-SearchandDownloadAsset leírást implementálja.

4. Release notes

4.1. v1.0.0

The project has moved out of the internal repository and, excluding updates, it is 1:1 compatible with version 0.7.0.

Changes compared to the internal version

- bump base image debian:11.2-slim → debian:11.7-slim
- Component upgrade:
 - ∘ Java 11.0.14.1_1-jre → 11.0.19_7-jre
 - Java 11.0.14.1_1-jdk → 11.0.19_7-jdk
 - Java 17.0.2_8-jre → 17.0.7_7-jre
 - Java 17.0.2_8-jdk → 17.0.7_7-jdk
 - Maven 3.8.5 → 3.8.8
- Docker image renaming:
 - base → icellmobilsoft/base
 - ∘ curl → icellmobilsoft/base-curl
 - ∘ java11jre → icellmobilsoft/base-java11jre
 - ∘ java17jre → icellmobilsoft/base-java17jre
 - builder/java11-maven → icellmobilsoft/builder-java11-maven
 - builder/java17-maven → icellmobilsoft/builder-java17-maven
 - builder/java11-galleon → icellmobilsoft/builder-java11-galleon
 - ∘ builder/java17-galleon → icellmobilsoft/builder-java17-galleon
 - builder/nexus-download → icellmobilsoft/builder-nexus-download

What's new

- New image:
 - icellmobilsoft/base Base image with default settings
 - icellmobilsoft/base-alpine Alpine base image with toolsets

- icellmobilsoft/base-curl Base image containing curl
- icellmobilsoft/base-java11jre Handles Java 11 LTS version
- icellmobilsoft/base-java17jre Handles Java 17 LTS version
- icellmobilsoft/builder-java11-maven Image used for Maven building with jdk 11
- icellmobilsoft/builder-java17-maven Image used for Maven building with jdk 17
- icellmobilsoft/builder-java11-galleon Galleon Image based on JDK 11 and Maven
- icellmobilsoft/builder-java17-galleon Galleon Image based on JDK 17 and Maven
- icellmobilsoft/builder-nexus-download Builder image for downloading Nexus artifacts

4.2. v1.1.0

All images are 1:1 compatible with version 1.0.0.

Storage optimization:

- Clearing the apt package manager cache (you must run apt update before installing packages!)
- Deleting package documentation (/usr/share/doc and /usr/share/doc-base)
- Deleting manual pages (/usr/share/man)

icellmobilsoft/builder-nexus-download

- All artifact download scripts have been included in the image.
- From now on, all scripts will log parameters and the sizes of downloaded files.
- The ENV names for downloaded files have been standardized according to common-nexus-download.sh.
 - \$NEXUS_DOWNLOAD_OUTPUT_FILE_NAME (Previously, \$OUTPUT_FILE was used in the sonatype-download.sh and maven-search-download.sh scripts.)
 - \$NEXUS DOWNLOAD OUTPUT FILE NAME SHA1 (Previously \$OUTPUT FILE.sha1)

4.3. v1.2.0

All images are 1:1 compatible with version 1.1.0.

- bump base image debian:11.7-slim → debian:11.8-slim
- bump base image alpine:3.18.? → alpine:3.18.4
- Component upgrade:
 - Java 11.0.19_7-jre → 11.0.20.1_1-jre
 - Java 11.0.19_7-jdk → 11.0.20.1_1-jdk
 - ∘ Java 17.0.7_7-jre → 17.0.8.1_1-jre
 - Java 17.0.7_7-jdk → 17.0.8.1_1-jdk
 - ∘ Galleon 5.1.0.Final → 5.2.1.Final

What's new

- **Multiarch build** In addition to linux/amd64 images, linux/arm64 images will also be produced from now on.
- New image:
 - 。 icellmobilsoft/base-java21jre Handles Java 21 LTS version
 - icellmobilsoft/builder-java21-maven Image used for Maven building with jdk 21
 - icellmobilsoft/builder-java21-galleon Galleon Image based on JDK 21 and Maven

4.4. v1.3.0

All images are 1:1 compatible with version 1.2.0.

Changes

- icellmobilsoft/builder-java* -maven builder images have been supplemented with:
 - apk install libxml2-utils git jq
 - ∘ user change: \$SYSTEM_USER → root

4.5. v1.4.0

All images are 1:1 compatible with version 1.3.0.

Changes

- The icellmobilsoft/builder-nexus-download builder image has changed:
 - Starting from this version, the environment variable NEXUS_OBJECT_CLASSIFIER is also used by the images.
 - Improvement in resolving NEXUS_OBJECT_GROUP if it contains a dot (.) in the artifact groupId
 - Enhancing sonatype-download.sh script with handling of SONATYPE_URL and SONATYPE REPOSITORY environment variables
- The icellmobilsoft/builder-nexus-download builder image has changed:
- In the case of Curl, URLs are now enclosed in double quotes to prevent the runtime environment from attempting to evaluate the download address. This fix has been added to all shell scripts.
- bump base image alpine:3.18.4 → alpine:3.18.5
- Component upgrade:
 - ∘ Java 11.0.20.1_1-jre → 11.0.21_9-jre
 - Java 11.0.20.1_1-jdk → 11.0.21_9-jdk
 - Java 17.0.8.1_1-jre → 17.0.9_9-jre
 - Java 17.0.8.1_1-jdk → 17.0.9_9-jdk
 - Java 21_35-jre → 21.0.1_12-jre

- Java 21_35-jdk → 21.0.1_12-jdk
- ∘ Galleon 5.1.0.Final → 5.2.1.Final

4.6. v1.5.0

All images are 1:1 compatible with version 1.4.0.

Changes

- The icellmobilsoft/builder-nexus-download builder image:
 - In the sonatype-download.sh script, the default value of the SONATYPE_REPOSITORY environment variable has been changed to public, allowing the Sonatype API to also find -SNAPSHOT versions.
 - A new DEBUG variable has been added. In case of true it prints the issued commands to the terminal for easy debugging.
 - ∘ Debian image upgrade: debian:11.8-slim → debian:12.8-slim
 - ∘ Galleon upgrade: 5.2.2.Final → 6.0.4.Final
 - bake-action upgrade docker/bake-action@v4 → docker/bake-action@v5

4.7. v1.6.0

All images are 1:1 compatible with version 1.5.0.

Changes

- The **builder-dind-runner** builder image introduced:
 - dockerfile/builder/dind/Dockerfile