

SMC Trading Bot

Windows VPS Setup Guide — Phone-Friendly

This guide is optimized for setting up the bot from your phone via RDP. Minimal typing required.

What You Need

Item	Details
Windows VPS	Windows Server 2019+ or Windows 10/11
RDP App	Microsoft Remote Desktop (free on iOS/Android)
Telegram Bot Token	From @BotFather on Telegram
Your Telegram ID	From @userinfobot on Telegram
MT5 Installed	With your broker account logged in

Step 1: Install RDP App

Download Microsoft Remote Desktop from your app store (free). Connect to your VPS using its IP address, username (usually Administrator), and password. You'll see the Windows desktop on your phone.

Step 2: Install Python and Git

Install Python:

1. Open browser on VPS, go to python.org/downloads
2. Download Python 3.11+
3. CRITICAL: Check 'Add Python to PATH' during installation
4. Click Install Now

Install Git:

1. Go to git-scm.com/download/win
2. Download and run installer, use all defaults

Install MT5 (if not already):

Download from your broker, install, and log in with your trading account. Keep MT5 running in the background.

Step 3: Download and Set Up the Bot

1. Right-click desktop → New → Folder → Name it 'bot'
2. Open the folder, type 'cmd' in the address bar, press Enter
3. Paste this command:

```
git clone https://github.com/iamlexceez/smc-trading-bot.git
```

4. Open the smc-trading-bot folder
5. Double-click setup.bat — it installs everything automatically

The setup script creates a virtual environment, installs all dependencies, and creates a .env file for you to edit.

Step 4: Configure the Bot

The .env file opens in Notepad. Fill in:

TELEGRAM_BOT_TOKEN=your_token_from_botfather
TELEGRAM_ADMIN_IDS=your_id_from_userinfobot
MT5_LOGIN=your_mt5_account_number
MT5_PASSWORD=your_mt5_password
MT5_SERVER=your_broker_server
TRADING_MODE=live

How to get your Telegram bot token:

1. Open Telegram, search @BotFather
2. Send /newbot, follow the prompts
3. Copy the token (looks like 123456:ABC-DEF1234...)

How to get your Telegram user ID:

1. Search @userinfobot on Telegram
2. Send /start
3. Copy your ID number

Step 5: Start the Bot

1. In the smc-trading-bot folder
2. Double-click start_bot.bat
3. A console window opens showing logs
4. You should see: SMC Trading Bot is running!
5. Open Telegram on your phone and send /start to your bot

That's it. The bot is running.

Step 6: Auto-Start on VPS Reboot

1. Press Win + R on the VPS
2. Type 'shell:startup' and press Enter
3. Right-click → New → Shortcut
4. Browse to start_bot.bat
5. Name it 'SMC Bot' → Finish

Now the bot restarts automatically whenever the VPS boots.

Step 7: Using the Bot from Telegram

What you want	Command
See the main menu	/start
Scan all symbols for signals	/scan
Analyze a specific pair	/analyze EURUSD
Run a backtest	/backtest EURUSD H1 180
Check open positions	/positions
See account balance	/account
View/change settings	/settings
Check session status	/sessions
Check news filter	/news EURUSD
Turn ON auto-trading	/settings → Auto-Trade → Confirm
Switch to live trading	/settings → Mode → Live → Confirm
Pause everything	/pause
Close all positions	/close_all → Confirm

Quick Reference — Minimum Viable Setup

1. RDP into VPS from phone
2. Install Python (check 'Add to PATH')
3. Install Git
4. Install MT5, log in to broker
5. Open CMD: `git clone https://github.com/iamlexcee/smc-trading-bot.git`
6. `cd smc-trading-bot`
7. Double-click `setup.bat`
8. Edit `.env` with your token, ID, and MT5 details
9. Double-click `start_bot.bat`
10. Message your bot on Telegram: `/start`

Troubleshooting

Problem	Solution
'Python is not recognized'	Reinstall Python, check 'Add to PATH'
'git is not recognized'	Install Git from git-scm.com/download/win
Bot starts but doesn't respond	Check token in .env, check admin ID, make sure you're messaging the right bot
'MT5 not available'	Ensure MT5 is installed and running, check MT5 credentials in .env
VPS disconnected, bot stopped	Reconnect via RDP, double-click start_bot.bat again
How to update the bot	Open CMD in the folder, run: git pull, then start_bot.bat