TCP Flow Control and Congestion Control

EECS 489 Computer Networks

http://www.eecs.umich.edu/courses/eecs489/w07


Z. Morley Mao Monday Feb 5, 2007

TCP Flow Control

 receive side of TCP connection has a receive buffer:

-flow control-


sender won't overflow receiver's buffer by transmitting too much, too fast



 speed-matching service: matching the send rate to the receiving app's drain rate

app process may be slow at reading from buffer

TCP Flow control: how it works



(Suppose TCP receiver discards out-of-order segments)

- spare room in buffer
- = RcvWindow
- = RcvBuffer-[LastByteRcvd LastByteRead]

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
 - guarantees receive buffer doesn't overflow

TCP Connection Management

Recall: TCP sender, receiver establish "connection" before exchanging data segments

- initialize TCP variables:
 - seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator
 Socket clientSocket = new
 Socket("hostname","port
 number");
- server: contacted by client
 Socket connectionSocket =
 welcomeSocket.accept();

Three way handshake:

Step 1: client host sends TCP SYN segment to server

- specifies initial seq #
- no data

Step 2: server host receives SYN, replies with SYNACK segment

- server allocates buffers
- specifies server initial seq. #

Step 3: client receives SYNACK, replies with ACK segment, which may contain data


TCP Connection Management (cont.)

Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




TCP Connection Management (cont.)

Step 3: client receives FIN, replies with ACK.


 Enters "timed wait" - will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



TCP Connection Management (cont)





Principles of Congestion Control


Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delays when congested
- maximum achievable throughput

- one router, finite buffers
- sender retransmission of lost packet



- always: $\lambda_{in} = \lambda_{out}(goodput)$
- "perfect" retransmission only when loss: $\lambda' > \lambda$
- retransmission of delayed (not lost) packet makes λ' larger (than in




"costs" of congestion:


more work (retrans) for given "goodput" unneeded retransmissions: link carries multiple copies of pkt Mao W07

11

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as and λ' increase?





Another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

Two broad approaches towards congestion control:

End-end congestion control:

- no explicit feedback from network
- congestion inferred from endsystem observed loss, delay
- approach taken by TCP

Network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Case study: ATM ABR congestion control


ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - Cl bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell
 - sender' send rate thus minimum supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
 - if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

TCP Congestion Control

- end-end control (no network assistance)
- sender limits transmission:

Roughly,

 CongWin is dynamic, function of perceived network congestion

rate =
$$\frac{CongWin}{RTT}$$
 Bytes/sec

How does sender perceive congestion?

- loss event = timeout or 3 duplicate acks
- TCP sender reduces rate (CongWin) after loss event


three mechanisms:

- AIMD
- slow start
- conservative after timeout events

TCP AIMD

multiplicative decrease: cut CongWin in half after loss event

additive increase: increase CongWin by 1 MSS every RTT in the absence of loss events: *probing*




TCP Slow Start

- When connection begins,CongWin = 1 MSS
 - Example: MSS = 500 bytes & RTT = 200 msec
 - initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - desirable to quickly ramp up to respectable rate

When connection begins, increase rate exponentially fast until first loss event

TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
 - double CongWin every RTT
 - done by incrementing CongWin for every ACK received
- Summary: initial rate is slow but ramps up exponentially fast



Refinement

- After 3 dup ACKs:
 - CongWin is cut in half
 - window then grows linearly
- <u>But</u> after timeout event:
 - Congwin instead set to 1 MSS;
 - window then grows exponentially
 - to a threshold, then grows linearly


Philosophy:

- 3 dup ACKs indicates network capable of delivering some segments
- timeout before 3 dup
 ACKs is "more alarming"

Refinement (more)

Q: When should the exponential increase switch to linear?

A: When Congwin gets to 1/2 of its value before timeout.



Implementation:

- Variable Threshold
- At loss event, Threshold is set to 1/2 of CongWin just before loss event

Summary: TCP Congestion Control

- When CongWin is below Threshold, sender in slowstart phase, window grows exponentially.
- When CongWin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

TCP sender congestion control

Event	State	TCP Sender Action	Commentary
ACK receipt for previously unacked data	Slow Start (SS)	CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance"	Resulting in a doubling of CongWin every RTT
ACK receipt for previously unacked data	Congestion Avoidance (CA)	CongWin = CongWin+MSS * (MSS/CongWin)	Additive increase, resulting in increase of CongWin by 1 MSS every RTT
Loss event detected by triple duplicate ACK	SS or CA	Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance"	Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS.
Timeout	SS or CA	Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start"	Enter slow start
Duplicate ACK	SS or CA	Increment duplicate ACK count for segment being acked	CongWin and Threshold not changed

TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
 - Ignore slow start
- Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- Just after loss, window drops to W/2, throughput to W/2RTT.
- Average throughout: .75 W/RTT

TCP Futures


- Example: 1500 byte segments, 100ms RTT, want
 10 Gbps throughput
- Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT\sqrt{L}}$$

- \rightarrow L = 2·10⁻¹⁰ Wow
- New versions of TCP for high-speed needed!

TCP Fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- Multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- Instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

Fairness and parallel TCP connections

- nothing prevents app from opening parallel cnctions between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 cnctions;
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2!

Delay modeling

Q: How long does it take to receive an object from a Web server after sending a request?

Ignoring congestion, delay is influenced by:

- TCP connection establishment
- data transmission delay
- slow start

Notation, assumptions:

- Assume one link between client and server of rate R
- S: MSS (bits)
- O: object size (bits)
- no retransmissions (no loss, no corruption)

Window size:

- First assume: fixed congestion window, W segments
- Then dynamic window, modeling slow start

TCP Delay Modeling: Slow Start (1)

Now suppose window grows according to slow start

Will show that the delay for one object is:

$$Latency = 2RTT + \frac{O}{R} + P \left[RTT + \frac{S}{R} \right] - (2^{P} - 1) \frac{S}{R}$$

where P is the number of times TCP idles at server:

$$P = \min\{Q, K-1\}$$

- where Q is the number of times the server idles if the object were of infinite size.
- and K is the number of windows that cover the object.

TCP Delay Modeling: Slow Start (2)

Delay components:


- 2 RTT for connection estab and request
- O/R to transmit object
- time server idles due to slow start

Server idles: P = min{K-1,Q} times

Example:

- \cdot 0/5 = 15 segments
- K = 4 windows
- Q = 2
- $P = min\{K-1,Q\} = 2$

Server idles P=2 times



TCP Delay Modeling (3)

$$\frac{S}{R} + RTT = \text{time from when server starts to send segment}$$


until server receives acknowledgement initiate TCP connection

$$2^{k-1} \frac{S}{R} = \text{time to transmit the kth window}$$

$$\left[\frac{S}{R} + RTT - 2^{k-1} \frac{S}{R}\right]^{+} = \text{idle time after the } k\text{th window}$$

delay =
$$\frac{O}{R} + 2RTT + \sum_{p=1}^{P} idleTime_{p}$$

= $\frac{O}{R} + 2RTT + \sum_{k=1}^{P} \left[\frac{S}{R} + RTT - 2^{k-1} \frac{S}{R} \right]$
= $\frac{O}{R} + 2RTT + P[RTT + \frac{S}{R}] - (2^{P} - 1) \frac{S}{R}$



TCP Delay Modeling (4)

Recall K = number of windows that cover object

How do we calculate K?

$$K = \min\{k : 2^{0}S + 2^{1}S + \dots + 2^{k-1}S \ge O\}$$

$$= \min\{k : 2^{0} + 2^{1} + \dots + 2^{k-1} \ge O/S\}$$

$$= \min\{k : 2^{k} - 1 \ge \frac{O}{S}\}$$

$$= \min\{k : k \ge \log_{2}(\frac{O}{S} + 1)\}$$

$$= \left\lceil \log_{2}(\frac{O}{S} + 1) \right\rceil$$


Calculation of Q, number of idles for infinite-size object, is similar (see HW).

HTTP Modeling

- Assume Web page consists of:
 - 1 base HTML page (of size O bits)
 - *M* images (each of size *O* bits)
- Non-persistent HTTP:
 - M+1 TCP connections in series
 - Response time = (M+1)O/R + (M+1)2RTT + sum of idle times
- Persistent HTTP:
 - 2 RTT to request and receive base HTML file
 - 1 RTT to request and receive M images
 - Response time = (M+1)O/R + 3RTT + sum of idle times
- Non-persistent HTTP with X parallel connections
 - Suppose M/X integer.
 - 1 TCP connection for base file
 - M/X sets of parallel connections for images.
 - Response time = (M+1)O/R + (M/X + 1)2RTT + sum of idle times

HTTP Response time (in seconds)

RTT = 100 msec, O = 5 Kbytes, M=10 and X=5




For low bandwidth, connection & response time dominated by transmission time.

Persistent connections only give minor improvement over parallel connections.

Mao W07

HTTP Response time (in seconds)

RTT = 1 sec, O = 5 Kbytes, M = 10 and X = 5



For larger RTT, response time dominated by TCP establishment & slow start delays. Persistent connections now give important improvement: particularly in high delay•bandwidth networks.

Issues to Think About

- What about short flows? (setting initial cwnd)
 - most flows are short
 - most bytes are in long flows
- How does this work over wireless links?
 - packet reordering fools fast retransmit
 - loss not always congestion related
- High speeds?
 - to reach 10gbps, packet losses occur every 90 minutes!
- Fairness: how do flows with different RTTs share link?

Security issues with TCP

- Example attacks:
 - Sequence number spoofing
 - Routing attacks
 - Source address spoofing
 - Authentication attacks


Network Layer

goals:

- understand principles behind network layer services:
 - routing (path selection)
 - dealing with scale
 - how a router works
 - advanced topics: IPv6, mobility
- instantiation and implementation in the Internet

Network layer

- transport segment from sending to receiving host
- on sending side encapsulates segments into datagrams
- on rcving side, delivers segments to transport layer
- network layer protocols in every host, router
- Router examines header fields in all IP datagrams passing through it




Key Network-Layer Functions

- forwarding: move packets from router's input to appropriate router output
- routing: determine route taken by packets from source to dest.
 - Routing algorithms

analogy:

- routing: process of planning trip from source to dest
- forwarding: process of getting through single interchange

Interplay between routing and forwarding



Connection setup

- 3rd important function in *some* network architectures:
 - ATM, frame relay, X.25
- Before datagrams flow, two hosts and intervening routers establish virtual connection
 - Routers get involved
- Network and transport layer cnctn service:
 - Network: between two hosts
 - Transport: between two processes

Network service model

Q: What service model for "channel" transporting datagrams from sender to rcvr?

Example services for individual datagrams:

- guaranteed delivery
- Guaranteed delivery with less than 40 msec delay

Example services for a flow of datagrams:

- In-order datagram delivery
- Guaranteed minimum bandwidth to flow
- Restrictions on changes in inter-packet spacing

Network layer service models:

	Network rchitecture	Service Model	Guarantees ?				Congestion
Ar			Bandwidth	Loss	Order	Timing	feedback
	Internet	best effort	none	no	no	no	no (inferred via loss)
	ATM	CBR	constant rate	yes	yes	yes	no congestion
	ATM	VBR	guaranteed rate	yes	yes	yes	no congestion
	ATM	ABR	guaranteed minimum	no	yes	no	yes
	ATM	UBR	none	no	yes	no	no

Network layer connection and connection-less service

- Datagram network provides network-layer connectionless service
- VC network provides network-layer connection service
- Analogous to the transport-layer services, but:
 - Service: host-to-host
 - No choice: network provides one or the other
 - Implementation: in the core

Virtual circuits

"source-to-dest path behaves much like telephone circuit"

- performance-wise
- network actions along source-to-dest path

- call setup, teardown for each call before data can flow
- each packet carries VC identifier (not destination host address)
- every router on source-dest path maintains "state" for each passing connection
- link, router resources (bandwidth, buffers) may be allocated to VC


VC implementation

A VC consists of:

- 1. Path from source to destination
- 2. VC numbers, one number for each link along path
- 3. Entries in forwarding tables in routers along path
- Packet belonging to VC carries a VC number.
- VC number must be changed on each link.
 - New VC number comes from forwarding table

Forwarding table






Forwarding table in northwest router:

Incoming interface	Incoming VC#	Outgoing interface	Outgoing VC #
1	12	2	22
2	63	1	18
3	7	2	17
1	97	3	87
•••			

Routers maintain connection state information!


Virtual circuits: signaling protocols

- used to setup, maintain teardown VC
- used in ATM, frame-relay, X.25
- not used in today's Internet



Datagram networks

- no call setup at network layer
- routers: no state about end-to-end connections
 - no network-level concept of "connection"
- packets forwarded using destination host address
 - packets between same source-dest pair may take different paths



Forwarding table

4 billion possible entries

Destination Address Range	Link Interface
11001000 00010111 00010000 00000000 through 11001000 00010111 00010111 11111111	0
11001000 00010111 00011000 00000000 through 11001000 00010111 00011000 11111111	1
11001000 00010111 00011001 00000000 through 11001000 00010111 00011111 11111111	2
otherwise	3

Longest prefix matching

Prefix Match	Link Interface
11001000 00010111 00010	0
11001000 00010111 00011000	1
11001000 00010111 00011	2
otherwise	3

Examples

DA: 11001000 00010111 00010110 10100001 Which interface?

DA: 11001000 00010111 00011000 10101010 Which interface?

Datagram or VC network: why?

Internet

- data exchange among computers
 - "elastic" service, no strict timing req.
- "smart" end systems (computers)
 - can adapt, perform control, error recovery
 - simple inside network, complexity at "edge"
- many link types
 - different characteristics
 - uniform service difficult

ATM

- evolved from telephony
- human conversation:
 - strict timing, reliability requirements
 - need for guaranteed service
- "dumb" end systems
 - telephones
 - complexity inside network