
Virtual Memory





Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time
 - Less I/O needed to load or swap programs into memory -> each user program runs faster





Virtual memory

- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes






Virtual memory (Cont.)

- Virtual address space logical view of how process is stored in memory
 - Usually start at address 0, contiguous addresses until end of space
 - Meanwhile, physical memory organized in page frames
 - MMU must map logical to physical
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation





Virtual Memory That is Larger Than Physical Memory








Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- invalid reference ⇒ abort
 - Not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager







Basic Concepts


- With swapping, the pager guesses which pages will be used before swapping them out again
- How to determine that set of pages?
- Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code
- Use page table with valid-invalid bit





Page table with Valid-Invalid Bit

- With each page table entry a valid–invalid bit is associated (v ⇒ in-memory, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:





 During MMU address translation, if valid–invalid bit in the page table entry is i ⇒ page fault





Page Table When Some Pages Are Not in Main Memory










Steps in Handling Page Fault

- 1. If there is a reference to a page, first reference to that page will trap to operating system
 - Page fault
- 2. Operating system looks at another table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory (go to step 3)
- 3. Find free frame (what if there is none?)
- 4. Swap page into frame via scheduled disk operation
- 5. Reset tables to indicate page now in memory Set validation bit = v
- 6. Restart the instruction that caused the page fault






Steps in Handling a Page Fault (Cont.)







Aspects of Demand Paging


- Pure demand paging: start process with no pages in memory
 - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
 - And for every other process pages on first access
- Actually, a given instruction could access multiple pages -> multiple page faults
 - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart





Instruction Restart

- Consider an instruction that could access several different locations
 - Block move



- Auto increment/decrement location
- Restart the whole operation?
 - What if source and destination overlap?





Free-Frame List

- When a page fault occurs, the operating system must bring the desired page from secondary storage into main memory.
- Most operating systems maintain a free-frame list -- a pool of free frames for satisfying such requests.



- Operating system typically allocate free frames using a technique known as **zero-fill-on-demand** -- the content of the frames zeroed-out before being allocated.
- When a system starts up, all available memory is placed on the free-frame list.





Stages in Demand Paging – Worse Case

- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
 - a) Wait in a queue for this device until the read request is serviced
 - b) Wait for the device seek and/or latency time
 - c) Begin the transfer of the page to a free frame





Stages in Demand Paging (Cont.)

- 6. While waiting, allocate the CPU to some other user
- Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- Determine that the interrupt was from the disk
- Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction






Performance of Demand Paging

- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Input the page from disk lots of time
 - Restart the process again just a small amount of time
- Page Fault Rate $0 \le p \le 1$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

$$EAT = (1 - p) \times memory access$$

- + p (page fault overhead
- + swap page out
- + swap page in)





Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = $(1 p) \times 200 + p$ (8 milliseconds) = $(1 - p) \times 200 + p \times 8,000,000$ = $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- If want performance degradation < 10 percent</p>
 - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
 - p < .0000025
 - one page fault in every 400,000 memory accesses






Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
 - Pool should always have free frames for fast demand page execution
 - Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
 - Designed to have child call exec()
 - Very efficient





What Happens if There is no Free Frame?

- Used up by process pages
- Also in demand from the kernel, I/O buffers, etc.
- How much to allocate to each?
- Page replacement find some page in memory, but not really in use, page it out
 - Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times






Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory





Need For Page Replacement







Basic Page Replacement


- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a **victim frame**
 - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- Continue the process by restarting the instruction that caused the trap

Note now potentially 2 page transfers for page fault – increasing EAT





Page Replacement





memory



Page and Frame Replacement Algorithms


- Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1





Graph of Page Faults Versus the Number of Frames







First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)

page frames 15 page


- How to faults ages of pages?
 - Just use a FIFO queue





Belady's Anomaly

- Consider the string 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
- Graph illustrating Belady's Anomaly








Optimal Algorithm

- Replace page that will not be used for longest period of time
 - 9 is optimal for the example
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs




• Optimal is all example of stack algorithms that don't suffer home Belady's Anomaly





Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page



- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- LRU is another example of stack algorithms; thus it does not suffer from Belady's Anomaly





LRU Algorithm Implementation

- Time-counter implementation
 - Every page entry has a time-counter variable; every time a page is referenced through this entry, copy the value of the clock into the time-counter
 - When a page needs to be changed, look at the time-counters to find smallest value
 - Search through a table is needed
- Stack implementation
 - Keep a stack of page numbers in a double link form:
 - Page referenced:
 - Move it to the top
 - Requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement






Stack Implementation

Use of a stack to record most recent page references









LRU Approximation Algorithms

- Needs special hardware
- Reference bit
 - With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
- Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however






LRU Approximation Algorithms (cont.)

- Second-chance algorithm
 - Generally FIFO, plus hardware-provided reference bit
- Clock replacement
 - If page to be replaced has
 - ▶ Reference bit = 0 -> replace it
 - Reference bit = 1 then:
 - Set reference bit 0, leave page in memory
 - Replace next page, subject to same rules





Second-chance Algorithm







Enhanced Second-Chance Algorithm

- Improve algorithm by using reference bit and modify bit (if available) in concert
- Take ordered pair (reference, modify):
 - (0, 0) neither recently used not modified best page to replace
 - (0, 1) not recently used but modified not quite as good, must write out before replacement
 - (1, 0) recently used but clean probably will be used again soon
 - (1, 1) recently used and modified probably will be used again soon and need to write out before replacement
- When page replacement called for, use the clock scheme but use the four classes replace page in lowest non-empty class
 - Might need to search circular queue several times






Counting Algorithms

- Keep a counter of the number of references that have been made to each page
 - Not common
- Lease Frequently Used (LFU) Algorithm:
 - Replaces page with smallest count
- Most Frequently Used (MFU) Algorithm:
 - Based on the argument that the page with the smallest count was probably just brought in and has yet to be used






Page-Buffering Algorithms

- Keep a pool of free frames, always
 - Then frame available when needed, not found at fault time
 - Read page into free frame and select victim to evict and add to free pool
 - When convenient, evict victim
- Possibly, keep list of modified pages
 - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected





Page-Buffering Algorithms

- Keep a pool of free frames which is never empty
 - Thus a frame is available when needed, not found at fault time
 - Read page into free frame and select victim to evict and add to free pool
 - When convenient, evict victim
- Possibly, keep list of modified pages
 - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - Generally useful to reduce penalty if wrong victim frame selected






Applications and Page Replacement

- All of these algorithms have OS guessing about future page access
- Some applications have better knowledge i.e., databases
- Memory intensive applications can cause double buffering
 - OS keeps copy of page in memory as I/O buffer
 - Application keeps page in memory for its own work
- Operating system can provide direct access to the disk, getting out of the way of the applications
 - Raw disk mode
- Bypasses buffering, locking, etc.






Allocation of Frames

- Each process needs minimum number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - Instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Maximum of course is total frames in the system
- Two major allocation schemes
 - Fixed allocation
 - Priority allocation
- Many variations





Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$-s_i$$
 =size of process p_i

$$-S = \sum s_i$$


$$-m$$
 =total number of frames

$$-a_i$$
 =allocation for $p_i = \frac{s_i}{S} \times m$

$$m = 64$$

 $s_1 = 10$
 $s_2 = 127$
 $a_1 = \frac{10}{137} \times 62 \approx 4$
 $a_2 = \frac{127}{137} \times 62 \approx 57$





Global vs. Local Allocation


- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - Process execution time can vary greatly
 - Greater throughput so more commonly used
- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory
 - What if a process does not have enough frames?





Non-Uniform Memory Access

- So far, we assumed that all memory accessed equally
- Many systems are NUMA speed of access to memory varies
 - Consider system boards containing CPUs and memory, interconnected over a system bus
- NUMA multiprocessing architecture







NUMA Access (Cont.)

- Optimal performance comes from allocating memory "close to" the CPU on which the thread is scheduled
 - And modifying the scheduler to schedule the thread on the same system board when possible
 - Solved by Solaris by creating Igroups
 - Structure to track CPU / Memory low latency groups
 - Used my schedule and pager
 - When possible schedule all threads of a process and allocate all memory for that process within the Igroup





Thrashing


- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need the replaced frame back
- This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system





Thrashing (Cont.)

Thrashing. A process is busy swapping pages in and out







Demand Paging and Thrashing

Why does demand paging work?

Locality model

- Process migrates from one locality to another
- Localities may overlap
- Why does thrashing occur?


 Σ size of locality > total memory size

- To avoid trashing:
 - Calculate the Σ size of locality
 - Policy:
 - if ∑ size of locality > total memory size → suspend or swap out one of the processes
- Issue: how to calculate "Σ size of locality"





Locality In A Memory-Reference Pattern









Working-Set Model

- $\Delta \equiv$ working-set window \equiv a fixed number of page references Example: 10,000 instructions
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass the entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- Example

page reference table

...2615777751623412344434344413234443444...











Working-Set Model

- $\Delta \equiv$ working-set window \equiv a fixed number of page references Example: 10,000 instructions
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass the entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program

page reference table

... 2615777751623412344434344413234443444...






- $D = \Sigma WSS_i \equiv \text{total demand frames}$
 - Approximation of locality






Working Sets and Page Fault Rates

- Direct relationship between working set of a process and its page-fault rate
- Working set changes over time
- Peaks and valleys over time







Page-Fault Frequency Algorithm

- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame

