GGZEM

Africa's Super App

BACK-END DEVELOPER - BUSINESS CASE

Package Tracker


Create a package tracking web application suite consisting of the following:

- 1) Web Tracker customer client web application (SPA)
- 2) Web Driver driver client web application (SPA)
- 3) Web Admin admin back-office client web application (SPA)
- 4) REST API business process back-end services
- 5) Websocket Events for real time updates and communication

Use the MEAN stack:

- 1) MongoDB
- 2) Express
- 3) Angular
- 4) Node.js

Overview



Database Entities

PACKAGE package_id (string guid) active_delivery_id (string guid)

description (string) weight (int grams)

width (int cm)

height (int cm)

depth (int cm)

from_name (string)

from_address (string) from_location (obj: lat, lng)

to_name (string)

to_address (string)

to_location (obj: lat, lng)

DELIVERY

delivery_id (string guid)
package_id (string guid)
pickup_time (timestamp)
start_time (timestamp)
end_time (timestamp)
location (obj: lat, lng)
status (enum: open,
picked-up, in-transit,

delivered, failed)

REST APIs

Package API (Data Format: JSON)

Method	URL	Description
GET	/api/package	Get all packages
GET	/api/package/{id}	Get package by id
POST	/api/package/{id}	Create new package
PUT	/api/package/{id}	Update package
DELETE	/api/package/{id}	Delete package

REST APIs

Delivery API (Data Format: JSON)

Method	URL	Description
GET	/api/delivery	Get all deliveries
GET	/api/delivery/{id}	Get delivery by id
POST	/api/delivery/{id}	Create new delivery
PUT	/api/delivery/{id}	Update delivery
DELETE	/api/delivery/{id}	Delete delivery

Websocket Events

Events (Data Format: Serialized JSON String)

Event	Туре	Payload	Description
location_changed	incoming	{event, delivery_id, location} Update the location of a delivery	
status_changed	incoming	{event, delivery_id, status}	Update the status of a delivery When the status changes from open to picked-up, set the pickup_time to current time When the status changes from picked-up to in-transit, set the start_time to current time When the status changes from in-transit to delivered or failed, set the end_time to current time
delivery_updated	broadcast	{event, delivery_object}	Broadcast when a delivery is updated


Web Tracker

A customer can enter a package ID to track their package. Use the rest API's to fetch the package. If the package has an active delivery, then fetch the delivery and create a websocket connection to listen for delivery update events. Display the package and delivery details and update the map with package source, destination and current location of the delivery.

Package Details Delivery Details			
 MAP	Enter Package ID Track		
	 	MAP	

Web Driver

A driver can enter a delivery ID to load their delivery. Use the rest API's to fetch the delivery and package and display the details. Use the browser location API to fetch the current location and display it on the map along with package source and destination location. Fetch the current browser location every 20 seconds and send a delivery location update websocket event.



Status Buttons

Send a status change websocket event when button is clicked.

Picked Up - change status to "picked-up", button is enabled if status is "open"

In Transit - change status to "in-transit", button is enabled if status is "picked-up"

Delivered - change status to "delivered", button enabled if status is "in-transit"

Failed - change status to "failed", button enabled if status is "in-transit"

Web Admin - Home

.

Package List	Create Package	
Delivery List	Create Delivery	

Web Admin - Create Package

.



Web Admin - Create Delivery

.

