# Looking for Real Exam Questions for IT Certification Exams!

We guarantee you can pass any IT certification exam at your first attempt with just 10-12 hours study of our guides.

Our study guides contain actual exam questions, you will get word to word same on your actual test; accurate answers with detailed explanation verified by experts and all graphics and drag-n-drop exhibits shown just as on the real test.

To test the quality of our guides, you can download the one-fourth portion of any guide from http://www.certificationking.com absolutely free.

**B**esides, we also offer complete version of following exams absolutely free. You can start your certification from these free guides and if you are satisfied you can buy the rest

- ◆ Microsoft: 70-270, 70-305 ◆ Cisco: 642-901 ◆ Oracle: 1Z0-007, 200 ◆ CompTIA: 220-601
- ◆ SUN: 310-011, 310-043 ◆ Citrix: 1Y0-A01, 1Y0-256 ◆ CIW: 1D0-420 ◆ Novell: 50-686
- ◆ Adobe: 9A0-029 ◆ Apple: 9L0-005, 9L0-505 ◆ Avaya: 132-S-100 ◆ Cognos: COG-105
- ◆ CWNP: PW0-100 ◆ EMC: E20-001 ◆ Hyperion: 4H0-002 ◆ HP: HP0-771, HP0-J24
- ◆ IBM: 000-253, 000-700 ◆ Juniper: JN0-100, JN0-201 ◆ Lotus: LOT-737
- ◆ Nortel: 920-803 ◆ SAS: A00-201 ◆ SNIA: S10-100 ◆ Sybase: 510-015
- ◆ Symantec: 250-101 ◆ TeraData: NR0-011

For pricing and placing order, please visit http://certificationking.com/order.html We accept all major credit cards through www.paypal.com

For other payment options and any further query, feel free to mail us at info@certificationking.com

## **QUESTION NO: 1 CORRECT TEXT**

Change the root Password to redtophat

Answer and Explanation:Boot the system in Single user modeUse the passwd command

### **QUESTION NO: 2 CORRECT TEXT**

Dig Server1.example.com, Resolve to successfully through DNS Where DNS server is 172.24.254.

Answer and Explanation:

#vi /etc/resolv.conf nameserver 172.24.254.254 # dig server1.example.com #host server1.example.com

DNS is the Domain Name System, which maintains a database that can help your computer translate domain names such as www.redhat.com to IP addresses such as 216.148.218.197. As no individual DNS server is large enough to keep a database for the entire Internet, they can refer requests to other DNS servers.

DNS is based on the named daemon, which is built on the BIND (Berkeley Internet Name Domain) package developed through the Internet Software Consortium

Users wants to access by name so DNS will interpret the name into ip address. You need to specify the Address if DNS server in each and every client machine. In Redhat Enterprise Linux, you need to specify the DNS server into /etc/resolv.conf file.

After Specifying the DNS server address, you can verify using host, dig and nslookup commands.

## **QUESTION NO: 3 CORRECT TEXT**

Create the partition having 100MB size and mount it on /mnt/neo

- 1. Use fdisk /dev/hda à To create new partition.
- 2. Type n à For New partitions
- 3. It will ask for Logical or Primary Partitions. Press I for logical.
- 4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.
- 5. Type the Size: +100M à You can Specify either Last cylinder of Size here.
- 6. Press P to verify the partitions lists and remember the partitions name.

- 7. Press w to write on partitions table.
- 8. Either Reboot or use partprobe command.
- 9. Use mkfs -t ext3 /dev/hda? Where ? is your partition number
- 10. Or
- 11. mke2fs -j /dev/hda? à To create ext3 filesystem.
- 12. mkdir /mnt/neo
- 13. vi /etc/fstab
- 14. Write:
- 15. /dev/hda? /mnt/neo ext3 defaults 1 2
- 16. Verify by mounting on current Sessions also:
- 17. mount /dev/hda? /mnt/neo

#### **QUESTION NO: 4 CORRECT TEXT**

Your System is going use as a router for 172.24.0.0/16 and 172.25.0.0/16. Enable the IP Forwarding.

Answer and Explanation:

- 1. echo "1" >/proc/sys/net/ipv4/ip\_forward
- 2. vi /etc/sysctl.conf

net.ipv4.ip\_forward=1

/proc is the virtual filesystem, containing the information about the running kernel. To change the parameter of running kernel you should modify on /proc. From Next reboot the system, kernel will take the value from /etc/sysctl.conf.

## **QUESTION NO: 5 CORRECT TEXT**

Some users home directory is shared from your system. Using showmount -e localhost command, the shared directory is not shown. Make access the shared users home directory.

- 1. Verify the File whether Shared or not ? : cat /etc/exports
- 2. Start the nfs service: service nfs start
- 3. Start the portmap service: service portmap start
- 4. Make automatically start the nfs service on next reboot: chkconfig nfs on
- 5. Make automatically start the portmap service on next reboot: chkconfig portmap on

- 6. Verify either sharing or not: showmount -e localhost
- 7. Check that default firewall is running on system? if running flush the iptables using iptables -F and stop the iptables service.

## **QUESTION NO: 6 CORRECT TEXT**

neo user tried by:

dd if=/dev/zero of=/home/neo/somefile bs=1024 count=70

files created successfully. Again neo tried to create file having 70K using following command:

dd if=/dev/zero of=/home/neo/somefile bs=1024 count=70

But he is unable to create the file. Make the user can create the file less then 70K.

## Answer and Explanation:

Very Tricky question from redhat. Actually question is giving scenario to you to implement quota to neo user. You should apply the quota to neo user on /home that neo user shouldn't occupied space more than 70K.

1. vi /etc/fstab

LABEL=/home /home ext3 defaults,usrquota 0 0 à To enable the quota on filesystem you should mount the filesystem with usrquota for user quota and grpquota for group quota.

- 2. touch /home/aquota.user àCreating blank quota database file.
- 3. mount -o remount /home à Remounting the /home with updated mount options. You can verify that /home is mounted with usrquota options or not using mount command.
- 4. quotacheck -u /home à Initialization the quota on /home
- 5. edquota -u neo /home à Quota Policy editor

See the snapshot

- 1 Disk quotas for user neo (uid 500):
- 2 Filesystem blocks soft hard inodes soft hard
- 4 /dev/mapper/vo-myvol 2 30 70 1 0 0

Can you set the hard limit 70 and soft limit as you think like 30.

Verify using the repquota /home command.

### **QUESTION NO: 7 CORRECT TEXT**

One Logical Volume is created named as myvol under vo volume group and is mounted. The Initial Size of that Logical Volume is 124MB. Make successfully that the size of Logical Volume 245MB without losing any data. The size of logical volume 240MB to 255MB will be acceptable.

## Answer and Explanation:

- 1. First check the size of Logical Volume: lvdisplay /dev/vo/myvol
- 2. Increase the Size of Logical Volume: Ivextend -L+121M /dev/vo/myvol
- 3. Make Available the size on online: resize2fs /dev/vo/myvol
- 4. Verify the Size of Logical Volume: lvdisplay /dev/vo/myvol
- 5. Verify that the size comes in online or not: df -h

We can extend the size of logical Volume using the Ivextend command. As well as to decrease the size of Logical Volume, use the Ivresize command. In LVM v2 we can extend the size of Logical Volume without unmount as well as we can bring the actual size of Logical Volume on online using ext2online command.

## **QUESTION NO: 8 CORRECT TEXT**

Quota is implemented on /data but not working properly. Find out the Problem and implement the quota to user1 to have a soft limit 60 inodes (files) and hard limit of 70 inodes (files).

## Answer and Explanation:

Quotas are used to limit a user's or a group of users' ability to consume disk space. This prevents a small group of users from monopolizing disk capacity and potentially interfering with other users or the entire system. Disk quotas are commonly used by ISPs, by Web hosting companies, on FTP sites, and on corporate file servers to ensure continued availability of their systems. Without quotas, one or more users can upload files on an FTP server to the point of filling a filesystem. Once the affected partition is full, other users are effectively denied upload access to the disk. This is also a reason to mount different filesystem directories on different partitions. For example, if you only had partitions for your root (/) directory and swap space, someone uploading to your computer could fill up all of the space in your root directory (/). Without at least a little free space in the root directory (/), your system could become unstable or even crash.

You have two ways to set quotas for users. You can limit users by inodes or by kilobyte-sized disk blocks. Every Linux file requires an inode. Therefore, you can limit users by the number of files or by absolute space. You can set up different quotas for different filesystems. For example, you can set different quotas for users on the /home and /tmp directories if they are mounted on their own partitions.

Limits on disk blocks restrict the amount of disk space available to a user on your system. Older versions of Red Hat Linux included LinuxConf, which included a graphical tool to configure quotas. As of this writing, Red Hat no longer has a graphical quota configuration tool. Today, you can configure quotas on RHEL only through the command line interface.

#### 1. vi /etc/fstab

/dev/hda11 /data ext3 defaults,usrquota 1 2

2. Either Reboot the System or remount the partition.

Mount -o remount /dev/hda11 /data

- 3. touch /data/aquota.user
- 4. quotacheck -ufm /data
- 5. quotaon -u /data
- 6. edquota -u user1 /data

and Specified the Soft limit and hard limit on opened file.

To verify either quota is working or not:

Soft limit specify the limit to generate warnings to users and hard limit can't cross by the user. Use the quota command or repquota command to monitor the quota information.

## **QUESTION NO: 9 CORRECT TEXT**

One Logical Volume named Iv1 is created under vg0. The Initial Size of that Logical Volume is 100MB. Now you required the size 500MB. Make successfully the size of that Logical Volume 500M without losing any data. As well as size should be increased online.

### Answer and Explanation:

The LVM system organizes hard disks into Logical Volume (LV) groups. Essentially, physical hard disk partitions (or possibly RAID arrays) are set up in a bunch of equal-sized chunks known as Physical Extents (PE). As there are several other concepts associated with the LVM system, let's start with some basic definitions:

- \* Physical Volume (PV) is the standard partition that you add to the LVM mix. Normally, a physical volume is a standard primary or logical partition. It can also be a RAID array.
- \* Physical Extent (PE) is a chunk of disk space. Every PV is divided into a number of equal sized PEs. Every PE in a LV group is the same size. Different LV groups can have different sized PEs.
- \* Logical Extent (LE) is also a chunk of disk space. Every LE is mapped to a specific PE.
- \* Logical Volume (LV) is composed of a group of LEs. You can mount a filesystem such as /home and /var on an LV.
- \* Volume Group (VG) is composed of a group of LVs. It is the organizational group for LVM. Most of the commands that you'll use apply to a specific VG.
- 1. Verify the size of Logical Volume: Ivdisplay /dev/vg0/lv1
- 2. Verify the Size on mounted directory: df -h or df -h mounted directory name
- 3. Use: Ivextend -L+400M /dev/vg0/lv1

- 4. resize2fs /dev/vg0/lv1 à to bring extended size online.
- 5. Again Verify using Ivdisplay and df -h command.

## **QUESTION NO: 10 CORRECT TEXT**

Create one partitions having size 100MB and mount it on /data.

Answer and Explanation:

- 1. Use fdisk /dev/hda àTo create new partition.
- 2. Type n àFor New partitions
- 3. It will ask for Logical or Primary Partitions. Press I for logical.
- 4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.
- 5. Type the Size: +100M àYou can Specify either Last cylinder of Size here.
- 6. Press P to verify the partitions lists and remember the partitions name.
- 7. Press w to write on partitions table.
- 8. Either Reboot or use partprobe command.
- 9. Use mkfs -t ext3 /dev/hda?

Or

mke2fs -j /dev/hda? à To create ext3 filesystem.

10. vi /etc/fstab

Write:

/dev/hda? /data ext3 defaults 1 2

11. Verify by mounting on current Sessions also:

mount /dev/hda? /data

## **QUESTION NO: 11 CORRECT TEXT**

You are new System Administrator and from now you are going to handle the system and your main task is Network monitoring, Backup and Restore. But you don't know the root password. Change the root password to redhat and login in default Runlevel.

Answer and Explanation:

When you Boot the System, it starts on default Runlevel specified in /etc/inittab:

Id:?:initdefault:

When System Successfully boot, it will ask for username and password. But you don't know the root's password. To change the root password you need to boot the system into single user mode. You can pass the kernel arguments from the boot loader.

1. Restart the System.

- 2. You will get the boot loader GRUB screen.
- 3. Press a and type 1 or s for single mode
- ro root=LABEL=/ rhgb queit s
- 4. System will boot on Single User mode.
- 5. Use passwd command to change.
- 6. Press ctrl+d

### **QUESTION NO: 12 CORRECT TEXT**

There are more then 400 Computers in your Office. You are appointed as a System Administrator. But you don't have Router. So, you are going to use your One Linux Server as a Router. How will you enable IP packets forward?

## Answer and Explanation:

- 1. /proc is the virtual filesystem, we use /proc to modify the kernel parameters at running time. # echo "1" >/proc/sys/net/ipv4/ip\_forward
- 2. /etc/sysctl.conf àwhen System Reboot on next time, /etc/rc.d/rc.sysinit scripts reads the file /etc/sysctl.conf. To enable the IP forwarding on next reboot also you need to set the parameter. net.ipv4.ip\_forward=1

Here 0 means disable, 1 means enable.

# **QUESTION NO: 13 CORRECT TEXT**

You Completely Install the Redhat Enterprise Linux 5 on your System. While start the system, it's giving error to load X window System. How will you fix that problem and make boot successfully run X Window System.

### Answer and Explanation:

Think while Problems occurred on booting System on Runlevel 5 (X Window).

- 1. /tmp is full or not
- 2. Quota is already reached
- 3. Video card or resolution or monitor is misconfigured.
- 4. xfs service is running or not.

#### Do These:

- 1. df -h /tmp à /tmp is full remove the unnecessary file
- 2. quota username àif quota is already reached remove unnecessary file from home directory.

- 3. Boot the System in runlevel 3. ayou can pass the Kernel Argument from boot loader.
- 4. Use command: system-config-display à It will display a dialog to configure the monitor, Video card, resolution etc.
- 5. Set the Default Runlevel 5 in /etc/inittab id:5:initdefault:
- 6. Reboot the System you will get the GUI login Screen.

# **QUESTION NO: 14 CORRECT TEXT**

There are two different networks, 192.168.0.0/24 and 192.168.1.0/24. Your System is in 192.168.0.0/24 Network. One RHEL 5 Installed System is going to use as a Router. All required configuration is already done on Linux Server. Where 192.168.0.254 and 192.168.1.254 IP Address are assigned on that Server. How will make successfully ping to 192.168.1.0/24 Network's Host?

# Answer and Explanation:

1. vi /etc/sysconfig/network GATEWAY=192.168.0.254

OR

vi /etc/sysconf/network-scripts/ifcfg-eth0

DEVICE=eth0

BOOTPROTO=static

ONBOOT=yes

IPADDR=192.168.0.?

NETMASK=255.255.255.0

GATEWAY=192.168.0.254

2. service network restart

### **QUESTION NO: 15 CORRECT TEXT**

Make a swap partition having 100MB. Make Automatically Usable at System Boot Time.

Answer and Explanation:

1. Use fdisk /dev/hda àTo create new partition. Type n à For New partition It will ask for Logical or Primary Partitions. Press I for logical. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key. Type the Size: +100M à You can Specify either Last cylinder of Size

here.Press P to verify the partitions lists and remember the partitions name. Default System ID is 83 that means Linux Native.Type t to change the System ID of partition.Type Partition NumberType 82 that means Linux Swap.Press w to write on partitions table.Either Reboot or use partprobe command.mkswap /dev/hda?à To create Swap File system on partition.swapon /dev/hda?à To enable the Swap space from partition.free -m à Verify Either Swap is enabled or not.vi /etc/fstab

/dev/hda? swap swap defaults 0 0Reboot the System and verify that swap is automatically enabled or not.

#### **QUESTION NO: 16 CORRECT TEXT**

You are a System administrator. Using Log files very easy to monitor the system. Now there are 50 servers running as Mail, Web, Proxy, DNS services etc. You want to centralize the logs from all servers into on LOG Server. How will you configure the LOG Server to accept logs from remote host?

## Answer and Explanation:

By Default system accept the logs only generated from local host. To accept the Log from other host configure:vi /etc/sysconfig/syslog

SYSLOGD\_OPTIONS="-m 0 -r"

Where

- -m 0 disables 'MARK' messages.
- -r enables logging from remote machines
- -x disables DNS lookups on messages recieved with -r service syslog restart

#### **QUESTION NO: 17 CORRECT TEXT**

You are giving the debug RHCT exam. The examiner told you that the password of root is redhat. When you tried to login displays the error message and redisplayed the login screen. You changed the root password, again unable to login as a root. How will you make Successfully Login as a root.

#### Answer and Explanation:

When root unable to login into the system think:

- 1. Is password correct?
- 2. Is account expired?
- 3. Is terminal Blocked?

Do these Steps:

- 3. Boot the System on Single user mode.
- 4. Change the password
- 5. Check the account expire date by using chage -I root command.

If account is expired, set net expire date: chage -E "NEVER" root

- 4. Check the file /etc/securetty à Which file blocked to root login from certain terminal.
- 5. If terminal is deleted or commented write new or uncomment.
- 6. Reboot the system and login as a root.

### **QUESTION NO: 18 CORRECT TEXT**

You are giving RHCT Exam and in your Exam paper there is a question written, make successfully ping to 192.168.0.254.

## Answer and Explanation:

In Network problem thinks to check:

- 1. IP Configuration: use ifconfig command either IP is assigned to interface or not?
- 2. Default Gateway is set or not?
- 3. Hostname is set or not?
- 4. Routing problem is there?
- 5. Device Driver Module is loaded or not?
- 6. Device is activated or not?

Check In this way:

- 1. use ifconfig command and identify which IP is assigned or not.
- 2. cat /etc/sysconfig/network àWhat, What is written here. Actually here are these parameters.

NETWORKING=yes or no

GATEWAY=x.x.x.x

**HOSTNAME=?** 

NISDOMAIN=?

- Correct the file
- 3. Use vi /etc/sysconfig/network-scirpts/ifcfg-eth0 and check the proper options

DEVICE=eth0

ONBOOT=yes

**BOOTPROTO**=static

IPADDR=x.x.x.x

NETMAKS=x.x.x.x

GATEWAY=x.x.x.x

4. Use service network restart or start command

## **QUESTION NO: 19 CORRECT TEXT**

Set the Hostname station?.example.com where ? is your Host IP Address.

# Answer and Explanation:

- 1. hostname station?.example.com à This will set the host name only for current session. To set hostname permanently.
- 2. vi /etc/sysconfig/network

HOSTNAME=station?.example.com

3. service network restart

### **QUESTION NO: 20 CORRECT TEXT**

The System you are using is for NFS (Network File Services). Some important data are shared from your system. Make automatically start the nfs and portmap services at boot time.

# Answer and Explanation:

We can control the services for current session and for next boot time also. For current Session, we use service servicename start or restart or stop or status. For automatically on next reboot time:

1. chkconfig servicename on or off

eg: chkconfig nfs on

chkconfig portmap on

or

ntsysv

Select the nfs and portmap services.

2. Reboot the system and identify whether services are running or not.

#### **QUESTION NO: 21 CORRECT TEXT**

There is one partition /dev/hda14 mounted on /data. The owner of /data is root user and root group. And Permission is full to owner user, read and execute to group member and no permission to others. Now you should give the full permission to user user1 without changing pervious permission.

# Answer and Explanation:

We know that every files/directories are owned by certain user and group. And Permissions are defines to owner user, owner group and other.

-rwxr-x--- àFull permission to owner user, read and write to owner group and no permission to others.

According to question: We should give the full permission to user user1 without changing the previous permission.

ACL (Access Control List), in ext3 file system we can give permission to certain user and certain group without changing previous permission. But that partition should mount using acl option. Follow the stepsvi /etc/fstab

/dev/hda14 /data ext3 defaults,acl 0 1Either Reboot or use: mount -o remount /datasetfacl -m u:user1:rwx /dataVerify using: getfacl /data

### **QUESTION NO: 22 CORRECT TEXT**

There are two different networks 192.168.0.0/24 and 192.168.1.0/24. Where 192.168.0.254 and 192.168.1.254 IP Address are assigned on Server. Verify your network settings by pinging 192.168.1.0/24 Network's Host.

Answer and Explanation:

1. vi /etc/sysconfing/network

**NETWORKING=yes** 

HOSTNAME=station?.example.com

GATEWAY=192.168.0.254

2. service network restart

Or

1. vi /etc/sysconfig/network-scripts/ifcfg-eth0

DEVICE=eth0

ONBOOT=yes

BOOTPROTO=static

IPADDR=X.X.X.X

NETMASK=X.X.X.X

GATEWAY=192.168.0.254

- 2. ifdown eth0
- 3. ifup eth0

#### **QUESTION NO: 23 CORRECT TEXT**

Your system is giving error while booting on Runlevel 5. Make successfully boot your system in runlevel 5.

While you load the X Window System, you will get the problem. To troubleshoot follow the following steps:

- 1. Check the /tmp is full?
- 2. Check your quota, hard limit is already crossed?
- 3. Check xfs service is running?
- 4. Boot the system on runlevel 3 and execute the system-config-display command
- 5. Edit the /etc/inittab to set default runlevel 5.

id:5:initdefault:

### **QUESTION NO: 24 CORRECT TEXT**

Your System is configured in 192.168.0.0/24 Network and your nameserver is 192.168.0.254. Make successfully resolve to server1.example.com.

Answer and Explanation:

Very Easy question, nameserver is specified in question,

1. vi /etc/resolv.conf

nameserver 192.168.0.254

2. host server1.example.com

## **QUESTION NO: 25 CORRECT TEXT**

One Package named zsh is dump on ftp://server1.example.com under /pub/updates directory and your FTP server is 192.168.0.254. Install the package zsh.

## Answer and Explanation:

1. rpm -ivh ftp://server1/example.com/pub/updates/zsh-\*

or

- 1. Login to ftp server: ftp ftp://server1.example.com using anonymous user.
- 2. Change the directory: cd pub and cd updates
- 3. Download the package: mget zsh-\*
- 4. Quit from the ftp prompt: bye
- 5. Install the package
- 6. rpm -ivh zsh-\*
- 7. Verify either package is installed or not : rpm -q zsh

## **QUESTION NO: 26 CORRECT TEXT**

Add a new logical partition having size 100MB and create the /data which will be the mount point for the new partition.

# Answer and Explanation:

- 1. Use fdisk /dev/hda àTo create new partition.
- 2. Type n àFor New partitions
- 3. It will ask for Logical or Primary Partitions. Press I for logical.
- 4. It will ask for the Starting Cylinder: Use the Default by pressing Enter Key.
- 5. Type the Size: +100M àYou can Specify either Last cylinder of Size here.
- 6. Press P to verify the partitions lists and remember the partitions name.
- 7. Press w to write on partitions table.
- 8. Either Reboot or use partprobe command.
- 9. Use mkfs -t ext3 /dev/hda?
- 10. Or
- 11. mke2fs -j /dev/hda? à To create ext3 filesystem.
- 12. vi /etc/fstab
- 13. Write:
- 14. /dev/hda? /data ext3 defaults 0 0
- 11. Verify by mounting on current Sessions also:
- 15. mount /dev/hda? /data

### **QUESTION NO: 27 CORRECT TEXT**

There is a server having 172.24.254.254 and 172.25.254.254. Your System lies on 172.24.0.0/16. Make successfully ping to 172.25.254.254 by Assigning following IP: 172.24.0.x Where x is your station number.

#### Answer and Explanation:

1. vi /etc/sysconfig/network-scripts/ifcfg-eth0

DEVICE=eth0

**BOOTPROTO**=static

ONBOOT=yes

IPADDR=x.x.x.x

NETMASK=x.x.x.x

- Enter the IP Address as given station number by your examiner: example: 172.24.0.1
- 3. Enter Subnet Mask
- 4. Enter Default Gateway and primary name server
- 5. press on ok

- 6. ifdown eth0
- 7. ifup eth0
- 8. verify using ifconfig

In the lab server is playing the role of router, IP forwarding is enabled. Just set the Correct IP and gateway, you can ping to 172.25.254.254.

# **QUESTION NO: 28 CORRECT TEXT**

Successfully resolv to server1.example.com where your DNS server is 172.24.254.254 Answer and Explanation:

- 1. vi /etc/resolv.conf nameserver 172.24.254.254
- 2. host server1.example.com

# **QUESTION NO: 29 CORRECT TEXT**

Make Successfully Resolve to server1.example.com where DNS Server is 192.168.0.254.

Answer and Explanation: 1. vi /etc/resolv.conf

Write: nameserver 192.168.0.254

#### **QUESTION NO: 30 CORRECT TEXT**

One Logical Volume is created named as myvol under vo volume group and is mounted. The Initial Size of that Logical Volume is 400MB. Make successfully that the size of Logical Volume 200MB without losing any data. The size of logical volume 200MB to 210MB will be acceptable.

- 1. First check the size of Logical Volume: Ivdisplay /dev/vo/myvol
- 2. Make sure that the filesystem is in a consistent state before reducing:
- # fsck -f /dev/vo/myvol
- 3. Now reduce the filesystem by 200MB.
- # resize2fs /dev/vo/myvol 200M

- 4. It is now possible to reduce the logical volume.
- #Ivreduce /dev/vo/myvol -L 200M
- 4. Verify the Size of Logical Volume: Ivdisplay /dev/vo/myvol
- 5. Verify that the size comes in online or not: df -h

# **QUESTION NO: 31 CORRECT TEXT**

You are working as an Administrator. There is a common data shared (/data) from 192.168.0.254 to all users in your local LAN. When user's system start, shared data should automatically mount on /common directory.

## Answer and Explanation:

To automatically mount at boot time we use the /etc/fstab file. Because /etc/rc.d/rc.sysinit file reads and mount all file system specified in /etc/fstab. To mount Network Sharing Files also use the /etc/fstab but filesystem is nfs.vi /etc/fstab

192.168.0.254:/data /common nfs defaults 0 0reboot the system.

### **QUESTION NO: 32 CORRECT TEXT**

Install the Redhat Linux RHEL 5 through NFS. Where your Server is server1.example.com having IP 172.24.254.254 and shared /var/ftp/pub. The size of the partitions are listed below:

/ à 1048

/home à 1028

/boot à 512

/var à 1028

/usr à 2048

Swap -> 1.5 of RAM Size

/storageà configure the RAID Level 0 of remaining all free space.

After completing the installation through NFS solve the following questions. There are two networks 172.24.0.0/16 and 172.25.0.0/16. As well as there are two domains example.com on 172.24.0.0/16 network and my133t.org on 172.25.0.0/16 network. Your system is based on example.com domain. SELinux should be in enforce mode.

- 1. Insert the CD on CD-ROM and start the system.
- 2. In Boot: Prompt type linux askmethod

- 3. It will display the language, keyboard selection.
- 4. It will ask you for the installation method.
- 5. Select the NFS Image from the list
- 6. It will ask the IP Address, Net mask, Gateway and Name Server. Select Use

Dynamic IP Configuration: because DHCP Server will be configured in your exam lab.

7. It will ask for the NFS Server Name and Redhat Enterprise Linux Directory.

Specify the NFS Server: 172.24.254.254

Directory: /var/ftp/pub

- 8. After Connecting to the NFS Server Installation start in GUI. Go up to the partition screen by selecting the different Options.
- 9. Create the partition According to the Question because Size and what-what partition should you create at installation time is specified in your question
- 10. Create the two RAID partitions having equal size of remaining all free space.
- 11. Click on RAID button
- 12. Type mount point /data
- 13. Select RAID Level 0
- 14. Click on ok
- 15. Then select the MBR Options, time zone and go upto package selections.

It is another Most Important Time of installation. Due to the time limit, you should care about the installation packages. At Exam time you these packages are enough.

X-Window System

**GNOME** Desktop

(these two packages are generally not required)

Administration Tools.

System Tools

Windows File Server

**FTP Servers** 

Mail Servers

Web Servers

**Network Servers** 

**Editors** 

**Text Based Internet** 

**Server Configuration Tools** 

Base

**Printing Supports** 

When installation will complete, your system will reboot. Jump for another Question.

#### **QUESTION NO: 33 CORRECT TEXT**

Create the group named sysusers.

# Answer and Explanation:

1. groupadd sysusers

groupadd command is used to create the group and all group information is stored in /etc/group file.

## **QUESTION NO: 34 CORRECT TEXT**

Create the user named jeff, marion, harold

# Answer and Explanation:

- 1. useradd jeff
- 2. useradd marion
- 3. useradd harold

useradd command is used to create the user. All user's information stores in /etc/passwd and user;s shadow password stores in /etc/shadow.

### **QUESTION NO: 35 CORRECT TEXT**

Make Secondary belongs the jeff and marion users on sysusers group. But harold user should not belongs to sysusers group.

#### Answer and Explanation:

- 1. usermod -G sysusers jeff
- 2. usermod -G sysuser marion
- 3. Verify by reading /etc/group file

Using usermod command we can make user belongs to different group. There are two types of group one primary and another is secondary. Primary group can be only one but user can belongs to more than one group as secondary.

usermod -g groupname username àTo change the primary group of the user usermod -G groupname username àTo make user belongs to secondary group.

### **QUESTION NO: 36 CORRECT TEXT**

Create the directory /storage and group owner should be the sysusers group.

Answer and Explanation:

- 1. chgrp sysusers /storage
- 2. Verify using Is -Id /storage command. You should get like

drwxr-x--- 2 root sysusers 4096 Mar 16 17:59 /storage

chgrp command is used to change the group ownership of particular files or directory.

Another way you can use the chown command.

chown root:sysusers /storage

## **QUESTION NO: 37 CORRECT TEXT**

Make on /storage directory that only the user owner and group owner member can fully access.

Answer and Explanation:

- 1. chmod 770 /storage
- 2. Verify using: ls-ld/storage

Preview should be like:

drwxrwx--- 2 root sysusers 4096 Mar 16 18:08 /storage

To change the permission on directory we use the chmod command. According to the question that only the owner user (root) and group member (sysusers) can fully access the directory so: chmod 770 /archive

### **QUESTION NO: 38 CORRECT TEXT**

Who ever creates the files/directories on /storage group owner should be automatically should be the same group owner of /storage.

Answer and Explanation:

- 1. chmod g+s /storage
- 2. Verify using: Is -Id /storage

Permission should be like:

drwxrws--- 2 root sysusers 4096 Mar 16 18:08 /storage

If SGID bit is set on directory then who every users creates the files on directory group owner automatically the owner of parent directory.

To set the SGID bit: chmod g+s directory

To Remove the SGID bit: chmod g-s directory

## **QUESTION NO: 39 CORRECT TEXT**

Install the Cron Schedule for jeff user to display "Hello" on daily 5:30.

Answer and Explanation:Login as a root usercat >schedule.txt

30 05 \* \* \* /bin/echo "Hello"

- 3. crontab -u jeff schedule.txt
- 4. service crond restart

The cron system is essentially a smart alarm clock. When the alarm sounds, Linux runs the commands of your choice automatically. You can set the alarm clock to run at all sorts of regular time intervals. Alternatively, the at system allows you to run the command of your choice once, at a specified time in the future.

Red Hat configured the cron daemon, crond. By default, it checks a series of directories for jobs to run, every minute of every hour of every day. The crond checks the /var/spool/cron directory for jobs by user. It also checks for scheduled jobs for the computer under /etc/crontab and in the /etc/cron.d directory.

Here is the format of a line in crontab. Each of these columns is explained in more detail: #minute, hour, day of month, month, day of week, command

\* \* \* \* \* command

#### **QUESTION NO: 40 CORRECT TEXT**

There is a NFS server 192.168.0.254 and all required packages are dumped in /var/ftp/pub of that server and the /var/ftp/pub directory is shared. Install the Redhat Enterprise Linux 5 by creating following partitions:

/ 1000

/boot 200

/home 1000

/var 1000

/usr 4000

swap 2X256 (RAM SIZE)

Answer and Explanation:

Note: Examiner will provide you the Installation startup CD. And here mentioned size may vary see on the exam paper.

1. Insert the CD on CD-ROM and start the system.

- 2. In Boot: Prompt type linux askmethod
- 3. It will display the language, keyboard selection.
- 4. It will ask you for the installation method.
- 5. Select the NFS Image from the list
- 6. It will ask the IP Address, Net mask, Gateway and Name Server. Select Use

Dynamic IP Configuration: because DHCP Server will be configured in your exam lab.

7. It will ask for the NFS Server Name and Redhat Enterprise Linux Directory.

Specify the NFS Server: 192.168.0.254

Directory: /var/ftp/pub

- 8. After Connecting to the NFS Server Installation start in GUI. Go up to the partition screen by selecting the different Options.
- 9. Create the partition According to the Question because Size and what-what partition should you create at installation time is specified in your question
- 10. Then select the MBR Options, time zone and go upto package selections.

It is another Most Important Time of installation. Due to the time limit, you should care about the installation packages. At Exam time you these packages are enough.

X-Window System

**GNOME Desktop** 

(these two packages are generally not required)

Administration Tools.

System Tools

Windows File Server

**FTP Servers** 

Mail Servers

Web Servers

**Network Servers** 

**Editors** 

**Text Based Internet** 

Server Configuration Tools

**Printing Supports** 

When installation will complete, your system will reboot. Jump for another Question.

### **QUESTION NO: 41 CORRECT TEXT**

There is a FTP server 192.168.0.254 and all required packages are dumped in /var/ftp/pub of that server and anonymous login is enabled. Install the Redhat Enterprise Linux 5 as an anonymous by creating following partitions:

/ 1000

/boot 200

/home 1000

/var 1000

/usr 4000

swap 2X256 (RAM SIZE)

# Answer and Explanation:

Note: Examiner will provide you the Installation startup CD. And here mentioned size may vary see on the exam paper.

- 1. Insert the CD on CD-ROM and start the system.
- 2. In Boot: Prompt type linux askmethod
- 3. It will display the Language, keyboard selection.
- 4. It will ask you for the installation method.
- 5. Select the FTP from the list
- 6. It will ask the IP Address, Net mask, Gateway and Name Server. Select Use

Dynamic IP Configuration: because DHCP Server will be configured in your exam lab.

7. It will ask for the FTP site name and Redhat Enterprise Linux Directory.

Specify the FTP Server: 192.168.0.254

Directory: pub à Because anonymous login on /var/ftp.

- 8. After Connecting to the FTP Server Installation will start. Go up to the partition screen by selecting the different Options.
- 9. Create the partition According to the Question because Size and what-what partition should you create at installation time is specified in your question
- 10. Then select the MBR Options, time zone and go upto package selections.

It is another Most Important Time of installation. Due to the time limit, you should be care about the installation packages. At Exam time you these packages are enough.

X-Window System

**GNOME** Desktop

(these two packages are generally not required)

Administration Tools.

System Tools

Windows File Server

**FTP Servers** 

Mail Servers

Web Servers

**Network Servers** 

**Editors** 

Text Based Internet

Server Configuration Tools

**Printing Supports** 

When installation will complete, your system will reboot. Jump for another Question.

## **QUESTION NO: 42 CORRECT TEXT**

There is a HTTP server 192.168.0.254 and all required packages are dumped in /var/www/html/rhel5 of that server. Install the Redhat Enterprise Linux 5 by creating following partitions:

/ 1000

/boot 200

/home 1000

/var 1000

/usr 4000

swap 2X256 (RAM SIZE)

Answer and Explanation:

Note: Examiner will provide you the Installation startup CD. And here mentioned size may vary see on the exam paper.

- 1. Insert the CD on CD-ROM and start the system.
- 2. In Boot: Prompt type linux askmethod
- 3. It will display the Language, keyboard selection.
- 4. It will ask you for the installation method.
- 5. Select the HTTP from the list
- 6. It will ask the IP Address, Net mask, Gateway and Name Server. Select Use

Dynamic IP Configuration: because DHCP Server will be configured in your exam lab.

7. It will ask for the Web site name and Redhat Enterprise Linux Directory.

Specify the HTTP Server: 192.168.0.254

Directory: rhel5 à Because Default Directory for http is /var/www/html

- 8. After Connecting to the HTTP Server Installation start. Go upto the partition screen by selecting the different Options.
- 9. Create the partition According to the Question because Size and what-what partition should you create at installation time is specified in your question
- 10. Then select the MBR Options, time zone and go upto package selections.

It is another Most Important Time of installation. Due to the time limit, you should be care about the installation packages. At Exam time you these packages are enough.

X-Window System

**GNOME** Desktop

(these two packages are generally not required)

Administration Tools.

System Tools

Windows File Server

**FTP Servers** 

Mail Servers

Web Servers