


Lab - Configuring Multiarea OSPFv2

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask
R1	Lo0	209.165.200.225	255.255.255.252
	Lo1	192.168.1.1	255.255.255.0
	Lo2	192.168.2.1	255.255.255.0
	S0/0/0 (DCE)	192.168.12.1	255.255.255.252
R2	Lo6	192.168.6.1	255.255.255.0
	S0/0/0	192.168.12.2	255.255.255.252
	S0/0/1 (DCE)	192.168.23.1	255.255.255.252
R3	Lo4	192.168.4.1	255.255.255.0
	Lo5	192.168.5.1	255.255.255.0
	S0/0/1	192.168.23.2	255.255.255.252

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Configure a Multiarea OSPFv2 Network

Part 3: Configure Interarea Summary Routes

Background / Scenario

To make OSPF more efficient and scalable, OSPF supports hierarchical routing using the concept of areas. An OSPF area is a group of routers that share the same link-state information in their link-state databases (LSDBs). When a large OSPF area is divided into smaller areas, it is called multiarea OSPF. Multiarea OSPF is useful in larger network deployments to reduce processing and memory overhead.

In the lab, you will configure a multiarea OSPFv2 network with interarea summary routes.

Note: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS Release 15.2(4)M3 (universalk9 image). Other routers and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of this lab for the correct interface identifiers.

Note: Make sure that the routers have been erased and have no startup configurations. If you are unsure, contact your instructor.

Required Resources

- 3 Routers (Cisco 1941 with Cisco IOS Release 15.2(4)M3 universal image or comparable)
- Console cables to configure the Cisco IOS devices via the console ports
- Serial cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings on the routers.

- Step 1: Cable the network as shown in the topology.
- Step 2: Initialize and reload the routers as necessary.
- Step 3: Configure basic settings for each router.
 - a. Disable DNS lookup.
 - b. Configure device name, as shown in the topology.
 - c. Assign **class** as the privileged EXEC password.
 - d. Assign **cisco** as the console and vty passwords.
 - e. Configure logging synchronous for the console line.
 - f. Configure an MOTD banner to warn users that unauthorized access is prohibited.
 - g. Configure the IP addresses listed in the Addressing Table for all interfaces. DCE interfaces should be configured with a clock rate of 128000. Bandwidth should be set to 128 Kb/s on all serial interfaces.
 - h. Copy the running configuration to the startup configuration.

Step 4: Verify Layer 3 connectivity.

Use the **show ip interface brief** command to verify that the IP addressing is correct and that the interfaces are active. Verify that each router can ping their neighbor's serial interface.

Part 2: Configure a Multiarea OSPFv2 Network

In Part 2, you will configure a multiarea OSPFv2 network with process ID of 1. All LAN loopback interfaces should be passive, and all serial interfaces should be configured with MD5 authentication using **Cisco123** as the key.

Step 1: Identify the OSPF router types in the topology.

```
Identify the Backbone router(s):
Identify the Autonomous System Boundary Router(s) (ASBR):
Identify the Area Border Router(s) (ABR):
Identify the Internal router(s):
```

Step 2: Configure OSPF on R1.

- a. Configure a router ID of 1.1.1.1 with OSPF process ID of 1.
- b. Add the networks for R1 to OSPF.

```
R1(config-router) # network 192.168.1.0 0.0.0.255 area 1
R1(config-router) # network 192.168.2.0 0.0.0.255 area 1
R1(config-router) # network 192.168.12.0 0.0.0.3 area 0
```

- c. Set all LAN loopback interfaces, Lo1 and Lo2, as passive.
- d. Create a default route to the Internet using exit interface Lo0.

Note: You may see the "%Default route without gateway, if not a point-to-point interface, may impact performance" message. This is normal behavior if using a Loopback interface to simulate a default route.

e. Configure OSPF to propagate the routes throughout the OSPF areas.

Step 3: Configure OSPF on R2.

- a. Configure a router ID of 2.2.2.2 with OSPF process ID of 1.
- b. Add the networks for R2 to OSPF. Add the networks to the correct area. Write the commands used in the space below.
- c. Set all LAN loopback interfaces as passive.

Step 4: Configure OSPF on R3.

- a. Configure a router ID of 3.3.3.3 with OSPF process ID of 1.
- b. Add the networks for R3 to OSPF. Write the commands used in the space below.
- c. Set all LAN loopback interfaces as passive.

Step 5: Verify that OSPF settings are correct and adjacencies have been established between routers.

a. Issue the **show ip protocols** command to verify OSPF settings on each router. Use this command to identify the OSPF router types and to determine the networks assigned to each area.

```
R1# show ip protocols
*** IP Routing is NSF aware ***
Routing Protocol is "ospf 1"
 Outgoing update filter list for all interfaces is not set
 Incoming update filter list for all interfaces is not set
 Router ID 1.1.1.1
 It is an area border and autonomous system boundary router
Redistributing External Routes from,
 Number of areas in this router is 2. 2 normal 0 stub 0 nssa
 Maximum path: 4
 Routing for Networks:
   192.168.1.0 0.0.0.255 area 1
   192.168.2.0 0.0.0.255 area 1
   192.168.12.0 0.0.0.3 area 0
 Passive Interface(s):
   Loopback1
   Loopback2
 Routing Information Sources:
                 Distance Last Update
   Gateway
   2.2.2.2
                               00:01:45
                       110
 Distance: (default is 110)
R2# show ip protocols
*** IP Routing is NSF aware ***
Routing Protocol is "ospf 1"
 Outgoing update filter list for all interfaces is not set
 Incoming update filter list for all interfaces is not set
 Router ID 2.2.2.2
 It is an area border router
 Number of areas in this router is 2. 2 normal 0 stub 0 nssa
 Maximum path: 4
 Routing for Networks:
   192.168.6.0 0.0.0.255 area 3
   192.168.12.0 0.0.0.3 area 0
   192.168.23.0 0.0.0.3 area 3
 Passive Interface(s):
   Loopback6
 Routing Information Sources:
                 Distance Last Update
   Gateway
   3.3.3.3
                        110
                               00:01:20
   1.1.1.1
                        110
                               00:10:12
 Distance: (default is 110)
```

R3# show ip protocols

```
*** IP Routing is NSF aware ***
   Routing Protocol is "ospf 1"
     Outgoing update filter list for all interfaces is not set
     Incoming update filter list for all interfaces is not set
     Router ID 3.3.3.3
     Number of areas in this router is 1. 1 normal 0 stub 0 nssa
     Maximum path: 4
     Routing for Networks:
       192.168.4.0 0.0.0.255 area 3
       192.168.5.0 0.0.0.255 area 3
       192.168.23.0 0.0.0.3 area 3
     Passive Interface(s):
       Loopback4
       Loopback5
     Routing Information Sources:
       Gateway Distance
                                 Last Update
       1.1.1.1
                           110
                                   00:07:46
       2.2.2.2
                           110
                                    00:07:46
     Distance: (default is 110)
   What is the OSPF router type for each router?
   R1:
   R2:
   R3:
b. Issue the show ip ospf neighbor command to verify that OSPF adjacencies have been established
   between routers.
   R1# show ip ospf neighbor
   Neighbor ID
                  Pri State
                                        Dead Time
                                                   Address
                                                                  Interface
                   0 FULL/ -
   2.2.2.2
                                        00:00:34
                                                   192.168.12.2 Serial0/0/0
   R2# show ip ospf neighbor
   Neighbor ID
                  Pri State
                                       Dead Time Address
                                                                 Interface
   1.1.1.1
                    0
                        FULL/ -
                                        00:00:36
                                                   192.168.12.1
                                                                   Serial0/0/0
   3.3.3.3
                    0
                        FULL/ -
                                        00:00:36
                                                   192.168.23.2 Serial0/0/1
   R3# show ip ospf neighbor
                                        Dead Time
   Neighbor ID
                  Pri
                        State
                                                                  Interface
                                                    Address
   2.2.2.2
                    0
                        FULL/ -
                                        00:00:38
                                                    192.168.23.1
                                                                   Serial0/0/1
c. Issue the show ip ospf interface brief command to display a summary of interface route costs.
   R1# show ip ospf interface brief
   Interface PID Area
                                     IP Address/Mask
                                                       Cost State Nbrs F/C
```

192.168.12.1/30

781 P2P 1/1

Se0/0/0

1

Lo1	1	1	192.168.1.1/24	1	LOOP	0/0	
Lo2	1	1	192.168.2.1/24	1	LOOP	0/0	
R2# show ip	ospf	interface brie	ef				
Interface	PID	Area	IP Address/Mask	Cost	State	Nbrs	F/C
Se0/0/0	1	0	192.168.12.2/30	<mark>781</mark>	P2P	1/1	
Lo6	1	3	192.168.6.1/24	1	LOOP	0/0	
Se0/0/1	1	3	192.168.23.1/30	<mark>781</mark>	P2P	1/1	
R3# show ip	ospf	interface brie	ef				
Interface	PID	Area	IP Address/Mask	Cost	State	Nbrs	F/C
Lo4	1	3	192.168.4.1/24	1	LOOP	0/0	
Lo5	1	3	192.168.5.1/24	1	LOOP	0/0	
Se0/0/1	1	3	192.168.23.2/30	781	P2P	1/1	

Step 6: Configure MD5 authentication on all serial interfaces.

Configure OSPF MD5 authentication at the interface level with an authentication key of Cisco123.

Why is it a good idea to verify that OSPF is functioning correctly before configuring OSPF authentication?

Step 7: Verify OSPF adjacencies have been re-established.

Issue the **show ip ospf neighbor** command again to verify that adjacencies have been re-established after MD5 authentication was implemented. Troubleshoot any issues found before moving on to Part 3.

Part 3: Configure Interarea Summary Routes

OSPF does not perform automatic summarization. Interarea summarization must be manually configured on ABRs. In Part 3, you will apply interarea summary routes on the ABRs. Using **show** commands, you will be able to observe how summarization affects the routing table and LSDBs.

Step 1: Display the OSPF routing tables on all routers.

a. Issue the **show ip route ospf** command on R1. OSPF routes that originate from a different area have a descriptor (O IA) indicating that these are interarea routes.

R1# show ip route ospf

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override

Gateway of last resort is 0.0.0.0 to network 0.0.0.0
```

b. Repeat the **show ip route ospf** command for R2 and R3. Record the OSPF interarea routes for each router.

R2:

R3:

Step 2: Display the LSDB on all routers.

a. Issue the **show ip ospf database** command on R1. A router maintains a separate LSDB for every area that it is a member.

R1# show ip ospf database

```
OSPF Router with ID (1.1.1.1) (Process ID 1)
              Router Link States (Area 0)
Link ID
              ADV Router
                             Age
                                        Seq# Checksum Link count
1.1.1.1
              1.1.1.1
                             1295
                                        0x80000003 0x0039CD 2
2.2.2.2
              2.2.2.2
                             1282
                                        0x80000002 0x00D430 2
              Summary Net Link States (Area 0)
Link ID
             ADV Router
                             Age
                                        Seq#
                                                 Checksum
192.168.1.1
              1.1.1.1
                             1387
                                        0x80000002 0x00AC1F
192.168.2.1
             1.1.1.1
                             1387
                                        0x80000002 0x00A129
192.168.4.1
             2.2.2.2
                                        0x80000001 0x000DA8
                             761
192.168.5.1
              2.2.2.2
                                        0x80000001 0x0002B2
                             751
                                        0x80000001 0x00596A
192.168.6.1
              2.2.2.2
                             1263
192.168.23.0
              2.2.2.2
                             1273
                                        0x80000001 0x00297E
              Router Link States (Area 1)
Link ID
              ADV Router
                                        Seg# Checksum Link count
                             Age
```

1.1.1.1	1.1.1.1	1342	0x80000006	0x0094A4 2	
	Summary Net Lin	k States (Ar	ea 1)		
Link ID	ADV Router	Age	Seq#	Checksum	
192.168.4.1	1.1.1.1	760	0x80000001	0x00C8E0	
192.168.5.1	1.1.1.1	750	0x80000001	0x00BDEA	
192.168.6.1	1.1.1.1	1262	0x80000001	0x0015A2	
192.168.12.0	1.1.1.1	1387	0x80000001	0x00C0F5	
192.168.23.0	1.1.1.1	1272	0x80000001	0x00E4B6	
	Type-5 AS External Link States				
Link ID	ADV Router	Age	Seq#	Checksum Tag	
0.0.0.0	1.1.1.1	1343	0x8000001	0x001D91 1	

b. Repeat the **show ip ospf database** command for R2 and R3. Record the Link IDs for the Summary Net Link States for each area.

R2:

R3:

Step 3: Configure the interarea summary routes.

- a. Calculate the summary route for the networks in area 1.
- b. Configure the summary route for area 1 on R1.

```
R1(config) # router ospf 1
R1(config-router) # area 1 range 192.168.0.0 255.255.252.0
```

- c. Calculate the summary route for the networks in area 3. Record your results.
- d. Configure the summary route for area 3 on R2. Write the commands you used in the space below.

Step 4: Re-display the OSPF routing tables on all routers.

Issue the **show ip route ospf** command on each router. Record the results for the summary and interarea routes.

R1:

R2: Step 5: Display the LSDB on all routers. Issue the show ip ospf database command again on each router. Record the Link IDs for the Summary Net Link States for each area. R1: R2: R3: What type of LSA is injected into the backbone by the ABR when interarea summarization is enabled?

Step 6: Verify end-to-end connectivity.

Lab - Configuring Multiarea OSPFv2

Verify that all networks can be reached from each router. If any issues exist, troubleshoot until they have been resolved.

Reflection

What are three advantages for designing a network with multiarea OSPF?

Router Interface Summary Table

Router Interface Summary					
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2	
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)	
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)	
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)	
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)	
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)	

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.