FREE GUIDE | AI DESIGN WORKFLOW

BUILD AN ANIMATED CLOTHING RACK HERO

Turn one product photo into an interactive e-commerce hero section. Garments drop onto a chrome rail, swing like real clothes, turn to face you on hover and fly into a product popup. Four copy-paste prompts and zero coding.



What you'll build: the 3D Hanging Rack Hero Section

See the live demo →

01 FRONT VIEW
Image prompt for the hero shot

02 SIDE VIEW
The 90° shot that hangs on the rail

03 BACK VIEW
For the front/back flip in the popup

04 BUILD PROMPT
The full section for any coding agent

START HERE

HOW IT WORKS

The section needs three photos of every product: **side** (shown on the rail), **front** (shown on hover) and **back** (shown when the shopper flips it in the popup). You make those with an AI image tool, then hand one big prompt to a coding agent that builds the whole section.

01

Generate the front view

Upload your product photo with Prompt 01. This becomes the master image that the other angles copy.

02

Generate the side view

Upload the front image with Prompt 02 for a perfect 90° profile on the same hanger.

03

Generate the back view

Upload the front image with Prompt 03 for the reverse side.

04

Prepare the photos

Transparent background, cropped tight, hook at the top edge. Checklist on page 6.

05

Build the section

Paste Prompt 04 into any AI coding agent, then drop your photo paths into the `CONTENT` list it creates. Repeat steps 1–4 for every product (up to 10 hang on the rail).

What you need

- One clear photo of each product (flat lay or worn is fine)
- An AI image tool that accepts a reference image
- An AI coding agent: Claude Code, Cursor, Lovable, Bolt, v0 or similar
- A free background remover if your image tool can't export transparent PNGs

Three golden rules

1. **Same hanger in every shot.** The rail looks real only if every garment hangs from an identical hook.
2. **Front first, then copy it.** Use your front image as the reference for the side and back shots so colours and size match.
3. **Same lighting, same scale.** Regenerate any angle that looks brighter, bigger or differently folded.

Short on time? Get the finished section.
Ready to install on Shopify, WordPress, Elementor, WooCommerce or HTML.
Get the template →

STEP 01 · IMAGE PROMPT

FRONT VIEW

01

Upload your original product photo, then paste this prompt. This shot appears when a shopper hovers a garment, and it's the master reference for every other angle.

PROMPT 01 · FRONT VIEW (0°) COPY EVERYTHING BELOW

```
Create an ultra-realistic, premium e-commerce product photograph using my uploaded product image as the exact reference.

**Camera Angle:** Perfect straight-on FRONT VIEW (0 degrees), showing the complete front of the garment symmetrically.

**Product Presentation:**
- Hang the product naturally on a premium dark walnut wooden hanger with a thin silver metal hook.
- The garment must hang vertically with realistic gravity, natural fabric folds, and accurate proportions.
- Keep the entire garment visible, including the hood, shoulders, sleeves, cuffs, pockets, and bottom hem.
- Center the product perfectly in the frame.

**Product Accuracy:**
- Preserve the exact original product design, color, fabric texture, stitching, logos, typography, graphics, prints, and their placements.
- Do not redesign, modify, replace, or invent any product details.
- Maintain realistic cotton fabric texture and natural fabric thickness.

**Photography Style:**
- Professional luxury fashion e-commerce studio photography.
- Soft, diffused studio lighting with natural shadows.
- Sharp fabric details, photorealistic stitching, realistic material depth.
- Pure transparent background (PNG).
- No mannequin, no human model, no props, no additional objects.

**Output:** Ultra-high-resolution 4K product photography, full garment visible, vertically centered, 2:3 aspect ratio.
```

TIP

Generate 3–4 versions and keep the one where the hanger hook sits straight and centred. Every other angle will copy it.

STEP 02 · IMAGE PROMPT

SIDE VIEW (90°)

02

Upload the **front-view image from Step 01** (not the original photo), then paste this prompt. This is the narrow profile that hangs on the rail by default, so it's the shot shoppers see first.

PROMPT 02 · SIDE PROFILE (90°) COPY EVERYTHING BELOW

```
Create an ultra-realistic, premium e-commerce product photograph using my uploaded product image as the exact reference.

**Camera Angle:** Exact LEFT SIDE PROFILE VIEW (90 degrees), matching the professional hoodie side-view reference image.

**Product Presentation:**
- Show the garment from a perfectly perpendicular side angle, not a three-quarter view.
- Hang the product naturally on the same premium dark walnut wooden hanger with a thin silver metal hook.
- The hood should fall naturally toward the back, showing realistic depth, thickness, and fabric folds.
- Clearly show the side profile of the shoulder, sleeve, cuff, body, bottom hem, and hood.
- The single visible sleeve should hang naturally down the side of the garment.
- The garment must maintain the same proportions, length, thickness, and silhouette as the original product.
- Keep the entire garment visible without cropping.

**Product Accuracy:**
- Preserve the exact original color, fabric texture, stitching, logo, graphics, typography, and print placement.
- Any partially visible front print must appear naturally distorted by the side perspective.
- Do not invent any new prints, seams, pockets, or design details.
- Maintain realistic fabric folds and garment structure.

**Photography Style:**
- Professional luxury fashion e-commerce product photography.
- Soft, diffused studio lighting identical to the front-view image.
- Extremely realistic cotton texture and natural garment shadows.
- Pure transparent background (PNG).
- No mannequin, no model, no additional objects.

**Output:** Ultra-high-resolution 4K product photography, full-length side profile, vertically centered, 2:3 aspect ratio.
```

CHECK BEFORE YOU CONTINUE

If you can see both sleeves or any of the front, the AI gave you a three-quarter view. Regenerate it. A true side view is narrow: roughly a third as wide as it is tall.

STEP 03 · IMAGE PROMPT

BACK VIEW

03

Upload the **front-view image from Step 01** again, then paste this prompt. Shoppers see this side when they tap “Back” or drag the garment around in the product popup.

PROMPT 03 · BACK VIEW (180°) COPY EVERYTHING BELOW

```
Create an ultra-realistic, premium e-commerce product photograph using my uploaded product image as the exact reference.

**Camera Angle:** Perfect straight-on BACK VIEW (180 degrees), showing the complete back of the garment symmetrically, the exact reverse of the front-view image.

**Product Presentation:**
- Hang the product on the same premium dark walnut wooden hanger with a thin silver metal hook, seen from behind.
- The garment must hang vertically with realistic gravity, natural fabric folds, and the same proportions and length as the front view.
- Show the back of the hood, shoulders, both sleeves, cuffs, and bottom hem. Keep the entire garment visible.
- Center the product perfectly in the frame, at the same scale and position as the front-view image.

**Product Accuracy:**
- Preserve the exact original color, fabric texture, and stitching.
- If the product has a back print, logo, or label, reproduce it exactly. If it has none, keep the back plain and do not invent any graphics.
- Front-only details (front pocket, drawstrings, front print) must not appear on the back.

**Photography Style:**
- Professional luxury fashion e-commerce product photography.
- Soft, diffused studio lighting identical to the front-view image.
- Extremely realistic cotton texture and natural garment shadows.
- Pure transparent background (PNG).
- No mannequin, no model, no additional objects.

**Output:** Ultra-high-resolution 4K product photography, full garment visible, vertically centered, 2:3 aspect ratio.
```

NO BACK PHOTO?

You can skip this step. Use the front image for the back as well; the flip will still work, it will just show the front on both sides.

STEP 04 · PREPARE

GET YOUR PHOTOS RAIL-READY

04

The animation hangs each photo from its very top edge. Five minutes of cleanup here is the difference between garments that hang on the rod and garments that float under it.



SIDE
width ÷ height 0.27–0.33

FRONT
0.6–0.75

BACK
0.6–0.75

----- crop line

The hook tip touches the **top edge**. Nothing is cut off at the sides or hem, and the background is transparent.

CHECK	WHAT IT SHOULD BE
Background	Fully transparent PNG or WebP. Remove the background if your tool added one.
Crop	Tight to the garment on all four sides. The **tip of the hanger hook touches the top edge**.
Side-view shape	Narrow: width ÷ height between **0.27 and 0.33** (for example 600 × 2000 px).
Front/back shape	Wider: width ÷ height between **0.6 and 0.75** (for example 1400 × 2000 px).
Size	About 1400–2000 px tall, exported as WebP under 300 KB each so the page loads fast.
File names	One pattern for everything, e.g. `hoodie-black-side.webp`, `hoodie-black-front.webp`, `hoodie-black-back.webp`.
How many	10 products fill the rail nicely. Fewer works, and you can repeat products to fill gaps.

STEP 05 · BUILD PROMPT

BUILD THE SECTION

05

Open your AI coding agent in an empty folder, put your photos in an `images` folder, and paste the whole prompt below. It builds one HTML file you can open straight in your browser.

COPYING FROM THIS PDF

Select from the first line (“Build me a…”) to the last (“…no console errors.”) in one go. If your PDF viewer merges lines, paste into a plain text editor first. The agent understands it either way.

PROMPT 04 · CLOTHING RACK HERO — COPY EVERYTHING BELOW

```
Build me a "clothing rack" hero section for the top of an e-commerce homepage (no header or nav, the hero is the first thing on the page). Write it as ONE self-contained HTML file (inline CSS + vanilla JS, no frameworks, no libraries). All product data must live in one `CONTENT` object at the top of the script so I can swap in my own products.

## What it looks like
- The hero fills the whole screen (`min-height: 100svh`) with everything centred vertically and horizontally. Background: a soft warm radial gradient (white at the top centre, fading to warm off-white `#f6f3ec` → `#efeae0`).
- Small centred eyebrow at the top: `COLLECTION TITLE | SUBTITLE` (12px, uppercase, 2px letter-spacing, weight 600; the second half at 45% opacity, a thin vertical divider between).
- Under it, a big headline (`<h1>`, uppercase, weight 800, `clamp(40px, 6.5vw, 92px)`, line-height .95, tight letter-spacing -0.045em, max about 14 characters wide so it breaks onto 2 lines). The last word is shown at 35% opacity for contrast, e.g. "YOUR BIG **HEADLINE**".
- The eyebrow, headline and button fade up into place (28px rise, 0.9s, staggered 120ms) when the page loads.
- Under the headline, a full-width horizontal chrome clothes rod (8px tall, metallic vertical gradient, small end caps on both sides).
- 10 garments hang side by side from the rod, centred as a row with a 10px gap. Each garment is a photo that already includes its own hanger, so the top of the image (the hook) touches the rod.
- By default every garment shows its **side view** (narrow photo). Each product has 3 photos: `side`, `front`, `back`.
- Each garment has a small cream price tag (`$199`) tied on a thin string from near the shoulder, hanging off to the right at about -24°. The card itself is counter-rotated about 16° so it hangs nearly upright. It has a tiny punched hole at the top, rounded bottom corners and a soft shadow.
- Below the rack: one line of text (15px, weight 600) and a pill button ("Shop the Collection", cream background, thin border; turns black on hover and lifts 1px).
- Garment height is calculated so the whole row fits the container width, with room left over for one garment turned to its front view: `h = (availableWidth - gaps - 2×18px) / (sum of side-view aspect ratios + biggest front-minus-side aspect difference)`, clamped to 120px minimum and a maximum of 420px or 40% of the screen height (whichever is smaller), so the whole hero fits on one screen. Read each photo's real aspect ratio from `naturalWidth/naturalHeight` once it loads. On phones (<800px) use a fixed height of about 230px and let the rack scroll sideways.

## Motion (the important part)
Use ONE `requestAnimationFrame` loop that only runs while something is moving and stops when everything has settled. Use real elapsed time (dt in seconds, capped at 1s) so the speed is right on slow or throttled frames.
```

1. **Pendulum swing.** Every garment is a damped pendulum hanging from its hook: angle `a` (degrees) and velocity `v`. Each frame, in sub-steps of at most 16ms: `v += (-30·a - 2.4·v)·h; a += v·h`. Clamp `|a|` to 12° (bounce back at 30% speed if it hits the limit). Rotate the garment wrapper by `a` with `transform-origin: top centre`, so it swings from the hook. Garments are perfectly still at rest; they only move when nudged.
2. **The tag lags behind.** The price tag follows the garment's angle with a delay (`tagAngle += (a - tagAngle)·(1 - e^(-7·dt))`) and is rotated by the difference, so it trails each swing.
3. **Drop-in entrance.** When the section scrolls into view (IntersectionObserver), each garment falls from about 150px above, fading in, overshoots 5px and settles (≈820ms, staggered 70ms per garment). As each one lands, give it a small sideways nudge (alternating direction, 16–30°/s) so it sways on the rod. Hide the garments until then.
4. **Hover turn (desktop mouse only).** Hovering a garment smoothly turns it from side view to front view:
   - Turn progress `k` eases toward 1 (0 on leave) with exponential smoothing, time constant ≈260ms. Draw with `e = smoothstep(k)`.
   - Width animates from side width to front width (`h × aspect`). An 18px gap opens on each side.
   - The side photo rotates in 3D (`perspective(900px) rotateY(0 → -88°)`) during the first half of the turn and disappears when edge-on.
   - The front photo fades in over the second half while scaling 0.9 → 1. The whole garment also eases from `rotateY(-12°)` to 0.
   - The hovered garment lifts 6px.
   - When the hover starts, knock the neighbours: the garment directly left gets +30°/s, directly right -30°/s, and the next ones out ±11°/s, so they swing away and settle.
   - The text line under the rack crossfades to the hovered product's name; it fades back on leave.
   - Keyboard focus does the same as hover.
5. **Scroll breeze.** On page scroll (throttled to every 100ms), measure scroll speed and give every visible garment a small nudge proportional to it (max ±12°/s), with varied direction per garment (e.g. `speed × sin(i·2.1+1)`), so the rack ripples as you scroll past.

Click: product popup
Clicking a garment opens a full-screen popup:
- Background: white at 96% opacity with a 26px backdrop blur, fading in over 0.4s.
- Left side: a big "stage" with the garment's front photo and its back photo stacked as a 3D card (`transform-style: preserve-3d`, back face pre-rotated 180°, `backface-visibility: hidden`).
- Right side, fading/sliding in about 0.2s later: counter `04 / 10`, product name, price, `Front | Back` tabs with an underline, size pills (S M L XL, first selected), a full-width black "Add to cart" button, and a footer row with the name and a "View product page" link. A "Close ×" button sits top right.
- **Flight in:** the stage animates (Web Animations API, 720ms, `cubic-bezier(.2,.8,.25,1)`) from the garment's exact spot on the rack to the centre along an arc. Keyframes: start at the garment's position and scale → a midpoint 55% of the way there, lifted 30–100px higher, slightly bigger, tilted 3° → final position. The stage starts side-on (`rotateY(-80°)`) and turns to face front while flying. Hide the original garment on the rack while the popup is open.
- Front/Back tabs flip the card 180° (0.8s ease-out). The user can also drag the garment left/right to spin it; on release it snaps to the nearest front or back and the tabs update.
- **Close** (button or Esc): flies back to the rack along the reverse arc (600ms, ease-in-out). The garment reappears and gets a nudge so it swings as it is hung back. Return keyboard focus to the garment.
- Accessibility: `role="dialog"` with `aria-modal`, Tab stays inside the popup, Esc closes it (listen at page level), the page doesn't scroll behind it.

Also include
- Respect `prefers-reduced-motion`: no swinging, drop or flight; turns and popups appear instantly.

````
- Placeholder art: if a product has no photos, draw simple grey SVG garment silhouettes (side and front) so the layout still works.
- The "Add to cart" button is only a demo (label changes to "Added ✓"). Leave a comment showing where to connect a real cart.
- Example `CONTENT`:
```js
const CONTENT = {
  rack: [
    { name:'Hoodie Black', price:'$199.00', url:'/products/hoodie-black',
      side:'images/hoodie-black-side.webp', front:'images/hoodie-black-front.webp',
back:'images/hoodie-black-back.webp' },
    // ... 10 products total
  ],
  garmentSizes: ['S','M','L','XL'],
};
```

## Photo requirements (tell me if mine don't fit)
Transparent-background PNG/WebP. Each photo is cropped tight to the garment, with the hanger hook at the very top edge. Side views are narrow (around 0.27–0.33 width/height); front and back views are wider (around 0.6–0.75).

When you're done, open the page in a browser and check: the garments land and sway, the hover turn works and pushes the neighbours, the popup flies in and out, and there are no console errors.
````

STEP 06 · FINISH

MAKE IT YOURS

Your agent puts every product in one list called `CONTENT` at the top of the script. That's the only part you need to edit.

Swap in your products

- Change each product's `name`, `price` and `url` (the link to its product page).
- Point `side`, `front` and `back` at your three photos for that product.
- Edit the headline, eyebrow, text line and button label straight in the HTML.
- Ask your agent: *"Connect the Add to cart button to my Shopify / WooCommerce cart."* The prompt deliberately leaves it as a demo.

Test it in 60 seconds

- Reload the page: garments drop onto the rod one by one and sway as they land.
- Hover a garment: it turns from side to front and pushes its neighbours aside.
- Scroll the page quickly: the whole rack ripples.
- Click a garment: it flies into the popup. Try Front/Back and drag to spin. Press Esc: it flies back and swings.
- Check on your phone: the rack scrolls sideways and tapping opens the popup.

If something looks off

Garments float below the rod	The photo has empty space above the hook. Crop so the hook tip touches the top edge.
A garment looks too wide on the rail	The side shot is really a three-quarter view. Regenerate it with Prompt 02.
Hover shows a smaller or brighter garment	Front and side were shot at different scale or lighting. Regenerate the side view using the front image as reference.
Grey or white box behind a garment	The background isn't transparent. Run it through a background remover.
Nothing animates	Your device may have "Reduce motion" turned on. That's expected: the section stays still on purpose.
Page loads slowly	Compress your photos to WebP under 300 KB each.

THAT'S IT. GO BUILD IT.

Three image prompts, one build prompt, and your store has a hero section that feels like walking into a real shop. More templates and prompts like this at heyyali.store.

SKIP THE BUILD

WANT IT READY-MADE?

Get the finished **3D Hanging Rack Hero Section**: the polished version of everything in this guide, with floating cloud effects and the full source code. Install it and swap in your products.



- ✓ Realistic hanging and swing animations
- ✓ Full-screen product showcase on click
- ✓ Mobile-friendly swipe interactions
- ✓ Hover turns each garment from side to front
- ✓ Animated floating cloud effects
- ✓ Ready-to-use source code and install guide

Works with **Shopify**, **WordPress**, **Elementor**, **WooCommerce** and **custom HTML** sites. Instant digital download, also included in Heyyali Pro.

Get the template → https://heyyali.store/product/3d-hanging-rack-hero-section/