# WikipediA

# **Turn restriction routing**

A <u>routing algorithm</u> decides the path followed by a <u>packet</u> from the source to destination <u>routers</u> in a <u>network</u>. An important aspect to be considered while designing a routing algorithm is avoiding a <u>deadlock</u>. **Turn restriction routing**<sup>[1][2]</sup> is a routing algorithm for <u>mesh</u>-family of <u>topologies</u> which avoids deadlocks by restricting the types of turns that are allowed in the algorithm while determining the route from source node to destination node in a network.

# Reason for deadlock Solution to deadlock Logic behind turn restriction routing Examples of turn restriction routing Dimension-ordered (X-Y) routing West first routing North last routing Negative first routing Advantages of turn restriction routing See also References

# Channel 1 OB IB Channel 3 Channel 4 Channel 3 Router 4 IB: Input Buffer OB: Output Buffer

Fig 1: Figure shows four channels with both input and output buffers full. All packets in output buffers are to be forwarded to next channel. But since their input buffers are full, this forwarding cannot take place. As a result, no packet can be moved any further. This results in a deadlock.

# Reason for deadlock

A deadlock (shown in fig 1) is a situation in which no further transportation of

packets can take place due to the saturation of network resources like <u>buffers</u> or <u>links</u>. The main reason for a deadlock<sup>[3]</sup> is the cyclic acquisition of <u>channels</u> in the network. For example, consider there are four channels in a network. Four packets have filled up the input buffers of these four channels and needs to be forwarded to the next channel. Now assume that the output buffers of all these channels are also filled with packets that need to be transmitted to the next channel. If these four channels form a cycle, it is impossible to transmit packets any further because the output buffers and input buffers of all channels are already full. This is known as cyclic acquisition of channels and this results in a deadlock.

# Solution to deadlock

Deadlocks can either be <u>detected</u>, broken or <u>avoided</u> from happening altogether. Detecting and breaking deadlocks in the network is expensive in terms of <u>latency</u> and resources. So an easy and inexpensive solution is to avoid deadlocks by choosing routing techniques that prevent cyclic acquisition of channels. 6 acquisition of channels.

# Logic behind turn restriction routing

Logic behind turn restriction routing derives from a key observation. A cyclic acquisition of channels can take place only if all the four possible clockwise (or anti-clockwise) turns have occurred. This means deadlocks can be avoided by prohibiting at least one of the clockwise turns and one of the anti-clockwise turns. All the clockwise and anti-clockwise turns that are possible in a non restricted routing algorithm are shown in fig 2.

# List of all clockwise turns in any route List of all anti-clockwise turns in any route

Fig 2: All possible turns in a network route- clockwise and anticlockwise.

# **Examples of turn** restriction routing

A turn restriction routing can be obtained by prohibiting at least one of the four possible clockwise turns and at least one of the four possible anti-clockwise turns in the routing algorithm. This means there are at least 16  $(4x4)^{[5]}$  possible turn restriction routing




Fig 3: Dimension-ordered (X-Y) routing

techniques as you have 4 clockwise turns and 4 anti-clockwise turns to choose from. Some of these techniques have been listed below.

## **Dimension-ordered (X-Y) routing**

Dimension ordered (X-Y) routing<sup>[2][5]</sup> (shown in fig 3) restricts all turns from y-dimension to x-dimension. This prohibits two anti-clockwise and two clockwise turns which is more than what is actually required. Even then since it restricts the number of turns that are allowed we can tell that this is an example for turn restriction routing.




Fig 4: West first routing

# West first routing

West first routing<sup>[2][5]</sup> (shown in fig 4) restricts all turns to the west direction. This means west direction should be taken first if needed in the proposed route.




Fig 5: North last routing

# **North last routing**

North last routing [2][7] (shown in fig 5) restricts turning to any other direction if the current direction is north. This means north direction should be taken last if needed in the proposed route.

### **Negative first routing**

Negative first routing [2][7] (shown in fig 6) restricts turning to a negative direction while the current direction is positive. West is considered as the negative direction in X-dimension and south is considered as the negative direction in Y-dimension. This means any hop in one of the negative directions should be taken before taking any other turn.




Fig 6: Negative first routing

# Advantages of turn restriction routing

- Avoiding deadlocks is less expensive to implement than deadlock detecting and breaking techniques.
- Turn restrictions provide alternate <u>minimum length paths</u> as well as non minimum length paths from one node to another, which allows routing around congested or failed links.<sup>[8]</sup>

For example, consider figure 7 below. Say there are multiple routers, F1, F2 etc., that feed packets to a congested, but low-cost link from source router S to destination router D. Implementing Turn restriction routing means that some of the turns from any of the feeder routers to the congested router S may now be restricted. Those feeder routers may have to use a longer path to get to destination D, thereby decongesting the link from S to D to an extent.




Fig 7: Topology of four routers F1, F2, S and D connected to each other. Turn restrictions could ease congestion on link S-D to an extent.

# See also

- Policy-based routing
- Deadlock
- Heuristic algorithms

# References

- 1. Solihin, Yan (2016). *fundamentals of parallel computer architecture*. solihin books. pp. 390–392. ISBN 9780984163007.
- CHRISTOPHER J. GLASS AND LIONEL M. NI. "The Turn Model for Adaptive Routing" (http://www.diit.unict.it/~vcatania/COURSES/semm\_06-07/DOWNLOAD/noc\_routing01.pdf) (PDF).
   Michigan State University.

- 3. Solihin, Yan (2016). *fundamentals of parallel computer architecture*. solihin books. pp. 388–389. ISBN 9780984163007.
- 4. Coulouris, George (2012). *Distributed Systems Concepts and Design*. Pearson. <u>ISBN</u> <u>978-0-273-76059-7</u>.
- 5. Solihin, Yan (2016). *fundamentals of parallel computer architecture*. solihin books. p. 390. ISBN 9780984163007.
- 6. Havender, James W (1968). "Avoiding deadlock in multitasking systems" (http://domino.research.i bm.com/tchjr/journalindex.nsf/a3807c5b4823c53f85256561006324be/c014b699abf7b9ea85256bf a00685a38?OpenDocument). *IBM Systems Journal*. **7** (2): 74–84. doi:10.1147/sj.72.0074 (https://doi.org/10.1147%2Fsj.72.0074).
- 7. Solihin, Yan (2016). Fundamentals of parallel computer architecture. Solihin books. pp. 390–391. ISBN 9780984163007.
- 8. Solihin, Yan (2016). fundamentals of parallel computer architecture. solihin books. p. 392.

Retrieved from "https://en.wikipedia.org/w/index.php?title=Turn\_restriction\_routing&oldid=940948258"

This page was last edited on 15 February 2020, at 17:33 (UTC).

Text is available under the Creative Commons Attribution-ShareAlike License; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy. Wikipedia® is a registered trademark of the Wikimedia Foundation, Inc., a non-profit organization.