Control flow: Matrix definition • Computer Science • 15min

■ A simple for loop merely cycles through elements of an array:

```
for counter = linspace(0,1,11)
        disp('Now at number:')
        disp(counter)
end
```

• This is useful in a number of applications both scientific and numerical. For instance, one can define a finite-difference matrix as follows:

```
% Preallocate a matrix
nrows = 10;
ncols = 10;
myData = ones(nrows, ncols);
% Loop through the matrix
for r = 1:nrows
    for c = 1:ncols
        if r == c
            myData(r,c) = 2;
        elseif abs(r - c) == 1
            myData(r,c) = -1;
        else
            myData(r,c) = 0;
        end
    end
end
```

Example: Heat conduction (Numerics & linear algebra) • Mech. Eng. • 30min


A finite difference approximation is a numerical method which approximates a derivative (as in a differential equation) by a finite difference, as follows.

$$f'(x) \approx \frac{f(x+h) - f(x)}{h}$$
 thus $f''(x) \approx \frac{f(x+h) - 2f(x) + f(x-h)}{h^2}$

Now, we can utilize this fact to solve a transient heat conduction problem (file heat_FTCS.m). (The picture replaces i by j and m by n but describes how each point is calculated.) j, n+1

$$\frac{1}{\alpha} \frac{du}{dt} = \frac{d^2 u}{dx^2} \text{ thus } \frac{1}{\alpha} \frac{u_i^m}{\delta t} = \frac{u_{i-1}^{m-1} - 2u_i^{m-1} + u_{i+1}^{m-1}}{\delta x^2}$$

Given a bar of material with $\alpha = 0.1$ heated to the initial condition $u(x,t=0) = \sin(\pi x/L)$ and boundary conditions u(x=0,t) = u(x=L,t) = 0, with a length L=1, find the temperature profile u(x,t) from $t_0=0$ to $t_{\max}=0.5$.



Use a for statement to perform the time iteration forward and the calculation at each spatial point of the array per time step.

• This is a good time to experiment with the plot editor as well on this data set.

Example: Radioactive decay chain (System of 1st-order ODEs) • Physics • 30min

This exercise will demonstrate the solution of first-order differential equations such as those used to describe radioactive decay processes. Given a large number of atoms, we may treat the number of atoms N as continuous. The rate of decay is proportional to the number of nuclei. We can write

$$\frac{dN}{dt} = -\lambda N$$

where λ is the decay constant characteristic of the material.

One advantage of modeling this system is that it has an analytical solution which we can use to assess the different methods of numerical solution that we will employ:

$$N(t)=N_0\exp(-\lambda t)$$

where N_0 is the initial amount of the material.

- First, let's define a function for the analytical solution. Open a new file and save it as rad_analytic.m.
- Write a function in this file to return the analytical value for N given N_0 , λ , t.

```
function N = rad_analytic(N0,lambda,t)
N = N0 * exp(-lambda * t);
```

■ Test the function for a few cases:

```
rad_analytic(0,100)==100 % test the initial condition
rad_analytic(1,100)<36.79 && rad_analytic(1,100)>36.77 % test floating point
values with bounds not equality
t_ana=[0:0.1:10];
N_ana=rad_analytic(t_ana,100);
plot(t ana,N ana)
```

For the numerical solution, MATLAB requires that the right-hand side of a differential equation (the non-differential expression) be available as a function. In other words, for

$$\frac{dN}{dt} = -\lambda N$$

the function should return simply the value $-\lambda N$.

- Open a new file and save it as dNdt.m. Write a function to return the analytical value for dN/dt given N, t. (Hard-code in the value of lambda as 1.0.)
- We will use the low-order ode23 method first.

```
[t_23,N_23] = ode23(@dNdt,[0,10],[100]);
```

• Compare the results visually.

```
plot(t 23,N 23,t ana,N ana);
```

ode23 is a low-order solver, however, and results can often be improved by moving to the slower but higher-order ode45 solver. (You will probably not perceive a difference in our work today.)

```
[t_45,N_45] = ode45(@dNdt,[0,10],[100]);
plot(t 23,N 23,t ana,N ana,t 45,N 45);
```

■ Calculate the residual error at each point of the analytical solution. Because the time-domain points calculated by the ODE solvers are not at the same points as the analytical solution we acquired above, the calculation of residuals (errors) is slightly complicated. We can either interpolate directly (using interp) or we can use the handy built-in function deval, which will

be demonstrated here.

```
sol = ode45(@dNdt,[0,10],[100]);
N_int = deval(sol,t_ana,1);
resids = N_ana-N_int;
plot(t_ana,resids)
```

Now let's introduce another species (or model a decay chain). Because we wrote this as a function in MATLAB, it can be easily vectorized. Let's first construct a hypothetical decay chain in which element A turns into B with half-life $t_{1/2,A} = 1.0$ and B turns into C with half-life $t_{1/2,B} = 20$. (Recall that $\lambda_A = (\ln 2)/t_{1/2,A}$.)

- Write the governing equations for this system.
- Convert these equations into matrix form.
- Make a copy of dNdt.m as decay_chain.m. Define the decay constants as l_A, etc. Set up the matrix form of the equations and return the result.
- Introduce the matrix equation into ode45 and plot the results. (We will forgo including the analytical solution at this time, but this can be readily done.)

```
N0=[100;0;0];
[T,N3]=ode45(@decay_chain,[0 50],N0);
plot(T,N3)
```

Example: Coolant flow in channel (2nd-order, PDE Toolbox) • Mech. Eng. • 20min

Now let's illustrate how you might set up a more complex geometry in MATLAB. The PDE Toolbox is a graphical interface for designing and calculating equations on a mesh geometry.

- Invoke the PDE Toolbox with pdetool.
- Create a rectangle and a circle overlapping a quarter of it. Change the set formula to R1-E1 to make the circle subtractive.
- First initialize a mesh, then refine the mesh. Now jiggle it.
- Change to Boundary Mode. Mixed boundary conditions can only be done in systems, so we'll cheat in this case and just set the outer and inner boundaries directly (perfect heat transfer at the surface).
 - Set the inner circle (coolant channel surface) to Dirichlet BC with h=1, r=400.
 - Set the outer (top) boundary (combustion surface) to Dirichlet BC with h=1, r=1700.
 - Set the three inner boundaries to Neumann BC with g=0, q=1.
- Set up the PDE. The types of PDE for which built-in solvers are available are shown here. Create an elliptic PDE with c = 1.0; a = 0.0; f = 0.0; and d = 1/3.6.

(If, like me, you don't recall the mathematical terms for each class of PDE, here's a list:

- elliptic = Laplace equation
- parabolic = heat equation
- hyperbolic = wave equation

Other types (including nonlinear PDEs) require direct implementation of a numerical method to solve. Next time we will look at a nonlinear PDE, the Burgers' equation, which introduces a shock wave in its solution.)

- Solve the PDE.
- Plot it. Add contours (10 lines), flat shading, and change the colormap to 'hot'. Examine the abs(grad(u)) plot as well; if the sides are not horizontal, try playing with parameters such as the mesh resolution to solve that problem.

Example: Shock waves (nonlinear PDE) • Aerospace Eng. • 30min

The inviscid Burgers' equation

$$\frac{\partial u}{\partial t} = -u \frac{\partial u}{\partial x} = -\frac{1}{2} \frac{\partial (u^2)}{\partial x}$$

describes advecting waves which can produce shocks, or discontinuities. It is used to describe acoustics or hydrodynamics (particularly in the more complicated viscous form). As this is a partial differential equation in both x and t, we will need a numerical method to solve the system in time and another to solve the system in space. Accordingly, we will adopt the first-order upwind scheme in time and space. (This method isn't terribly stable, but will do for our purposes: consult a numerical methods text for more information on stability.)

This builds on some of the ideas of the finite difference example from last time, but extends them to more dimensions. We also will not construct an explicit matrix, but will use nested for loops to achieve the same effect.

The first-order upwind scheme uses the quantities at time step n to calculate the values at time step n, making its implementation straightforward.


We can approximate the Burgers' equation above with this scheme as

$$\frac{u_{j}^{n+1}-u_{j}^{n}}{\Delta t} = -u_{j}^{n} \frac{u_{j+1}^{n}-u_{j-1}^{n}}{2 \Delta x}$$

yielding

$$u_{j}^{n+1} = u_{j}^{n} \left[1 - \Delta t \frac{u_{j+1}^{n} - u_{j-1}^{n}}{2 \Delta x} \right]$$

as the fundamental expression for each calculation of u.



- Open a new script file and save it as burgers.m.
- Specify the fundamental parameters as variables to make them easy to adjust. (We will use the conventions of centimeters and seconds.)

■ For anything interesting to happen, the initial condition must be nontrivial. Let's have a cosine-shaped wave at t = 0: $u(x,0) = u_0(x) = 1 - \cos(x)$.

```
end
u = zeros(nt,nx+1);
u(1,:)=u0;
```

• This completely specifies the parameters for our problem, so let's put some thought into the structure of the main calculation routine. We require the solution at each step to meet the equation above, so

```
u(n+1,j) = u(n,j) * (1 - dt * (u(n,j+1)-u(n,j-1))/(2*dx)); should just about fit the bill.
```

■ Note that the above equation requires the introduction of three new variables: u, n, j. n and j refer to a specific case of a repeated calculation, and so are good candidates for using a for loop. u can be initialized directly from u0 in the first time through the loop. Write this code and try to execute the script.

```
for n=1:nt
    for j=1:nx+1
        if (x(j) == xmin)
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,j+1)-u(n,nx))/(2*dx));
        elseif (x(j) == xmax)
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,1)-u(n,j-1))/(2*dx));
        else
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,j+1)-u(n,j-1))/(2*dx));
        end
    end
end
```

Try to run the code now. It fails because we still have edge cases: j+1 and j-1 aren't always valid statements since you can't use a negative index in MATLAB. Careful thought reveals that we need to define the endpoint boundary conditions: do we want them to be at a fixed temperature or merely insulating (nonconductive)? (Incidentally, this is where matrices can be very convenient, especially in higher dimensions than 1 space plus 1 time.)

We choose to have periodic boundary conditions (which *de facto* means that $u_0 = u_{max}$). (If instead we had chosen insulating boundary conditions, we would simply have set the outermost two points equal to each other; fixed value boundary conditions would have required us to set the endpoints to a definite value.)

Set up a condition to test if we are at an endpoint and to wrap the equation around if we are (this is inside both loops):

```
for n=1:nt
    for j=1:nx+1
        if (x(j) == xmin)
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,j+1)-u(n,nx))/(2*dx));
        elseif (x(j) == xmax)
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,1)-u(n,j-1))/(2*dx));
        else
            u(n+1,j) = u(n,j) * (1 - dt * (u(n,j+1)-u(n,j-1))/(2*dx));
        end
    end
end
```

Notice that past about t = 0.25s the solution becomes unstable. This is actually the numerical expression of a physical result: the inviscid Burgers' equation develops a shock wave at this point. To accurately model it numerically involves introducing a viscosity term for the full Burgers' equation, but we will forgo that at the present time. (Feel free to implement this yourself; see


Wikipedia for details on the full equation form.) The numerical integrator can also be improved.

For nonlinear equations, you often have to worry about an additional component to the mesh spacing and time step size: the equation itself may introduce unexpected behavior that cannot be analytically expressed!

MATLAB also provides the pdenonlin function which may be a useful tool if your nonlinear PDE is of the correct form.

Example: Radioactive decay scheme (System of 1st-order ODEs) • Physics • 20min

Now that we have seen how to introduce a decay chain, let's explore a decay scheme consisting of six isotopes of five elements.



Radon-211 decays via two competing chains to the stable lead-207 as illustrated above. First we need to cast this reaction into a matrix form so that we can feed it into the ODE solver.

- Write the explicit first-order decay equations for this reaction.
- Again, put these into matrix form and write corresponding dNdt functions for each of them. Don't forget to convert the half-lives to decay constants.
- Put the resulting matrix equation into ode45. Note that the system takes an inordinately long time to resolve due to the wildly different time scales of the decay chain. Try using the stiff equation solver ode15s instead.

```
N0=[100;0;0;0;0;0];
tic;[T,N6]=ode45(@decay_scheme,[0 5e5],N0);toc %45s
tic;[T,N6]=ode113(@decay_scheme,[0 5e5],N0);toc %63s
tic;[T,N6]=ode15s(@decay_scheme,[0 5e5],N0);toc %0.017s
plot(T,N6)
```