## **4.1.2.** Type conversion instructions (destructive)

CBW	converts the byte from AL to the word in AX (sign extension)	
CWD	converts the word from AX to the doubleword in DX:AX (sign extension)	
CWDE	converts the word from AX to the doubleword in EAX (sign extension)	
CDQ	converts the doubleword from EAX to the quadword in EDX:EAX (sign extension)	
MOVZX d, s	loads in d (REGISTER !), which must be of size larger than s (reg/mem), the UNSIGNED contents of s (zero extension)	-
MOVSX d, s	load in d (REGISTER!), which must be of size larger than s (reg/mem), the SIGNED contents of s (sign extension)	-
	http://www.c-jump.com/CIS77/ASM/DataTypes/T77_0270_sext_example_movsx.htm !!!!!!!!!!	

**CBW** converts the <u>signed byte</u> from AL into the <u>signed word</u> AX (extends the sign bit of the byte from AL into the whole AH, thus destroying the previous content of AH). For example,

```
mov al, -1 ; AL=0FFh ; extends the byte value -1 from AL to the word value -1 in AX (0FFFFh).
```

Similarly, for the signed conversion word - doubleword, the **CWD** instruction extends the <u>signed word</u> from AX into the <u>signed doubleword</u> in DX:AX. Example:

```
mov ax,-10000 ; AX = 0D8F0h
cwd ; obtains the value -10000 in DX:AX (DX = 0FFFFh ; AX = 0D8F0h)
cwde ; obtains the value -10000 in EAX (EAX = 0FFFFD8F0h)
```

The **unsigned** conversion is done by "zerorizing" the higher byte or word of the initial value (for example, by mov ah, 0 or mov dx, 0 - a similar effect like applying the MOVZX instruction)

Why CWD coexists with CWDE? The CWD instruction must remain for backwards compatibility reasons, but also to assure the proper functioning of the (I)MUL and (I)DIV instructions.

MOV ah, 0c8h

MOVSX ebx, ah ; EBX = FFFFFC8h MOVSX ax,[v] ; MOVSX ax, byte ptr DS:[offset v] MOVZX edx, ah ; EDX = 000000C8h MOVZX eax, [v] ; syntax error – op.size not specified

Movsx eax, v : syntax error ! (v is not reg/mem as the syntax requires, but a constant !)

## Atenție! NU sunt acceptate sintactic:

CBD CWDE EBX, BX MOVSX EAX, [v]
CWB CWD EDX,AX MOVZX EAX, [EBX]
CDW MOVZX AX, BX MOVSX dword [EBX], AH

CDB !!! (super-înghesuire!! ©) MOVSX EAX, -1 CBW BL

## 4.1.3. The impact of the little-endian representation on accessing data (pag.119 – 122 – coursebook)

If the programmer uses data consistent with the size of representation established at definition time (for example accessing bytes as bytes and not as bytes sequences interpretted as words or doublewords, accessing words as words and not as bytes pairs, accessing doubewords as doublewords and not as sequences of bytes or words) then the assembly language instructions will automatically take into account the details of representation (they will manage automatically the little-endian memory layout). If so, the programmer must NOT provide himself any source code measures for assuring the correctness of data management. Example:

```
a db 'd', -25, 120
b dw -15642, 2ba5h
c dd 12345678h
```

mov al, [a] ;loads in AL the ASCII code of 'd'

mov bx, [b] ;loads in BX the value -15642; the order of bytes in BX will be reversed compared to the memory representation of b, because only the memory representation uses little-endian! At register level data is stored according to the usual structural representation (equiv.to a big endian representation).

mov edx, [c] ; loads in EDX the value of the doubleword 12345678h

If we need accessing or interpreting data in a different form than that of definition then we must use explicit type conversions. In such a case, the programmer must assume the whole responsability of correctly accessing and interpreting data. In such cases the programmer must be aware of the little-endian representation details (the particular memory layout corresponding to that variable/memory area) and use proper and consistent accessing mechanisms Ex pag.120-122.

```
segment data
```

```
a dw 1234h ;because of the little-endian representation, in memorie the bytes have the following placement:
```

```
b dd 11223344h ;34h 12h 44h 33h 22h 11h ; address a a+1 b b+1 b+2 b+3 c db -1
```

segment code

mov al, byte [a+1] ;accessing a as a byte, calculating the address a+1, selecting the byte from the address a+1 (the byte with the value of 12h) and transfer it in the AL register

```
mov dx, word [b+2]; dx:=1122h
```

mov dx, word [a+4] ;dx:=1122h because b+2 = a+4, these pointer type expressions compute the same address, specifically the address of the byte 22h.

mov dx, [a+4] ;this instruction is equivalent to the previous one, specifying the conversion operator WORD not being required.

mov bx, [b] ;bx:=3344h

mov bx, [a+2]; bx:=3344h, because the following addresses are equal: b=a+2.

mov ecx, dword [a] ;ecx:=33441234h, because the doubleword that starts at the address of a is composed of the following bytes: 34h 12h 44h 33h, which (because of the little-endian representation) form the following doubleword: 33441234h.

mov ebx, [b] ; ebx := 11223344h mov ax, word [a+1] ; ax := 4412h mov eax, dword [a+1] ; eax := 22334412h

mov dx, [c-2] ; DX := 1122h because c-2 = b+2 = a+4

mov bh, [b] ;bh := 44h ;ch := 12h mov cx, [b+3] ;CX := 0FF11h

#### 4.2. OPERATIONS.

# 4.2.1. <u>Arithmetic operations</u>

Operands are represented in complementary code (see 1.5.2.). The microprocessor performs additions and substractions "seeing" only bits configurations, NOT signed or unsigned numbers. The rules of binary adding or substracting two numbers do not impose previously considering the operands as signed or unsigned, because independently of interpretation, additions and subtractions works the same way. So, at the level of these operations, the signed or unsigned interpretation depends on a further context and is left to the programmer.

The addition and the subtraction are evaluated in the same way (adding or subtracting the binary configurations) not taking into account the sign (interpretation) of these configurations! This does not apply to multiplication and division. When using these operations we need to know beforehand if the operands will be interpreted as signed or unsigned.

For example, if A and B are bytes:

```
A = 9Ch = 10011100b (= 156 in the <u>unsigned</u> interpretation and -100 in the <u>signed</u> interpretation) B = 4Ah = 01001010b (= 74, both in <u>signed</u> and <u>unsigned</u> interpretation)
```

The microprocessor performs the addition C = A + B obtaining C = E6h = 11100110b (= 230 in the <u>unsigned</u> interpretation and -26 in the <u>signed</u> one)

We though notice that the simple addition of the bits configuration (without taking into account a certain interpretation at the moment of addition) assures the result correctness, both in signed and unsigned interpretation.

# <u>ARITHMETIC INSTRUCTIONS – page 123 (coursebook)</u>

# **4.2.1.3.** Examples – page 129-130 (coursebook)

## 4.2.2. <u>Logical bitwise operations</u> (AND, OR, XOR and NOT instructions).

AND is recommended for isolating a certain bit or for forcing the value of some bits to 0.

OR is suitable for forcing certain bits to 1.

XOR is suitable for complementing the value of some bits.

NOT is used for complementing the operand's contents (reg/mem).

## 4.2.3. Shifts and rotates.

Bit shifting instructions can be classified in the following way:

- Logic shifting instructions
- left - SHL
- right - SHR

- Arithmetic shifting instructions
- left - SAL
- right - SAR

Bit rotating instructions can be classifed in the following way:

- Rotating instructions without carry
- left - ROL
- right - ROR
- Rotating instructions with carry
- left - RCL
- right - RCR

For giving a suggestive definition for shifts and rotates let's consider as an initial configuration one byte having the value X = abcdefgh, where a-h are binary digits, h is the least significant bit, bit 0, a is the most significant one, bit 7, and k is the actual value from CF (CF=k). We then have:

SHL X,1; has the effect X = bcdefgh0 and CF = a SHR X,1; has the effect X = 0abcdefg and CF = h SAL X,1; identically to SHL

SAR X,1; has the effect X = aabcdefg and CF = h ROL X,1; has the effect X = bcdefgha and CF = a ROR X,1; has the effect X = habcdefg and CF = h RCL X,1; has the effect X = bcdefghk and CF = a RCR X,1; has the effect X = kabcdefg and CF = h

#### 4.3. BRANCHING, JUMPS, LOOPS

# 4.3.1. <u>Unconditional jump</u>

Three instructions fall into this cathegory: JMP (equiv. to GOTO from other languages), CALL (a procedure call means a control transfer from the call's point to the first instruction from the called routine) and RET (control transfer back to the first executable instruction after the CALL).

JMP operand	Unconditional jump to the address specified by operand	-
CALL operand	Transfers control to the procedure identified by operand	-
<b>RET</b> $[n]$	Transfers control to the first instruction after CALL	-

## 4.3.1.1. JMP instruction

Syntax: **JMP** *operand* 

where *operand* is a <u>label, register</u> or a <u>memory address</u> containing an <u>address</u>. Its effect is the unconditional control transfer to the instruction following the label, to the address contained in the register or to the address specified by the memory variable respectively. For example, after running the sequence

mov ax,1
jmp AdunaDoi
AdunaUnu: inc ax
jmp urmare
AdunaDoi: add ax,2

urmare: . . .

AX will hold the value 3. **inc** şi **jmp** between *AdunaUnu* and *AdunaDoi* will not be executed, unless a jump to *AdunaUnu* will be done from another step of the program.

As mentioned above, the jump may be made to an address stored in a register or in a memory variable. Examples:

If in case (1) we wish to replace the register destination operand with a memory variable destination operand, a possible solution is:

```
b resd 1
(1') ...
mov [b], DWORD etich ; b := offset etich
jmp [b] ; NEAR jump – memory variable operand
; JMP DWORD PTR DS:[offset_b]
```

**Exemplul 4.3.1.2**. – pag.142-143 (coursebook) – control transfer to a label. Analysis and comparison.

# 4.3.2. Conditional jump instructions

#### 4.3.2.1. Comparisions between operands

CMP d,s	compares the operands values (does not modify them - fictious subtraction $d$ - $s$ )	OF,SF,ZF,AF,PF and CF
TEST d,s	non-destructive d AND s	OF = 0, CF = 0 SF,ZF,PF - modified, AF - undefined

The CMP instruction does not make any difference between the two above cases, because as we mentioned in 4.2.1.1 addition and subtraction are performed always in the same way (adding or subtracting binary configurations) no matter their interpretations (signed or unsigned). So it's not the matter to interpret the operands of CMP as being signed or unsigned, but to further interpret the RESULT of the subtraction! Conditional jump instructions are responsible to do that (Section 4.4.2.2).

# 4.3.2.2. Conditional jumps

Table 4.1. (pag.146 – coursebook) presents the conditional jump instructions together with their semantics and according to which flags values the jumps are made. For all the conditional jump instructions the general syntax is

<conditional\_jump\_instruction> label

The effect of the conditional jump instructions is expressed as "jump if operand1 <<relationship>> operand2" (where on the two operands a previously CMP or SUB instruction is supposed to have been applied) or relative to the actual value set for a certain flag. As easy can be noticed based on the conditions that must be verified, instructions on the same line in the table have similar effect.

When two <u>signed</u> numbers are compared, "less than" and "greater than" terms are used and when two <u>unsigned</u> numbers are compared "below" and "above" terms are respectively used.

# 4.3.2.3. Examples along with comments...... pag.148-162 (coursebook).

- comparative analysis and discussion of the concepts of: signed vs. unsigned representations, overflow, actual effects of conditional jump instructions, specific flags (CF, OF, SF, ZF)

# 4.3.3. Repetitive instructions (coursebook pag.162 – 164)

These are: LOOP, LOOPE, LOOPNE and JECXZ. Their syntax is

<instruction> label

**LOOP** performs the repetitive run of the instructions block starting at *label*, as long as the value of CX register is different from 0. **It first performs decrementation of ECX, then the test and eventually the jump.** The jump is "short" (max. 127 bytes – so pay attention to the "distance" between LOOP and the label!). – PAY ATTENTION!! CHECK IT!!! (short jump is out of range!)

When the end of loop conditions are more complex **LOOPE** and **LOOPNE** may be used. **LOOPE** (*LOOP while Equal*) differ from LOOP by ending condition, loop is ended either if ECX=0, either if ZF=0. In the case of **LOOPNE** (*LOOP while Not Equal*) the loop will end either if ECX=0, either if ZF=1. Even if the loop exit shall be based on value of ZF, CX decrementation is done anyway. **LOOPE** is also known as **LOOPNZ** and **LOOPNE** is also known as **LOOPNZ**. These are usually used preceded by a CMP or SUB instruction.

**JECXZ** (*Jump if ECX is Zero*) performs the jump to the operand label only if ECX=0, being useful when we want to test the value in ECX before entering in a loop. In the following example, JECXZ instruction is used to avoid entering the loop if ECX=0:

```
jecxz MaiDeparte ;if ECX=0 a jump over the loop is made Bucla:

Mov BYTE [esi],0 ;initializing the current byte inc si ;passing to the next byte loop Bucla ;resume the loop or ending it MaiDeparte: . . .
```

If a loop is entered with ECX=0, ECX is first decremented, obtaining the value 0FFFF FFFFh (= -1, so a value different from 0), the loop being resumed until 0 in ECX will be reached, namely  $2^32 = 4.294.967.296$  more times!

It's important to say here that <u>none of the presented repetitive instructions affects the flags</u>.

dec ecx loop Bucla and jnz Bucla

although semantic equivalent, they do not have the same effect, because DEC modifies OF, ZF, SF and PF, while LOOP doesn't affect any flag.

## 4.3.4. CALL and RET instructions

A procedure call is done by using the **CALL** instruction, it can be a *direct* or an *indirect* call. The direct call has the syntax:

**CALL** operand

Similar to JMP, **CALL** transfers the control to the address specified by the operand. In addition to JMP, before performing the jump, CALL saves to the stack the address of the instruction following CALL (the returning address). In other words, we have the equivalence:

CALL operand push dword A push dword A push dword A

The end of the called sequence is marked by a **RET** instruction. This pops from the stack the returning address stored there by CALL, transferring the control to the instruction from this address. The RET syntax is:

**RET** [n]

where n is an optional parameter. It indicates freeing from the stack n bytes below the returning address.

RET instruction can be illustrated by this equivalence:

```
B resd 1
. . . . (near return) ⇔ pop dword [B] add esp,n jmp [B]
```

Usually, as it is natural, CALL and RET are used in the following context:

CALL may also take the transfer address from a register or from a memory variable. Such a call is identified as an *indirect call*. Example:

```
call ebx ;address taken from a registercall [vptr] ;address taken from a memory variable
```

Concluding, the destination operand of a CALL instruction may be:

- a procedure name
- the name of a register containing an address
- a memory address