

User manual Gesroom Connector



1	Introduc	ction	3
2	Requirer	ments	3
3	Installati	ion	4
4	Configur	ration	5
	4.1 Ser	ver Configuration	6
	4.1.1	Server baseuri	6
	4.1.2	Server username and password	6
	4.2 Cale	endar Configuration	7
	4.2.1	Mandatory parameters	7
	4.2.1.	1 Id attribute	7
	4.2.1.	2 Server attribute	7
	4.2.1.	3 Plugncast / calendarui	7
	4.2.1.	4 Resource	7
	4.2.2	Optional parameters (classic)	8
	4.2.2.	display all the meetings or a part of the meetings in the day	8
	4.2	.2.1.1 StartOffset StartRelated	8
	4.2	.2.1.2 EndOffset / EndRelated	8
	4.2.3	Optional parameters (advanced)	9
	4.2.3.	1 RequestWindow	9
	4.2.3.	2 CachePersistence	9
	4.2.3.	3 Label	9
	4.2.3.	4 SendCacheOnServerError	9
5	Troubles	shooting / debug	10
6	Appendi	ix	11
	6.1 Ma	pping	11
	6.2 Act	tivation of Safeware Web services for Innes V1.10.10 when installing your Gesroom	า



This document provides installation and deployment information for administrators planning to deploy the **Gesroom-calendar** compatible with Innes digital signage.

The **Gesroom-calendar** is the bridge component allowing the Innes players to communicate with Gesroom servers.

Gesroom-calendar system must be installed and configured properly.

2 Requirements

The requirements must be filled before the installation.

- Innes PlugnCast Server V2.50.31 (or above) or
- Innes Briva Server V2.50.25 (or above)
- Safeware Web services for Innes V1.10.10 need to be installed properly by Safeware
 - Note: see example in appendix to install yourself Safeware Web services for Innes
 V1.10.10 on a Gesroom server 5.4.4
- If the resource "classroom" is not defined, the label from the configuration.xml file is used.
- The date/time given in the XML are assumed to be local dates and are stored as such.
- get access to the Gesroom system:

http://safeware-demo.hds-group.com/gesroom_innes/gestion/login.asp




3 Installation

• Go to the Innes Briva (or PlugnCast) Server Web Interface with your Web browser by typing:

http://<host>/.configuration

<host>: IP address (or DNS name) of your Innes Briva or PlugnCast Server.

- Log-in as "Super Administrator"
- Go to "Applets Manager" and click "Install" button.
- Select "Gesroom-calendar.saz" file and follow the installation steps.
- Result:





4 Configuration

The configuration file *configuration.xml* for **Gesroom-calendar** is located here:

<Innes Data Folder>\Server\.accounts\<domain>\.applets\.Gesroomcalendar\configuration.xml

- **♣** The **<Innes Data Folder>** is the data folder of Innes Briva or PlugnCast Server.
- The <domain> is your currently domain.

In these examples <domain> value is my_company.

Vista Example

C:\Users\Public\Documents\Innes\Server\.accounts\my_company\.applets\.Gesroom-calendar\configuration.xml

XP Example

C:\Documents and Settings\All Users\Documents\Innes\Server\.accounts\my_company\.applets\.Gesroom-calendar\configuration.xml

XML Syntax

After editing the configuration file make sure that it respects the XML specification.

The configuration file must be encoded in UTF-8. Be sure that you editing software don't changes the characters encoding.

Be careful with XML escaping (1). Observe the following entities:

code	character
<	<
>	>
&	&
'	1
"	II

• Disabled/enabled

```
<!-- Example 1: -->
<!--<scc:server>
...
</scc:server>-->
```

```
<!-- Example 1: -->
<scc:server>
...
</scc:server>
```

The configuration of Gesroom-calendar has two parts:

- Server Configuration
- Calendar Configuration

¹ For detailed information http://www.w3.org/TR/xml-entity-names/ or http://en.wikipedia.org/wiki/List of XML and HTML character entity references



4.1 Server Configuration

It is possible to configure multiple servers in the configuration file. If multiple servers are configured, be sure that the id attribute of each server is unique.

Within the tag <scc:servers>, take a look to the *Example 1* in the configuration file. In this example it is disabled. In order to enable it, remove the xml commentary tags at the beginning and the end of the block.

4.1.1 Server baseuri

The Gesroom base URL is defined as below:

http://safeware-demo.hds-group.com/ws_innes/WSINNES.asmx

4.1.2 Server username and password

The username/password to authenticate against the server.



Example

4.2 Calendar Configuration

Within the tag <scc:calendars>, take a look to the *Example 1* in the configuration file. This example is disabled, to enable it, remove the xml commentary tags at the beginning and the end of the block.

4.2.1 Mandatory parameters

4.2.1.1 *Id attribute*

The id attribute identifies a calendar. It is used lately as a reference to the calendar, we recommend assigning ids easy to remember.

4.2.1.2 Server attribute

The server attribute is a reference to a configured server. The server attribute is formed like this: url(#<serverid>).

Example: url(#myServer)

4.2.1.3 Plugncast / calendarui

Example

The text plugncast is free text but this name will need to be pasted inside url(#....)

Please see below below

```
<scc:calendar id="room" server="url(#plugncast)">
  <param name="resource">room.ics</param>
  </scc:calendar>
```

Please see calendar configuration

4.2.1.4 Resource

The resource parameter is the internal resource ID in the Gesroom system. For each calendar it is mandatory to define the resource(s) that are present. The procedure to follow to get the resource IDs is defined in the system requirement chapter.

Get a calendar with a single resource "room1"

Example:



All others parameters of the calendar are optional (or for advanced use).

4.2.2 Optional parameters (classic)

4.2.2.1 display all the meetings or a part of the meetings in the day

4.2.2.1.1 StartOffset StartRelated

StartOffset specifies whether the meetings can be displayed before they occur. Default value is zero.

StartRelated specifies whether the meeting can be displayed just before the meeting occurs (**event-start**) or at the beginning of the day (**day-start**).

startRelated	startOffset	Result
event-start	-600	The meeting is visible 600 sec before the event starts
day-start	0	The meetings are visible at the beginning of the day
		(00h00)

Attention: the value start-offset can be negative!

4.2.2.1.2 EndOffset / EndRelated

EndOffset specifies whether the meeting can be display after the event finished with n offset in second. Default value is zero.

EndRelated specifies whether the meeting need to be hidden immediately after they have finished (**event-end**) or only at the end of the day (**day-end**).

endRelated	endOffset	Result
event-end 600		Keep displayed the meetings until there are finished and
		600 seconds (10 minutes) after the end of the event.
day-end	0	Keep displayed the meetings until the end of the day (23:59:59)

Display 10 minutes before the meeting starts / hide 10 minutes after the meeting is finished

Attention the value startOffset can be negative



 Display all the meeting at the beginning of the day / hide 10 minutes after the meeting is finished

4.2.3 Optional parameters (advanced)

4.2.3.1 RequestWindow

Permits to define the requested time window for the ICS. If the value in days is 5, the ICS will contain the meeting for the next 5 days. In case network anomaly, MeetingRoom should be then able to display the meeting for the next 5 days anyway.

If not defined, the default value is 7.

4.2.3.2 CachePersistence

MeetingRoom is fetching through Gesroom applet by default ICS every 1 minutes. To avoid network traffic, it is possible to allow applet to update ICS every 5 minutes (or more). In this case, set a cache persistency to 300 (sec) to authorize MeetingRoom to use an existing ICS old of 5 minutes (or less).

Default value is 300 seconds

4.2.3.3 Label

The value of this parameter is used if no classroom resource is found

4.2.3.4 SendCacheOnServerError

The default value is false. If this parameter is enabled (value true), the connector sends the calendar from the cache (if present) in case of error while retrieving the new calendar information.

This example shows how to enable sendCacheOnServerError parameter.



5 Troubleshooting / debug

You can test the whole configuration accessing to the following address:

http://<your_domaine>/plugnCast/.applets/.gesroom-calendar/2ical.php?calendarId=<calendarId>

- The <host> is the IP address or DNS of your Innes Briva or PlugnCast Server.
- The **<calendarId>** is the reference of the calendar to test.

Example:

Ex: if you are on the PlugnCast server (or Briva server)

This address returns a meetingroom.ics file that contains the result of the configured calendar.

Please, if any error message is displayed check your configuration.

You can also test your configuration by using the console mode of the view.

It is possible to run the connector in debug mode by using the following URL

Ex: if you are on the PlugnCast server (or Briva server)

EX: http://localhost/plugnCast/.applets/.Gesroom-calendar/2ical.php?calendarId=all_rooms&debug=yes

This will show the connector running step by step which can allow more detailed troubleshooting.

Note when meeting are missing in ICS file:

 ${\it ICS file is filled properly when invoking get Meetings One Room And Attendee \ with}$

- start_Date = YYYY-MM-D1T00:00:00Z and end_Date = YYYY-MM-DD2T23:59:00Z
- this way of invokation is used by SignMeeting and MeetingRoom

ICS is filled is not filled properly (some meeting are missing for unknown reason) when invoking getMeetingsOneRoomAndAttendee with

- start_Date = YYYY-MM-D1T00:00:00Z and end_Date = YYYY-MM-DD2T00:00Z
- more investigation at Gesroom server end should be required to have more information on the root cause



6.1 Mapping

The following data mapping is used between the Gesroom XML and the ICS format.

Gesroom	ICS
UNID	UID
Room_Name	LOCATION
Title	SUMMARY
Description	DESCRIPTION
start_Date	DTSTART
end_Date	DTEND
Organizer	ORGANIZER
Attendees	ATTENDEES

6.2 Activation of Safeware Web services for Innes V1.10.10 when installing your Gesroom server

The **Safeware Web services for Innes V1.10.10** have to be installed on your Gesroom server when your server is installed and configured (contact your Safeware support) so that the server can work with INNES solutions.


In case this **Safeware Web Services for Innes V1.10.10** have not been installed by Safeware, this is a guide as example to install yourself:

Download Safeware Web service for Innes V1.10.10 since

http://www.innes.pro/fr/support

Briva > Bria calendar connector > Briva connectors > Gesroom > connector Gesroom Calendar PlugnCast and Screen Composer G2 > PlugnCast connectors > connector Gesroom Calendar


- Inflate the archive (which is a directory ws_innes)
- Copy this directory ws_innes at the root of directory inetpub of your Gesroom server
- In Windows **IIS (Internet Information Service)**, publish a Web service "WSINNES" whose path is the one of the directory **ws_innes** (previously copied) in application pool SAFEWARE,
 - o Go to Applications Pools and check that "SAFEWARE" application already exists
 - If not create a new one called "SAFEWARE" by a right click on Application pools




o Right click on Sites > Default Web site



Create an application





 When the installation of Safeware Web services for Innes V1.10.10 is finished, test it with the URL

http://localhost/ws_innes/wsinnes.asmx