# [MS-RDPRFX]: Remote Desktop Protocol: RemoteFX Codec Extension

#### **Intellectual Property Rights Notice for Open Specifications Documentation**

- **Technical Documentation.** Microsoft publishes Open Specifications documentation for protocols, file formats, languages, standards as well as overviews of the interaction among each of these technologies.
- **Copyrights.** This documentation is covered by Microsoft copyrights. Regardless of any other terms that are contained in the terms of use for the Microsoft website that hosts this documentation, you may make copies of it in order to develop implementations of the technologies described in the Open Specifications and may distribute portions of it in your implementations using these technologies or your documentation as necessary to properly document the implementation. You may also distribute in your implementation, with or without modification, any schema, IDL's, or code samples that are included in the documentation. This permission also applies to any documents that are referenced in the Open Specifications.
- No Trade Secrets. Microsoft does not claim any trade secret rights in this documentation.
- Patents. Microsoft has patents that may cover your implementations of the technologies described in the Open Specifications. Neither this notice nor Microsoft's delivery of the documentation grants any licenses under those or any other Microsoft patents. However, a given Open Specification may be covered by Microsoft Open Specification Promise or the Community Promise. If you would prefer a written license, or if the technologies described in the Open Specifications are not covered by the Open Specifications Promise or Community Promise, as applicable, patent licenses are available by contacting iplq@microsoft.com.
- Trademarks. The names of companies and products contained in this documentation may be covered by trademarks or similar intellectual property rights. This notice does not grant any licenses under those rights. For a list of Microsoft trademarks, visit www.microsoft.com/trademarks.
- **Fictitious Names.** The example companies, organizations, products, domain names, email addresses, logos, people, places, and events depicted in this documentation are fictitious. No association with any real company, organization, product, domain name, email address, logo, person, place, or event is intended or should be inferred.

**Reservation of Rights.** All other rights are reserved, and this notice does not grant any rights other than specifically described above, whether by implication, estoppel, or otherwise.

**Tools.** The Open Specifications do not require the use of Microsoft programming tools or programming environments in order for you to develop an implementation. If you have access to Microsoft programming tools and environments you are free to take advantage of them. Certain Open Specifications are intended for use in conjunction with publicly available standard specifications and network programming art, and assumes that the reader either is familiar with the aforementioned material or has immediate access to it.

# **Revision Summary**

Date	Revision History	Revision Class	Comments
04/23/2010	0.1	Major	First Release.
06/04/2010	1.0	Major	Updated and revised the technical content.
07/16/2010	1.0	No change	No changes to the meaning, language, or formatting of the technical content.
08/27/2010	2.0	Major	Significantly changed the technical content.
10/08/2010	3.0	Major	Significantly changed the technical content.
11/19/2010	4.0	Major	Significantly changed the technical content.
01/07/2011	5.0	Major	Significantly changed the technical content.
02/11/2011	6.0	Major	Significantly changed the technical content.
03/25/2011	7.0	Major	Significantly changed the technical content.
05/06/2011	8.0	Major	Significantly changed the technical content.
06/17/2011	9.0	Major	Significantly changed the technical content.
09/23/2011	10.0	Major	Significantly changed the technical content.
12/16/2011	11.0	Major	Significantly changed the technical content.
03/30/2012	12.0	Major	Significantly changed the technical content.
07/12/2012	13.0	Major	Significantly changed the technical content.
10/25/2012	14.0	Major	Significantly changed the technical content.
01/31/2013	15.0	Major	Significantly changed the technical content.
08/08/2013	15.0	No change	No changes to the meaning, language, or formatting of the technical content.
11/14/2013	15.0	No change	No changes to the meaning, language, or formatting of the technical content.
02/13/2014	16.0	Major	Significantly changed the technical content.
05/15/2014	16.0	No change	No changes to the meaning, language, or formatting of the technical content.

## **Contents**

1	Introduction	6
	1.1 Glossary	6
	1.2 References	
	1.2.1 Normative References	6
	1.2.2 Informative References	
	1.3 Protocol Overview (Synopsis)	7
	1.3.1 RemoteFX Codec	7
	1.3.1.1 Message Flows	8
	1.4 Relationship to Other Protocols	10
	1.5 Prerequisites/Preconditions	10
	1.6 Applicability Statement	11
	1.7 Versioning and Capability Negotiation	11
	1.8 Vendor-Extensible Fields	
	1.9 Standards Assignments	
	•	
2	Messages	12
	2.1 Transport	12
	2.2 Message Syntax	12
	2.2.1 Capabilities Messages	
	2.2.1.1 TS_RFX_CLNT_CAPS_CONTAINER	12
	2.2.1.1.1 TS_RFX_CAPS	13
	2.2.1.1.1.1 TS_RFX_CAPSET	13
	2.2.1.1.1.1.1 TS_RFX_ICAP	14
	2.2.1.2 TS_RFX_SRVR_CAPS_CONTAINER	15
	2.2.1.3 TS_FRAME_ACKNOWLEDGE_CAPABILITYSET	15
	2.2.2 Encode Messages	16
	2.2.2.1 Common Data Types	
	2.2.2.1.1 TS_RFX_BLOCKT	16
	2.2.2.1.2 TS_RFX_CODEC_CHANNELT	17
	2.2.2.1.3 TS_RFX_CHANNELT	18
	2.2.2.1.4 TS_RFX_CODEC_VERSIONT	18
	2.2.2.1.5 TS_RFX_CODEC_QUANT	18
	2.2.2.1.6 TS_RFX_RECT	19
	2.2.2.2 Encode Header Messages	20
	2.2.2.2.1 TS_RFX_SYNC	20
	2.2.2.2.2 TS_RFX_CODEC_VERSIONS	20
	2.2.2.2.3 TS_RFX_CHANNELS	21
	2.2.2.2.4 TS_RFX_CONTEXT	21
	2.2.2.3 Encode Data Messages	22
	2.2.2.3.1 TS_RFX_FRAME_BEGIN	22
	2.2.2.3.2 TS_RFX_FRAME_END	23
	2.2.2.3.3 TS_RFX_REGION	23
	2.2.2.3.4 TS_RFX_TILESET	24
	2.2.2.3.4.1 TS_RFX_TILE	26
	2.2.3 Control Messages	
	2.2.3.1 TS_FRAME_ACKNOWLEDGE_PDU	
_	Protocol Details	
	3.1 Common Details	
	3.1.1 Abstract Data Model	30

3.1.1.1 State Machine	
3.1.2 Timers	
3.1.3 Initialization	
3.1.4 Higher-Layer Triggered Events	32
3.1.5 Processing Events and Sequencing Rules	32
3.1.5.1 Processing the TS_RFX_CLNT_CAPS_CONTAINER Message	
3.1.7 Other Local Events	
3.1.8 RemoteFX Algorithm	
3.1.8.1 Encoding	
3.1.8.1.1 Input Tiling.	
3.1.8.1.2 Differencing (Optional)	
3.1.8.1.3 Color Conversion (RGB to YCbCr)	
3.1.8.1.4 DWT	
3.1.8.1.5 Quantization	
3.1.8.1.6 Linearization	
3.1.8.1.7 RLGR Entropy Encoding	
3.1.8.1.7.1 RLGR1	
3.1.8.1.7.2 RLGR3	
3.1.8.1.7.3 RLGR1/RLGR3 Pseudocode	
3.1.8.1.7.3.1 RLGR1/RLGR3 Decode	
3.1.8.1.7.3.2 RLGR1/RLGR3 Encode	
3.1.8.2 Decoding	
3.1.8.2.1 RLGR Entropy Decoding	
3.1.8.2.2 Sub-Band Reconstruction	
3.1.8.2.3 Dequantization	
3.1.8.2.4 Inverse DWT	
2.1.0.2 E. Colon Communica (VCh Cu to DCD)	40
3.1.8.2.5 Color Conversion (YCbCr to RGB)	
3.1.8.2.6 Reconstructed Frame	48
3.1.8.2.6 Reconstructed Frame	48 48
3.1.8.2.6 Reconstructed Frame	48 48
3.1.8.2.6 Reconstructed Frame	48 48 48
3.1.8.2.6 Reconstructed Frame	48 48 48 <b>51</b>
3.1.8.2.6 Reconstructed Frame	48 48 48 <b>51</b> 51
3.1.8.2.6 Reconstructed Frame	48 48 48 <b>51</b> 51 52
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages	48 48 48 <b>51</b> 51 52 52
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages	48 48 48 <b>51</b> 51 52 52 53
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages	48 48 48 <b>51</b> 51 52 52 53 54
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence	48 48 48 <b>51</b> 51 52 52 53 54 57
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message.	48 48 48 <b>51</b> 51 52 52 53 54 57
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message. 4.2.4.2 Entropy Decoded Data.	48 48 48 <b>51</b> 52 53 54 57 61
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence 4.2.4.1 Input TS_RFX_TILESET Message 4.2.4.2 Entropy Decoded Data 4.2.4.2.1 Y Component Data	48 48 48 51 52 53 54 57 61 62
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence 4.2.4.1 Input TS_RFX_TILESET Message 4.2.4.2 Entropy Decoded Data 4.2.4.2.1 Y Component Data 4.2.4.2.2 Cb Component Data	48 48 48 51 51 52 53 54 57 61 62 66
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence 4.2.4.1 Input TS_RFX_TILESET Message 4.2.4.2 Entropy Decoded Data 4.2.4.2.1 Y Component Data 4.2.4.2.2 Cb Component Data 4.2.4.2.3 Cr Component Data	48 48 48 51 52 52 53 54 57 61 62 66 71
3.1.8.2.6 Reconstructed Frame 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence 4.2.4.1 Input TS_RFX_TILESET Message 4.2.4.2 Entropy Decoded Data 4.2.4.2.1 Y Component Data 4.2.4.2.2 Cb Component Data	48 48 48 51 52 52 53 54 57 61 62 66 71 75
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples	48 48 48 51 52 52 53 54 57 61 62 66 71 75
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples.  4.1 Sample Use Case.  4.2 Annotated RemoteFX Messages.  4.2.1 Capabilities Messages.  4.2.2 Encode Header Messages.  4.2.3 Encode Data Messages.  4.2.4 Sample Decode Data Flow Sequence.  4.2.4.1 Input TS_RFX_TILESET Message.  4.2.4.2 Entropy Decoded Data.  4.2.4.2.1 Y Component Data.  4.2.4.2.2 Cb Component Data.  4.2.4.2.3 Inverse Quantization/DWT.  4.2.4.3.1 Level 3 Sub-bands.	48 48 48 51 52 52 53 54 57 61 62 66 71 75 75
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message. 4.2.4.2 Entropy Decoded Data. 4.2.4.2.1 Y Component Data. 4.2.4.2.2 Cb Component Data. 4.2.4.2.3 Cr Component Data. 4.2.4.3 Inverse Quantization/DWT. 4.2.4.3.1 Level 3 Sub-bands. 4.2.4.3.1.1 LL3.	48 48 48 51 52 53 54 57 61 62 66 71 75 75
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples 4.1 Sample Use Case 4.2 Annotated RemoteFX Messages 4.2.1 Capabilities Messages 4.2.2 Encode Header Messages 4.2.3 Encode Data Messages 4.2.4 Sample Decode Data Flow Sequence 4.2.4.1 Input TS_RFX_TILESET Message 4.2.4.2 Entropy Decoded Data 4.2.4.2.1 Y Component Data 4.2.4.2.1 Y Component Data 4.2.4.2.2 Cb Component Data 4.2.4.2.3 Inverse Quantization/DWT 4.2.4.3.1 Level 3 Sub-bands 4.2.4.3.1.1 LL3 4.2.4.3.1.2 HL3 4.2.4.3.1.3 LH3 4.2.4.3.1.4 HH3	48 48 51 51 52 53 54 57 61 62 66 71 75 76 76
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message. 4.2.4.2 Entropy Decoded Data. 4.2.4.2 Entropy Decoded Data. 4.2.4.2 Cb Component Data. 4.2.4.2.3 Cr Component Data. 4.2.4.2.3 Inverse Quantization/DWT. 4.2.4.3 Inverse Quantization/DWT. 4.2.4.3.1.1 LL3. 4.2.4.3.1.2 HL3. 4.2.4.3.1.3 LH3. 4.2.4.3.1.4 HH3. 4.2.4.3.1.5 Inverse DWT-X (LL3 - HL3).	48 48 51 51 52 53 54 57 61 62 66 71 77 76 76 77
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message. 4.2.4.2 Entropy Decoded Data. 4.2.4.2.1 Y Component Data. 4.2.4.2.1 Y Component Data. 4.2.4.2.3 Cr Component Data. 4.2.4.2.3 Inverse Quantization/DWT. 4.2.4.3.1 Level 3 Sub-bands. 4.2.4.3.1.1 LL3. 4.2.4.3.1.2 HL3. 4.2.4.3.1.3 LH3. 4.2.4.3.1.4 HH3. 4.2.4.3.1.5 Inverse DWT-X (LL3 - HL3). 4.2.4.3.1.6 Inverse DWT-X (LH3 - HH3).	48 48 51 51 52 53 54 57 61 62 66 71 77 77 77
3.1.8.2.6 Reconstructed Frame. 3.1.8.3 RemoteFX Stream. 3.1.8.3.1 Encode Message Sequencing.  4 Protocol Examples. 4.1 Sample Use Case. 4.2 Annotated RemoteFX Messages. 4.2.1 Capabilities Messages. 4.2.2 Encode Header Messages. 4.2.3 Encode Data Messages. 4.2.4 Sample Decode Data Flow Sequence. 4.2.4.1 Input TS_RFX_TILESET Message. 4.2.4.2 Entropy Decoded Data. 4.2.4.2 Entropy Decoded Data. 4.2.4.2 Cb Component Data. 4.2.4.2.3 Cr Component Data. 4.2.4.2.3 Inverse Quantization/DWT. 4.2.4.3 Inverse Quantization/DWT. 4.2.4.3.1.1 LL3. 4.2.4.3.1.2 HL3. 4.2.4.3.1.3 LH3. 4.2.4.3.1.4 HH3. 4.2.4.3.1.5 Inverse DWT-X (LL3 - HL3).	48 48 51 51 52 53 54 57 61 62 66 71 77 77 77

4.2.4.3.2 Level 2 Sub-bands	78
4.2.4.3.2.1 LL2	78
4.2.4.3.2.2 HL2	78
4.2.4.3.2.3 LH2	79
4.2.4.3.2.4 HH2	
4.2.4.3.2.5 Inverse DWT-X (LL2 – HL2)	80
4.2.4.3.2.6 Inverse DWT-X (LH2 - HH2)	
4.2.4.3.2.7 Inverse DWT-Y (L1 – H1)	83
4.2.4.3.3 Level 1 Sub-bands	85
4.2.4.3.3.1 LL1	85
4.2.4.3.3.2 HL1	85
4.2.4.3.3.3 LH1	88
4.2.4.3.3.4 HH1	
4.2.4.3.3.5 Inverse DWT-X (LL1 - HL1)	
4.2.4.3.3.6 Inverse DWT-X (LH1 - HH1)	
4.2.4.3.3.7 Inverse DWT-Y (L0 – H0)	
4.2.4.3.4 Reconstructed Y Component	
4.2.4.3.5 Reconstructed Cb Component	
4.2.4.3.6 Reconstructed Cr Component	
4.2.4.4 Inverse Color Conversion	
4.2.4.5 Decoded Image	137
5 Security	120
5.1 Security Considerations for Implementers	
5.2 Index of Security Parameters	
5.2 Index of Security Parameters	130
6 Appendix A: Product Behavior	139
7 Change Tracking	140
8 Index	141

## 1 Introduction

The Remote Desktop Protocol: RemoteFX Codec Extension is an extension to the Remote Desktop Protocol: Basic Connectivity and Graphics Remoting (as specified in <a href="MS-RDPBCGR">[MS-RDPBCGR</a>]). The RemoteFX Codec Extension specifies a lossy image codec that can be used to encode screen images by using efficient and effective compression.

Sections 1.8, 2, and 3 of this specification are normative and can contain the terms MAY, SHOULD, MUST, MUST NOT, and SHOULD NOT as defined in RFC 2119. Sections 1.5 and 1.9 are also normative but cannot contain those terms. All other sections and examples in this specification are informative.

#### 1.1 Glossary

The following terms are defined in [MS-GLOS]:

#### little-endian

The following terms are specific to this document:

**blit:** Also known as block image transfer. An operation in which a rectangular block of pixels in a source image is copied onto a destination image.

**discrete wavelet transform (DWT):** A discrete wavelet transform is a mathematical procedure that can be used to derive a discrete representation of a signal.

**entropy coding:** A lossless data compression scheme used to generate compression codes for input symbols based on their statistical properties.

quantization: A technique used to reduce a range of values to a single representative value.

**tile-based transform:** A transform technique in which an input image is segmented into a grid of disjoint tiles and the transform is then applied separately to each individual tile.

**YCbCr color space:** A color space where each color is represented as a triplet (Y,Cb,Cr), where Y stands for the Luma (brightness) component and Cb,Cr stand for the two Chroma (color) components.

MAY, SHOULD, MUST, SHOULD NOT, MUST NOT: These terms (in all caps) are used as described in <a href="[RFC2119">[RFC2119]</a>. All statements of optional behavior use either MAY, SHOULD, or SHOULD NOT.

#### 1.2 References

References to Microsoft Open Specifications documentation do not include a publishing year because links are to the latest version of the documents, which are updated frequently. References to other documents include a publishing year when one is available.

#### 1.2.1 Normative References

We conduct frequent surveys of the normative references to assure their continued availability. If you have any issue with finding a normative reference, please contact <a href="mailto:dochelp@microsoft.com">dochelp@microsoft.com</a>. We will assist you in finding the relevant information.

6 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

[ARLGR] Malvar, H.S., "Adaptive Run-Length / Golomb-Rice Encoding of Quantized Generalized Gaussian Sources with Unknown Statistics", Proceedings of the Data Compression Conference, 2006 (DCC 2006) pp. 23 - 32, March 2006,

http://ieeexplore.ieee.org/stamp/stamp.jsp?arnumber=1607237

[MS-RDPBCGR] Microsoft Corporation, "Remote Desktop Protocol: Basic Connectivity and Graphics Remoting".

[RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997, <a href="http://www.rfc-editor.org/rfc/rfc2119.txt">http://www.rfc-editor.org/rfc/rfc2119.txt</a>

[T123] ITU-T, "Network-Specific Data Protocol Stacks for Multimedia Conferencing", Recommendation T.123, May 1999, http://www.itu.int/rec/T-REC-T.123/en

**Note** There is a charge to download the specification.

[T125] ITU-T, "Multipoint Communication Service Protocol Specification", Recommendation T.125, February 1998, <a href="http://www.itu.int/rec/T-REC-T.125-199802-I/en">http://www.itu.int/rec/T-REC-T.125-199802-I/en</a>

**Note** There is a charge to download the specification.

[X224] ITU-T, "Information technology - Open Systems Interconnection - Protocol for Providing the Connection-Mode Transport Service", Recommendation X.224, November 1995, <a href="http://www.itu.int/rec/T-REC-X.224-199511-I/en">http://www.itu.int/rec/T-REC-X.224-199511-I/en</a>

**Note** There is a charge to download the specification.

#### 1.2.2 Informative References

[MS-GLOS] Microsoft Corporation, "Windows Protocols Master Glossary".

## 1.3 Protocol Overview (Synopsis)

The Remote Desktop Protocol: RemoteFX Codec Extension reduces the bandwidth associated with desktop remoting by efficiently compressing images. This is achieved by using the RemoteFX codec. The following sections provide an overview of this codec.

#### 1.3.1 RemoteFX Codec

One of the core requirements of desktop remoting is the ability to efficiently compress server-side screen images so that they can be transported over a network and displayed on a client screen. Any codec used for this purpose needs to be able to deliver effective compression (to reduce network bandwidth requirements) and operate with low-latency (to enable efficient interactions with remoted content). A typical desktop screen contains textual content (synthetic images) along with video and photographic content (natural images). Given the sensitivity of the human eye to the sharp features present in textual content, any applied compression has to be visually lossless; otherwise the text will appear blurred.

The RemoteFX codec has been designed to achieve efficient compression, satisfying the goals of high quality and low latency while using a modest amount of computing resources. It is a **tile-based transform** codec. The transform chosen was a **discrete wavelet transform (DWT)** because it enables superior compression performance when compressing textual bitmap regions at high quality. The **entropy coding** is performed using the Run-Length Golomb-Rice Coder (RLGR) ([ARLGR]] section 3), which yields compression gains at relatively low computing requirements. The core functional blocks of the RemoteFX codec are shown in the following diagram.




Figure 1: Core functional blocks of the RemoteFX codec

## 1.3.1.1 Message Flows

RemoteFX codec messages must be transported in order over a lossless transport such as TCP/IP. The message syntax has been designed with this prerequisite.

There are two types of messages: (1) capability messages sent from the client to the server; and (2) encode stream messages sent from the server to the client. The encode stream messages can be broadly categorized as header or data messages. The syntax of each message is described in detail in section 2. Processing events and sequencing rules are described in section 3.

The message sequence is depicted in the following diagram. Note that the messages in this diagram are encapsulated in RDP wire structures (described in [MS-RDPBCGR] section 2.2) when sent on the wire – for the sake of simplicity only the RemoteFX messages are shown. The encapsulating RDP structures are referenced in sections  $\underline{2}$  and  $\underline{3}$  when describing the structure and processing of the RemoteFX messages.




Figure 2: The RemoteFX message sequence

The client initiates the session by sending a TS\_RFX\_CAPS Capabilities message (section 2.2.1.1). This is the only message sent from the client to the server; it lists the client-side support and preferences for various RemoteFX codec properties.

The server initializes its encoding state based on the client Capabilities message. It starts the encoding stream (section 2.2.2) by sending a sequence of Header Messages (section 2.2.2) that inform the client of the RemoteFX properties selected by the server:

- 1. The TS\_RFX\_SYNC message (section <u>2.2.2.2.1</u>) contains the RemoteFX magic number and the version of the wire format.
- The TS\_RFX\_CODEC\_VERSIONS message (section <u>2.2.2.2.2</u>) contains the version of the RemoteFX codec.
- 3. The TS\_RFX\_CHANNELS message (section <a href="2.2.2.2.3">2.2.2.3</a>) lists the channel or multi-monitor information.

4. The TS\_RFX\_CONTEXT message (section <a href="2.2.2.2.4">2.2.2.4</a>) contains the encoding properties of the stream.

The header messages are followed by the Data messages (section 2.2.2.3), which represent the sequence of encoded frames in the stream:

- 1. The TS\_RFX\_FRAME\_BEGIN and TS\_RFX\_FRAME\_END messages (sections <u>2.2.2.3.1</u> and <u>2.2.2.3.2</u> respectively) are used to demarcate an encoded frame.
- 2. The TS\_RFX\_REGION message (section <u>2.2.2.3.3</u>) contains the list of rectangles that have been encoded.
- 3. The TS\_RFX\_TILESET message (section <u>2.2.2.3.4</u>) encapsulates the list of tiles that have been encoded.

## 1.4 Relationship to Other Protocols

This protocol extends the Remote Desktop Protocol: Basic Connectivity and Graphics Remoting [MS-RDPBCGR] by adding advanced compression techniques.

## 1.5 Prerequisites/Preconditions

The following capabilities are mandatory when used with RemoteFX:

- The client MUST support fast-path graphics output ([MS-RDPBCGR] section 2.2.9.1.2) and acknowledge this support by specifying the FASTPATH\_OUTPUT\_SUPPORTED (0x0001) flag in the General Capability Set ([MS-RDPBCGR] section 2.2.7.1.1).
- The client MUST send the Multifragment Update Capability Set ([MS-RDPBCGR] section 2.2.7.2.6). The MaxRequestSize field in the client-to-server Multifragment Update Capability Set MUST be set to a value greater than or equal to the value in the MaxRequestSize field of the server-to-client Multifragment Update Capability Set. The client-to-server Multifragment Update Capability Set is transported in the Confirm Active PDU as specified in [MS-RDPBCGR] section 2.2.1.13.2, and the server-to-client Multifragment Update Capability Set is transported in the Demand Active PDU as specified in [MS-RDPBCGR] section 2.2.1.13.1.
- The client MUST send the <u>Large Pointer Capability Set</u> (<u>[MS-RDPBCGR]</u> section 2.2.7.2.7) and the LARGE\_POINTER\_FLAG\_96x96 (0x00000001) MUST be present in the <u>largePointerSupportFlags</u> field.
- If the <u>Revision 2 Bitmap Cache Capability Set</u> (<u>[MS-RDPBCGR]</u> section 2.2.7.1.4.2) is sent by the client, then the ALLOW\_CACHE\_WAITING\_LIST\_FLAG (0x0002) MUST be present in the **CacheFlags** field.
- The client MUST support the Stream Surface Bits Surface Command ([MS-RDPBCGR] section 2.2.9.2.2). Support for this surface command MUST be advertised in the Surface Commands Capability Set ([MS-RDPBCGR] section 2.2.7.2.9).
- The client MUST support a color depth of 32 bits per pixel. This means that the RNS\_UD\_32BPP\_SUPPORT (0x0008) flag must be set in the **supportedColorDepths** field of the Client Core Data structure ([MS-RDPBCGR] section 2.2.1.3.2).

The TS FRAME ACKNOWLEDGE CAPABILITYSET (section 2.2.1.3) SHOULD<1> be sent by the client. Furthermore, if the **connectionType** field of the Client Core Data ([MS-RDPBCGR] section 2.2.1.3.2) is set to any value other than CONNECTION\_TYPE\_LAN (0x06), then the RemoteFX server SHOULD NOT<2> indicate that the RemoteFX codec is supported, that is, none of the

TS BITMAPCODEC ([MS-RDPBCGR] section 2.2.7.2.10.1.1) structures included in the **bitmapCodecArray** field of the TS BITMAPCODECS ([MS-RDPBCGR] section 2.2.7.2.10) structure have the **codecGUID** field set to CODEC\_GUID\_REMOTEFX.

#### 1.6 Applicability Statement

This protocol is applicable in situations in which it is necessary to optimize the bandwidth required for graphics remoting. The advanced compression techniques specified in this document enable the efficient transfer of server-side images and video.

## 1.7 Versioning and Capability Negotiation

This protocol builds on the basic Remote Desktop Protocol [MS-RDPBCGR]. The features provided by this extension are negotiated during the capabilities negotiation phase of the RDP connection sequence (see [MS-RDPBCGR] section 1.3.1.1). In effect, this extension merely expands the set of capabilities used by the base RDP. (RDP versioning and capability negotiation is described in [MS-RDPBCGR] section 1.7.)

Some capabilities, which are specified as optional in [MS-RDPBCGR] section 2.2.7.2, are mandatory when used with RemoteFX. These capabilities are described in detail in section 2.1.

## 1.8 Vendor-Extensible Fields

None.

#### 1.9 Standards Assignments

None.

## 2 Messages

## 2.1 Transport

This protocol is an extension to the <u>Remote Desktop Protocol: Basic Connectivity and Graphics Remoting Specification</u> and all packets are tunneled within the RDP transport (<u>[MS-RDPBCGR]</u> section 2.1).


## 2.2 Message Syntax

All multiple-byte fields within a message MUST be marshaled in **little-endian** byte order, unless otherwise specified.

#### 2.2.1 Capabilities Messages

#### 2.2.1.1 TS\_RFX\_CLNT\_CAPS\_CONTAINER

The TS\_RFX\_CLNT\_CAPS\_CONTAINER structure is the top-level client capability container that wraps a TS\_RFX\_CAPS (section 2.2.1.1.1) structure and is sent from the client to the server. It is encapsulated in the **codecProperties** field of the <u>Bitmap Codec</u> ([MS-RDPBCGR] section 2.2.7.2.10.1.1) structure, which is ultimately encapsulated in the <u>Bitmap Codecs Capability Set</u> ([MS-RDPBCGR] section 2.2.7.2.10), which is encapsulated in a client-to-server Confirm Active PDU ([MS-RDPBCGR] section 2.2.1.13.2).



**length (4 bytes):** A 32-bit, unsigned integer. Specifies the combined size, in bytes, of the **length, captureFlags, capsLength**, and **capsData** fields.

**captureFlags (4 bytes):** A 32-bit, unsigned integer. A collection of flags that allow a client to control how data is captured and transmitted by the server.


Flag	Meaning							
CARDP_CAPS_CAPTURE_NON_CAC 0x00000001	The client supports mixing RemoteFX data with data compressed by other codecs. The set of other codecs supported by the client will be negotiated using the Bitmap Codecs Capability Set ( <a href="MS-RDPBCGR">[MS-RDPBCGR</a> ] section 2.2.7.2.10).							

capsLength (4 bytes): A 32-bit, unsigned integer. Specifies the size, in bytes, of the capsData field.

**capsData (variable):** A variable-sized field that contains a <u>TS\_RFX\_CAPS (section 2.2.1.1.1)</u> structure.

## 2.2.1.1.1 TS\_RFX\_CAPS

The TS\_RFX\_CAPS structure contains information about the decoder capabilities.



**blockType (2 bytes):** A 16-bit, unsigned integer. Specifies the data block type. This field MUST be set to CBY\_CAPS (0xCBC0).


**blockLen (4 bytes):** A 32-bit, unsigned integer. Specifies the combined size, in bytes, of the **blockType**, **blockLen**, and **numCapsets** fields. This field MUST be set to 0x0008.


**numCapsets (2 bytes):** A 16-bit, unsigned integer. Specifies the number of <u>TS\_RFX\_CAPSET</u> (<u>section 2.2.1.1.1.1</u>) structures contained in the **capsetsData** field. This field MUST be set to 0x0001.

**capsetsData (variable):** A variable-sized array of TS\_RFX\_CAPSET (section 2.2.1.1.1.1) structures. The structures in this array MUST be packed on byte boundaries. The **blockType** and **blockLen** fields of each TS\_RFX\_CAPSET structure identify the type and size of the structure.

## 2.2.1.1.1.1 TS\_RFX\_CAPSET

The TS\_RFX\_CAPSET structure contains the capability information specific to the RemoteFX codec. It contains a variable number of <u>TS\_RFX\_ICAP (section 2.2.1.1.1.1.1)</u> structures that are used to configure the encoder state.






- **blockType (2 bytes):** A 16-bit, unsigned integer. Specifies the data block type. This field MUST be set to CBY\_CAPSET (0xCBC1).
- **blockLen (4 bytes):** A 32-bit, unsigned integer. Specifies the combined size, in bytes, of the **blockType**, **blockLen**, **codecId**, **capsetType**, **numIcaps**, **icapLen**, and **icapsData** fields.
- **codecId (1 byte):** An 8-bit, unsigned integer. Specifies the codec ID. This field MUST be set to 0x01.
- **capsetType (2 bytes):** A 16-bit, unsigned integer. This field MUST be set to CLY\_CAPSET (0xCFC0).
- **numIcaps (2 bytes):** A 16-bit, unsigned integer. The number of TS\_RFX\_ICAP structures contained in the **icapsData** field.
- **icapLen (2 bytes):** A 16-bit, unsigned integer. Specifies the size, in bytes, of each TS\_RFX\_ICAP structure contained in the **icapsData** field.
- **icapsData (variable):** A variable-length array of TS\_RFX\_ICAP (section 2.2.1.1.1.1.1) structures. Each structure MUST be packed on byte boundaries. The size of each TS\_RFX\_ICAP structure within the array is specified in the **icapLen** field.

## 2.2.1.1.1.1.1 TS\_RFX\_ICAP

The TS RFX ICAP structure specifies the set of codec properties that the decoder supports.



- **version (2 bytes):** A 16-bit, unsigned integer. Specifies the codec version. This field MUST be set to CLW\_VERSION\_1\_0 (0x0100), to indicate protocol version 1.0.
- **tileSize (2 bytes):** A 16-bit, signed integer. Specifies the width and height of a tile. This field MUST be set to CT\_TILE\_64x64 (0x0040), indicating that a tile is 64 x 64 pixels.
- flags (1 byte): An 8-bit, unsigned integer. Specifies operational flags.

Flag	Meaning
CODEC_MODE 0x02	When this flag is set, it indicates that only image mode is supported by the decoder, and therefore, the codec MUST operate in image mode. When this flag is not set, it indicates that both the image mode and the video mode of the codec are supported by the decoder and the codec MUST operate in video mode.

When operating in image mode, the encode headers messages (section <u>2.2.2.2</u>) MUST always precede an encoded frame. When operating in video mode, the header messages MUST be present at the beginning of the stream and are optional elsewhere.

**colConvBits (1 byte):** An 8-bit, unsigned integer. Specifies the color conversion transform. This field MUST be set to CLW\_COL\_CONV\_ICT (0x1), and the transformation is by the equations in sections 3.1.8.1.3 and 3.1.8.2.5.


**transformBits (1 byte):** An 8-bit, unsigned integer. Specifies the DWT. This field MUST be set to CLW\_XFORM\_DWT\_53\_A (0x1), the DWT transform given by the lifting equations for the DWT shown in section 3.1.8.1.4 and by the lifting equations for the inverse DWT shown in section 3.1.8.2.4.

**entropyBits (1 byte):** An 8-bit, unsigned integer. Specifies the entropy algorithm. This field MUST be set to one of the following values.

Value	Meaning						
CLW_ENTROPY_RLGR1 0x01	RLGR algorithm as described in 3.1.8.1.7.1.						
CLW_ENTROPY_RLGR3 0x04	RLGR algorithm as described in section 3.1.8.1.7.2.						

## 2.2.1.2 TS\_RFX\_SRVR\_CAPS\_CONTAINER


The TS\_RFX\_SRVR\_CAPS\_CONTAINER structure is the top-level server capability container, which is sent from the server to the client. It is encapsulated in the **codecProperties** field of the Bitmap Codec structure ([MS-RDPBCGR] section 2.2.7.2.10.1.1), which is ultimately encapsulated in the Bitmap Codecs Capability Set ([MS-RDPBCGR] section 2.2.7.2.10). The Bitmap Codecs Capability Set is encapsulated in a server-to-client Demand Active PDU ([MS-RDPBCGR] section 2.2.1.13.1).



**reserved (variable):** A variable-sized array of bytes. All the bytes in this field MUST be set to 0. The size of the field is given by the corresponding **codecPropertiesLength** field of the parent TS BITMAPCODEC, as specified in [MS-RDPBCGR] section 2.2.7.2.10.1.1 Bitmap Codecs Capability Set.

#### 2.2.1.3 TS\_FRAME\_ACKNOWLEDGE\_CAPABILITYSET

The TS\_FRAME\_ACKNOWLEDGE\_CAPABILITYSET structure advertises support for frame acknowledgment using the <u>TS\_FRAME\_ACKNOWLEDGE\_PDU (section 2.2.3.1)</u> structure. This capability is sent by both the client and the server and is encapsulated in a server-to-client <u>Demand Active PDU ([MS-RDPBCGR]</u> section 2.2.1.13.1) or a client-to-server <u>Confirm Active PDU ([MS-RDPBCGR]</u> section 2.2.1.13.2).



**capabilitySetType (2 bytes):** A 16-bit unsigned integer. The type of capability set. This field MUST be set to CAPSETTYPE\_FRAME\_ACKNOWLEDGE (0x001E).

**lengthCapability (2 bytes):** A 16-bit unsigned integer. The length, in bytes, of the capability data.

maxUnacknowledgedFrameCount (4 bytes): A 32-bit unsigned integer. When sent by the server, it MAY be set to 0, in which case it simply advertises the server's ability to receive and process the TS\_FRAME\_ACKNOWLEDGE\_PDU (section 2.2.3.1). If it is not set to 0, it can be used by the client as a hint that indicates the number of in-flight TS\_FRAME\_ACKNOWLEDGE\_PDUs that the server is prepared to accept. When sent by the client, it provides a hint to the server as to how many in-flight frames the client can buffer.

client, it provides a hint to the server as to how many in-flight frames the client can buffer. Note that if the server chooses to have more in-flight frames than this number specifies, it is possible that the client could be overloaded with frame data. The client MAY set this field to 0, but this behavior SHOULD be avoided because it provides very little information to the server other than that the client acknowledges frames.


## 2.2.2 Encode Messages

An encoded RemoteFX stream comprises a sequence of encode messages. The sequencing and encapsulation of these messages are described in section 3.1.8.3.1.

#### 2.2.2.1 Common Data Types

## 2.2.2.1.1 TS\_RFX\_BLOCKT

The TS\_RFX\_BLOCKT structure identifies the type of an encode message and specifies the size of the message.



**blockType (2 bytes):** A 16-bit, unsigned integer. Specifies the data block type. This field MUST be set to one of the following values.


Value	Meaning
CBT_TILE 0xCAC3	A <b>TS_RFX_TILE</b> (section 2.2.2.3.4.1) structure.
CBY_CAPS	A TS_RFX_CAPS (2.2.1.1.1) structure.

Value	Meaning
0xCBC0	
CBY_CAPSET 0xCBC1	A TS_RFX_CAPSET (2.2.1.1.1.1) structure.
WBT_SYNC 0xCCC0	A <b>TS_RFX_SYNC</b> (section <u>2.2.2.2.1</u> ) structure.
WBT_CODEC_VERSIONS 0xCCC1	A <b>TS_RFX_CODEC_VERSIONS</b> (section <u>2.2.2.2.2</u> ) structure.
WBT_CHANNELS 0xCCC2	A <b>TS_RFX_CHANNELS</b> (section <u>2.2.2.2.3</u> ) structure.

**blockLen (4 bytes):** A 32-bit, unsigned integer. Specifies the size, in bytes, of the data block. This size includes the size of the **blockType** and **blockLen** fields, as well as all trailing data.

## 2.2.2.1.2 TS\_RFX\_CODEC\_CHANNELT

The TS\_RFX\_CODEC\_CHANNELT structure is an extension of the TS\_RFX\_BLOCKT structure. It is present as the first field in messages that are targeted for a specific combination of codec and channel.



**blockType (2 bytes):** A 16-bit, unsigned integer. Specifies the data block type. This field MUST be set to one of the following values.

Value	Meaning
WBT_CONTEXT 0xCCC3	A <u>TS_RFX_CONTEXT</u> (section 2.2.2.2.4) structure.
WBT_FRAME_BEGIN 0xCCC4	A TS_RFX_FRAME_BEGIN (section 2.2.2.3.1) structure.
WBT_FRAME_END 0xCCC5	A TS_RFX_FRAME_END (section <u>2.2.2.3.2</u> ) structure.
WBT_REGION 0xCCC6	A TS_RFX_REGION (section 2.2.2.3.3) structure.
WBT_EXTENSION 0xCCC7	A TS_RFX_TILESET (section <u>2.2.2.3.4</u> ) structure.


**blockLen (4 bytes):** A 32-bit, unsigned integer. Specifies the size, in bytes, of the data block. This size includes the size of the **blockType**, **blockLen**, **codecId**, and **channelId** fields, as well as all trailing data.

**codecId (1 byte):** An 8-bit, unsigned integer. Specifies the codec ID. This field MUST be set to 0x01.

**channelId (1 byte):** An 8-bit, unsigned integer. Specifies the channel ID. If the **blockType** is set to WBT\_CONTEXT (0xCCC3), then **channelId** MUST be set to 0xFF. For all other values of **blockType**, **channelId** MUST be set to 0x00.

## 2.2.2.1.3 TS\_RFX\_CHANNELT

The TS\_RFX\_CHANNELT structure is used to specify the screen resolution of a channel.




**channelId (1 byte):** An 8-bit, unsigned integer. Specifies the identifier of the channel. This field MUST be set to 0x00.

width (2 bytes): A 16-bit, signed integer. Specifies the frame width of the channel. This field SHOULD<3> be within the range of 1 to 4096 (inclusive).

**height (2 bytes):** A 16-bit, signed integer. Specifies the frame height of the channel. This field SHOULD<4> be within the range of 1 to 2048 (inclusive).

## 2.2.2.1.4 TS\_RFX\_CODEC\_VERSIONT

The TS\_RFX\_CODEC\_VERSIONT structure is used to specify support for a specific version of the RemoteFX codec.



**codecId (1 byte):** An 8-bit, unsigned integer. Specifies the codec ID. This field MUST be set to 0x01. The decoder SHOULD ignore this field.

**version (2 bytes):** A 16-bit, signed integer. This field MUST be set to 0x0100. The decoder SHOULD ignore this field.

## 2.2.2.1.5 TS\_RFX\_CODEC\_QUANT


The TS\_RFX\_CODEC\_QUANT structure holds the scalar **quantization** values for the ten sub-bands in the 3-level DWT decomposition. Each field in this structure MUST have a value in the range of 6 to 15.

0	1	2	3	4	5	6	7	8	9	1 0	1	2	3	4	5	6	7	8	9	2 0	1	2	3	4	5	6	7	8	9	3	1
	L	LL3 LH3						HL3 HH3							LH2 HL2 HH2							LH1									
	Н	L1			Н	H1																									

- **LL3 (4 bits):** A 4-bit, unsigned integer. The LL quantization factor for the level-3 DWT subband.
- **LH3 (4 bits):** A 4-bit, unsigned integer. The LH quantization factor for the level-3 DWT subband.
- **HL3 (4 bits):** A 4-bit, unsigned integer. The HL quantization factors for the level-3 DWT subband.
- **HH3 (4 bits):** A 4-bit, unsigned integer. The HH quantization factors for the level-3 DWT subband.
- **LH2 (4 bits):** A 4-bit, unsigned integer. The LH quantization factor for the level-2 DWT subband.
- **HL2 (4 bits):** A 4-bit, unsigned integer. The HL quantization factor for the level-2 DWT subband.
- **HH2 (4 bits):** A 4-bit, unsigned integer. The HH quantization factor for the level-2 DWT subband.
- **LH1 (4 bits):** A 4-bit, unsigned integer. The LH quantization factors for the level-1 DWT subband.
- **HL1 (4 bits):** A 4-bit, unsigned integer. The HL quantization factors for the level-1 DWT subband.
- **HH1 (4 bits):** A 4-bit, unsigned integer. The HH quantization factor for the level-1 DWT subband.

## 2.2.2.1.6 TS\_RFX\_RECT

The TS\_RFX\_RECT structure is used to specify a rectangle.




- **x (2 bytes):** A 16-bit, unsigned integer. The X-coordinate of the rectangle.
- y (2 bytes): A 16-bit, unsigned integer. The Y-coordinate of the rectangle.
- width (2 bytes): A 16-bit, unsigned integer. The width of the rectangle.

height (2 bytes): A 16-bit, unsigned integer. The height of the rectangle.

## 2.2.2.2 Encode Header Messages

#### 2.2.2.2.1 TS\_RFX\_SYNC

The TS\_RFX\_SYNC message MUST be the first message in any encoded stream. The decoder MUST examine this message to determine whether the protocol version is supported.




**BlockT (6 bytes):** A <u>TS\_RFX\_BLOCKT (section 2.2.2.1.1)</u> structure. The **blockType** field MUST be set to WBT\_SYNC (0xCCC0).

magic (4 bytes): A 32-bit, unsigned integer. This field MUST be set to WF\_MAGIC (0xCACCACCA).

**version (2 bytes):** A 16-bit, unsigned integer. Indicates the version number. This field MUST be set to WF\_VERSION\_1\_0 (0x0100).

## 2.2.2.2.2 TS\_RFX\_CODEC\_VERSIONS

The TS\_RFX\_CODEC\_VERSIONS message indicates the version of the RemoteFX codec that is being used.




**BlockT (6 bytes):** A <u>TS\_RFX\_BLOCKT (section 2.2.2.1.1)</u> structure. The **blockType** field MUST be set to WBT\_CODEC\_VERSIONS (0xCCC1).

**numCodecs (1 byte):** An 8-bit, unsigned integer. Specifies the number of codec version data blocks in the **codecs** field. This field MUST be set to 0x01.

**codecs (3 bytes):** A <u>TS RFX CODEC VERSIONT (section 2.2.2.1.4)</u> structure. The **codecId** field MUST be set to 0x01 and the **version** field MUST be set to WF\_VERSION\_1\_0 (0x0100).

## 2.2.2.2.3 TS\_RFX\_CHANNELS

The TS\_RFX\_CHANNELS message contains the list of channels. Each active monitor on the server must correspond to an entry in this list. The list can have more entries than the number of active monitors. The decoder endpoint MUST be able to support channels with different frame dimensions.




**BlockT (6 bytes):** A <u>TS\_RFX\_BLOCKT (section 2.2.2.1.1)</u> structure. The **blockType** field MUST be set to WBT\_CHANNELS (0xCCC2).

**numChannels (1 byte):** An 8-bit, unsigned integer. Specifies the number of channel data blocks in the **channels** field.

**Channels (variable):** A variable-length array of <u>TS\_RFX\_CHANNELT (section 2.2.2.1.3)</u> structures. The number of elements in this array is specified in the **numChannels** field.

#### 2.2.2.4 TS\_RFX\_CONTEXT

The TS\_RFX\_CONTEXT message contains information regarding the encoding properties being used.




**CodecChannelT (8 bytes):** A <u>TS RFX CODEC CHANNELT</u> structure. The **blockType** field MUST be set to WBT CONTEXT (0xCCC3).

**ctxId (1 byte):** An 8-bit unsigned integer. Specifies an identifier for this context message. This field MUST be set to 0x00. The decoder SHOULD ignore this field.

**tileSize (2 bytes):** A 16-bit unsigned integer. Specifies the tile size used by the RemoteFX codec. This field MUST be set to CT\_TILE\_64x64 (0x0040), indicating that a tile is 64 x 64 pixels.

**properties (2 bytes):** A 16-bit unsigned integer. Contains a collection of bit-packed property fields. The format of this field is described by the following bitfield diagram.



flags (3 bits): A 3-bit unsigned integer. Specifies operational flags.

Flag	Meaning
CODEC_MODE 0x02	The codec is operating in image mode. If this flag is not set, the codec is operating in video mode.

When operating in image mode, the Encode Headers messages (section 2.2.2.2) MUST always precede an encoded frame. When operating in video mode, the header messages MUST be present at the beginning of the stream and MAY be present elsewhere.

- **cct (2 bits):** A 2-bit unsigned integer. Specifies the color conversion transform. This field MUST be set to COL\_CONV\_ICT (0x1) to specify the transform defined by the equations in sections 3.1.8.1.3 and 3.1.8.2.5. The decoder SHOULD ignore this field.
- **xft (4 bits):** A 4-bit unsigned integer. Specifies the DWT. This field MUST be set to CLW\_XFORM\_DWT\_53\_A (0x1), which indicates the DWT given by the equations in sections 3.1.8.1.4 and 3.1.8.2.4.
- **et (4 bits):** A 4-bit unsigned integer. Specifies the entropy algorithm. This field MUST be set to one of the following values.

Value	Meaning
CLW_ENTROPY_RLGR1 0x01	RLGR algorithm as detailed in 3.1.8.1.7.1.
CLW_ENTROPY_RLGR3 0x04	RLGR algorithm as detailed in 3.1.8.1.7.2.


The decoder SHOULD ignore this value and use the value defined in the properties field of TS RFX TILESET (section 2.2.2.3.4) (section 2.2.2.3.4).

- **qt (2 bits):** A 2-bit unsigned integer. Specifies the quantization type. This field MUST be set to SCALAR\_QUANTIZATION (0x1). The decoder SHOULD ignore this field.
- **r (1 bit):** A 1-bit field reserved for future use. This field MUST be ignored when received.

#### 2.2.2.3 Encode Data Messages

#### 2.2.2.3.1 TS\_RFX\_FRAME\_BEGIN

The TS\_RFX\_FRAME\_BEGIN message indicates the start of a new frame for a specific channel in the encoded stream.




**CodecChannelT (8 bytes):** A <u>TS\_RFX\_CODEC\_CHANNELT (section 2.2.2.1.2)</u> structure. The **blockType** field MUST be set to WBT\_FRAME\_BEGIN (0xCCC4).

**frameIdx (4 bytes):** A 32-bit unsigned integer. Specifies the index of the frame in the current video sequence. This field is used when the codec is operating in video mode, as specified using the **flags** field of the <u>TS\_RFX\_CONTEXT</u> (section 2.2.2.2.4) message. If the codec is operating in image mode, this field MUST be ignored. If the codec is operating in video mode, this field SHOULD be ignored.

**numRegions (2 bytes):** A 16-bit signed integer. Specifies the number of <u>TS\_RFX\_REGION</u> (section 2.2.2.3.3) messages following this TS\_RFX\_FRAME\_BEGIN message. That is, the number of regions in the frame.

## 2.2.2.3.2 TS\_RFX\_FRAME\_END


The TS\_RFX\_FRAME\_END message specifies the end of a frame for a specific channel in the encoded stream.



**CodecChannelT (8 bytes):** A <u>TS RFX CODEC CHANNELT (section 2.2.2.1.2)</u> structure. The **blockType** field MUST be set to WBT\_FRAME\_END (0xCCC5).

## 2.2.2.3.3 **TS\_RFX\_REGION**

The TS\_RFX\_REGION message contains information about the list of change rectangles on the screen for a specific channel. It also specifies the number of trailing <u>TS\_RFX\_TILESET</u> (section <u>2.2.2.3.4</u>) messages.



23 / 142

[MS-RDPRFX] - v20140502

Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

Release: Thursday, May 15, 2014

regionFlags	num	Rects	rects (variable)
regio	пТуре	numT	ilesets

**CodecChannelT (8 bytes):** A <u>TS\_RFX\_CODEC\_CHANNELT (section 2.2.2.1.2)</u> structure. The **blockType** field MUST be set to WBT\_REGION (0xCCC6).

**regionFlags (1 byte):** An 8-bit, unsigned integer. Contains a collection of bit-packed property fields. The format of this field is described by the following bitfield diagram.

0	1	2	3	4	5	6	7
Irf	reserved						

**Irf (1 bit):** A 1-bit unsigned integer. This field MUST be set to 0x1. The decoder SHOULD ignore this field.

reserved (7 bits: A 7-bit integer reserved for future use. This field MUST be ignored.

**numRects (2 bytes):** A 16-bit, unsigned integer. Specifies the number of <u>TS\_RFX\_RECT\_(section 2.2.2.1.6)</u> structures present in the **rects** field.


**rects (variable):** A variable-length array of TS\_RFX\_RECT (section 2.2.2.1.6) structures. This array defines the region. The number of rectangles in the array is specified in the **numRects** field. Processing rules for the rectangles in this array are specified in section 3.1.8.2.6.

**regionType (2 bytes):** A 16-bit, unsigned integer. Specifies the region type. This field MUST be set to CBT\_REGION (0xCAC1).

**numTilesets (2 bytes):** A 16-bit, unsigned integer. Specifies the number of TS\_RFX\_TILESET (section 2.2.2.3.4) messages following this TS\_RFX\_REGION message. This field MUST be set to 0x0001.

## 2.2.2.3.4 TS\_RFX\_TILESET

The TS\_RFX\_TILESET message contains encoding parameters and data for an arbitrary number of encoded tiles.




properties	numQuant	tileSize						
numTiles	tilesDataSize							
	quantVals	(variable)						
tiles (variable)								

**CodecChannelT (8 bytes):** A <u>TS RFX CODEC CHANNELT (section 2.2.2.1.2)</u> structure. The **blockType** field MUST be set to WBT\_EXTENSION (0xCCC7).

**subtype (2 bytes):** A 16-bit, unsigned integer. Specifies the message type. This field MUST be set to CBT\_TILESET (0xCAC2).

idx (2 bytes): A 16-bit, unsigned integer. Specifies the identifier of the <u>TS\_RFX\_CONTEXT</u> (section 2.2.2.2.4) message referenced by this TileSet message. This field MUST be set to 0x0000. The decoder SHOULD ignore this field.

**properties (2 bytes):** A 16-bit unsigned integer. Contains a collection of bit-packed property fields. The format of this field is described by the following bitmask diagram.



**It (1 bit):** A 1-bit field that specifies whether this is the last TS\_RFX\_TILESET in the region. This field MUST be set to TRUE (0x1). The decoder SHOULD ignore this field.

flags (3 bits): A 3-bit unsigned integer. Specifies operational flags.

Flag	Meaning
CODEC_MODE 0x02	The codec is operating in image mode. If this flag is not set, the codec is operating in video mode.

The encoder MUST set this value to the value of flags that is set in the properties field of TS\_RFX\_CONTEXT. The decoder MUST ignore this flag and MUST use the flags specified in the **flags** field of the TS\_RFX\_CONTEXT.

**cct (2 bits):** A 2-bit unsigned integer. Specifies the color conversion transform. This field MUST be set to COL\_CONV\_ICT (0x1) to specify the transform defined by the equations in sections 3.1.8.1.3 and 3.1.8.2.5. The decoder SHOULD ignore this field.

**xft (4 bits):** A 4-bit unsigned integer. Specifies the DWT. This field MUST be set to CLW\_XFORM\_DWT\_53\_A (0x1), which indicates the DWT given by the equations in sections 3.1.8.1.4 and 3.1.8.2.4. The decoder SHOULD ignore this field.

**et (4 bits):** A 4-bit unsigned integer. Specifies the entropy algorithm. This field MUST be set to one of the following values.


Value	Meaning
CLW_ENTROPY_RLGR1 0x01	RLGR algorithm as detailed in 3.1.8.1.7.1.
CLW_ENTROPY_RLGR3 0x04	RLGR algorithm as detailed in 3.1.8.1.7.2.

- **qt (2 bits):** A 2-bit unsigned integer. Specifies the quantization type. This field MUST be set to SCALAR\_QUANTIZATION (0x1). The decoder SHOULD ignore this field.
- **numQuant (1 byte):** An 8-bit, unsigned integer. Specifies the number of TS\_RFX\_CODEC\_QUANT (section <u>2.2.2.1.5</u>) structures present in the **quantVals** field.
- **tileSize (1 byte):** An 8-bit, unsigned integer. Specifies the width and height of a tile. This field MUST be set to 0x40. The decoder SHOULD ignore this field.
- **numTiles (2 bytes):** A 16-bit, unsigned integer. Specifies the number of TS\_RFX\_TILE (section <u>2.2.2.3.4.1</u>) structures present in the **tiles** field.
- **tilesDataSize (4 bytes):** A 32-bit, unsigned integer. Specifies the size, in bytes, of the **tiles** field. The **tiles** field contains encoded data for all of the tiles that have changed.
- **quantVals (variable):** A variable-length array of TS\_RFX\_CODEC\_QUANT (section 2.2.2.1.5) structures. The number of structures present in the array is indicated in the **numQuant** field.
- **tiles (variable):** A variable-length array of TS\_RFX\_TILE (section 2.2.2.3.4.1) structures. The number of structures present in the array is indicated in the **numTiles** field, while the total size, in bytes, of this field is specified by the **tilesDataSize** field.

## 2.2.2.3.4.1 TS\_RFX\_TILE

The TS\_RFX\_TILE structure specifies the position of the tile on the frame and contains the encoded data for the three tile components of Y, Cb, and Cr.

0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1 2 3 4 5 6 7 8 9 0 1								
	BlockT							
	quantIdxY							
quantIdxCr	xl	dx	yIdx					
	YL	en	CbLen					
	Cr	Len	YData (variable)					



- **BlockT (6 bytes):** A <u>TS\_RFX\_BLOCKT (section 2.2.2.1.1)</u> structure. The **blockType** field MUST be set to CBT\_TILE (0xCAC3).
- quantIdxY (1 byte): An 8-bit, unsigned integer. Specifies an index into the TS\_RFX\_CODEC\_QUANT array provided in the TS\_RFX\_TILESET message. The specified TS\_RFX\_CODEC\_QUANT element MUST be used for de-quantization of the sub-bands for the Y-component.
- quantIdxCb (1 byte): An 8-bit, unsigned integer. Specifies an index into the TS\_RFX\_CODEC\_QUANT array provided in the TS\_RFX\_TILESET message. The specified TS\_RFX\_CODEC\_QUANT element MUST be used for de-quantization of the sub-bands for the Cb-component.
- quantIdxCr (1 byte): An 8-bit, unsigned integer. Specifies an index into the TS RFX CODEC QUANT array provided in the TS RFX TILESET message. The specified TS\_RFX\_CODEC\_QUANT element MUST be used for de-quantization of the sub-bands for the Cr-component.
- **xIdx (2 bytes):** A 16-bit, unsigned integer. The X-index of the encoded tile in the screen tile grid.
- yIdx (2 bytes): A 16-bit, unsigned integer. The Y-index of the encoded tile in the screen tile grid.
- YLen (2 bytes): A 16-bit, unsigned integer. Specifies the size, in bytes, of the YData field.
- **CbLen (2 bytes):** A 16-bit, unsigned integer. Specifies the size, in bytes, of the **CbData** field.
- CrLen (2 bytes): A 16-bit, unsigned integer. Specifies the size, in bytes, of the CrData field.
- **YData (variable):** A variable-length array. Contains the encoded data for the Y-component of the tile. The size, in bytes, of this field is specified by the **YLen** field.
- **CbData (variable):** A variable-length array. Contains the encoded data for the Cb-component of the tile. The size, in bytes, of this field is specified by the **CbLen** field.
- **CrData (variable):** A variable-length array. Contains the encoded data for the Cr-component of the tile. The size, in bytes, of this field is specified by the **CrLen** field.

#### 2.2.3 Control Messages

## 2.2.3.1 TS\_FRAME\_ACKNOWLEDGE\_PDU

The TS\_FRAME\_ACKNOWLEDGE\_PDU structure is a client-to-server PDU sent to the server whenever the client receives a <a href="frame-Marker Command">Frame Marker Command</a> (<a href="mailto:IMS-RDPBCGR">IMS-RDPBCGR</a>] section 2.2.9.2.3) with the <a href="mailto:frameAction">frameAction</a> field set to SURFACECMD\_FRAMEACTION\_END (0x0001) and it has finished

processing this particular frame (that is, the surface bits have been rendered on the screen). The server uses this acknowledgment to throttle the rate at which it generates frames of data to avoid overloading the client with too many updates. The server SHOULD NOT wait for an acknowledgment for each frame before sending the next frame. Instead, the server SHOULD have a "window" mechanism where it allows multiple frames to be unacknowledged before it slows down its frame rate (or stops completely).

0	1	2	3	4	5	6	7	8	9	1 0	1	2	3	4	5	6	7	8	9	2 0	1	2	3	4	5	6	7	8	9	3 0	1
														tp	ktH	ead	er														
	x224Data										mcsSDrq (variable)																				
												se	cur	ityH	ead	er (	(var	iabl	le)												
													sł	nare	Dat	аНе	ead	er													
	fra								ran	neID	)																				

**tpktHeader (4 bytes):** A TPKT Header as specified in <a>[T123]</a> section 8.

x224Data (3 bytes): An X.224 Class 0 Data TPDU, as specified in [X224] section 13.7.

mcsSDrq (variable): Variable-length PER-encoded MCS Domain PDU (DomainMCSPDU) that encapsulates an MCS Send Data Request structure (SDrq, choice 25 from DomainMCSPDU). This is as specified in [T125] section 11.32, and the ASN.1 structure definitions are specified in [T125] section 7, parts 7 and 10. The userData field of the MCS Send Data Request PDU contains a Security Header, Share Data Header, and a frame ID.

**securityHeader (variable):** Optional security header. The presence and format of the security header depend on the Encryption Level and Encryption Method selected by the server ([MS-RDPBCGR] sections <u>5.3.2</u> and <u>2.2.1.4.3</u>). If the Encryption Level selected by the server is greater than ENCRYPTION\_LEVEL\_NONE (0) and the Encryption Method selected by the server is greater than ENCRYPTION\_METHOD\_NONE (0), this field MUST contain one of the following headers:

 Non-FIPS Security Header ([MS-RDPBCGR] section 2.2.8.1.1.2.2) if the Encryption Method selected by the server is ENCRYPTION\_METHOD\_40BIT (0x00000001), ENCRYPTION\_METHOD\_56BIT (0x00000008), or ENCRYPTION\_METHOD\_128BIT (0x00000002).

• FIPS Security Header ([MS-RDPBCGR] section 2.2.8.1.1.2.3) if the Encryption Level selected by the server is ENCRYPTION\_METHOD\_FIPS (0x00000010).

If the Encryption Level selected by the server is ENCRYPTION\_LEVEL\_NONE (0) and the Encryption Method selected by the server is ENCRYPTION\_METHOD\_NONE (0), this header MUST NOT be included in the PDU.

**shareDataHeader (18 bytes):** Share Data Header ([MS-RDPBCGR] section 2.2.8.1.1.1.2) containing information about the packet. The type subfield of the **pduType** field of the <u>Share Control Header</u> ([MS-RDPBCGR] section 2.2.8.1.1.1.1) within the Share Data Header MUST be set to PDUTYPE\_DATAPDU (0x0007). The **pduType2** field of the Share Data Header MUST be set to PDUTYPE2\_FRAME\_ACKNOWLEDGE (0x38).

**frameID (4 bytes):** A 32-bit unsigned integer. This field specifies the 32-bit identifier of the frame that was sent to the client using a Frame Marker Command and is being acknowledged as delivered. The **frameID** field MUST be populated with the value of the **frameID** field that was specified in the Frame Marker Command associated with the frame being acknowledged. If the **frameID** field is set to the value 0xFFFFFFFF, the server SHOULD<5> assume that all in-flight frames have been acknowledged.

## 3 Protocol Details

#### 3.1 Common Details

#### 3.1.1 Abstract Data Model

This section describes a conceptual model of possible data organization that an implementation maintains to participate in this protocol. The described organization is provided to facilitate the explanation of how the protocol behaves. This document does not mandate that implementations adhere to this model, as long as their external behavior is consistent with that described in this document.

**Operational Mode:** Stores the operational mode currently in use. Operational modes include video mode, and image mode.

**EntropyAlgorithm:** Stores the entropy algorithm currently in use. Entropy algorithms include RLGR1 and RLGR3.

**FrameIndex:** A 32-bit integer variable. Used by the server to keep track of the current index of the encoded frame within an encoding session. This variable is used only when the **OperationalMode** is video mode. If the **OperationalMode** is image mode, the server does not need to maintain this variable.

In video mode, this variable should be initialized to 0 at the start of the session and then incremented by 1 after every encoded frame. The current value of this variable is stored in the **frameIdx** field of the <u>TS\_RFX\_FRAME\_BEGIN</u> message (section <u>2.2.2.3.1</u>).

#### 3.1.1.1 State Machine

The following figure and table describe the state machine of the codec at the server end.




Figure 3: Server state diagram

State Name	Description
ServerUninitialized	This is the initial state of the server. In this state, the server waits for the TS RFX CLNT CAPS CONTAINER message from the client. On receiving this message, the server processes it as described in section 3.1.5.1. If it finds a compatible TS RFX ICAP, it initializes itself and gets into the SendHeaders state. Otherwise, the connection is terminated (section 3.1.5.1).
SendHeaders	In this state, the server sends the Header message sequence as described in section 3.1.8.3.1 and shown in Figure 17. The server then transitions to the SendFrameData state.
SendFrameData	In this state, the server sends the encoded frame data messages as described in section $\underline{3.1.8.3.1}$ and shown in Figure 18. The server then transitions to the FrameDataSent state.
FrameDataSent	If the <b>OperationalMode</b> of the server is image mode, the server transitions to the SendHeaders state. If the <b>OperationalMode</b> is video mode, the server transitions to either the SendFrameData state or the SendHeaders state.

#### **3.1.2 Timers**

None.

#### 3.1.3 Initialization

The <u>Bitmap Codecs Capability Set</u> message ([MS-RDPBCGR] section 2.2.7.2.10) MUST be processed by the server, as specified in section <u>3.1.5.1</u>, before RemoteFX encoding begins. This establishes the encoding properties that will be used by the server when sending the encoded data stream.

The Bitmap Codecs Capability Set is sent by the client, encapsulating the TS RFX CLNT CAPS CONTAINER (section 2.2.1.1). The server ultimately processes the encapsulated TS\_RFX\_CLNT\_CAPS\_CONTAINER (section 2.2.1.1) message as specified in section 3.1.5.1, picking a TS RFX ICAP (section 2.2.1.1.1.1.1) element. From that point on, the server uses the capability properties listed in that element to encode RemoteFX data streams.

#### 3.1.4 Higher-Layer Triggered Events

None.

## 3.1.5 Processing Events and Sequencing Rules

**Establishing the connection:** RemoteFX capabilities messages are exchanged to establish the encoding properties used by the server, as specified in sections 3.1.3 and 3.1.5.1. A compliant server MUST process the TS RFX CLNT CAPS CONTAINER message as specified in section 3.1.5.1 before RemoteFX encoding can begin.

**Sending RemoteFX encoded data:** RemoteFX encoded data is sent to the client as a sequence of the RemoteFX messages defined in section <u>2.2.2</u>. A compliant server MUST always send the encoded messages in the correct order, as specified in section <u>3.1.8.3.1</u>.

**Header messages:** The encoded message sequence MUST include header messages, as specified in section <u>3.1.8.3.1</u>.

Header messages contain information about the encoding properties used for encoding data messages, and are used by the client to decode the message stream. Header messages MUST always specify the encoding properties initialized and stored in **OperationalMode** and **EntropyAlgorithm**. The encode header and data message sequences are shown in the figures Generation of RemoteFX encode header messages and Generation of RemoteFX encode data messages (section 3.1.8.3.1).

Header messages can appear multiple times within the message stream, depending on the **OperationalMode** property:

- If the encoder is initialized with OperationalMode set to video mode, then it MUST send the encode header message sequence at the start of the stream. The encode header message sequence is then followed by an arbitrary number of encode data message sequences.
- If the encoder is initialized with **OperationalMode** set to image mode, then it MUST send the encode header message sequence before every encode data message sequence.

**Entropy Algorithm:** The server MUST use the entropy algorithm, initialized and stored in **EntropyAlgorithm**, to encode every data message in the encoded data stream.

**Error conditions:** If the client receives an out-of-sequence, unspecified, or malformed message, then the client MUST treat this as an error and terminate the RDP connection.

## 3.1.5.1 Processing the TS\_RFX\_CLNT\_CAPS\_CONTAINER Message

The structure and fields of the  $\overline{\text{TS RFX CLNT CAPS CONTAINER}}$ , and its constituent members, are specified in section 2.2.1.1.

TS\_RFX\_CLNT\_CAPS\_CONTAINER has a <u>TS\_RFX\_CAPS</u> field. The TS\_RFX\_CAPS field contains a <u>TS\_RFX\_CAPSET</u> sub-field, which is composed of a variable number of <u>TS\_RFX\_ICAP</u> structures.

The encoder parses the TS\_RFX\_CLNT\_CAPS\_CONTAINER message to get to the array of TS\_RFX\_ICAP structures. It processes each element of this array to check whether it can support all the properties listed in that TS\_RFX\_ICAP element. From this set of supported elements, it will arbitrarily pick one element and use only the properties listed in that specific TS\_RFX\_ICAP to encode the data stream.

For example, if the decoder supports both RLGR1 and RLGR3, the client can specify support for both of them. This support is specified using two TS\_RFX\_ICAP elements in the TS\_RFX\_CAPSET message that the client sends to the server. If the encoder also supports both RLGR1 and RLGR3, it then arbitrarily picks one of the TS\_RFX\_CAPSET elements to use for encoding.

Once a TS\_RFX\_ICAP element has been picked, the **OperationalMode** and **EntropyAlgorithm** ADM elements are set as follows.

- If the TS\_RFX\_ICAP element's **flags** field is set to include the 0x02 flag, the **OperationalMode** is set to image mode; otherwise, the **OperationalMode** is set to video mode.
- When the TS\_RFX\_ICAP element's **entropyBits** field is set to 0x01, the **EntropyAlgorithm** is set to RLGR1; when **entropyBits** is set to 0x04, **EntropyAlgorithm** is set to RLGR3.

**Error conditions:** If the server cannot support any of the TS\_RFX\_ICAP elements, it MUST stop sending messages and consider the RDP connection terminated.

#### 3.1.6 Timer Events

None.

#### 3.1.7 Other Local Events

None.

#### 3.1.8 RemoteFX Algorithm

RemoteFX is a tile-based transform codec. It has the same functional stages as those found in most structured compression systems (section  $\underline{1.3.1}$ ). At the encode endpoint, these stages are transform, quantization, and entropy encoding. The inverse of these operations (in the reverse order) takes place at the decode endpoint. RemoteFX uses DWTs and Run-Length Golomb-Rice Coding (RLGR) ([ARLGR] section 3) for transformation and entropy encoding respectively.

## **3.1.8.1** Encoding

The functional stages involved in the encoding path are illustrated in the following figure. Each of these stages is described in the subsections that follow.

33 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

Release: Thursday, May 15, 2014




Figure 4: RemoteFX encoding stages

#### 3.1.8.1.1 Input Tiling

The input to the encoder is an arbitrary region contained within an image to be encoded. The input image is overlaid with a tile grid anchored to the top left corner of the screen (0, 0) and aligned to the tile size (the tile size MUST be  $64 \times 64$  pixels). The set of tiles that map to the input region are computed. These tiles are candidates for further processing, and each tile is processed independently of the others.

## 3.1.8.1.2 Differencing (Optional)

If the RemoteFX codec is to be used as a video codec, the encoder can, optionally, do differencing between current and previous frames to compute the smallest set of tiles that have changed. The differencing is done by comparing the set of input tiles in the current frame with collocated tiles from the previous frame to determine whether any pixels have changed. Only the input tiles with changed pixels in the current frame are processed for compression. Note that the input tile is compressed as is; this algorithm does not compress the tile of difference values formed by subtracting the input tile pixels of the current frame from the collocated tile pixels in the previous frame. This means that the decoder does not need to determine whether the encoder is doing differencing. The encoder can use differencing to reduce the number of tiles that it needs to encode, thereby reducing the bandwidth required to send the compressed tiles to the decoder. If the codec is to be used as an image codec, this stage MUST be skipped.

## 3.1.8.1.3 Color Conversion (RGB to YCbCr)

Each input tile is converted from the RGB color space to the **YCbCr color space**. The transform used takes an RGB input value with each component in the range [0-255] and transforms it into Y, Cb, and Cr, in the ranges [0.0, 255.0], [-128.0, 127.0], and [-128.0, 127.0], respectively. The Y-component is level-shifted down by 128, so that it also falls into the [-128.0, 127.0] range. The input tile in this level-shifted symmetric YCbCr color space is used as the input for the next stage of DWT. The matrix equation for this conversion is shown in the following figure.

$$[Y \quad Cb \quad Cr] = [R \quad G \quad B] \begin{bmatrix} 0.299 & -0.168935 & 0.499813 \\ 0.587 & -0.331665 & -0.418531 \\ 0.114 & 0.50059 & -0.081282 \end{bmatrix}$$

Figure 5: The RGB to YCbCr conversion matrix

#### 3.1.8.1.4 DWT

Each tile component (Y, Cb, Cr) is individually transformed by a 2-D DWT using a 5/3 wavelet basis. The filter coefficients used for both of the lifting-based implementations are presented in the following figure.

$$H[n] = \left| \frac{X[2n+1] - \left\lfloor \frac{X[2n] + X[2n+2]}{2} \right\rfloor}{2} \right| L[n] = X[2n] + \left\lfloor \frac{H[n-1] + H[n]}{2} \right\rfloor$$

a. High-pass coefficients

b. Low-pass coefficients

## Figure 6: Lifting equations for the DWT

Filtering at the boundary is done by mirroring the input coefficients. For example, if there are eight input coefficients:

then, after mirroring, the coefficients get logically extended as follows:

This logical extension should be used when filtering at boundaries where coefficients are required before or after the first and last available coefficient.

For each level of decomposition, we first perform the DWT in the vertical direction, followed by the DWT in the horizontal direction. After the first level of decomposition, there are 4 sub-bands: LL1, LH1, HL1, For each successive level of decomposition, the LL sub-band of the previous level is used as the input. Each tile component undergoes three levels of decomposition. This results in 10 sub-bands per component. LH1, HL1, and HH1 contain the highest frequency bands present in the image tile, while LL3 contains the lowest frequency band.

The three-level DWT decomposition is illustrated in the following figure.




Figure 7: Three-level DWT decomposition

## 3.1.8.1.5 Quantization

The encoder determines a scale value for each sub-band and uses it to quantize all the coefficients in that sub-band, which is done by dividing each coefficient by the scale value and rounding it. These scale values are represented as quantization factors in a  $\underline{\mathsf{TS}}$   $\underline{\mathsf{RFX}}$   $\underline{\mathsf{CODEC}}$   $\underline{\mathsf{QUANT}}$  structure, which is embedded in a  $\underline{\mathsf{TS}}$   $\underline{\mathsf{RFX}}$   $\underline{\mathsf{TILESET}}$  message. The conversion between a scale value and a quantization factor is given by the following figure.

Scale \_ value = (1<< (quantization \_ factor - 6))

Figure 8: Quantization factor to scale value conversion

#### 3.1.8.1.6 Linearization

The quantized tile components are linearized by raster scanning each of the sub-bands. The sub-band coefficient scan and traversal order is illustrated in the following figure.




Figure 9: Raster scan of sub-band coefficients

Linearization of the sub-bands is conducted in the following sequence: HL1, LH1, HH1, HL2, LH2, HH2, HL3, LH3, HH3, and LL3, as shown in the following figure.




Figure 10: Sub-band traversal order

The coefficients from LL3 also undergo differential encoding. Except for the first coefficient, every raster-scanned LL3 coefficient is subtracted from its previous neighbor. For example, if the raster-scanned LL3 coefficients are

[64, 32, 42, 54, 50, 60, 40, 70]

37 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

$$[64, -32, 10, 12, -4, -10, -20, 30]$$

# 3.1.8.1.7 RLGR Entropy Encoding

Each 64 x 64-pixel tile contains an array of 4,096 coefficients. This coefficient array is losslessly entropy-encoded using the RLGR algorithm ([ARLGR]] section 3). The three tile components are assembled into an encoded tile packet (section 2.2.2.3.4.1). RLGR is an algorithm that adaptively switches between Run-Length encoding of zeros and Golomb-Rice coding of nonzero coefficients. There are two variants of the RLGR algorithm that can be used, RLGR1 and RLGR3. The decoder endpoint specifies its preference through the capabilities negotiation (see the **entropyBits** field in section 2.2.1.1.1.1.1). The pseudocode that describes the complete RLGR1/RLGR3 algorithm in detail is given in section 3.1.8.1.7.3.

#### 3.1.8.1.7.1 RLGR1

The RLGR algorithm is described in [ARLGR]. In this specification, the parameter adaptation rules, which are central to the algorithm, are detailed in section [ARLGR] section 3. The specific adaptation values used by RLGR1 are given in the following two tables.

p = 0	decrease $k_R$ by setting $k_{RP} = k_{RP} - 2$
p = 1	no change in $k_R$
p > 1	increase $k_R$ by setting $k_{RP} = k_{RP} + p$

Figure 11: Adaptation rule for RLGR1/RLGR3 parameter kR

k = 0	$u = 0 : k_i$	$p = k_P + 3$
X = 0	u > 0 : k	$p = k_P - 3$
k > 0	complete run	$k_P = k_P + 4$
	partial run	$k_P = k_P - 6$

Figure 12: Adaptation rule for RLGR1/RLGR3 main parameter k

The initial value for the parameters  $k_{RP}$  and  $k_P$  is 8, and the value of L is 8. Both the parameters  $k_{RP}$  and  $k_P$  are clipped to the range [0, 80] after every update.

#### 3.1.8.1.7.2 RLGR3

The core RLGR algorithm [ARLGR] switches between the Run-Length and the Golomb-Rice mode as a stream of data is encoded, based on the Run-Length parameter, k, as shown in figure "Adaptation rule for RLGR1/RLGR3 main parameter k" in section 3.1.8.1.7.2. The Golomb-Rice mode in the RLGR algorithm [ARLGR], operates by encoding one coefficient at a time and updating the Golomb-Rice parameter, kR, as shown in figure "Adaptation rule for RLGR1/RLGR3 parameter kR" in section 3.1.8.1.7.2. In RLGR3, the Run-Length mode parameter, k, and the Golomb-Rice parameter, kR, are updated exactly as in RLGR1, but the Golomb-Rice mode is processed differently. Once the algorithm enters into the Golomb-Rice mode, RLGR3 takes the sum of the next two coefficients and Golomb-Rice encodes the sum and updates the parameters k and kR as with RLGR1. After the sum is encoded, the value of the first coefficient is emitted as binary code in the exact number of bits it takes to represent the sum. Pseudocode for Golomb-Rice mode in RLGR3 encode follows.

```
ENCODER GOLOMB-RICE MODE:

SUM = COEFF[n] + COEFF[n+1] // sum of the next two coefficients in the input stream GOLOMB_RICE_ENCODE(SUM) // Golomb-Rice encode the value of SUM BINARY_ENCODE(COEFF[n]) // using LOG2(SUM) bits

UPDATE RLGR PARAMETERS(SUM) // update RLGR parameters (k,kR) based on SUM
```

The decoder follows the same sequence of steps as the encoder, as it decodes the encoded data. The pseudocode for the decoder in Golomb-Rice mode is given below.

In general, RLGR3 encodes faster than RLGR1 but is marginally worse in terms of compression ratio.

# 3.1.8.1.7.3 RLGR1/RLGR3 Pseudocode

# 3.1.8.1.7.3.1 RLGR1/RLGR3 Decode

The following pseudocode sample shows how to decode a stream of bits encoded using the RLGR1/RLGR3 algorithm.

```
// Constants used within the RLGR1/RLGR3 algorithm

#define KPMAX (80)  // max value for kp or krp
#define LSGR (3)  // shift count to convert kp to k
#define UP_GR (4)  // increase in kp after a zero run in RL mode
#define DN_GR (6)  // decrease in kp after a nonzero symbol in RL mode
#define UQ_GR (3)  // increase in kp after nonzero symbol in GR mode
#define DQ_GR (3)  // decrease in kp after zero symbol in GR mode
#define DQ_GR (3)  // decrease in kp after zero symbol in GR mode

//
// Gets (returns) the next nBits from the bitstream
// The layout of N bits in the bitstream with regard to a byte array is:
```

39 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
[0..N] -> [0..7] (MSB..LSB), [8..15] (MSB..LSB) ...,
// where (MSB..LSB) denotes a byte.
//
UINT GetBits(
  UINT nBits
   );
// From current output pointer, write "value", check and update *termsToDecode
//
VOID
WriteValue(
   INT value,
   INT *termsToDecode
   );
// From current output pointer, write next nZeroes terms with value 0;
// check and update *termsToDecode
//
VOID
WriteZeroes(
  UINT nZeroes,
   INT *termsToDecode
   );
// Returns the least number of bits required to represent a given value
//
UINT
GetMinBits(
   UINT val// returns ceil(log2(val))
// Converts from (2 * magnitude - sign) to integer
//
INT
GetIntFrom2MagSign(
  UINT twoMs
   );
// Update the passed parameter and clamp it to the range [0, KPMAX]
// Return the value of parameter right-shifted by LSGR
11
INT
UpdateParam(
  INT* param,
                 // parameter to update
   INT deltaP
                 // update delta
   )
{
```

40 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
*param += deltaP;// adjust parameter
    if (*param > KPMAX) *param = KPMAX;// max clamp
    if (*param < 0) *param = 0;// min clamp
    return (*param >> LSGR);
// Outputs the Golomb/Rice encoding of a non-negative integer
//
UINT
GetGRCode(
  INT* krp,
    INT* kr
    INT vk;
    UINT mag;
    // chew up/count leading 1s and escape 0
    for (vk=0;GetBits(1)==1;) {
        vk++;
    }
    // get next *kr bits, and combine with leading 1s
    mag = (vk << *kr) | GetBits(*kr);
    \ensuremath{//} adjust kpr and kr based on \ensuremath{\text{vk}}
    if (!vk)
        *kr = UpdateParam(kpr, -2);
    }
    else if (vk!=1)// at 1, no change!
        *kr = UpdateParam(kpr, vk);
    return (mag);
}
\ensuremath{//} Routine that reads and decodes stream of RLGR data
11
VOID
RLGR Decode(
   RLGR MODE rlgrMode, // RLGR1 || RLGR3
    INT termsToDecode
    // initialize the parameters
    INT k = 1;
    INT kp = k << LSGR;</pre>
    INT kr = 1;
    INT krp = kr << LSGR;</pre>
```

```
while (termsToDecode > 0)
    INT run;
    if (k)
        // RL MODE
        while (GetBits(1) == 0)
            // we have an RL escape "0", which translates to a run (1<<k) of zeros
            WriteZeroes(1<<k, &termsToDecode);
            k = UpdateParam(\&kp,UpGR); // raise k and kp up because of zero run
        }
        if (termsToDecode > 0)
            \ensuremath{//} next k bits will contain remaining run of zeros
            run = GetBits(k);
            WriteZeroes(run, &termsToDecode);
        }
        if (termsToDecode > 0)
            // get nonzero value, starting with sign bit and
            // then GRCode for magnitude - 1
            UINT sign = GetBits(1);
            // magnitude - 1 was coded (because it was nonzero)
            INT mag = (INT)GetGRCode(&krp,&kr) + 1;
            WriteValue(sign ? -mag : mag, &termsToDecode);
            k = UpdateParam(\&kp, -DnGR); // lower k and kp because of nonzero term
    }
    else
        // GR (GOLOMB-RICE) MODE
        UINT mag = GetGRCode(&krp, &kr); // values coded are 2*magnitude - sign
        if (rlgrMode == RLGR1)
        {
            if (!mag)
                WriteValue(0, &termsToDecode);
               k = UpdateParam(&kp, UqGR); // raise k and kp due to zero
            }
            else
                WriteValue(GetIntFrom2MagSign(mag), &termsToDecode);
                k = UpdateParam(\&kp, -DqGR); // lower k and kp due to nonzero
        else // rlgrMode == RLGR3
            // In GR mode FOR RLGR3, we have encoded the
            // sum of two (2*mag - sign) values
            // maximum possible bits for first term
```

```
UINT nIdx = GetMinBits(mag);
                // decode val1 is first term's (2*mag - sign) value
                UINT val1 = GetBits(nIdx);
                // val2 is second term's (2*mag - sign) value
                UINT val2 = mag - val1;
                if (val1 && val2) {
                   // raise k and kp if both terms nonzero
                    k = UpdateParam(&kp, -2*DqGR);
                else if (!val1 && !val2) {
                   // lower k and kp if both terms zero
                    k = UpdateParam(&kp, 2*UqGR);
               WriteValue(GetIntFrom2MagSign(val1), &termsToDecode);
               WriteValue (GetIntFrom2MagSign(val2), &termsToDecode);
           }
      }
  }
}
```

### 3.1.8.1.7.3.2 RLGR1/RLGR3 Encode

The following pseudocode sample shows how to encode a stream of input symbols using the RLGR1/RLGR3 algorithm.

```
// Constants used within the RLGR1/RLGR3 algorithm
\#define KPMAX (80) // max value for kp or krp
\#define LSGR (3) // shift count to convert kp to k
#define UP GR (4) // increase in kp after a zero run in RL mode
\#define DN_GR (6) // decrease in kp after a nonzero symbol in RL mode
\#define\ UQ\_GR (3) // increase in kp after nonzero symbol in GR mode
#define DQ GR (3) // decrease in kp after zero symbol in GR mode
// Returns the next coefficient (a signed int) to encode, from the input stream
//
INT
GetNextInput();
//
// Emit bitPattern to the output bitstream.
// The bitPattern value represents a bit sequence that is generated by shifting
// new bits in from the right. If we take the binary representation of bitPattern,
// with N(numBits-1) being the leftmost bit position and 0 being the rightmost bit position,
// the mapping of bitPattern to the output bytes is as follows:
11
//
      bitPattern[N..0] -> byte[MSB..LSB] .. byte[MSB..LSB]
//
VOID
```

```
OutputBits(
   INT numBits,
                 // number of bits in bitPattern
   INT bitPattern // bit pattern
11
// Emit a bit (0 or 1), count number of times, to the output bitstream
//
VOID
OutputBit(
  INT count,
                 // number of times to emit the bit
   INT bit
                 // 0 or 1
  );
// Returns the least number of bits required to represent a given value
//
UINT
GetMinBits(
  INT val
              // returns ceil(log2(val))
   );
//
// Converts the input value to (2 * abs(input) - sign(input)),
// where sign(input) = (input < 0 ? 1 : 0) and returns it
//
UINT
Get2MagSign(
  INT input // input value
   );
//
// Update the passed parameter and clamp it to the range [0,KPMAX]
// Return the value of parameter right-shifted by LSGR
//
INT
UpdateParam(
  INT* param,
INT deltaP
                  // parameter to update
                 // update delta
   )
{
   *param += deltaP;
   if (*param > KPMAX) *param = KPMAX;
   if (*param < 0) *param = 0;
   return (*param >> LSGR);
}
// Outputs the Golomb/Rice encoding of a non-negative integer
//
VOID
CodeGR (
   TNT*
         krp, // GR parameter, used and updated based on the input value
   UINT val
                // input non-negative value to be encoded
   )
{
   INT kr = *krp >> LSGR;
```

44 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
// unary part of GR code
    UINT vk = val >> kr;
    OuputBit(vk, 1);
    OutputBit(1, 0);
    \ensuremath{//} remainder part of GR code, if needed
    if (kr) {
        OutputBits(kr, val & ((1 << kr) - 1));
    // update krp, only if it is not equal to \ensuremath{\text{1}}
    if (vk == 0) {
        UpdateParam(krp, -2);
    else if (vk > 1) {
       UpdateParam(krp, vk);
}
// Routine that outputs a stream of RLGR1/RLGR3-encoded bits
VOID
RLGR Encode (
   RLGR_MODE rlgrMode // RLGR1 || RLGR3
   // initialize the parameters
   INT k = 1;
   INT kp = 1 \ll LSGR;
    INT kr = 1;
    INT krp = 1 << LSGR;</pre>
    // process all the input coefficients
    while (1)
        INT input;
        if (k)
        {
            // RUN-LENGTH MODE
            // collect the run of zeros in the input stream
            INT numZeros = 0;
            while ((input = GetNextInput()) == 0) {
                ++ numZeros;
            // emit output zeros
            INT runmax = 1 \ll k;
            while (numZeros >= runmax)
                OutputBit(1, 0);
                                             // output a zero bit
                numZeros -= runmax;
                k = UpdateParam(&kp, UpGR); // update kp, k
                runmax = 1 << k;
```

```
// output a 1 to terminate runs
    OuputBit(1, 1);
    // output the remaining run length using k bits
    OutputBits(k, numZeros);
    // encode the nonzero value using GR coding
    INT mag = abs(input);
                                     // absolute value of input coefficient
    INT sign = (input < 0 ? 1 : 0); // sign of input coefficient</pre>
                           // output the sign bit
    OutputBit(1, sign);
    CodeGR(&krp, mag - 1); // output GR code for (mag - 1)
    k = UpdateParam(&kp, -DnGR);
}
else
    // GOLOMB-RICE MODE
    if (rlgrMode == RLGR1)
    {
        // RLGR1 variant
        // convert input to (2*magnitude - sign), encode using GR code
        UINT twoMs = Get2MagSign(GetNextInput());
        CodeGR(&krp, twoMs);
        // update k, kp
        if (!twoMs) {
           k = UpdateParam(&kp, UqGR);
        else {
           k = UpdateParam(&kp, -DqGR);
    else // rlgrMode == RLGR3
        // RLGR3 variant
        // convert the next two input values to (2*magnitude - sign) and
        // encode their sum using GR code
        UINT twoMs1 = Get2MagSign(GetNextInput());
        UINT twoMs2 = Get2MagSign(GetNextInput());
        UINT sum2Ms = twoMs1 + twoMs2;
        CodeGR(&krp, sum2Ms);
        // encode binary representation of the first input (twoMs1).
        OutputBits(GetMinBits(sum2Ms), twoMs1);
        // update k,kp for the two input values
        if (twoMs1 && twoMs2) {
           k = UpdateParam(&kp, -2*DqGR);
```

#### **3.1.8.2** Decoding

The functional stages involved in the decoding path are illustrated in the following figure. Compared to the encoding stages, the decoding stage operations are the operations of the encoding stage in reverse order.




Figure 13: RemoteFX decoding stages

### 3.1.8.2.1 RLGR Entropy Decoding

The three encoded tile components (Y, Cb, and Cr) are entropy decoded independently. The algorithm used is either inverse RLGR1 or RLGR3, depending on which one was used for encoding. For details of the decoding process, refer to [ARLGR] (the encoding process is described in section 3.1.8.1.7).

### 3.1.8.2.2 Sub-Band Reconstruction

The RLGR entropy decoding stage results in the generation of an array of 4096 coefficients per tile component. The last 64 coefficients (which correspond to the LL3 sub-band) are differentially decoded. After this step, the coefficients are rearranged to form the sub-band structure shown in the figure in section 3.1.8.1.6 that describes the sub-band traversal order.

# 3.1.8.2.3 Dequantization

The quantization factors used for each sub-band are specified in the TS\_RFX\_TILE (section  $\underline{2.2.2.3.4.1}$ ) structure. A scale value is computed from the quantization factor using the formula shown in the figure in section  $\underline{3.1.8.1.5}$ . Each coefficient in the appropriate sub-band is dequantized by multiplying it with this scale value and rounded.

#### 3.1.8.2.4 Inverse DWT

Each tile component undergoes three levels of inverse discrete wavelet transformation (IDWT). The 5/3 lifting equations used for the IDWT are presented in the following figure.

$$X[2n] = L[n] - \left\lfloor \frac{H[n-1] + H[n] + 1}{2} \right\rfloor \qquad X[2n+1] = 2 * H[n] + \left\lfloor \frac{X[2n] + X[2n+2]}{2} \right\rfloor$$
a. Even coefficients
b. Odd coefficients

# Figure 14: Lifting equations for inverse DWT

This stage results in the decoded Y, Cb, and Cr components for the tile.

# 3.1.8.2.5 Color Conversion (YCbCr to RGB)

The Y-component is first level shifted up by 128 so that it falls in the [0.0, 255.0] range. The three YCbCr components are then transformed to the RGB color space by using the following transform matrix.

$$\begin{bmatrix} R & G & B \end{bmatrix} = \begin{bmatrix} Y & Cb & Cr \end{bmatrix} \begin{bmatrix} 1.0 & 1.0 & 1.0 \\ 0.0 & -0.344 & 1.77 \\ 1.403 & -0.714 & 0.0 \end{bmatrix}$$

Figure 15: The YCbCr to RGB conversion matrix

#### 3.1.8.2.6 Reconstructed Frame

Each decoded RGB tile is intersected and clipped against the set of rectangles from the **rects** field of the <u>TS\_RFX\_REGION</u> (section 2.2.2.3.3) message. This gives a set of clipped rectangles, which are blitted to the appropriate location on the screen. Doing this for all the tiles present in the <u>TS\_RFX\_TILESET</u> (section 2.2.2.3.4) message will result in the reconstructed frame.

There are two reasons for doing this tile-region intersection. One is that the changed region on the screen, which comprises a set of arbitrary-sized rectangles, is converted to 64x64 tiles (section 3.1.8.1.1) and these tiles can extend beyond the boundary of the rectangles of the change region. The second reason is that the differencing operation (section 3.1.8.1.2) could cull some of these tiles and the decoder will not receive these tiles within the TS\_RFX\_TILESET message.

# 3.1.8.3 RemoteFX Stream

A RemoteFX stream is defined to be the set of all of the codec messages, sent sequentially from an encoder endpoint to a decoder endpoint. There is no message to signify the end of a stream. If the RemoteFX codec is to be used as an image codec, the stream only contains messages pertaining to a single image. If the RemoteFX codec is to be used as a video codec, the stream can contain an arbitrary number of images.

#### 3.1.8.3.1 Encode Message Sequencing

An encoded RemoteFX stream is composed of a sequence of encode messages that are described in section <u>2.2.2</u>. The sequence of encode messages is encapsulated inside an Extended Bitmap Data structure ([MS-RDPBCGR] section 2.2.9.2.1.1), which is encapsulated in a Stream Surface Bits Surface Command ([MS-RDPBCGR] section 2.2.9.2.2).

48 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

All encode messages start with a TS\_RFX\_BLOCKT (section <a href="2.2.2.1.1">2.2.2.1.1</a>) structure. When parsing the message blocks, the **blockLen** field of a TS\_RFX\_BLOCKT MUST be used to obtain the length of the data block. This length MUST NOT be less than the length based on the **blockType** field of the TS\_RFX\_BLOCKT.

The RemoteFX stream is structured as a set of header messages followed by encoded data messages. The header messages contain global information necessary to decompress the data messages. The header messages are described in section 2.2.2.2, and the data messages are described in section 2.2.2.3. The stream MUST start with the header messages and any of these headers can appear in the stream at a later stage. The header messages can be repeated.




Figure 16: Message sequencing in the RemoteFX stream

The first message in a RemoteFX stream MUST be the TS\_RFX\_SYNC (section <a href="2.2.2.2.1">2.2.2.2</a>. This message MUST be followed by the TS\_RFX\_CHANNELS (section <a href="2.2.2.2.2.2">2.2.2.2</a>.), TS\_RFX\_CODEC\_VERSIONS (section <a href="2.2.2.2.2">2.2.2.2</a>.), and TS\_RFX\_CONTEXT (section <a href="2.2.2.2.2">2.2.2.2</a>.) messages, as shown in the figure that follows. It is permissible for these three messages to occur in any order. These three messages contain all of the information needed to initialize the decoder.




Figure 17: Generation of RemoteFX encode header messages

The TS\_RFX\_CHANNELS message MUST contain a single channel, and the frame dimensions of this channel are given by the **width** and **height** fields of the corresponding <u>TS\_RFX\_CHANNELT</u> structure (section <u>2.2.2.1.3</u>). The decoder MUST check the TS\_RFX\_CODEC\_VERSIONS and TS\_RFX\_CONTEXT messages to determine whether it is compatible with the RemoteFX codec version and the encoding properties listed in these messages. If the decoder cannot support the codec version, the channel frame dimensions, or any of the listed encoding properties, it MUST reject the encoded stream.

The data associated with each encoded frame or image is always bracketed by the TS\_RFX\_FRAME\_BEGIN (section 2.2.2.3.1) and TS\_RFX\_FRAME\_END (section 2.2.2.3.2) messages. The sequence of blocks that comprise a frame are described in the figure that follows. There MUST only be one TS\_RFX\_REGION (section 2.2.2.3.3) message per frame and one TS\_RFX\_TILESET (section 2.2.2.3.4) message per TS\_RFX\_REGION. All of the messages corresponding to a frame associated with a given channel MUST occur consecutively within the codec byte-stream. The messages corresponding to frames from two different channels MUST NOT be interleaved.




Figure 18: Generation of RemoteFX encode data messages

# 4 Protocol Examples

# 4.1 Sample Use Case

Consider the case of a remote endpoint system with one monitor configured to use a display resolution of  $1280 \times 1024$  pixels. In this scenario, there is one instance of the RemoteFX encoder running on the remote system. The encoder is configured to use one channel with frame buffer dimensions of  $1280 \times 1024$ . As the contents of the screen are updated over time, the changes are captured, and the affected regions in the frame buffer corresponding to the bounding rectangles of the updated areas are fed as input to the encoder to compress.

The encoder examines the update regions and determines the set of tiles that correspond to those regions. The tile grid is anchored to the frame at (0, 0) and aligned to the tile size. This means that as an update region (for example, a window being dragged) moves around on the screen, the number of tiles corresponding to that update region can vary. In the figure that follows, the regions A and B are the same size  $(3 \times 3)$  but they correspond to 9 and 16 tiles respectively due to their location on the screen. In the case of border tiles where the update region is not aligned to the tile grid, the area of the tile outside of the actual update region can contain arbitrary data and hence cannot be relied upon to contain valid image data. In the figure that follows, region B is not aligned to the tile grid and hence the perimeter tiles only contain a partial image.






Figure 19: Update region to tile grid mapping

The single monitor configuration results in a TS\_RFX\_CHANNELS (section 2.2.2.2.3) header message that specifies one channel set to  $1280 \times 1024$ . For every frame that is encoded due to region updates, the message sequence that results is described in the encode messages diagram in section 3.1.8.3.1. The TS\_RFX\_REGION (section 2.2.2.3.3) message contains the list of updated rectangles, and the accompanying TS\_RFX\_TILESET (section 2.2.2.3.4) message contains the corresponding set of tiles. The TS\_RFX\_TILE (section 2.2.2.3.4.1) structure contains the location of the tile in the frame. Conceptually, the decoder can decode each tile, **blit** it to the proper location in a temporary frame buffer, and then blit all of the updated rectangles to an output frame buffer.

# 4.2 Annotated RemoteFX Messages

#### 4.2.1 Capabilities Messages

The following is an annotated network capture of the  $\underline{\sf TS}$  RFX CLNT CAPS CONTAINER message (section  $\underline{\sf 2.2.1.1}$ ).

```
00000000 31 00 00 00 01 00 00 00 25 00 00 00 c0 cb 08 00 00000010 00 00 01 00 c1 cb 1d 00 00 00 01 c0 cf 02 00 08 00000020 00 00 01 40 00 00 01 01 01 00 01 40 00 01 01 01 00 01 40 00 01 01 01 00000030 04
```

#### TS RFX CAPS message (section 2.2.1.1.1):

```
c0 cb -> TS_RFX_CAPS::blockType = CBY_CAPS
08 00 00 00 -> TS_RFX_CAPS::blockLen = 8
01 00 -> TS_RFX_CAPS::numCapsets = 1
```

# TS RFX CAPSET message (section 2.2.1.1.1.1):

```
c1 cb -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::blockType = CBY_CAPSET
1d 00 00 00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::blockLen = 29
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::codecId = 1
C0 cf -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::capsetType = CLY_CAPSET
02 00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::numIcaps = 2
08 00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::icapLen = 8
```

#### TS RFX ICAP message (section 2.2.1.1.1.1):

```
00 01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::version = CLW_VERSION_1_0
40 00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::tileSize = 64
00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::flags = VIDEO_MODE (0)
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::colConvBits = CLW_COL_CONV_ICT
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::transformBits = CLW_XFORM_DWT_53_A
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[0]::entropyBits = CLW_ENTROPY_RLGR1
00 01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::version = CLW_VERSION_1_0
40 00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::tileSize = 64
00 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::flags = VIDEO_MODE (0)
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::colConvBits = CLW_COL_CONV_ICT
01 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::transformBits = CLW_XFORM_DWT_53_A
04 -> TS_RFX_CAPS::TS_RFX_CAPSET[0]::TS_RFX_ICAP[1]::entropyBits = CLW_ENTROPY_RLGR3
```

The client has specified support for both RLGR1 and RLGR3, by including two TS\_RFX\_ICAP elements. The server can pick either of the two and use the corresponding encoding properties, as described in section 3.1.5.1.

The following is an annotated dump of the <u>TS\_RFX\_SRVR\_CAPS\_CONTAINER</u> message (section <u>2.2.1.2</u>).

The server has sent an array of bytes set to zero as described in section 2.2.1.2.

#### 4.2.2 Encode Header Messages

The following is an annotated network capture of the <a href="Encode Header Messages">Encode Header Messages</a> (section 2.2.2.2).

53 / 142

```
[MS-RDPRFX] — v20140502
Remote Desktop Protocol: RemoteFX Codec Extension
```

Copyright © 2014 Microsoft Corporation.

#### TS RFX SYNC message (section 2.2.2.2.1):

```
c0 cc -> TS_RFX_SYNC::BlockT::blockType = WBT_SYNC
0c 00 00 00 -> TS_RFX_SYNC::BlockT::blockLen = 12
ca ac cc ca -> TS_RFX_SYNC::magic = WF_MAGIC
00 01 -> TS_RFX_SYNC::version = 0x0100
```

### TS RFX CONTEXT message (section 2.2.2.2.4):

```
c3 cc -> TS_RFX_CONTEXT::CodecChannelT::BlockT::blockType = WBT_CONTEXT
0d 00 00 00 -> TS_RFX_CONTEXT::CodecChannelT::BlockT::blockLen = 13
01 -> TS_RFX_CONTEXT::CodecChannelT::codecId = 1
ff -> TS_RFX_CONTEXT::CodecChannelT::channelId = 255
00 -> TS_RFX_CONTEXT::ctxId = 0
40 00 -> TS_RFX_CONTEXT::tileSize = 64
28 a8 -> TS_RFX_CONTEXT::properties
TS_RFX_CONTEXT::properties::flags = VIDEO_MODE (0)
TS_RFX_CONTEXT::properties::cct = COL_CONV_ICT (1)
TS_RFX_CONTEXT::properties::xft = CLW_XFORM_DWT_53_A (1)
TS_RFX_CONTEXT::properties::et = CLW_ENTROPY_RLGR3 (4)
TS_RFX_CONTEXT::properties::qt = SCALAR_QUANTIZATION (1)
TS_RFX_CONTEXT::properties::r = RESERVED
```

#### TS RFX CODEC VERSIONS message (section 2.2.2.2.2):

```
c1 cc -> TS_RFX_CODEC_VERSIONS::BlockT::blockType = WBT_CODEC_VERSION
0a 00 00 00 -> TS_RFX_CODEC_VERSIONS::BlockT::blockLen = 10
01 -> TS_RFX_CODEC_VERSIONS::numCodecs = 1
01 -> TS_RFX_CODEC_VERSIONS::TS_RFX_CODEC_VERSIONT::codecId = 1
00 01 -> TS_RFX_CODEC_VERSIONS::TS_RFX_CODEC_VERSIONT::version 0x0100
```

#### TS RFX CHANNELS message (section 2.2.2.2.3):

```
c2 cc -> TS_RFX_CHANNELS::BLockT::blockType = WBT_CHANNELS
0c 00 00 00 -> TS_RFX_CHANNELS::BlockT::blockLen = 12
01 -> TS_RFX_CHANNELS::numChannels = 1
00 -> TS_RFX_CHANNELS::TS_RFX_CHANNELT::channelId = 0
40 00 -> TS_RFX_CHANNELS::TS_RFX_CHANNELT::width = 64
40 00 -> TS_RFX_CHANNELS::TS_RFX_CHANNELT::height = 64
```

The server has chosen to encode using RLGR3 (TS\_RFX\_CONTEXT) and specified one channel with dimensions of 64x64 (TS\_RFX\_CHANNELS).

#### 4.2.3 Encode Data Messages

The following is an annotated network capture of the <a href="Encode Data Messages">Encode Data Messages</a> (section 2.2.2.3).

```
00000000 c4 cc 0e 00 00 00 01 00 00 00 00 01 00 c6 cc
```

54 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
00000010 17 00 00 00 01 00 cd 01 00 00 00 00 00 40 00 40
00000020 00 c1 ca 01 00 c7 cc d9 03 00 00 01 00 c2 ca 00
00000030 00 51 50 01 40 01 00 be 03 00 00 66 66 77 88 98
00000040 c3 ca be 03 00 00 00 00 00 00 00 00 26 01 3d
00000050 01 48 01 19 82 1d 10 62 9d 28 85 2c a2 14 b2 88
00000060 52 ca 21 4b 28 85 2c a2 14 b2 88 52 ca 21 4b 28
00000070 85 2c a2 14 b2 88 52 ca 21 4b 28 85 2c a2 14 b2
00000080 88 52 ca 21 4b 28 85 2c a2 14 b2 88 52 ca 21 4b
00000090 28 85 2c a2 14 b2 88 52 ca 21 4b 28 85 2c a2 14
000000A0 b2 88 52 ca 21 4b 28 85 2c a2 14 b0 00 20 f4 40
000000B0 0c c1 1e 20 26 22 20 33 23 c4 23 88 86 50 f1 22
00000000 68 4c 91 85 10 34 4c 84 78 a2 0d 13 21 1e 29 06
000000D0 89 90 8f 14 83 44 f4 23 c5 20 d1 3d 08 f1 48 34
000000E0 4f 42 3c 52 0d 13 d0 8f 14 83 44 f4 23 c5 20 d1
000000F0 3d 08 f1 48 34 4f 42 3c 52 0d 13 d0 8f 14 83 44
00000100 f4 23 c5 20 00 08 47 70 15 02 e0 7f e4 9d c2 51
00000110 71 f4 99 c9 57 ff 32 87 9d 17 d6 50 6e 06 2f ac
00000120 a0 9c 0c 5f 59 41 38 18 be b2 82 70 31 7d 65 00
00000130 00 10 ff 9c 33 41 f1 c4 b0 3c ff a2 15 bd 7b ea
00000140 86 9b 5f fc 78 8c f5 ed a8 68 da fd 3c 45 7a f4
00000150 d4 34 6d 7e 9e 22 bd 7a 6a 1a 36 bf 4f 11 5e bd
00000160 35 0d 1b 5f a7 88 af 5e 9a 86 8d af d3 c4 57 af
00000170 4d 43 46 d7 e9 e2 20 30 00 1b 04 7f 04 31 5f c2
00000180 94 af 05 29 5e 0a 52 bc 14 a5 78 29 25 78 29 25
00000190 78 29 25 68 52 4a f0 52 4a f0 52 4a d0 a4 95 e0
000001A0 a4 95 e0 a4 95 a1 49 2b c1 49 2b c1 49 2b 42 92
000001B0 57 82 92 57 82 92 56 85 24 af 05 24 af 05 24 ad
000001C0 0a 49 5e 0a 49 5e 0a 49 5a 14 92 bc 14 92 bc 14
000001D0 92 b4 29 25 78 29 25 78 00 02 0f 02 00 ac 13 fc
000001E0 c0 0a 20 10 2b 27 f9 80 b0 08 aa 3d 60 8c 0b 24
000001F0 ff 30 80 c0 aa 13 fc c2 03 05 90 9f e6 10 18 2c
00000200 84 ff 30 81 82 c8 4f f3 08 18 2c 84 ff 31 03 05
00000210 90 9f ff d8 40 60 59 09 fe 61 01 81 64 27 f9 84
00000220 06 0b 21 3f cc 20 30 59 09 fe 61 03 05 90 9f e6
00000230 10 30 59 09 fe 62 00 00 42 15 00 10 15 01 fe 20
00000240 84 d5 01 0a 8f f1 40 33 78 17 f9 c2 03 83 01 78
00000250 e1 01 c1 00 bc 70 80 e0 80 5e 38 40 70 40 2f 1c
00000260 20 38 20 17 8e 10 00 00 87 d5 08 70 ef 81 a2 d8
00000270 ff ff ff fb d1 2d 4e a6 ce 20 a4 ef 05 78 35 3a
00000280 9b 38 82 93 bc 15 e0 d4 ea 66 71 05 27 78 2b c1
00000290 29 d4 cc e2 0a 4e f0 57 82 53 a9 99 c4 14 9d e0
000002A0 af 04 a7 53 33 88 29 3b c1 5e 09 4e a6 67 10 52
000002B0 77 82 bc 00 18 00 1b fc 11 c1 0f 4a c1 4f 4a c1
000002C0 4f 4a a1 4d 95 42 9e 95 42 9e 95 42 9b 2a 85 3d
000002D0 2a 85 3d 2a 85 36 55 0a 7a 55 0a 7a 55 0a 6c aa
000002E0 14 f4 aa 14 f4 aa 14 d9 54 29 e9 54 29 e9 54 29
000002F0 b2 a8 53 d2 a8 53 d2 a8 53 65 50 a7 a5 50 a7 a5
00000300 50 a6 ca a1 4f 4a a1 4f 4a a1 4d 95 42 9e 95 42
00000310 9e 95 42 9b 2a 80 00 41 e3 80 3f e2 09 9c 00 22
00000320 07 03 e1 26 70 06 07 1f 04 67 00 61 df 02 67 00
00000330 Oc 3b fe 01 33 80 06 1d ff 00 99 c0 03 0e ff 80
00000340 4c e0 01 87 7f c0 26 70 00 c3 bf e0 13 38 00 61
00000350 df f0 09 9c 00 30 ef f8 04 ce 00 18 77 fc 02 67
00000360 00 0c 3b fe 01 33 80 06 1d ff 00 99 c0 03 0e ff
00000370 80 4c e0 01 87 7f c0 26 70 00 00 08 3c 20 1f f1
00000380 00 f0 05 02 93 84 3d 20 f0 52 81 c7 ff ff ea 54
00000390 01 80 05 f5 4a 80 30 00 b6 a5 40 18 00 5f 54 a8
000003A0 03 00 0b ea 95 00 60 01 6d 4a 80 30 00 00 22 3f
000003B0 ba 08 10 2b 1f f2 20 3e 49 9c 1f 6e 0f 5a 0f fb
```

```
000003C0 18 46 ae 27 9b 83 cb 41 f3 18 46 ae 27 9b 83 c5 000003D0 a0 f9 8c 22 d7 13 8d c1 e2 d0 7c c6 11 6b 89 c6 000003E0 e0 f1 68 3e 63 08 b5 c4 e3 70 78 b4 1f 31 84 5a 000003F0 e2 71 b8 3c 5a 0f 98 c2 2d 71 30 83 c0 00 c5 cc 00000400 08 00 00 00 01 00
```

#### TS RFX FRAME BEGIN message (section 2.2.2.3.1):

```
c4 cc -> TS_RFX_FRAME_BEGIN::CodecChannelT::blockType = WBT_FRAME_BEGIN
0e 00 00 00 -> TS_RFX_FRAME_BEGIN::CodecChannelT::blockLen = 14
01 -> TS_RFX_FRAME_BEGIN::CodecChannelT::codecId = 1
00 -> TS_RFX_FRAME_BEGIN::CodecChannelT::channelId = 0
00 00 00 00 -> TS_RFX_FRAME_BEGIN::frameIdx = 0
01 00 -> TS_RFX_FRAME_BEGIN::numRegions = 1
```

### TS RFX REGION message (section 2.2.2.3.3):

```
c6 cc -> TS_RFX_REGION::CodecChannelT::blockType = WBT_REGION
17 00 00 00 -> TS_RFX_REGION::CodecChannelT::blockLen = 23
01 -> TS_RFX_REGION::CodecChannelT::codecId = 1
00 -> TS_RFX_REGION::CodecChannelT::channelId = 0
0d -> TS_RFX_REGION::regionFlags
TS_RFX_REGION::regionFlags::lrf = 1
01 00 -> TS_RFX_REGION::numRects = 1
00 00 -> TS_RFX_REGION::TS_RFX_RECT::x = 0
00 00 -> TS_RFX_REGION::TS_RFX_RECT::y = 0
40 00 -> TS_RFX_REGION::TS_RFX_RECT::width = 64
40 00 -> TS_RFX_REGION::TS_RFX_RECT::height = 64
c1 ca -> TS_RFX_REGION::regionType = CBT_REGION
01 00 -> TS_RFX_REGION::numTilesets = 1
```

# TS RFX TILESET message (section 2.2.2.3.4):

```
c7 cc -> TS RFX TILESET::CodecChannelT::blockType = WBT EXTENSION
d9 03 00 00 -> TS RFX TILESET::CodecChannelT::blockLen = 985
01 -> TS RFX TILESET::codecId = 1
00 -> TS RFX TILESET::channelId = 0
c2 ca -> TS RFX TILESET::subtype = CBT TILESET
00 00 \rightarrow TS_RFX_TILESET::idx = 0x00
51 50 -> TS RFX TILESET::properties
TS_RFX_TILESET::properties::lt = TRUE (1)
TS RFX TILESET::properties::flags = VIDEO MODE (0)
TS_RFX_TILESET::properties::cct = COL_CONV_ICT (1)
TS RFX TILESET::properties::xft = CLW XFORM DWT 53 A (1)
TS RFX TILESET::properties::et = CLW ENTROPY RLGR3 (4)
TS RFX TILESET::properties::qt = SCALAR QUANTIZATION (1)
01 -> TS RFX TILESET::numQuant = 1
40 -> TS_RFX_TILESET::tileSize = 64
01 00 -> TS RFX TILESET::numTiles = 1
df 03 00 00 -> TS RFX TILESET::tilesDataSize = 991
66 66 77 88 98 -> TS RFX TILESET::quantVals
TS RFX TILESET::quantVals::LL3 = 6
TS RFX TILESET::quantVals::LH3 = 6
TS_RFX_TILESET::quantVals::HL3 = 6
TS RFX TILESET::quantVals::HH3 = 6
```

56 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
TS_RFX_TILESET::quantVals::LH2 = 7
TS_RFX_TILESET::quantVals::HL2 = 7
TS_RFX_TILESET::quantVals::HH2 = 8
TS_RFX_TILESET::quantVals::LH1 = 8
TS_RFX_TILESET::quantVals::HL1 = 8
TS_RFX_TILESET::quantVals::HL1 = 9
```

# TS RFX TILE message (section 2.2.2.3.4.1):

```
c3 ca -> TS_RFX_TILE::BlockT::blockType = CBT_TILE
be 03 -> TS_RFX_TILE::BlockT::blockLen = 958

00 -> TS_RFX_TILE::quantIdxY = 0

00 -> TS_RFX_TILE::quantIdxCb = 0

00 -> TS_RFX_TILE::quantIdxCr = 0

00 00 -> TS_RFX_TILE::xIdx = 0

00 00 -> TS_RFX_TILE::yIdx = 0

26 01 -> TS_RFX_TILE::YLen = 294

3d 01 -> TS_RFX_TILE::CbLen = 317

48 01 -> TS_RFX_TILE::CrLen = 328

00000053:00000178 -> TS_RFX_TILE::YData

0000179:000002b5 -> TS_RFX_TILE::CbData

000002b6:000003fd -> TS_RFX_TILE::CrData
```

#### TS RFX FRAME END message (section 2.2.2.3.2):

```
c5 cc -> TS_RFX_FRAME_END::CodecChannelT::blockType = WBT_FRAME_END
08 00 00 00 -> TS_FRAME_END::CodecChannelT::blockLen = 14
01 -> TS_FRAME_END::CodecChannelT::codecId = 1
00 -> TS_FRAME_END::CodecChannelT::channelId = 0
```

The server has sent a frame that is delineated by TS\_RFX\_FRAME\_BEGIN and TS\_RFX\_FRAME\_END messages. The frame contains a single region, which has a single tileset. This tileset, in turn, consists of one 64x64 tile. The compressed sizes, in bytes, for the YCbCr components of this tile are (294, 317, 328).

# 4.2.4 Sample Decode Data Flow Sequence

The following sections present a sequence of annotated dumps of an encoded tile as it goes through the steps of the decoding algorithm. The sequence starts with the <u>TS\_RFX\_TILESET (section 2.2.2.3.4)</u> message, which contains the encoded tile data, and ends with the resulting decoded 64x64 XRGB image.

# 4.2.4.1 Input TS\_RFX\_TILESET Message

The following is an annotated dump of a TS\_RFX\_TILESET (section 2.2.2.3.4) message containing a single encoded 64x64 tile.

```
000000000 c7 cc 3e 0b 00 00 01 01 c2 ca 00 00 51 50 01 40 00000010 01 00 23 0b 00 00 66 66 77 88 98 c3 ca 23 0b 00 000000020 00 00 00 00 00 00 00 00 ae 03 cf 03 93 03 c0 01 000000030 01 15 48 99 c7 41 a1 12 68 11 dc 22 29 74 ef fd 00000040 20 92 e0 4e a8 69 3b fd 41 83 bf 28 53 0c 1f e2 00000050 54 0c 77 7c a3 05 7c 30 d0 9c e8 09 39 1a 5d ff 00000060 e2 01 22 13 80 90 87 d2 9f fd fd 50 09 0d 24 a0
```

57 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
00000070 8f ab fe 3c 04 84 c6 9c de f8 80 c3 22 50 af 4c
00000080 2a 7f fe e0 5c a9 52 8a 06 7d 3d 09 03 65 a3 af
00000090 d2 61 1f 72 04 50 8d 3e 16 4a 3f ff fd 41 42 87
000000A0 24 37 06 17 2e 56 05 9c 1c b3 84 6a ff fb 43 8b
000000B0 a3 7a 32 43 28 e1 1f 50 54 fc ca a5 df ff 08 04
000000C0 48 15 61 d9 76 43 f8 2a 07 e9 65 f7 c6 89 2d 40
000000D0 a1 c3 35 8d f5 ed f5 91 ae 2f cc 01 ce 03 48 c0
000000E0 8d 63 f4 fd 50 20 2d 0c 9b b0 8d 13 c0 8a 09 52
000000F0 1b 02 6e 42 3b d0 13 4e 84 01 26 88 6a 04 84 34
00000100 2a a5 00 ba 54 48 58 ea 54 02 b4 1d a7 fa 47 82
00000110 ec 7a 77 fd 00 92 66 62 04 a6 9b ff f6 80 c0 69
00000120 01 c2 3e 90 14 20 2f fc 40 96 59 58 0c b1 13 68
00000130 20 2e b5 f5 df ff f8 fc 56 88 60 24 53 b5 41 46
00000140 5f f8 f1 7e de 4a 08 97 e0 55 03 8f e5 75 61 03
00000150 f2 e1 90 01 a2 8e 88 04 98 05 93 6b ff ea c0 60
00000160 a1 88 04 49 bf f7 ff 8c b4 59 90 80 30 64 53 ff
00000170 f5 c4 48 da da cb 80 38 61 57 b2 af 00 e8 7b 46
00000180 e6 d8 02 03 8a 06 18 14 32 83 d0 8a ee bc 81 b4
00000190 28 c4 7f f9 a1 69 00 91 c5 51 ff fe 3f e9 f1 70
000001A0 30 24 10 a7 cb 1f 8a 24 93 ed 83 00 36 20 d1 50
000001B0 e7 d8 ad 58 20 09 22 80 d0 ca 5d 1a d7 f1 60 75
000001C0 2a f2 d7 f8 c0 32 45 86 00 43 01 fe 80 f7 42 81
000001D0 74 84 4c a1 60 4c cb 14 58 01 4d 18 a1 aa 47 0e
000001E0 11 1a 40 7d 41 02 e3 30 cd 33 81 34 06 46 83 a2
000001F0 47 1c 04 aa 20 12 a2 8b 81 c4 9c a0 2e 06 32 f8
00000200 86 85 01 e8 70 f9 46 09 6a bf e0 f5 a4 c8 78 e7
00000210 d2 97 0b bc 3c 97 ff d5 40 94 b2 c1 18 18 11 1f
00000220 43 c1 18 c3 83 7f 9a 31 c4 8e 70 56 da f6 17 de
00000230 d1 02 0d 42 21 13 dc 3a 3c 40 9e f4 01 43 ea 0c
00000240 46 73 a2 7b 0c 80 ff e4 ad 2e 09 b4 63 b0 8c 54
00000250 59 fa ac 76 36 10 05 f0 98 88 83 42 00 20 71 cc
00000260 c1 a9 97 3e 5a 0d 04 50 92 23 20 0d 0a 1c 57 d7
00000270 ff 10 f2 03 0f 58 1b a5 11 f8 f1 b4 12 db 1a 48
00000280 56 1f e3 c7 50 e9 16 b4 bc b0 40 93 ea b5 5b 2f
00000290 fc 50 0a 6f cc 25 e0 06 ab 5f 24 fe 8b cb 42 43
000002A0 7e 69 02 25 c7 38 00 6e e5 80 a8 a4 30 44 15 8f
000002B0 e9 0c d3 a6 c2 14 34 4a fe 03 7f 06 a5 91 02 54
000002C0 fl al al 53 bf 11 f2 8f 83 67 80 09 08 12 3f fd
000002D0 44 91 c2 83 30 50 07 02 82 4d 31 34 06 41 79 6f
000002E0 f0 cc 03 79 00 2c 05 24 ec 8d 29 15 af 44 c8 eb
000002F0 4f e1 fd f1 41 48 81 08 af fe 51 48 ce e7 f9 b6
00000300 0a 30 83 11 f0 0c 3b d2 a6 24 24 ef 25 fa 5a 3e
00000310 92 3e 79 0e 35 61 c8 aa 1c 2e 9a 27 7f ff f0 7d
00000320 30 5b bc 91 ff fe 43 24 28 66 a7 70 99 28 6e 2b
00000330 18 2b d4 a1 77 3b 96 9f f7 eb be 1f 04 34 75 84
00000340 31 42 4c 65 aa 09 50 a0 c4 51 31 d3 26 3a 1b f4
00000350 6e 4a 4e 17 25 84 78 7d 2c 3f 46 18 ca 5f f9 e5
00000360 38 2f d8 71 94 94 e2 cc a3 15 b0 da a9 cb 58 e4
00000370 18 77 93 8a 51 c6 23 c4 4e 6d d9 14 1e 9b 8d bc
00000380 cb 9d c4 18 05 f5 a9 29 f8 6d 29 38 c7 44 e5 3a
00000390 cd ba 61 98 4a 57 02 96 42 02 d9 37 11 de 2d d4
000003A0 3f fe 61 e7 33 d7 89 4a dd b0 34 47 f4 dc ad aa
000003B0 c9 9d 7e 6d 4b cc dc 17 89 57 fd bb 37 75 47 5a
000003C0 ec 2c 6e 3c 15 92 54 64 2c ab 9e ab 2b dd 3c 66
000003D0 a0 8f 47 5e 93 1a 37 16 f4 89 23 00 00 b0 33 56
000003E0 fa 14 le ff 48 7a 7e 0f 10 1f f4 91 c8 10 56 84
000003F0 ff 08 ec b4 ac 0e 0f ff ad c5 e0 1a 2f 82 04 9f
00000400 91 c2 0e fe 48 36 79 01 42 14 ff fe 30 f0 08 18
00000410 f1 81 45 9a 60 c1 79 f0 14 12 10 ce ea 31 5a ff
```

```
00000420 fc 20 13 82 2f c9 02 1f 81 cb 00 e1 10 d2 b4 be
00000430 87 ff b0 le 27 81 b7 04 06 3c c2 04 f6 06 0e 28
00000440 bc 40 bf 12 1e 86 d4 6a 7f 18 1b 96 85 4c 16 80
00000450 df 2c a5 8d 86 a3 4a 8a b4 1b a1 38 a9 d5 ff ff
00000460 ea 06 20 d2 95 1e f4 2f b2 12 0e 61 78 4a 17 52
00000470 5d e4 25 1f fe c0 b3 1f ff ff ec 02 82 80 90 41
00000480 88 de 48 2c 42 52 0b 2f 43 7e 50 78 f2 67 78 41
00000490 34 3d c8 0f 67 al eb 21 fe c0 1f 22 60 41 6c 00
000004A0 92 4b 60 10 d0 0d 01 35 05 0e 87 a2 a0 5d 1f a3
000004B0 af 7f f1 be 8f cd a5 00 1c 10 40 15 76 81 05 ef
000004C0 ee 00 60 84 00 99 40 4a 82 17 e9 fc c4 7f ff fd
000004D0 04 80 06 06 dc af a7 7e 94 75 74 01 00 e0 91 00
000004E0 85 7f 8e d6 0b 20 21 30 ca 62 8e 07 04 e9 45 40
000004F0 5f 47 4a 30 15 41 cb df ff fc bf c3 b4 46 6a 01
00000500 40 d0 a7 34 18 24 1c 2a 45 fe a8 05 08 61 fd a8
00000510 80 71 01 25 9c c1 47 17 37 02 7a 15 ff f3 01 45
00000520 7f d6 80 60 83 67 f8 9d 2f f4 dd 8c 30 01 51 42
00000530 bc 43 7a 6b 9f 84 1e 00 48 c1 e0 b7 e0 7e 99 f2
00000540 4a e9 40 02 81 c3 00 24 3a c5 52 0f 91 c8 68 25
00000550 40 99 a4 25 1a 04 d0 a2 91 dd eb 93 00 21 49 24
00000560 8b 40 75 38 14 a1 fd 3f 88 25 bf 32 00 e3 19 fc
00000570 b9 f8 6f 81 c0 01 b3 93 20 09 08 25 84 e1 34 d4
00000580 1b 48 88 11 a0 15 59 d7 07 81 81 3b a1 40 2e 2f
00000590 48 70 09 c4 76 49 0f 2e 50 2e 46 19 a4 16 a2 1b
000005A0 84 a2 89 58 fc 4f 3f 40 90 4c a3 01 32 09 02 80
000005B0 9c 91 13 2c ba de 5d 99 f2 ff ff 3d 5a 1f a9 02
000005C0 90 8f f3 08 bd 01 f8 d0 2a 95 41 0c 40 0a 20 c4
000005D0 d4 cc 6b 0f f0 80 b1 5d 28 3d 08 c2 f8 31 02 49
000005E0 88 14 28 ed e8 86 3b 00 9f 95 06 37 15 a4 59 c8
000005F0 80 b6 10 f0 e5 b8 18 00 56 1c ff 95 21 0e 7f 2b
00000600 c5 08 59 10 e1 46 31 8d ec e0 a1 99 bb 21 ff fe
00000610 30 10 d0 05 e3 08 50 fc f3 0e 00 8d 68 8e 07 a6
00000620 80 34 42 ed 1f 88 00 f0 8a 21 ae f7 fb 80 28 86
00000630 Of ff ff 82 ea 47 95 91 e0 04 01 44 0c 29 ff 0e
00000640 33 e8 c0 54 04 23 fc 81 5b f0 3c 07 10 70 30 d8
00000650 21 6f ef de 46 09 43 fa 5f ff 0d 72 30 dd 00 db
00000660 e4 48 24 97 08 46 b1 49 c4 4d 80 12 60 ff a4 a6
00000670 ff f6 8c 00 40 05 02 b4 0f f0 3e fc 84 38 81 94
00000680 8b fe 49 ef c0 10 49 88 28 a2 1c 2a 8b 64 d4 86
00000690 d7 ff ff ff eb 91 6b 11 10 00 69 4c bf b4 1c d8
000006A0 00 07 16 80 60 0a 1c 82 42 27 82 43 c9 0a 64 20
000006B0 5a 5f 4e bf 8c 38 82 36 02 07 72 79 07 23 b4 bb
000006C0 57 5f e8 04 dd 39 e9 07 95 be 04 2b dd 8e 22 dc
000006D0 14 2c 61 a3 a9 cd 4f 82 5d a0 44 df f4 96 ff f5
000006E0 2b ff fe 01 19 d2 a2 9e 43 a5 7f f0 4c 4c 2b 3c
000006F0 33 e2 55 ff 04 06 29 2c 0d 22 5d 7c 93 ba 18 af
00000700 f9 32 a6 c3 99 46 79 e3 06 a6 38 8b 92 22 4b db
00000710 1b 36 20 b0 6c 20 ce 37 42 e1 66 d4 49 34 42 8b
00000720 fa 9c 12 99 dc 06 87 fa 46 f8 2f 04 a9 d8 82 07
00000730 a6 30 0f c0 df 35 e8 90 f0 ff ff a8 e0 d7 02 60
00000740 1a c3 20 28 a2 31 29 3c eb 04 a5 dd 48 0e 82 a4
00000750 b6 56 22 06 57 e0 da 10 27 31 0e 11 77 fe 02 60
00000760 16 48 81 8c 0d 05 17 7f cb bb 7e 25 2a 41 fd 8a
00000770 7f c9 36 7c e0 98 7e 92 ef 7e 06 03 13 3e 20 3a
00000780 bf 4c c3 0f 2e 80 74 bf 39 3c f0 a6 b2 e9 3f 41
00000790 55 1f 2c f5 d2 7e 8c ae 4e aa 61 3c bc 3f c4 c7
000007A0 36 dc 23 c8 b8 52 e2 8a 80 18 00 00 b2 46 a2 56
000007B0 0d 12 94 aa bd 01 07 ff fa 34 0c 5f f8 0c 12 50
000007C0 af d6 d1 89 40 a4 ff e0 ce c4 49 25 9d c1 ff 7e
```

```
000007D0 60 24 5d cc 10 c0 be 5a 12 d3 c3 fe 2d 40 7c 28
000007E0 9e 71 01 d2 6e 86 0b c8 f2 9b 45 08 4c 04 52 7e
000007F0 f2 7e d9 cc 0b 1c 20 80 ae af fe b0 6d 23 f2 41
00000800 e3 2e 20 11 4b 74 89 dd ff a8 38 a3 95 82 15 f0
00000810 d0 d5 f1 92 8e ee c0 26 81 e9 47 ff ee 0d 20 34
00000820 31 3a ef 40 b2 29 47 19 7f 04 27 f1 90 85 09 86
00000830 7d 42 e2 54 5d 5f e8 0e d0 2c aa 16 bf 04 a7 f8
00000840 a2 46 0b 08 7a 79 e9 28 62 7c 33 f4 0b 14 82 fa
00000850 61 eb c1 ff 4c a4 11 7f 03 68 44 c1 1f 81 3a 6c
00000860 77 95 02 2b 53 80 e5 10 1e 90 e8 fd 1f a6 40 0b
00000870 13 ff 4e 4d 7f 52 e8 af 9a c1 80 0f 0a 14 02 3c
00000880 c0 09 13 e7 dc c0 1a 28 a0 e4 83 8e 03 88 d5 af
00000890 la bd 91 00 b7 4e ba df f8 db cc 02 43 c4 14 2a
000008A0 3f c8 0d 09 1c 44 f4 01 3c ca 28 56 80 a6 85 00
000008B0 ea 3e 8f eb 9f fc 6e 07 c4 e0 30 78 a0 1e 6f 54
000008C0 78 51 ff 56 4a 01 47 02 4c 21 3b fb 90 0a cc 1d
000008D0 d2 47 ff fc 70 18 22 c0 b9 2f e9 7f 91 d3 66 2f
000008E0 80 2c 24 a7 fa 84 51 ab 6b 72 00 ab 33 04 cf 43
000008F0 ff 17 51 84 0c 01 50 10 8f 90 34 41 44 84 8e 08
00000900 19 04 48 50 84 38 3d 02 52 f9 7c d2 d0 1f 13 42
00000910 a0 21 41 c4 02 02 3d 09 c8 fd 60 7d 35 4f 7f ff
00000920 f9 97 6a d8 00 c3 83 00 09 50 4b 90 8a c7 94 4d
00000930 47 c1 62 32 28 24 09 52 2e 2e 1c 96 44 a0 09 c8
00000940 ce 64 a9 1c 19 0e 52 3e 3e 19 93 a0 36 26 22 08
00000950 9a 00 dd 66 3a 93 d5 89 d1 40 06 d4 a8 22 73 7b
00000960 3d 3f e3 04 94 ff ff ff fc 0c 56 77 ac e0 c4 06
00000970 1f b8 a5 80 fd 68 1c 32 16 03 de 71 2a 3d 14 19
00000980 be c2 88 d9 24 92 5f c5 90 0a 85 c2 3f 87 03 a8
00000990 26 17 c4 06 86 12 87 76 0a 48 16 ed 96 93 ec 1b
000009A0 30 73 e8 1a 3f ff 4d ce 40 f3 0c 51 4b 84 9e 67
000009B0 2b 15 40 1a a0 fc 10 0f d8 81 35 87 ff 98 0f 40
000009C0 00 ba c0 71 e2 00 18 28 b3 82 cc 80 6a a0 43 ff
000009D0 2d d6 04 8a 68 ff ff fc 1a f3 1a 2a 06 c0 01
000009E0 40 0c 30 c1 d0 d7 4f cb 74 1f 07 d3 b4 0d 88 98
000009F0 ea da 9f ce 2b 3c 55 b3 40 14 ff ff ff ea db 9b
00000A00 92 d8 68 08 0b 41 09 26 40 8c f1 b0 9a 98 c0 80
00000A10 8b f0 3d e7 ec 19 68 21 03 29 7f e1 6d 4c 0f 01
00000A20 d1 51 01 1a 50 2a 59 27 80 c1 6e 33 f1 80 e1 49
00000A30 08 e9 17 ff ff ff 80 5a 10 10 36 5e ca f8 3a 00
00000A40 le b0 06 84 01 f3 07 lb 4a c0 le 21 43 8e a5 55
00000A50 77 c7 65 7c c2 df 5e 0c 42 20 d2 48 61 c8 1c 65
00000A60 f8 fe 4c 88 71 1f 82 50 81 a3 54 09 13 28 52 f5
00000A70 e0 82 c3 06 7f fa 2c cf f8 f4 7f ff fd 01 49 a4
00000A80 b8 de 62 84 fe ed 65 1f 3c 3c b2 50 76 30 5b 03
00000A90 c0 08 a6 64 90 c8 cd 14 6e 69 46 7a c6 1c 87 d7
00000AA0 48 7b 49 05 2d 5e 7f cb 67 f0 d9 0d 1e 9e 53 b7
00000AB0 64 a5 a5 10 39 06 11 3f b1 a9 a6 e8 4d 47 77 da
00000AC0 43 76 89 45 09 70 c2 38 0f 09 6f e7 2d 82 35 07
00000AD0 fe 64 18 2e b8 04 42 54 80 43 12 6c 9a 55 c9 0a
00000AE0 a0 79 47 52 65 2a ff 50 11 c9 4e fe 5b 30 a4 e8
00000AF0 30 63 ff 21 12 1b dc 1c 01 41 51 1f ff fa c3 e3
00000B00 55 f1 66 e2 d5 78 5e fa 4d f2 61 01 26 15 a9 f9
00000B10 d9 32 41 90 36 4e ae e3 0b 16 56 8c 6e 42 5d d8
00000B20 le fe 1d 40 3a 50 9f 09 14 eb 6e 48 7a 91 88 7b
00000B30 7d 8f 72 42 39 b0 1c 65 18 23 8b 60 30 00
```

TS\_RFX\_TILESET message (section 4.2.4.1).

```
c7 cc -> TS RFX TILESET::CodecChannelT::blockType = WBT EXTENSION
3e 0b 00 00 -> TS RFX TILESET::CodecChannelT::blockLen = 2878
01 -> TS RFX TILESET::codecId = 1
00 -> TS RFX TILESET::channelId = 0
c2 ca -> TS RFX TILESET::subtype = CBT TILESET
00 00 \rightarrow TS RFX TILESET::idx = 0x00
51 50 -> TS RFX TILESET::properties
TS RFX TILESET::properties::lt = TRUE (1)
TS RFX TILESET::properties::flags = VIDEO_MODE (0)
TS RFX TILESET::properties::cct = COL CONV ICT (1)
TS RFX TILESET::properties::xft = CLW XFORM DWT 53 A (1)
TS RFX TILESET::properties::et = CLW ENTROPY RLGR3 (4)
TS RFX TILESET::properties::qt = SCALAR QUANTIZATION (1)
01 -> TS RFX TILESET::numQuant = 1
40 -> TS RFX TILESET::tileSize = 64
01 00 -> TS RFX TILESET::numTiles = 1
23 0b 00 00 -> TS RFX TILESET::tilesDataSize = 2851
66 66 77 88 98 -> TS RFX TILESET::quantVals
TS_RFX_TILESET::quantVals::LL3 = 6
TS RFX TILESET::quantVals::LH3 = 6
TS RFX TILESET::quantVals::HL3 = 6
TS RFX TILESET::quantVals::HH3 = 6
TS RFX TILESET::quantVals::LH2 = 7
TS_RFX_TILESET::quantVals::HL2 = 7
TS RFX TILESET::quantVals::HH2 = 8
TS RFX TILESET::quantVals::LH1 = 8
TS RFX TILESET::quantVals::HL1 = 8
TS RFX TILESET::quantVals::HH1 = 9
```

### TS\_RFX\_TILE message (section 2.2.2.3.4.1).

```
c3 ca -> TS_RFX_TILE::BlockT::blockType = CBT_TILE
23 0b -> TS_RFX_TILE::BlockT::blockLen = 2851
00 -> TS_RFX_TILE::quantIdxY = 0
00 -> TS_RFX_TILE::quantIdxCb = 0
00 -> TS_RFX_TILE::quantIdxCr = 0
00 00 -> TS_RFX_TILE::xIdx = 0
00 00 -> TS_RFX_TILE::yIdx = 0
ae 03 -> TS_RFX_TILE::YLen = 942
cf 03 -> TS_RFX_TILE::CbLen = 975
93 03 -> TS_RFX_TILE::CrLen = 915
0000002e:000003db -> TS_RFX_TILE::YData
000003dc:000007aa -> TS_RFX_TILE::CbData
000007ab:00000b3d -> TS_RFX_TILE::CrData
```

#### 4.2.4.2 Entropy Decoded Data

The following are dumps of the Y, Cb, and Cr components of the tile after they are decoded using the <u>RLGR3 (section 3.1.8.1.7.2)</u> algorithm. The decoded data for each component has 4,096 (64x64) coefficients, and they contain the quantized DWT sub-bands (see the figure illustrating three-level DWT decomposition in section <u>3.1.8.1.4</u>) at the following ranges.

```
00000000:000003FF -> HL1 (32x32 coefficients)
00000400:000007FF -> LH1 (32x32 coefficients)
00000800:00000BFF -> HH1 (32x32 coefficients)
```

61 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

```
00000C00:00000CFF -> HL2 (16x16 coefficients)
00000D00:00000DFF -> LH2 (16x16 coefficients)
00000E00:00000EFF -> HH2 (16x16 coefficients)
00000F00:00000F3F -> HL3 (8x8 coefficients)
0000F40:00000F7F -> LH3 (8x8 coefficients)
0000F80:00000FFF -> HH3 (8x8 coefficients)
```

# 4.2.4.2.1 Y Component Data

The following is a dump of the Y component data, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000030	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000040	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000050	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000060	+1	+0	+2	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0
00000070	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
08000000	+0	+0	+1	+0	+0	+0	+2	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000090	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000000A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0
000000B0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0
00000000	+0	+0	+0	+0	+0	+0	-3	+0	+0	+0	+1	+0	+0	+0	+0	+0
000000D0	+0	+2	+0	+0	+0	+0	+0	+0	+0	+1	+0	-2	+4	-5	-1	+0
00000E0	+0	+0	+0	+0	+0	-1	-3	+0	+0	+0	+0	+0	+0	+0	+0	+0
000000F0	+0	-3	+0	+3	+0	+0	+0	+0	+0	+0	-1	+4	+4	<b>-</b> 5	-1	+0
00000100	+0	+0	+0	+0	+0	-2	+5	+0	+0	+0	+0	+0	+0	+2	+1	+0
00000110	+2	-5	-4	+1	+0	+0	+0	+0	+0	+0	+1	+3	-1	+5	+0	-1
00000120	+0	+0	+0	+0	+0	-2	-2	-3	+0	+0	+0	+0	+0	+3	+0	+0
00000130	+7	+0	-4	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	-1	+2	-1
00000140	+0	+0	+0	+0	+0	-3	+1	+5	+0	+0	+0	+0	+0	+0	-1	+0
00000150	+0	+1	+7	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
00000160	+0	+0	+0	+0	+2	+0	+0	+0	-2	+0	+0	+0	+0	+0	+1	+0
00000170	-9	-3	+5	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
00000180	+0	+0	+0	+0	+0	+0	-1	-1	-1	+0	+0	+0	+0	+0	+0	+6
00000190	-2	-8	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
000001A0	+0	+0	+0	+0	-3	+0	+0	+0	+0	+0	+0	-1	+0	-1	+0	+5
000001B0	+2	+3	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+2	+0	+0	+0
000001C0	+0	+0	+0	-1	+1	+0	+0	-1	+2	+0	+0	+1	+0	+0	-1	+0
000001D0	-1	+7	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	-2	+0	+0
000001E0	+0	+0	+0	+3	-1	+0	-1	+0	+1	+0	+0	+0	+1	+2	-1	+0
000001F0	<b>-</b> 5	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	-4	+0	+0	+0
00000200	+0	+0	-1	-6	+1	+0	-1	+0	+0	+0	+0	+0	+0	+0	+6	+0
00000210	-1	+0	+1	+0	+0	+1	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000220	+0	+0	+3	-5	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	-1	+1
00000230	+10	+0	+0	+0	-1	+1	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0
00000240	+0	+0	+7	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-5	-5
00000250	+3	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	-1	+0	+0	+0	+0
00000260	+0	-1	-2	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+3	-1	-7
00000270	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-6	+0	+0	+0	+0
00000280	+0	+0	-8	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+3	+2	+4
00000290	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+6	-1	+0	+0	+0	+0
000002A0	-1	+7	-1	+0	+0	+0	-1	-1	+0	+0	+0	+0	+0	-3	-1	+6
000002B0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+3	+1	+0	+0	+0	+0

000002C0	+0	+4	+1	+2	-2	-2	+0	-1	+0	+0	+0	+0	+1	-1	-7	+1
000002D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-6	+0	+0	+0	+0	+0
000002E0	-1	-10	+3	+1	+2	+0	-2	+1	+1	+0	+0	+0	+0	+0	-1	+0
000002F0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+3	-2	+0	+0	+0	+0	+0
00000300	+6	-8	-2	+0	-2	+1	+0	+0	-1	-1	-1	+1	+1	+1	+6	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0	+0	+4	+1	+0	+0	+0	+0	+0
00000320	+3	+2	+0	+1	+0	+0	+1	+1	+0	+0	+1	-2	+5	-3	+2	+0
00000330	+0	+0	+0	+1	+0	+0	+0	+0	+0	-2	+0	+0	+0	+0	+0	+0
00000340	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	-3	+0	+1
00000350	+0	+0	+1	+1	+0	+0	+0	+0	+0	-4	+0	+0	+0	+0	+0	+0
00000360	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1
00000370	-1	-1	+0	+0	+1	+0	+0	+0	+3	+0	+0	+0	+0	+0	+0	+0
00000370	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000390	+0	+0	+1	+1	+1	-2	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000330	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003R0	-1	+0	-2	+1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+3	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000410	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000410	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000420	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000430	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	-1	-1	+0	+0	-1	-1
00000440			+0				+0	+0	+1		+0	+0			+0	+0
00000450	+1 -1	+0 -1	+0 -1	+0 +0	+0	+0		+0 -1	+0	+0 +0	+0	+0	+0 +0	+0 +0	+0	
					+0	+0	+0									+0
00000470 00000480	+0 -1	-1 -1	+0	+0	+0	+0	+0	+0	+0	+0	+0 +0	+0	+0	+0	+0 +0	+0
			-1	+0	+0	+0	+0	+0	+0	+0		+0	+0	+0		+0
00000490	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004B0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	-2	-8	+2	+0
000004C0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004D0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+1	+0	-2	+4	+4	-1	+0
000004E0	+0	+0	+0	+0	+0	-1	+3	-1	+0	+0	+0	+0	+0	+0	+1	+0
000004F0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+3	+3	-7	-1	+0
00000500	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000510	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+6	+3
00000520	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
00000530	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-8	+0
00000540	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-2	-2	+2	-1
00000550	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000560	+0	+0	+0	+0	+0	-1	+0	+0	+1	+1	+3	+1	+0	+0	+0	+0
00000570	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000580	+0	+0	+0	+0	+0	-1	+0	-1	-5	-3	-4	-6	-6	+7	+1	+1
00000590	-1	+0	+0	+0	+0	+0	+0	+0	-1	-2	-3	+0	+1	+0	+0	+0
000005A0	+0	+0	+0	+0	+0	+1	+0	+2	-1	+0	-2	-3	+1	+1	-8	+6
000005B0	+0	-1	+1	+0	+0	+0	+0	+1	+1	+0	+0	+6	-3	-1	+0	+0
000005C0	+0	+0	+0	-1	+5	+2	-6	-2	+0	+0	+0	+2	+7	-6	-1	+0
000005D0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1	-1	+1	+6	+0	+0
000005E0	+0	+0	+0	+0	-2	+1	+0	+0	+0	+0	+0	+0	+0	-1	+6	-1
000005F0	+1	-6	+7	+0	+0	+0	+0	+0	+0	+0	+0	+1	-1	-1	+0	+0
00000600	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000610	-1	-2	+0	-8	+6	+6	+4	+3	+3	+4	-1	-2	+0	+0	+0	+0
00000620	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+2	-1
00000630	-1	+7	-8	+0	+1	-2	-4	-3	-1	+1	-3	-4	+1	+0	+0	+0
00000640	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+1	-3	<b>-</b> 5	+0
00000650	+1	+0	+0	+8	-1	-7	-9	-7	-2	+6	+3	+0	+0	+0	+0	+0
00000660	+0	+0	+1	+0	+0	+0	-1	-1	+0	+0	+0	+0	+0	+1	-1	+0

00000670	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000680	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1
00000690	+1	+0	+0	+0	+0	+0	-1	+1	+0	+0	+1	-1	+0	+0	+0	+0
000006A0	-1	+1	-1	+1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000006B0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	-1	+0	+0	+0	+0	+0
000006C0	+0	+1	+1	+3	+3	+0	+1	+1	-1	+1	+0	+0	+0	+0	+0	+0
000006D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+1	+0
000006E0	+0	+0	+2	+1	-4	-5	-8	-6	-4	+1	+0	+0	-1	+0	+0	+0
000006F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
00000700	+3	-9	<b>-</b> 5	+10	+2	+2	+0	-1	+2	+6	-4	-1	+0	+0	+0	+0
00000710	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000720	-1	+2	-1	-1	+1	+0	+0	+0	+0	+0	-1	+4	-2	-1	+1	-1
00000730	+1	-1	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0
00000740	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1
00000750	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000760	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	-1
00000770	+0	-1	+1	+1	+0	+1	+0	-1	+3	-1	+0	+0	+0	+0	+0	+0
00000780	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1
00000790	-1	-1	+1	+1	+1	+0	-2	-3	+0	+0	+0	+0	+0	+0	+0	+0
000007A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007B0	+0	+0	-1	+4	+2	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007D0	+0	+0	+0	+0	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000800	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000810	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000820 00000830	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
	+0	+0 +0	+0	+0 +0	+0+0	+0 +0	+0 +0	+0+0	+0 +0	+0						
00000840 00000850	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000850	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000870	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000870	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000890	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000000000000000000000000000000000000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000000H0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0
00000800	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000000000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	-1	+1	+0	+0
000008E0	+0	+0	+0	+0	+0	-1	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008F0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	-2	+0	+0	+0
00000900	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000910	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+1	-1
00000920	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000930	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000940	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000950	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000960	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000970	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000980	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+1
00000990	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009A0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1
000009B0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0
000009C0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
000009D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+1	+0	+0	+0
000009E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
000009F0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
00000A00	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A10	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0

00000A20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000A30	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
00000A40	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0
00000A50	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0
00000A60	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0
00000A70	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
08A00000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1
00000A90	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0
00AA0	+0	+1	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AB0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AC0	+0	+0	-1	+0	+0	+1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AD0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AE0	+0	-1	-1	+2	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AF0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B00	+1	-1	+0	+0	+0	+0	+0	+0	+0	+1	-1	+0	+0	+0	+0	+0
00000B10	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0
00000B30	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B40 00000B50	+0+0	+0+0	+0	+0+0	+0+0	+0	+0+0	+0+0	+0	+0	+0	+0	+0	+0	+0 +0	+0
00000B50	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B80	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B70	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B00	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B30	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BH0	+0	+0	-1	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BD0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BF0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000000	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000C10	+1	+0	+0	+1	+0	+0	+1	+0	+0	+0	+0	+0	+0	-1	+0	+0
00000C20	-1	-1	+0	-5	+3	-2	+1	+0	-1	+0	+0	+0	+0	+1	-4	-1
00000C30	+0	+0	+1	-5	-2	+1	+1	+1	+6	-2	-1	+0	+1	-4	+21	+6
00000C40	+0	+0	<b>-</b> 5	-1	+1	+2	+4	+4	+3	+5	+0	+0	-1	+4	-8	-11
00000C50	+0	+0	-2	+8	-1	+0	+3	+1	-18	+16	+1	-1	+2	+0	-4	-4
00000060	+0	+0	-6	+1	-3	-1	+1	+14	-23	+1	+0	+1	+0	+1	-3	-1
00000C70	+0	+0	+0	-5	-2	+3	-1	+11	-8	-3	+0	+1	+0	-1	-3	+1
00000C80	+0	+14	+1	+0	-1	+0	+0	-15	-2	+7	+1	-1	+1	-3	-1	-1
00000C90	-2	-14	+0	+1	+0	+0	+5	-18	+14	-7	-1	-1	-2	+13	+1	-1
00000CA0	+3	-14	+1	-2	+2	-1	+11	-16	-2	+2	-1	+1	+0	-9	+0	-1
00000CB0	+19	+1	+1	+1	+0	+2	+2	+8	+0	+0	+0	+0	+1	-13	+0	+0
00000CC0	-6	-3	-1	+0	-2	-2	+6	+13	+0	+0	+0	+1	+9	+1	+0	+0
00000CD0	-1	+2	+0	+0	+1	+0	-5	+0	+0	-1	+0	+0	+1	+1	+0	+0
00000CE0	+0	+0	+0	+0	+0	+0	+1	-2	-4	+1	+4	+4	-2	+0	+0	-1
00000CF0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	-4	-1	+0	+0	+0	+0
00000D00	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000D10	-2	-1	+1	+1	-1	-3	+0	-2	-3	+0	+0	+0	+0	+0	+0	+0
00000D20	-2	-2	+0	+1	-1	+2	+0	+0	+0	+1	-1	+1	+0	+1	-8	-1
00000D30	+0	+0	+1	-3	+0	+0	-1	+3	+0	+0	+1	-3	-3	-3	+3	-4
00000D40 00000D50	+0+0	+0+0	+0	+1 -1	+0 +2	+0 +7	+3 -1	-3 +0	+3 +3	-1 -2	+1 +1	+1 +0	+0 +4	+1 -1	-5 +0	+20 ±1
00000D50	+0	+0	+0 -3	-1 +2	+2 -9	+ / -12	-1 -19		+3 -1	-2 +2	+1	+0 -1	+4	-1 +9	+0 -13	+1 +0
00000D60	+0	+1	-3 -4	+2 -13	-9 +0	+0	-19 +16	+10 -7	+0	+2	+0 -3	-1 +1	+1 -2	+9 -1	-13 +2	+0 -1
00000D70	+0	+1	+0	+1	+1	+0	+16	- / +4	-3	-17	-3 -14	+1	-2 -4	-14	+2 -1	+0
00000D80	-1	+1	+0	-1	+0	+1	+1	-2	-3 +1	+3	+17	+13	+15	+9	-1 -2	+0
00000D30	+2	-3	+2	+2	-2	+2	+1	-1	+1	+0	+0	-2	+5	+7	-1	+0
00000DA0	+1	+4	-7	-14	-2 -7	+2	-2	+0	+0	+0	+0	+0	+0	-1	+1	+0
00000DB0	-3	+17	+8	-14	+4	+8	-2 -9	+6	+0	+1	+0	+0	+0	+0	+0	+0
00000000	J	/	1 0	Τ.	. 7	. 0	)	. 0	. 0		. 0	. 0	. 0	. 0	. 0	. 0

```
00000DD0 -1
               +1
                    +0
                         +0
                               +0
                                    +0
                                         +0
                                              -2
                                                   -2
                                                        +2
                                                             +0
                                                                  +0
                                                                       +5
                                                                            -1
                                                                                 +0
                                                                                      +0
              +0
                                             +0
                                                   -5
                                                       -4
                                                            -2
                                                                       _1
00000DE0 -1
                    + 0
                         + 0
                              + 0
                                   +0
                                         + 0
                                                                  -6
                                                                            +0
                                                                                 +0
                                                                                      +0
               +0
                                    +0
                                         +0
                                              +0
                                                   +0
                                                        +0
                                                             -7
00000DF0 +0
                    +0
                         +0
                               +0
                                                                  +1
                                                                       +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000E00
          +0
               +0
                    +0
                         +0
                               +0
                                    +0
                                         +0
                                              +0
                                                   +0
                                                        +0
                                                             +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000E10
          +0
               +0
                    +0
                         +1
                               +0
                                    +0
                                         +0
                                              +0
                                                   +0
                                                        +0
                                                             +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000E20
          +0
               +0
                    +0
                         +0
                               +0
                                    +0
                                         +0
                                              +0
                                                   +0
                                                        +0
                                                             +0
                                                                  +0
                                                                       -1
                                                                            +0
                                                                                 -4
                                                                                      -1
00000E30
          +0
               +0
                    +0
                         +0
                               +0
                                    +0
                                         -1
                                              -1
                                                   +1
                                                        -1
                                                             +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 +2
                                                                                      +2
          +0
               +0
                    +0
                         +3
                               +0
                                    +0
                                         +1
                                              +1
                                                   -1
                                                        +1
                                                             +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 -4
                                                                                      -8
00000E40
                                              -1
                                                   -1
00000E50
          +0
               +0
                    +0
                         -1
                               +0
                                    +0
                                         -1
                                                        +0
                                                             +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000E60
         +0
              +0
                    +0
                         +1
                               +1
                                    -1
                                         -3
                                              +3
                                                   +0
                                                        +0
                                                             +0
                                                                  -1
                                                                       +1
                                                                            +0
                                                                                      +0
00000E70
         +0
             +1
                    -2
                         +0
                              +0
                                   -1
                                         +3
                                              +1
                                                   +2
                                                        -1
                                                             +0
                                                                  +0
                                                                       +0
                                                                            -2
                                                                                 -1
                                                                                      +0
00000E80
         +0 +0
                    +0
                         +0
                              +0
                                   +0
                                        +0
                                             +0
                                                  +1
                                                       +0
                                                            +1
                                                                  +1
                                                                      +0
                                                                            -3
                                                                                 +0
                                                                                      +0
                   +0
                                                  -1
                                                                                +0
00000E90
          +0 +0
                         +0
                              +0
                                   +0
                                        +1
                                             +0
                                                       +2
                                                            +0
                                                                 -1
                                                                      +1
                                                                            +0
                                                                                      +0
              +1
00000EA0
          +1
                    +0
                         +0
                              +0
                                   +0
                                        +0
                                             -1
                                                  +0
                                                       +0
                                                            +0
                                                                  -1
                                                                      +0
                                                                            -2
                                                                                 +0
                                                                                      +0
00000EB0
          +2
               +2
                    +1
                         -1
                              +0
                                   -1
                                        +0
                                             +0
                                                  +0
                                                       +0
                                                            +0
                                                                 +0
                                                                      +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000EC0
          -2
               +2
                    +0
                         +0
                              +1
                                   -2
                                        +1
                                             -1
                                                  -1
                                                       +0
                                                            +0
                                                                  +0
                                                                       +0
                                                                            +0
                                                                                 +0
                                                                                      +0
00000ED0
          +0
               +0
                    +0
                         +0
                              +0
                                   +0
                                        +1
                                             +0
                                                  +0
                                                       +0
                                                            +0
                                                                 -1
                                                                      -2
                                                                            +0
                                                                                 +0
                                                                                      +0
                                                                  -1
               +0
                         +0
                              +0
                                   +0
                                             +0
                                                  +1
                                                       +1
                                                            -1
                                                                      +0
00000EE0
          +0
                    +0
                                        +0
                                                                            +0
                                                                                 +0
                                                                                      +0
07300000
         +0 +0
                    +0
                         +0
                              +0
                                   +0
                                        +0
                                             +0
                                                  +0
                                                       +0
                                                            +1
                                                                 +0
                                                                      +0
                                                                            +0
                                                                                + 0
                                                                                      +0
00000F00 +0 +0
                   -2
                         -2
                              +1
                                   +0
                                        -1
                                             -2
                                                  +0
                                                       -1
                                                            +8
                                                                 +6
                                                                      +3
                                                                            +0
                                                                                 -1
                                                                                      -6
                       -13
00000F10 +0 +4
                   +5
                             -53
                                   -3
                                        -2
                                             +0
                                                  -2
                                                      -15
                                                            -7
                                                                +25
                                                                            +3
                                                                                     -25
00000F20 +26 -12 +5 +20
                             +6
                                   +7
                                        -5
                                             -13
                                                  +2
                                                       -2
                                                            +5
                                                               -54
                                                                    +10
                                                                           -2
                                                                                +30
                                                                                      +3
00000F30 -46 +11
                    -9
                                                       -3
                                                                 -5
                         -1
                              -2
                                       -18
                                             -2
                                                            +3
                                                                           -1
                                                                                -5
                                   +1
                                                  +8
                                                                      -4
                                                                                      -2
00000F40
          -3
              +0
                   +1
                        -10
                              -3
                                   +1
                                                  -5
                                                       -1
                                                            -3
                                                                 +3
                                                                      +7
                                                                                -13
                                        -1
                                             +1
                                                                           -14
                                                                                     +10
00000F50
         +0
               -1
                   +11
                         +2
                              +5
                                   +2
                                       +12
                                             +0
                                                  -8
                                                      +24
                                                           -21
                                                                 -49
                                                                       -4
                                                                           +10
                                                                                +9
                                                                                     +31
00000F60
          -1
               +5
                   +10
                         +1
                             +13
                                   -57
                                        -52
                                             +9
                                                  +12
                                                       -6
                                                            -18
                                                                 +5
                                                                      +1
                                                                           -3
                                                                                 -4
                                                                                      -1
00000F70
                    +8
                                   +7
                                         +7
                                                                 +2
         +13
              +21
                        +11
                              +3
                                              -2
                                                  -3
                                                       -1
                                                            +0
                                                                      -14
                                                                           -19
                                                                                 -7
                                                                                     +1
                                                       -7
00000F80
          -1
               -1
                    -3
                         -2
                              +0
                                   +0
                                        -1
                                             -1
                                                  -1
                                                            +3
                                                                 +4
                                                                      +7
                                                                            -1
                                                                                 -6
                                                                                     -14
               -7
                   +3
                             -16
                                             -1
                                                  -9
                                                            +7
00000F90
          -1
                        -12
                                   -2
                                        +2
                                                       +1
                                                                -21
                                                                      +25
                                                                            -4
                                                                                 -2
                                                                                     -23
                                                       -2
                                                                 -7
00000FA0
         +2
              +2
                   +3
                         -4
                             +22
                                   -4
                                        +5
                                             -4
                                                  -2
                                                            +4
                                                                      +0
                                                                           +0
                                                                                 +3
                                                                                      +2
00000FB0 +17
              -6
                   +7
                        +5
                              +3
                                   +1
                                        -5
                                             +0
                                                  +1
                                                       +0
                                                            +0
                                                                +6
                                                                      +1
                                                                            -4
                                                                                +2
                                                                                     +0
00000FC0
         -1
              +1
                   -1
                        -14
                              +3
                                   +0
                                        -7
                                             -4
                                                 +50
                                                      -13
                                                          -11
                                                                +34
                                                                     -26
                                                                          -23
                                                                                -3
                                                                                     -1
00000FD0 +45 -4 +21
                        +57 -17
                                  -43 -17 -15 +27
                                                       -7
                                                          +25 +30 -23
                                                                          +65
                                                                               -13 -88
00000FE0 +45 -103 +85 +71 -116
                                  +88 -30 -57 +57 -101 +94 +25 +17
                                                                           +5
                                                                                +6 -107
00000FF0 +15 -31 +20 -26 +142 -18 -23 -95 +69
                                                       -7 -13
                                                                -9
                                                                     +5 +18 -38
                                                                                    -18
```

#### 4.2.4.2.2 Cb Component Data

The following is a dump of the Cb component data, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

```
00000000
         +0
             +0
                 +0
                     +0
                         +0
                             +0
                                  +0
                                     +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
                                             +0
                                                                     +0
00000010 +0
             +0
                 +0
                     +0
                         +0
                             +0
                                  +0
                                     +0
                                         +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
             +0
                 +0
                     +0
                                         +0
                                             +0
                                                         +0
                                                                 +0
                                                                     +0
00000020 +0
                         +0
                             +0
                                  +0
                                     +0
                                                 +0
                                                     +0
                                                             +0
                                     +0
00000030 +0
             +0 +0
                    +0
                         +0
                             +0
                                 +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
00000040 +0
            +0 +0 +0 +0
                             +0
                                 +0
                                     +0
                                         +1
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
00000050 +0
            +0 +0 +0 +0
                             +0
                                 +0
                                     +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
00000060 +0 +0 -1 +0 +0
                                         -1 +0
                             +0
                                 +0
                                     +0
                                                +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
         -1
             +1
                 -1 +0 +0
                             +0
                                 +0
                                         +0 +0 +0
                                                     +0
                                                         +0
                                                                     +0
00000070
                                     + 0
                                                             +0
                                                                 + 0
08000000
         +0
                 +0 +0
                         +0
                             +0
                                 +9
                                     -1
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
             +0
00000090
         +0
             -1
                 +7
                     +0
                         +0
                             +0
                                 +0
                                     +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
         +0
             +0
                 +0
                     +0
                         +0
                             +0
                                 +1
                                         +0
                                             +0
                                                     +0
                                                         +0
000000A0
                                     +1
                                                 +0
                                                             +0
                                                                 +0
                                                                     +0
000000B0
         +0
             -6
                 +3 +2
                         +2
                             +0
                                 +0
                                     +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +1
                                                             -1
                                                                 +1
                                                                      +0
000000C0
         +0
             +0
                 +0 +0
                         +0
                             +0
                                 -8
                                     +0
                                         +0
                                             +0
                                                 +0
                                                     +0
                                                         +0
                                                             +0
                                                                 +0
                                                                     +0
                                                         -7
         +0
                 -2 -1
                         -1
                             +1
                                 +0
                                     +1
                                         +0
                                             +0
                                                 +0
                                                     +3
                                                             +7
                                                                 -8
                                                                     +1
000000D0
             -6
000000E0 +0 +0 +0 +0 +0
                            +5
                                -4
                                     +0
                                         +0
                                            +0
                                                +0
                                                     +0
                                                         +0
                                                            +0
                                                                 +0
                                                                     +0
000000F0 +1 +6 +0 -10 +0 +0 +0
                                     -1 + 0
                                             +1 +0
```

00000100	+0	+0	+0	+0	+0	+5	+4	+0	+0	+0	+0	+0	+0	+1	+1	+0
00000110	-2	+6	+9	-2	+0	+0	+0	+0	+0	+0	+0	+1	+0	+2	+6	+0
00000120	+0	+0	+0	+0	-1	-6	-2	-2	+0	+0	+0	+0	+0	+1	+0	+0
00000130	-7	+0	+5	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
00000140	+0	+0	+0	+0	+2	-6	+0	+4	+0	+0	+0	+0	+0	+1	-1	+1
00000150	+0	-1	-7	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-9	+0	+0
00000160	+0	+0	+0	+0	+8	+0	+0	+0	-2	+0	+0	+0	+0	+1	+1	+0
00000170	+6	+3	-4	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+2	+0	+0
00000180	+0	+0	+0	+0	+0	+0	-1	-2	-1	+0	+0	+0	+0	+0	+0	-4
00000100	+1	+6	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+9	+0	+0
00000130	+0	+0	+0	+0	-8	+1	+0	+1	+0	+0	+0	+0	+0	+1	+0	-3
000001B0	-1	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-8	+1	+0	+0
000001C0	+0	+0	+0	+0	+1	+0	+0	+0	-1	+0	+0	+0	+0	+0	+1	+0
000001D0	+0	-4	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	<b>-</b> 5	+0	+0	+0
000001E0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0
000001F0	+3	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+8	+0	+0	+0
00000200	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	+0
00000210	+0	+0	+0	+0	-1	+1	+0	+0	-1	+0	-1	+0	+1	+0	+0	+0
00000220	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000230	-5	+0	+0	+0	+0	+0	-1	+0	+0	+0	+1	-2	+0	+0	+0	+0
00000230	+0	+0	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+3	+2
00000250	-1	+0	+0	+0	+0	+0	+0	+0	+0	+2	+0	+2	+0	+0	+0	+0
00000260	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	+1	+4
00000270	+0	+0	+0	+0	+0	+2	+0	+0	+0	-1	-1	+10	+0	+0	+0	+0
00000280	+0	+0	+2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	-1	-2
00000290	+0	+0	+0	+0	+0	-2	+2	+0	+0	+0	-10	+1	+0	+0	+0	+0
000002A0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+2	+1	-4
000002B0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0	-3	-1	+0	+0	+0	+0
000002C0	+0	-1	+0	-1	+1	+1	+0	+0	+0	+0	+0	+0	-1	+1	+6	+0
000002D0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+1	+12	+0	+0	+0	+0	+0
000002E0	+0	+1	-1	+0	-1	+0	+1	+0	-1	+0	+0	+0	+0	+0	+2	+0
000002E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-7	+5	+0	+0	+0	+0	+0
00000300	-1	+1	+1	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1	-8	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0	+0	-11	-1	+0	+0	+0	+0	+0
00000320	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	-1	+5	-4	+0
00000330	+0	+0	+0	+0	+0	+0	+0	+0	+1	+6	+0	+0	+0	+0	+0	+0
00000340	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+7	+1	+0
00000350	+0	+0	+0	+0	+0	+0	+0	+0	-2	+10	+0	+0	+0	+0	+0	+0
00000360	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+4	-1	+0
00000370	+0	+0	+0	+0	+0	+0	+0	+0	-10	+1	+0	+0	+0	+0	+0	+0
00000380	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+3	+0
00000390	+1	+0	+0	+0	+0	+1	-2	+0	+1	+0	+0	+0	+0	+0	+0	+0
000003A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003H0	+1	+0	+1	+0	-1	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003D0	+0	+0	+0	-2	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003F0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000400	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000410	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000420	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+2	+4	+5	+2	-1
00000430	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000440	+0	+0	+0	+0	+0	+0	+0	-1	+7	+4	-8	-7	-4	-4	-6	-7
00000440	+7	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000450	+1	+1	+1	+0	+0	+0	+0	-3	-3	+1	+0	+0	+0	+0	+0	+0
00000400	+1	-8	+6	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000480	+1	+1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000490	+0	+0	-1	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0

000004B0	+0	-1	+1	+1	-6	+8	-1	+0	+0	+0	+0	+0	+2	+8	+2	+2
000004C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004D0	+0	+0	+0	+1	+0	+0	-8	+7	+7	+4	+5	+8	+1	-1	-7	+0
000004E0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+1	+0
000004F0	+0	-1	+1	+0	+0	+0	+0	+1	-2	-4	-4	-1	+1	-1	+0	+0
00000500	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000510	+0	+0	+1	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+2	-2
00000520	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0
00000530	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0
00000530	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	-1	+2	-1
00000550	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000560	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	-3	-1	+1	+0	+1	+0
00000570	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0
00000580	+0	+0	+0	+0	+1	-4	-6	+4	+7	+5	+4	+6	+5	-5	+0	+0
00000590	+1	+0	+0	+0	+0	+0	+0	+0	-1	-4	-3	+0	+0	+0	+0	+0
00000530	+0	+0	+0	+0	+1	+5	-1	+0	+1	+1	+1	+2	+0	-1	+5	-4
000005B0	+0	+0	+0	+0	+0	+0	+0	+1	+2	+0	+1	+5	-3	+2	+0	+0
000005C0	+0	+0	+0	+0	-1	+0	+1	+0	+0	+0	+0	-1	-3	+3	+0	+0
000005D0	+0	+0	+0	+0	+0	+0	+1	+0	-1	+0	-1	-1	+1	-2	+0	+0
000005E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	+1
000005F0	-1	+3	-4	+0	+0	+0	+0	+0	+0	+0	+1	-2	-7	+2	+0	+0
00000600	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000610	+1	+1	+0	+5	-5	-4	-3	-3	-7	-9	+3	+8	-1	+0	+0	+0
00000620	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000630	+1	-4	+4	+0	-1	+1	+3	+4	+2	-2	+4	+8	-2	+0	+0	+0
00000640	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+2	+2	+0
00000650	-1	+0	+0	-4	+0	+5	+6	+7	+2	-9	-7	+0	+1	+0	+0	+0
00000660	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0
00000670									+0		+0	+0				+0
	+0	+0	+0	+0	+0	+0	+1	+0		+1			+0	+0	+0	
00000680	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1
00000690	+0	+0	+0	+0	+0	+0	-2	+4	+0	+0	+0	+2	+0	+0	+0	+0
000006A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000006B0	+0	+0	+0	+0	+0	+0	+0	-1	-5	+2	-1	+0	+0	+0	+0	+0
000006C0	+0	+0	+0	-1	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000006D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0
000006E0	+0	+0	+0	+0	+1	+1	+2	+1	+1	+0	+0	+0	+0	+0	+0	+0
000006F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	-1	+0	+0	+0	+0
00000700	+0	+1	+1	-2	+0	-1	+0	+1	-1	-1	+1	+0	+0	+0	+1	+0
00000710	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000720	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+1	-1	+0
00000730	+0	-1	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0	+0
00000730	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	-3	+0
00000750	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000760	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+8	-7
00000770	+0	+0	+0	+0	+0	+0	+1	-2	-11	+2	+0	+0	+0	+0	+0	+0
00000780	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+2
00000790	+5	+0	-9	-10	-7	-4	+7	+9	+0	+0	+0	+0	+0	+0	+0	+0
000007A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007B0	+0	+0	+0	-4	-2	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007D0	+0	+0	+0	+0	+2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000810	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000820	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000830	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000840	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0
00000850	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0

00000860	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0
00000870	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
08800000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000890	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
0A800000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008B0	+0	-1	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+1	-2	+1	+0
000008C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008D0	+0	+0	+0	-1	+0	+0	+0	+1	+0	+0	+0	+2	+0	-1	+0	+0
000008E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008F0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000900	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000910	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000920	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000930	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0
00000940	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000950	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000960	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000970	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0
00000980	+0	+0	+0	+0	+0	-1	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000990	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009A0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009B0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0
000009E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009F0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+1	+0	+0	+0
000000A00	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A10	+1	+0	+0	+0	-1	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0
00000A20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A30	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-2	+0	+0	+0	+0
00000A40	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A50	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+1	+0	+0	+0	+0
000000A60	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A70 00000A80	+0	+0	+0	+0	+0	+0	-1 +0	-1 +0	+0	+0	+0	+0	+0	+0	+0	+0
00000A80	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0
00000A30	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AA0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0
00000AD0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AC0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AE0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0
00000B00	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B10	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B30	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0
00000B40	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	+0	+0
00000B50	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B60	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0
00000B70	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0
00000B80	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B90	+1	+0	+0	+1	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BA0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BB0	+0	+0	+1	+1	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BC0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BD0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BF0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000C00	+0	+0	+0	+1	+0	+0	+1	-1	+0	+0	+0	+0	+0	+0	+0	+0

```
00000C10 -1 +0 +0 +2 +0
                            -1
                                -2
                                   +1 +1 -2 +0
                                                  +0
                                                      +0 +0 +0
                                                                  +0
00000C20 +1 +1 -2 -8
                       _1
                                   -1 -5 +9 +2
                            +1
                                +0
                                                  +0
                                                      +0 -1
                                                             +2
                                                                  + 0
00000C30 +0
           +0 +1 -17
                            +0
                                -1
                                   -1 -18 +20
                                                             -8
                        +0
                                              -1
                                                  +1
                                                      +0 +5
                                                                  +8
00000C40
         +0
            +0 +17
                    +1
                        +0
                            +0
                                +2
                                   +3
                                      -6 -10
                                               +3
                                                  -1
                                                      +1
                                                          +0
                                                             +3
                                                                +32
00000C50
         +0
             -1
                +5
                    +5
                        -1
                            +0
                                +5
                                   +4 +14
                                          -16
                                               +1
                                                   +0
                                                      +0
                                                          -1 -17
00000C60
         +0
             -1 -17
                    -3
                        -2
                            +1
                                -1
                                   -9
                                      +15
                                           -1
                                               +0
                                                   +1
                                                      -1
                                                          -1
                                                             -8
                                                                  -4
000000070
         +0
            +1
                +0
                    +3
                        +1
                            -1
                                +1
                                   -6
                                      +3
                                           +2
                                               +0
                                                  +2
                                                      -1
                                                          +2 +11
                                                                  +0
000000080
            -3
               +0
                    +1
                                   +7
                                       +1
                                           -3
                                                   -1
                                                         +0
                                                             +4
                                                                  +0
         + \cap
                        +1
                            + \Omega
                                + 0
                                              +0
                                                      -4
00000C90
                                -2 + 10
                                       -7
         +0
            +3 +0
                    +0
                        +0
                            +0
                                           +4
                                              +0
                                                   -1
                                                      +3 -24
                                                              -2
                                                                  +0
00000CA0
                +0
                   +2
00000CB0
           +1 +0
                   -1 +0
                            +0
                                -2
                                       +0
                                          +0 +1
                                                   -2
                                                      +0 +24
                                                              +0
                                                                  +0
00000CC0
        +1 +2 +1
                   +0 +0 +0
                               -1 -17
                                       +0 +0 +0
                                                  -1 -26
                                                         +0
                                                             +0
                                                                  +0
            -1
                                       -1 +0 +0
                                                             +0
00000CD0
        +0
                +0 +0 +0 +0 +22 -2
                                                  +2
                                                      -7
                                                         -3
                                                                  +0
00000CE0
         +0
            +0
                +0 +0 +0
                           +0
                               -1
                                   +2
                                       +1
                                          -1
                                              -2
                                                  -4
                                                      +8
                                                         +0
                                                             +0
                                                                  +0
00000CF0
         +0
             +0
                +0 +0
                        +0
                            +0
                               +0
                                   -1
                                       +0
                                           +0
                                              +3
                                                  +2
                                                      +0
                                                          +0
                                                              +0
                                                                  +0
00000D00
         +0
             +0
                +0
                    +0
                        -2
                            +0 +10
                                   +6
                                       -2
                                           +0
                                               +0
                                                   +0
                                                      +0
                                                          +0
                                                              +0
                                                                  +0
00000D10
         +1
            +1
                +0 +2
                        -3 -19
                               -9 -13 -13 +14
                                              -2
                                                  +0
                                                      +0
                                                          +0
                                                              +0
                                                                  +0
                               +0 +0 +0 -2 +14
                +0 +0 +1
                                                      -2
                                                          -2
00000D20
        +1
            +1
                           -1
                                                  +2
                                                              +6
                                                                  +8
000000030 +0
            +0 +1 -2 +0
                           +0
                               +0
                                  +1
                                      +0 +1 +0 -17
                                                      -6 +1
                                                             -8
                                                                  -9
00000D40 +0 +0 +1 -1 +0 +1 +1 -1 +0 +0
                                                  -2
                                                      -1 +0 +0
                                                                  -2
00000D50 +0 +0 +1 +1 -1 -8
                               +0 +3 -1 +0 +1
                                                  +1
 \tt 00000D60 +0 +1 -7 +13 +13 +12 +14 -7 +0 +0 +0 \\
                                                  -1
                                                     +1 +9 -7
                                                                  +2
00000D70 +0 +0 -1 +2 +0 +0
                                                  +2 +0 +1 -12
                               -8 +4 +0 -9 +2
                                                                 +3
00000D80 +0 +0 +0 +0 +0 +0
                               +0 -2
                                      +1 +9 +10
                                                  -4 +2 +35 +4
                                                                  + 0
00000D90
         +0 +0
                +0 +1 +0
                            +0
                                -1
                                   +1
                                       +0
                                           -1 -10
                                                  -8 -21 -13 +3
                                                                  +0
00000DA0
         -1
            +1
                -1
                    +0
                        +1
                            -1
                                +0
                                   +1
                                       +0
                                           +1
                                              +1
                                                   -5 + 14 + 14
                                                              -2
                                                                  + 0
00000DB0
                    +3
         +0
             +0
                +2
                        +2
                            +0
                                +1
                                   +1
                                       +0
                                           +1
                                               +0
                                                   +0
                                                      +1
                                                              -1
00000DC0
         +0
            -3
                -1
                    +0
                        +0
                            -2
                                +2
                                   +0
                                       -1
                                           -1
                                              +0
                                                  +0
                                                      -1
                                                          +1
                                                              +0
                                                                  +0
000000000
         +0
            -1
                + 0
                    +0
                        +0
                            +0
                                +2
                                  -12
                                       -4
                                           +1
                                              +1
                                                  +2 -20
                                                         +4
                                                             +0
                                                                  + 0
00000DE0
         +0
            +0
                +0
                   +0
                        +0
                                   -3 + 19 + 16 + 15 + 24
                                                      +3
                                                          +0
                                                              +0
                                                                  +0
                            +0
                                +0
00000DF0
        +0
            +0
               +0
                   +0
                       +0
                            +0
                                +0
                                   +0
                                      +0
                                          +0
                                              +6
                                                      +0
                                                         +0
                                                             +0
                                                                  +0
00000E00
            +0 +0
                   +0
                       +0
                            +0
                                      +0
                                          +0 +0
                                                             +0
00000E10
        +0 +0 +0 +4 -1
                            +0
                                +0
                                   -1
                                      +3 -2 +0
                                                  +0
                                                      +0
                                                         +0
                                                             +0
                                                                  +0
00000E20
        +0 +0 +0 -1 +0 +0
                               +0 +0 +0 -1 +3
                                                  +0
                                                      +0
                                                         -1
                                                             +2
                                                                  +0
00000E30
         +0
             +0
                +1 +0 +0
                            +0
                                +0
                                   +0
                                       -1 +2 +2
                                                  -1
                                                      +1
                                                          -1
                                                              +3
                                                                  +4
00000E40
         +0
             +0
                +1
                    +2
                        +0
                            +0
                                +0
                                   +1
                                       +2
                                          -1
                                              +0
                                                  +0
                                                      +0
                                                          +0
                                                              +1
                                                                  +0
00000E50
         +0
             +0
                -2
                    -1
                        -1
                            +0
                                +0
                                   +1
                                       +1
                                           +0
                                              +0
                                                  +0
                                                      +0
                                                          +0
                                                              -1
                                                                  +0
00000E60
         +0
             +1
                -2
                    +0
                        +0
                            +0
                                +2
                                   -2
                                       +0
                                          +0
                                               +0
                                                  -1
                                                      +1
                                                          -1
                                                              +4
                                                                  +0
00000E70
         +0
            +0
                +0 +0
                        +0
                            +0
                                -2
                                   +0
                                       -1
                                          +0
                                              -1
                                                   -1
                                                      +1
                                                          -1
                                                              +3
                                                                  +0
            +0 +0 +0 +0
        +0
                                       -1 +0 +0
                                                      +0 +6
00000E80
                            +0
                               +0
                                   +0
                                                  -1
                                                             +0
                                                                  +0
00000E90 + 0 + 0 + 0 + 0 + 0
                                       +1 -1
                                                      -2 + 0 + 0
                                                                  +0
                            +0
                               +0 +0
                                              +0
                                                  -2
00000EA0 +0 +0 +0 +0 +0 +0
                               +0
                                  +1
                                      +0 +0 +1
                                                  -2
                                                      +0 -2 +0
                                                                  +0
00000EB0 +0 +0 -1 +0 +0 +0
                              +0 +0 +0 +0 +0
                                                  +0
                                                     -1 +0 +0
-1 +0 +0
                                                                 +0
00000ED0 +0 +0 +0 +0 +0 +0
                              +2 -3 +0 +0 +0
                                                  +2
                                                      +6 +0 +0
                                                                 +0
00000 \text{EE}0 + 0 + 0 + 0 + 0 + 0
                            +0
                               +0
                                       +0
                                           -1 + 0
                                                  +2
                                                      +0 +0 +0
                                   -1
                                                                  +0
00000EF0
         +0
            +0
                +0
                   +0
                        +0
                            +0
                                +0
                                   +0
                                       +0
                                          +0
                                              -1
                                                  +0
                                                      +0
                                                          +0
                                                             +0
                                                                  +0
00000F00
         +0
            -9
                -1
                    -2
                        +5
                            +1
                                +1
                                       +1 +33
                                               -2
                                                  -2
                                                      +5
                                                              +2
                                   +0
                                                          +1
                                                                  -3
00000F10
         -4 -14
                -3
                    +2 +76
                            +4
                                +5 +17
                                       +3 - 37
                                               +1 -15
                                                      -8
                                                          +3
                                                              -1
                                                                 +80
                            +7 -16 +15
00000F20
         -5 +14
                -2 -11
                       +2
                                       -2
                                          +3
                                              -2 +29
                                                      -2
                                                          +1 -51
                                                                  -8
00000F30
           -4 + 3
                   +4 +6
                           +4 +35
                                       -1 +1
                                              -2
                                                  +8
                                                      -3
                                                          -7 +17
                                                                  +1
         +6
                                   -1
         +1 -4 +35
                   -4 +34 -5
                                                      +3 -17 +46
00000F40
                               +2
                                   -1
                                      +3 +0 +0
                                                  +2
                                                                 +10
00000F50
         -2 +4 -9
                   -5
                       -2 +3
                               +4
                                  +0 +1 +4 +28 +33
                                                      +2
                                                         -3 + 14
00000F60
        -1 +0 -4 -1 -7 +38 +60
                                  -5 -3 +2 +6
                                                  +1
                                                      +4
                                                         +4
                                                            -3
                                                                  +1
        -1 -3 -2 -7 -28 -5 -31 +8 +2 +0 +0
00000F70
                                                  -8 +56 +85 +24
                                                                 -3
        +0 -10 +3 -4 +4 +2 +1 +0 +1 +4 +2 +4 +15 +10 +6
                                                                 -9
00000F80
00000F90
         -1 -1
                -4 +1 +5
                           +2
                               +0
                                  +4 +1 +13
                                              -3 +10 -11 -4
                                                             +2
                                                                  +7
00000FA0
         -1 +0 -2 +1 -14
                           -3 +2 +2
                                      +0
                                          -1
                                              -1 +3
                                                      +0 -5 -9
                                                                  -4
         -2
            +2
                -5 -28 +1
                           +7 +17
                                       +0
                                           +0
                                                      +5 +15
00000FB0
                                   +1
                                              +0 -18
```

```
00000FC0 +55   -4 +34   -14 +18   -33   +7   -1   -16   +19-109   -29   +19+123   +10   -6   00000FD0   -31   +13-129   +32   +31   -43   +7   +9   +83   -29   -34   +15   +32   -44   -12   -18   00000FE0   +79   +31   -21   -40   +58   -51   -33   +63   -8   +35   -31   -13   -10   -20   -44+102   00000FF0   -11   +9   +2   +17-136   +4   -58+208   -49   +6   +4   +11   -83   -38   +84   +54
```

### 4.2.4.2.3 Cr Component Data

The following is a dump of the Cr component data, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

```
00000030 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0
00000080 +0 +0 +1 +0 +0 +0 -13 +2
                    -1 +0 +0 +0
                            +0 +0 +0
                                   +0
00000090 +0 +1 -10 +0 +0 +0 +0 +0 +0 +0
                             +0 +0 +0
                           +0
                                   +0
000000A0 +0 +0 +0 +0 +0 +1 -1
                   -1
                    +0 +0 +0
                           +0
                             +0 +0 +0
                                   +0
+0
00000000 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +1 \ \ +12 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0
                                   +0
000000000 \ \ +0 \ \ +8 \ \ +2 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ -1 \ \ +3 \ \ -3 \ \ +3
                                  -1
00000100 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad -7 \quad -4 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad -2 \quad -1 \quad +0
00000120 + 0 + 0 + 0 + 0 + 1 + 9 + 1 + 2 + 0 + 0 + 0 + 0 + 0 - 2 + 0
                                   +0
        -3 -1
            +0
              +0 +0 +0
                     +0
00000130
    +6 +0
                       +0
                         +0
                           +0
                             +0 +0
                                 +0
00000140 +0 +0 +0 +0 -3 +9 -1 -3 +0
                       +0
                         +0
                           +0 +0 +0 +1
                                   +0
+0
000001 \texttt{A}0 \quad +0 \quad +0 \quad +0 \quad +0 \quad +13 \quad -1 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad -1 \quad +0 \quad +3
 \verb| 000001C0 +0 +0 +0 +0 +0 -2 +0 +0 -1 +2 +0 +0 +0 +0 +0 +1 +0 \\
+0
000001E0
    +0 +0
        +0 -1 +0
              +0
                 -1
                   +0
                    +1
                       +0 +0
                           +0
                             +0 +1
                                 -1
    000001F0
                             -5 +0 +0
                                   +0
+0
00000210 -1 +0 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
                                   +0
00000220 +0 +0 -1 +1 +0 +0 +0 +0 +0 +0 +0 +0 -1 -1 +1
00000260 \quad +0 \quad +0 \quad +1 \quad +0 \quad +0 \quad +0 \quad -1 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad +2 \quad +0 \quad -5
00000280
    +0 +0 +2 +0 +0 +0 +0 +0 +0 +0
                           +0 +0 +2 +1
                                   +3
00000290 +0 +0
        +0 +0 +0 +0 +0 +0 +0 +6 -1
                             +0 +0 +0
000002A0 +0 -2 +0 +0 +0 +0 -1 -1
                    +0 +0 +0
                           +0 +0 -2 -1
                                   +4
000002C0 + 0 -1 + 0 + 0 -1 -1 + 0 + 0 + 0 + 0 + 0 + 0 + 0 + 0 -1 -6 + 0
000002D0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -1 -8 +0 +0 +0 +0 +0
```

000002F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+5	-4	+0	+0	+0	+0	+0
00000300	-1	+2	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+1	+6	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0	+0	+7	+1	+0	+0	+0	+0	+0
00000310	-1	+0	+0	+0	+0	+0	+1	+1	+0	+0	+0	+0	+0	-4	+3	+0
00000320										-4	+0	+0			+0	+0
	+0	+0	+0	+0	+0	+0	+0	+0	-1				+0	+0		
00000340	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-5	-2	+0
00000350	+0	+0	+1	+1	+0	+0	+0	+0	+1	-7	+0	+0	+0	+0	+0	+0
00000360	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+1
00000370	+0	-1	+0	+1	+0	+0	+0	+0	+7	+0	+0	+0	+0	+0	+0	+0
00000380	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	+0
00000390	-1	+0	+0	+1	+0	-1	+1	+1	-1	+0	+0	+0	+0	+0	+0	+0
000003A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003B0	-1	+0	-1	+0	+1	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003C0	+0	+0	+0	+2	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000003D0		+0														+0
	+0		+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	
000003F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000400	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000410	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000420	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-3	-6	-6	-3	+1
00000430	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000440	+0	+0	+0	+0	+0	+0	+0	+1	-10	-5	+11	+9	+6	+5	+9	+11
00000450	-11	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000460	-1	-1	-1	+0	+0	+0	+0	+4	+4	-1	+0	+0	+0	+0	+0	+0
00000470	-1	+11	-10	+2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000480	-1	-1	-1	+0	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0
00000490	+0	+0	+1	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000130	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000004H0	+0	+1	-2	+0	+3	-4	+0	+0	+0	+0	+0	+0	-1	-4	-1	-1
000004B0										+0	+0	+0	+0	+0	+0	+0
	+0	+0	+0	+0	+0	+0	+1	+0	+0							
000004D0	+0	+0	+0	+0	+0	+0	+4	-3	-3	-2	-2	-4	-1	+1	+3	+0
000004E0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	-1	+0
000004F0	+0	+1	-1	+0	+0	+0	+0	-1	+1	+2	+2	+0	+0	+0	+0	+0
00000500	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0
00000510	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+2
00000520	+0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000530	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-3	+0
00000540	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+2	+1	-1	+1
00000550	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000560	+0	+0	+0	+0	+0	+0	+0	+0	+0	+3	+2	+1	+0	+0	+0	+0
00000570	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000580	+0	+0	+0	+0	-1	+6	+8	-5	-7	-5	-4	-5	-4	+5	+0	+0
00000590	-1	+0	+0	+0	+0	+0	+0	+0	+0	-1	-1	+0	+0	+0	+0	+0
00000530	+0	+0	+0	+0	-2	-8	+1	+0	-1	+0	-1	-2	+0	+1	-6	+4
	+0	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	-1	+0	+0
000005B0																
000005C0	+0	+0	+0	+0	-1	+0	+1	+0	+0	+0	+0	+1	+4	-4	+0	+0
000005D0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+3	+0	+0
000005E0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+4	-1
000005F0	+1	-4	+5	+0	+0	+0	+0	+0	+0	+0	+0	+1	+2	-1	+0	+0
00000600	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000610	-1	-1	+0	<b>-</b> 5	+4	+4	+3	+3	+4	+4	-1	-4	+0	+0	+0	+0
00000620	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-1
00000630	-1	+4	-5	+0	+1	-1	-3	-3	-1	+1	-3	-5	+1	+0	+0	+0
00000640	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-2	-3	+0
00000650	+1	+0	+0	+5	+0	-5	-6	-5	-1	+6	+4	+0	-1	+0	+0	+0
00000660	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000670	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000680	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	-1
00000690	+1	+0	+0	+0	+0	+0	+0	-1	+0	+0	+1	-1	+0	+0	+0	+0
0000000000	ΓT	1-0	1.0	1 0	1 0	1 0	1.0	. т	1.0	1-0	L.T.	T	1.0	1.0	1.0	ru

000006A0	-1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0
000006B0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0
000006C0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0
000006D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000006E0	+0	+0	+0	+0	+1	+2	+1	+1	+1	+0	+0	+0	-1	+0	+0	+0
000006E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0
00000010	-1	+2	+1	-2	-2	+1	+0	-1	+0	-1	+1	+0	+0	+0	+0	+0
00000700																+0
	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	
00000720	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	-1	+1	+0
00000730	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-1	+0	+0	+0	+0	+0
00000740	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+1	+0
00000750	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000760	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-4	+2
00000770	+0	+0	+0	+0	+0	+0	+0	+1	+7	-2	+0	+0	+0	+0	+0	+0
00000780	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1
00000790	-2	-1	+5	+6	+4	+3	<b>-</b> 5	-6	+1	+0	+0	+0	+0	+0	+0	+0
000007A0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007B0	+0	+0	+0	+4	+2	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007D0	+0	+0	+0	+0	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000007F0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00800000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000810	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000820	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000830	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000840	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+1	+0	+0	+0	+0	+0
00000850	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000860	+0	+0	+0	+0	+0	+0	+0	+2	-1	+0	+0	+0	+0	+0	+0	+0
00000870	+0	+0	+2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000880	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000890	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
0A800000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008B0	+0	+1	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	-1	+0
000008C0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+1	+0	+0
000008E0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000008F0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000900	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000910	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	-1
00000920	+0	+0	+0	+0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000930	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000940	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000950	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000960	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000970	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000980	+0	+0	+0	+0	+0	+1	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0
00000990	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009A0	+0	+0	+0	+0	-2	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1
000009B0	+0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0	+0
00000900	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0
000009D0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
000009E0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
000009E0	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A10	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000A10	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0
00000A20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+1	+0	+0	+0	+0
	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0 -1	+0	+0
00000A40	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	- T	+0	+0

00000A50																
	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0
00000A60	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1	+0	+0
00000A70	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000170	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+1
00000A00			+0			+0				+0		+0	+0	+0	+0	+0
	+0	+0		+0	+0		+0	+0	+0		+1					
0AA00000	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AB0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AC0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AD0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000AF0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B00	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B10	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B20	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B20	+0	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0
00000B30				+0		+0	+0	+0				+0	+0	+1	+0	
	+0	+0	+0		+0				+0	+0	+0					+0
00000B50	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B60	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B70	+0	+0	+0	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0
00000B80	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000B90	-1	+0	+0	+0	+0	+0	-1	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BA0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BB0	+0	+0	-1	-1	+1	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BC0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BD0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BE0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0	+0
00000BE0							+0	+0	+0	+0	+0	+0	+0	+0	+0	
	+0	+0	+0	+0	+0	+0										+0
00000C00	+0	+0	+0	-1	+0	+0	-1	+1	-1	+0	+0	+0	+0	+0	+0	+0
00000C10	+1	+0	+0	-4	+0	+1	+2	+0	-2	+3	+0	+0	+0	+0	+0	+0
00000C20	-1	-1	+3	+13	-2	+1	-2	+2	+7	-15	-1	+0	+0	+1	-1	+0
00000C30	+0	+0	-3	+25	+2	-1	+0	+0	+20	-7	+1	-1	+0	-2	+6	-3
00000C40	+0	+0	-20	+0	-1	-1	-2	-4	+5	+5	-1	+0	-1	+1	-3	-17
00000C50	+0	+1	-5	-7	+2	+0	-3	-3	-13	+12	+0	+0	+1	+0	+7	-2
00000060	+0	+1	+28	+0	+1	-1	+2	+10	-16	+1	+0	+1	-1	+0	+3	+1
00000C70			+0	_	_			. 7	-5	-2	+0			_	_	+0
000000000	+0	-1	TU	-3	-2	+2	+0	+ /			TU	+0	+0	-1	-6	
	+0	-1 -2		-3 -3	-2 -1	+2	+0	+7				+0	+0+1			
00000C80	+0	-2	+1	-3	-1	-1	+0	-10	-2	+4	+0	+0	+1	-1	-2	+0
00000C80 00000C90	+0+0	-2 +3	+1 -1	-3 +0	-1 +0	-1 +1	+0 +3	-10 -12	-2 +9	+4 -5	+0+0	+0 +0	+1 -2	-1 +16	-2 +1	+0+0
00000C80 00000C90 00000CA0	+0 +0 -1	-2 +3 +2	+1 -1 +0	-3 +0 -4	-1 +0 +2	-1 +1 +0	+0 +3 +7	-10 -12 -11	-2 +9 -2	+4 -5 +1	+0 +0 +0	+0 +0 -1	+1 -2 +0	-1 +16 -7	-2 +1 +0	+0 +0 +0
00000C80 00000C90 00000CA0 00000CB0	+0 +0 -1 -3	-2 +3 +2 -1	+1 -1 +0 +0	-3 +0 -4 +1	-1 +0 +2 -1	-1 +1 +0 +0	+0 +3 +7 +2	-10 -12 -11 +6	-2 +9 -2 +0	+4 -5 +1 +0	+0 +0 +0 +0	+0 +0 -1 +0	+1 -2 +0 +0	-1 +16 -7 -16	-2 +1 +0 +0	+0 +0 +0 +0
00000C80 00000C90 00000CA0 00000CB0 00000CC0	+0 +0 -1 -3 +1	-2 +3 +2 -1	+1 -1 +0 +0	-3 +0 -4 +1 -1	-1 +0 +2 -1 +1	-1 +1 +0 +0	+0 +3 +7 +2 +1	-10 -12 -11 +6 +12	-2 +9 -2 +0 +0	+4 -5 +1 +0 +0	+0 +0 +0 +0 +0	+0 +0 -1 +0 +0	+1 -2 +0 +0 +18	-1 +16 -7 -16 +0	-2 +1 +0 +0 +0	+0 +0 +0 +0 +0
00000C80 00000C90 00000CA0 00000CB0 00000CC0	+0 +0 -1 -3 +1 +0	-2 +3 +2 -1 -1	+1 -1 +0 +0 -1 +0	-3 +0 -4 +1 -1 +0	-1 +0 +2 -1 +1	-1 +1 +0 +0 +0	+0 +3 +7 +2 +1	-10 -12 -11 +6 +12 +1	-2 +9 -2 +0 +0	+4 -5 +1 +0 +0	+0 +0 +0 +0 +0 +0	+0 +0 -1 +0 +0	+1 -2 +0 +0 +18 +4	-1 +16 -7 -16 +0 +2	-2 +1 +0 +0 +0	+0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CA0 00000CB0 00000CC0 00000CD0	+0 +0 -1 -3 +1 +0 +0	-2 +3 +2 -1 -1 +0 +0	+1 -1 +0 +0 -1 +0	-3 +0 -4 +1 -1 +0	-1 +0 +2 -1 +1 +0 +0	-1 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1	-10 -12 -11 +6 +12 +1 -1	-2 +9 -2 +0 +0 -1	+4 -5 +1 +0 +0 +0	+0 +0 +0 +0 +0 +0 +1	+0 +0 -1 +0 +0 -2 +3	+1 -2 +0 +0 +18 +4 -5	-1 +16 -7 -16 +0 +2 +0	-2 +1 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CA0 00000CB0 00000CC0	+0 +0 -1 -3 +1 +0	-2 +3 +2 -1 -1	+1 -1 +0 +0 -1 +0	-3 +0 -4 +1 -1 +0	-1 +0 +2 -1 +1	-1 +1 +0 +0 +0	+0 +3 +7 +2 +1	-10 -12 -11 +6 +12 +1	-2 +9 -2 +0 +0	+4 -5 +1 +0 +0	+0 +0 +0 +0 +0 +0	+0 +0 -1 +0 +0	+1 -2 +0 +0 +18 +4	-1 +16 -7 -16 +0 +2	-2 +1 +0 +0 +0	+0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CA0 00000CB0 00000CC0 00000CD0	+0 +0 -1 -3 +1 +0 +0	-2 +3 +2 -1 -1 +0 +0	+1 -1 +0 +0 -1 +0	-3 +0 -4 +1 -1 +0	-1 +0 +2 -1 +1 +0 +0	-1 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1	-10 -12 -11 +6 +12 +1 -1	-2 +9 -2 +0 +0 -1	+4 -5 +1 +0 +0 +0	+0 +0 +0 +0 +0 +0 +1	+0 +0 -1 +0 +0 -2 +3	+1 -2 +0 +0 +18 +4 -5	-1 +16 -7 -16 +0 +2 +0	-2 +1 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0
00000C80 00000CA0 00000CB0 00000CC0 00000CD0 00000CE0 00000CF0	+0 +0 -1 -3 +1 +0 +0	-2 +3 +2 -1 -1 +0 +0	+1 -1 +0 +0 -1 +0 +0	-3 +0 -4 +1 -1 +0 +0	-1 +0 +2 -1 +1 +0 +0	-1 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0	-10 -12 -11 +6 +12 +1 -1 +0	-2 +9 -2 +0 +0 +0 +0	+4 -5 +1 +0 +0 +0 +3 +0	+0 +0 +0 +0 +0 +0 +1 -3	+0 +0 -1 +0 +0 -2 +3	+1 -2 +0 +0 +18 +4 -5 +0	-1 +16 -7 -16 +0 +2 +0 +0	-2 +1 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CE0 00000CF0	+0 +0 -1 -3 +1 +0 +0 +0	-2 +3 +2 -1 -1 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0	-3 +0 -4 +1 -1 +0 +0 +0	-1 +0 +2 -1 +1 +0 +0 +0	-1 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8	-2 +9 -2 +0 +0 +1 +0 +1 +0 +3	+4 -5 +1 +0 +0 +3 +0	+0 +0 +0 +0 +0 +1 -3 +0	+0 +0 -1 +0 +0 -2 +3 -1 +0	+1 -2 +0 +0 +18 +4 -5 +0	-1 +16 -7 -16 +0 +2 +0 +0 +0	-2 +1 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CE0 00000CF0 00000D00	+0 +0 -1 -3 +1 +0 +0 +0	-2 +3 +2 -1 -1 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1	-1 +0 +2 -1 +1 +0 +0 +0 +2 +3	-1 +0 +0 +0 +0 +0 +0 +0 +27	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19	-2 +9 -2 +0 +0 +1 +0 +1 +0 +3 +20	+4 -5 +1 +0 +0 +3 +0 +0 -21 +0	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5	+0 +0 -1 +0 +0 -2 +3 -1 +0 +0	+1 -2 +0 +0 +18 +4 -5 +0 +0	-1 +16 -7 -16 +0 +2 +0 +0 +0 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CE0 00000CF0 00000D10 00000D10 00000D20	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1	-2 +3 +2 -1 -1 +0 +0 +0 -1 -1	+1 -1 +0 +0 -1 +0 +0 +0 +0 +0	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5	-1 +0 +2 -1 +1 +0 +0 +2 +3 +0	-1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2	-2 +9 -2 +0 +0 +1 +0 +3 +20 +0	+4 -5 +1 +0 +0 +3 +0 +0 -21 +0	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5	+0 +0 -1 +0 -2 +3 -1 +0 +0 -1 +7	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2	-1 +16 -7 -16 +0 +2 +0 +0 +0 +1 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 +0 +5	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CE0 00000CF0 00000D10 00000D10 00000D20 00000D30	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0	-2 +3 +2 -1 +0 +0 +0 -1 -1 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 -1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0	-1 +0 +2 -1 +1 +0 +0 +2 +3 +0 -1	-1 +0 +0 +0 +0 +0 +0 +27 -1 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1	-2 +9 -2 +0 +0 +1 +0 +3 +20 +0 -1	+4 -5 +1 +0 +0 +3 +0 +0 -21 +0 -1	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1	+0 +0 -1 +0 -2 +3 -1 +0 +0 -1 +7 +1	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2 -1	-1 +16 -7 -16 +0 +2 +0 +0 +0 +1 +0 +1	-2 +1 +0 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +7
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CF0 00000CF0 00000D10 00000D20 00000D30 00000D40	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 -1 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 -1 -1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0	-1 +0 +2 -1 +1 +0 +0 +2 +3 +0 -1 -1 +3	-1 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5	+0 +3 +7 +2 +1 -14 +0 -13 +12 +0 +0 -2 +1	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1	-2 +9 -2 +0 +0 -1 +0 +3 +20 +0 -1 +2	+4 -5 +1 +0 +0 +3 +0 -21 +0 -1 -1	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0	+0 +0 -1 +0 +0 -2 +3 -1 +0 +0 -1 +7 +1 +0	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2 -1 +1	-1 +16 -7 -16 +0 +2 +0 +0 +0 +1 +0 +1 +0 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +7 +7
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CF0 00000D10 00000D10 00000D20 00000D30 00000D40 00000D50	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 -1 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 -1 -1 -1 +11	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1	-1 +0 +2 -1 +1 +0 +0 +2 +3 +0 -1 +3 -14	-1 +0 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 +0 -2 +1	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7	-2 +9 -2 +0 +0 +1 +0 +3 +20 +0 +1 +2 -1	+4 -5 +1 +0 +0 +3 +0 -21 +0 -1 -1 +1	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 +0	+0 +0 -1 +0 -2 +3 -1 +0 +0 -1 +7 +1 +0 +0	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2 -1 +1	-1 +16 -7 -16 +0 +0 +0 +0 +1 +0 +0 +1 +0 +2	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +7 +7 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CF0 00000D10 00000D10 00000D20 00000D30 00000D40 00000D50 00000D50	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 -1 +0 +0 -1 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 -1 -1 -1 +11 +3	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2	-1 +0 +2 -1 +1 +0 +0 +2 +3 +0 -1 +3 -1 +3	-1 +0 +0 +0 +0 +0 +0 +0 +27 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 +0 -2 +1 -14 +9	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5	-2 +9 -2 +0 +0 +1 +0 +3 +20 +0 +1 +2 -1 +2	+4 -5 +1 +0 +0 +3 +0 -21 +0 -1 -1 +1 +1	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 +0 -2	+0 +0 -1 +0 -2 +3 -1 +0 +7 +1 +0 -1	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2 -1 +1 +0 -1	-1 +16 -7 -16 +0 +0 +0 +0 +0 +1 +0 +0 +2 -2	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5	+0 +0 +0 +0 +0 +0 +0 +0 +0 +4 +3 +7 +0 +0
00000C80 00000C90 00000CB0 00000CC0 00000CD0 00000CF0 00000D10 00000D20 00000D30 00000D40 00000D50 00000D50 00000D70 00000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2 +0	-1 +0 +2 -1 +1 +0 +0 +0 +2 +3 +0 -1 +3 +1 +1 +0 +1	-1 +10 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3	-2 +9 -2 +0 +0 +1 +0 +3 +20 +0 -1 +2 -1 +2	+4 -55 +1 +0 +0 +0 +3 +0 -21 +0 -1 -1 -1 +1 +11 -11	+0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 +0 -2	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +2	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +1 +2 -1 +0 -1 -2	-1 +16 -7 -16 +0 +0 +0 +0 +1 +0 +0 +2 -2 -18	-2 +1 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3	+0 +0 +0 +0 +0 +0 +0 +0 +0 +1 +0 +1 +7 +0 +0 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 0000D20 0000D30 0000D40 0000D50 0000D50 0000D70 0000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -11 +00 -11 +00 +00 +00 +00 -11 -11 +31 +00 -1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -17 +2 +0 -2	-1 +0 +2 -1 +1 +0 +0 +0 +2 +3 +0 -1 +3 +0 +1 +0 +1 +0 +0 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1	-1 +10 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2	-2 +9 -2 +0 +0 +0 +0 +3 +20 +0 -1 +2 -1 +0 -2 +1	+44 -55 +11 +00 +00 +33 +00 -211 +01 -11 +111 -111 +2	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 +0 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +7 +1 +0 +0 -2 +7 +1 +1 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -22 +00 +188 +44 -55 +00 +00 +11 +22 -11 +10 -12 +12	-1 +16 -7 -16 +0 +2 +0 +0 +0 +1 +0 +0 +1 +0 -2 -2 -18 +9	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 -2	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -4 +3 +7 +0 +0 -1 +0
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 0000D20 0000D30 0000D50 0000D50 0000D70 0000D80 0000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -17 +2 +0 -2 -1	-1 +0 +2 -1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -13	-1 +1 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0 +5	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2 -1	-2 +9 -2 +0 +0 +0 +0 +3 +20 -1 +2 -1 +0 -2 +1 +0	+44 -55 +11 +00 +00 +33 +00 -211 +01 -11 +11 -11 +21 +0	+0 +0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 -2 -10 +11 +0	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +7 +1 +0 +0 +0 -1 +7 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -22 +00 +18 +44 -55 +00 +0 +11 +22 -1 +11 -0 -2 -3	-1 +166 -7 -166 +0 +0 +0 +0 +0 +0 +1 +0 +0 +0 +1 +0 +0 +0 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 -2 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +1 +3 +7 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 00000D30 00000D40 00000D50 00000D70 00000D80 00000D80 00000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2 +0 -2 -1 +2	-1 +0 +2 -1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -1 -1 +1 +0 +1 +1	-1 +10 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2	-2 +9 -2 +0 +0 +0 +0 +3 +20 +0 -1 +2 -1 +0 -2 +1	+44 -55 +11 +00 +00 +33 +00 -211 +01 -11 +111 -111 +2	+0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 +0 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +7 +1 +0 +0 -2 +7 +1 +1 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -22 +00 +188 +44 -55 +00 +00 +11 +22 -11 +10 -12 +12	-1 +166 -7 -166 +0 +0 +0 +0 +0 +0 +1 +0 +0 +2 -2 -18 +9 -3 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 -2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -4 +3 +7 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 0000D20 0000D30 0000D50 0000D50 0000D70 0000D80 0000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -17 +2 +0 -2 -1	-1 +0 +2 -1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -14 -0 -13	-1 +1 +0 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0 +5	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2 -1	-2 +9 -2 +0 +0 +0 +0 +3 +20 -1 +2 -1 +0 -2 +1 +0	+44 -55 +11 +00 +00 +33 +00 -211 +01 -11 +11 +111 +21 +0	+0 +0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 -2 -10 +11 +0	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +7 +1 +0 +0 +0 -1 +7 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -22 +00 +18 +44 -55 +00 +0 +11 +22 -1 +11 -0 -2 -3	-1 +166 -7 -166 +0 +0 +0 +0 +0 +0 +1 +0 +0 +0 +1 +0 +0 +0 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 -2 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +1 +3 +7 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 00000D30 00000D40 00000D50 00000D70 00000D80 00000D80 00000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 -1 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2 +0 -2 -1 +2	-1 +0 +2 -1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -1 -1 +1 +0 +1 +1	-1 +1 +0 +0 +0 +0 +0 +27 -1 +0 +5 -10 +0 +0 +2-7 -1	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0 -2	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2 -1 +0	-2 +9 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+44 -55 +11 +00 +00 +33 +00 -21 +0 -1 -1 -1 +11 +11 -11 +2 +0 +0	+0 +0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 -2 -10 +11 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +2 +9 +1 +0	+1 -2 +0 +0 +18 +4 -5 +0 +0 +1 +2 -1 +1 +0 -1 -2 +12 -3 +0	-1 +166 -7 -166 +0 +0 +0 +0 +0 +0 +1 +0 +0 +2 -2 -18 +9 -3 +0	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 -2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -4 +3 +7 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CD0 00000CD0 00000CF0 00000D10 00000D30 00000D40 00000D50 00000D70 00000D80 00000D80 00000D80 00000D80 00000D80	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 +0 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1 +1 -1	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2 +0 -2 -1 +2	-1 +0 +2 -1 +1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -1 +1 +0 -3 +1	-1 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0 -2 +1 -14 -14 -14 -14 -14 -14 -14 -15 -16 -16 -16 -16 -16 -16 -16 -16 -16 -16	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2 -1 +0 +1 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1	-2 +9 -2 +0 +0 +0 +0 +3 +20 -1 +2 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+44 -5 +1 +0 +0 +0 +3 +0 +0 -21 +1 +11 +2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 -2 -10 +0 +0 -2 -10 +0 -1	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +2 +9 +1 +0 +0	+11 -22 +00 +188 +44 -55 +00 +00 +11 +22 -11 +11 -22 +122 -33 +00 +00	-1 +166 -7 -166 +0 +0 +0 +0 +0 +1 +0 +0 +2 -2 -18 +9 -3 +0 -1	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 +5 -2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -4 +3 +7 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0
00000C80 00000C90 00000CD0 00000CD0 00000CD0 00000CD0 00000D10 00000D30 00000D40 00000D50 00000D70 00000D80 00000D80 00000D80 00000D80 00000DB0 00000DB0	+0 +0 -1 -3 +1 +0 +0 +0 -1 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-2 +3 +2 -1 +0 +0 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+1 -1 +0 +0 +0 +0 +0 +0 +0 -1 -1 -1 +11 +3 +0 -1 +1 +1 +1 +1 +2 +0	-3 +0 -4 +1 -1 +0 +0 +0 -3 -1 +5 +0 -1 -17 +2 +0 -2 -1 +2 -1 +0	-1 +0 +2 -1 +1 +0 +0 +0 +2 +3 +0 -1 +3 -14 +0 -1 +1 +0 -3 +1 -1 +0	-1 +1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +3 +7 +2 +1 -14 +1 +0 -13 +12 +0 -2 +1 -14 +9 +0 +0 -2 +1 -14 +9 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	-10 -12 -11 +6 +12 +1 -1 +0 -8 +19 +0 -2 +1 -2 +7 -5 +3 -2 -1 +0 +1 +0 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1 +1	-2 +9 -2 +0 +0 +0 +0 +3 +20 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +3	+44 -5 +1 +0 +0 +0 +3 +0 +0 -21 +1 +11 +2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +1 -3 +0 +3 -5 -2 +1 +0 -2 -10 +0 +0 -2 -10 +0 -1	+0 +0 -1 +0 -2 +3 -1 +0 -1 +7 +1 +0 -1 +2 +9 +1 +0 +0 -1 +0 -1 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+11 -22 +00 +188 +44 -55 +00 +00 +11 +22 -11 +12 -33 +00 +00 +14	-1 +166 -7 -166 +0 +0 +0 +0 +0 +1 +0 +0 +2 -2 -18 +9 -3 +0 -1 -3	-2 +1 +0 +0 +0 +0 +0 +0 +0 -3 +5 -2 +0 -3 +5 -3 +5 -2 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0	+0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -4 +3 +7 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0

```
000000E10 \quad +0 \quad +0 \quad +0 \quad -6 \quad +1 \quad +0 \quad -1 \quad +2 \quad -4 \quad +3 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0 \quad +0
 \tt 00000E20 +0 +0 +0 +0 +0 +0 +0 +0 +0 +0 -1 +1 -1 +0 +0 +0 -1 +0 \\
00000E30 +0 +0 -1 -1 +0 +0 +0 +0 +0 -1 -1
                                            +0 +0 +0 -1
                                                         -2
00000E40 +0 +0
              -2 -2 +0 +0
                           +0 -1
                                 -2 +1 +0
                                               +0 +0
                                                      -2
                                            +0
00000E50 +0 +0 +3 +1 +1
                        +0 +0 -1 -1 +0 +0 +0 +0 +0 +0
                                                         +0
00000E60 + 0 -1 + 3 + 0 + 1 -1 -2 + 2 + 0 + 0 + 0 + 0 + 0 + 0 -1
                                                         +0
00000E70 + 0 + 0 + 1 - 1 + 0 - 1 + 2 + 1 + 2 - 1 + 0 + 0 + 0 - 1 - 1 + 0
 \texttt{00000ED0} \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ +0 \ \ -1 \ \ -4 \ \ +0 \ \ +0 \ \ +0 
00000EF0 +0 +0 +0 +0 +0 +0 +0 +0 +0 +1
                                            +0 +0 +0 +0
00000F00 +0 +13 +4 +5 -8 -2 +0 +1 -1 -43 -7 -3 -4 +1 -1
                                                         +1
00000F10 +5 +22 -1 -1 -54 -2 -2 -4 -4 +52 -5 +17 +7 +1 -3 -33
00000F20 -4 -25 +1 +15 +3 +2 +2 -11 +4 -14 +5 -34 +6 -1 +35 +6
00000F30 +11 +4 -2 -5 -4 -7 -21 +1 -2 +0 +1 -6 +1 +3 -11 +0
00000F40 -2 +6 -45 +14 -45 +4 -1 +1 -3 +1 +1 -7 -7 +5 -19 -4
00000F50 \quad +2 \quad -4 \quad +8 \quad +4 \quad -1 \quad +3 \quad +0 \quad +0 \quad +2 \quad -15 \quad -27 \quad -36 \quad -2 \quad +5 \quad -1 \quad +14
00000F60 +2 -5 +7 +0 +8 -39 -41 +6 +1 +4 -12 -6 +0 -2 -2 -1
00000F70 \quad -4 \quad -5 \quad -3 \quad +6 \ +14 \quad -2 \ +22 \quad -5 \quad -2 \quad -1 \quad +0 \quad +5 \quad -33 \quad -51 \quad -15 \quad +2
 \tt 00000F80 + 0 + 14 - 1 + 8 - 5 - 1 + 0 + 0 - 1 - 2 - 5 - 5 - 10 - 5 - 3 + 2 \\
              +5 -4 -8 -1 +0 -3 +2 -13 +5 -14 +15
00000F90 +2 +5
                                                  -1
00000FA0 +1 -1 +2 -3 +15 -1 +3 -3 +1 +5 -4 -2 +0 +2
00000FB0 -4 +0 +2 +15 +0 -5 -12 +0 +0 +0 +0 +12
                                               -3 -10 +4 +0
00000FC0 -68 +7 -44 +27 -28 +42 -3 +3 +1 -23+147 +12 +8-162 +6 +3
00000FD0 +10 -12+147 -60 -13 -24 -1 +1 -44 +40 +33 -24 -22 +48 -14 -22
00000FE0 -38 -3 -1 +61 -68 +60 -4 -37 +1 -18 +2 +29 +29 +8 +18 -74
00000FF0 +10 +5 -17 -22+108 -16 +33-124 +22 -7 +0 -4 +48 +26 -46 -33
```

## 4.2.4.3 Inverse Quantization/DWT

The following sections present the three-level inverse DWT of the Y component data. The inverse DWT process follows the steps shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4, in reverse order. The inverse DWT steps for the Cb and Cr components are the same as for the Y component, so the intermediate data dumps for these two components have been omitted, but their final reconstructed data is presented in sections 4.2.4.4 and 4.2.4.5.

#### 4.2.4.3.1 Level 3 Sub-bands

The following are annotated dumps of the four level 3 de-quantized sub-bands (LL3, LH3, HL3, and HH3). The LL3 sub-band first gives inverse differential encoding before being de-quantized (section 3.1.8.1.6). The level 3 sub-bands have dimensions of 8x8.

All the coefficients are displayed in 11.5 fixed-point representation.

#### 4.2.4.3.1.1 LL3

The following is a dump of the LL3 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

0000000	-32	+0	-32	-480	-384	-384	-608	-736
00000008	+864	+448	+96	+1184	+352	-384	-480	-512

75 / 142

[MS-RDPRFX] — v20140502 Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

Release: Thursday, May 15, 2014

+928	+800	+1472	+3296	+2752	+1376	+832	+352
+1216	+992	+1792	+2752	+2016	+4096	+3680	+864
+2304	-992	+1728	+4000	+288	+3104	+2144	+320
+2144	-1088	+1920	+2720	+3264	+3424	+3616	+192
+672	-320	+320	-512	+4032	+3456	+2720	-320
+1888	+1664	+1248	+960	+1120	+1696	+480	-96
	+1216 +2304 +2144 +672	+1216 +992 +2304 -992 +2144 -1088 +672 -320	+1216 +992 +1792 +2304 -992 +1728 +2144 -1088 +1920 +672 -320 +320	+1216 +992 +1792 +2752 +2304 -992 +1728 +4000 +2144 -1088 +1920 +2720 +672 -320 +320 -512	+1216 +992 +1792 +2752 +2016 +2304 -992 +1728 +4000 +288 +2144 -1088 +1920 +2720 +3264 +672 -320 +320 -512 +4032	+1216 +992 +1792 +2752 +2016 +4096 +2304 -992 +1728 +4000 +288 +3104 +2144 -1088 +1920 +2720 +3264 +3424 +672 -320 +320 -512 +4032 +3456	+1216 +992 +1792 +2752 +2016 +4096 +3680 +2304 -992 +1728 +4000 +288 +3104 +2144 +2144 -1088 +1920 +2720 +3264 +3424 +3616 +672 -320 +320 -512 +4032 +3456 +2720

## 4.2.4.3.1.2 HL3

The following is a dump of the HL3 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	-64	-64	+32	+0	-32	-64
80000008	+0	-32	+256	+192	+96	+0	-32	-192
00000010	+0	+128	+160	-416	-1696	-96	-64	+0
00000018	-64	-480	-224	+800	+256	+96	+224	-800
00000020	+832	-384	+160	+640	+192	+224	-160	-416
00000028	+64	-64	+160	-1728	+320	-64	+960	+96
00000030	-1472	+352	-288	-32	-64	+32	-576	-64
00000038	+256	-96	+96	-160	-128	-32	-160	-64

## 4.2.4.3.1.3 LH3

The following is a dump of the LH3 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

+32	-32	+32	-96	-320	+32	+0	-96	00000000
+320	-416	-448	+224	+96	-96	-32	-160	80000008
+0	+384	+64	+160	+64	+352	-32	+0	00000010
+992	+288	+320	-128	-1568	-672	+768	-256	00000018
+288	-1664	-1824	+416	+32	+320	+160	-32	00000020
-32	-128	-96	+32	+160	-576	-192	+384	00000028
-64	+224	+224	+96	+352	+256	+672	+416	00000030
+32	-224	-608	-448	+64	+0	-32	-96	00000038

## 4.2.4.3.1.4 HH3

The following is a dump of the HH3 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	-32	-96	-64	+0	+0	-32	-32
80000000	-32	-224	+96	+128	+224	-32	-192	-448
00000010	-32	-224	+96	-384	-512	-64	+64	-32
00000018	-288	+32	+224	-672	+800	-128	-64	-736
00000020	+64	+64	+96	-128	+704	-128	+160	-128
00000028	-64	-64	+128	-224	+0	+0	+96	+64
00000030	+544	-192	+224	+160	+96	+32	-160	+0
00000038	+32	+0	+0	+192	+32	-128	+64	+0

## 4.2.4.3.1.5 Inverse DWT-X (LL3 - HL3)

The following is a dump of the L2 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	-16	+0	+0	+0	-336	-416	-520
80000008	-368	-320	-400	-496	-592	-704	-688	-816
00000010	+864	+664	+464	+160	-16	+984	+960	+968
00000018	+208	+80	-432	-448	-464	-496	-400	-784
00000020	+928	+832	+736	+1288	+1328	+2696	+3424	+2784
00000028	+3808	-352	+2272	+1400	+912	+520	+384	+384
00000030	+1280	+1144	+1264	+744	+2144	+1856	+2464	+3576
00000038	+1488	+3216	+3920	+3912	+3520	+2784	+1152	-448
00000040	+1472	+1792	-1216	-456	+1840	+3040	+3600	+3016
00000048	-128	+1768	+2896	+2952	+2112	+1040	+608	-224
00000050	+2080	+624	-1088	+264	+1872	+3008	+3504	+280
00000058	+3968	+4272	+3296	+3104	+3168	+3336	-336	-144
00000060	+2144	-1752	+240	+968	+288	-608	-352	+1800
00000068	+4080	+3648	+3472	+3296	+2992	+344	+0	-128
00000070	+1632	+2120	+1584	+1224	+1248	+1312	+992	+808
00000078	+1264	+1264	+1776	+1112	+576	-24	+16	-112

## 4.2.4.3.1.6 Inverse DWT-X (LH3 - HH3)

The following is a dump of the H2 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

-280	-240	-264	+96	+0	+32	-80	-64	00000000
+0	+64	-40	-16	+8	+32	-16	-64	80000008
+272	-16	+168	-32	-416	+96	-80	-128	00000010
-256	+640	-216	-304	-488	-544	+200	+48	00000018
-360	+208	+504	+416	-192	+96	+0	+32	00000020
-80	-16	+312	+384	+240	+352	-544	+608	00000028
-2112	-1344	-624	-800	+112	+896	-112	+32	00000030
-80	+1392	+760	+384	-72	-16	+1496	-192	00000038
-168	+48	+336	+240	+296	+96	+128	-96	00000040
+16	+272	-384	-1680	-2152	-2112	+416	+128	00000048
-272	+208	+56	-608	-496	-128	+32	+448	00000050
+16	-112	+48	-176	-136	-96	+24	+144	00000058
+384	+160	+648	+240	-16	+496	+1272	-128	00000060
+16	+16	-168	+288	+288	+160	+256	-32	00000068
+88	-32	-16	+0	-24	-48	-24	-128	00000070
+0	+0	+32	-192	-632	-560	-496	-560	00000078

## 4.2.4.3.1.7 Inverse DWT-Y (L2 - H2)

The following is a dump of the LL2 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+32	+64	-32	+0	-96	-72	-176	-240
80000008	-304	-304	-432	-504	-576	-664	-752	-816
00000010	+368	+244	+248	+184	+120	-48	-24	-194
00000018	-172	-190	-240	-340	-472	-596	-624	-736
00000020	+960	+744	+400	+368	-48	+1032	+1088	+972
00000028	+216	-12	-176	-208	-304	-368	-752	-656

77 / 142

[MS-RDPRFX] - v20140502

Remote Desktop Protocol: RemoteFX Codec Extension

Copyright © 2014 Microsoft Corporation.

Release: Thursday, May 15, 2014

00000030	+712	+648	+712	+148	+480	+2032	+2176	+2444
00000038	+1944	+304	+8	-318	-324	-380	+940	-564
00000040	+976	+872	+640	+1592	+1136	+2360	+3328	+2828
00000048	+3480	-180	+2368	+1524	+872	+472	+72	+552
00000050	+1176	+1036	+896	+804	+2568	+3146	+3596	+3100
00000058	+3596	+192	+3764	+3156	+2772	+1984	+236	-68
00000060	+1248	+1200	+768	+784	+2336	+1916	+3032	+4812
00000068	+1280	+2740	+3752	+3828	+3136	+2248	+464	-368
00000070	+1440	+1268	+1320	+286	+628	+1302	+952	+260
00000078	+208	+4768	+3824	+3802	+3716	+3070	+2904	-440
08000000	+1504	+1784	-1712	-660	+2120	+3184	+4248	+4156
00000088	-96	+812	+3960	+4064	+2760	+852	-224	-192
00000090	+1512	+1420	-1200	+444	+2568	+3670	+3908	+1992
00000098	+2124	+3264	-44	-148	+68	+1410	+224	-144
000000A0	+1904	+544	-1072	+364	+2056	+2812	+3376	+500
8A000000	+3832	+4052	+4400	+4248	+4096	+3504	-416	-160
000000B0	+2840	-866	-764	-198	+48	+1038	+1836	+578
000000B8	+4216	+3828	+3728	+3462	+3164	+2050	-408	-120
000000C0	+1984	-2404	+56	+1224	+472	-960	-536	+1744
000000C8	+4024	+3508	+3440	+3220	+2936	+404	+48	-144
000000D0	+1616	+2090	+1700	+1202	+1280	+1314	+516	+1926
000000D8	+2728	+2958	+3028	+2828	+2308	-112	+60	-100
000000E0	+1760	+1496	+1360	+1244	+1128	+996	+928	+572
000000E8	+1560	+1384	+1976	+1284	+528	+44	+8	-120
000000F0	+1504	+1448	+1264	+1196	+1128	+964	+864	+748
000000F8	+440	+392	+856	+20	+144	+108	+8	-120

## 4.2.4.3.2 Level 2 Sub-bands

The following are the dumps of the four level 2 de-quantized sub-bands (LL2, LH2, HL2, and HH2). LL2 is reconstructed from level 3 sub-bands. LH2, HL2, and HH2 are generated by de-quantizing the corresponding decoded sub-bands, as shown in sections 4.2.4.2 and 4.2.4.2.1.

All the coefficients are displayed in 11.5 fixed-point representation.

## 4.2.4.3.2.1 LL2

The LL2 sub-band is the same as that shown in section 4.2.4.3.1.7.

#### 4.2.4.3.2.2 HL2

The following is a dump of the HL2 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+64	+0	+0	+0	+0	+0	+0	+0
80000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+64	+0	+0	+64	+0	+0	+64	+0
00000018	+0	+0	+0	+0	+0	-64	+0	+0
00000020	-64	-64	+0	-320	+192	-128	+64	+0
00000028	-64	+0	+0	+0	+0	+64	-256	-64
00000030	+0	+0	+64	-320	-128	+64	+64	+64
00000038	+384	-128	-64	+0	+64	-256	+1344	+384
00000040	+0	+0	-320	-64	+64	+128	+256	+256
00000048	+192	+320	+0	+0	-64	+256	-512	-704
00000050	+0	+0	-128	+512	-64	+0	+192	+64
00000058	-1152	+1024	+64	-64	+128	+0	-256	-256

00000060	+0	+0	-384	+64	-192	-64	+64	+896
00000068	-1472	+64	+0	+64	+0	+64	-192	-64
00000070	+0	+0	+0	-320	-128	+192	-64	+704
00000078	-512	-192	+0	+64	+0	-64	-192	+64
08000000	+0	+896	+64	+0	-64	+0	+0	-960
88000000	-128	+448	+64	-64	+64	-192	-64	-64
00000090	-128	-896	+0	+64	+0	+0	+320	-1152
00000098	+896	-448	-64	-64	-128	+832	+64	-64
0A00000A0	+192	-896	+64	-128	+128	-64	+704	-1024
8A000000	-128	+128	-64	+64	+0	-576	+0	-64
000000B0	+1216	+64	+64	+64	+0	+128	+128	+512
000000B8	+0	+0	+0	+0	+64	-832	+0	+0
000000C0	-384	-192	-64	+0	-128	-128	+384	+832
000000C8	+0	+0	+0	+64	+576	+64	+0	+0
000000D0	-64	+128	+0	+0	+64	+0	-320	+0
000000D8	+0	-64	+0	+0	+64	+64	+0	+0
000000E0	+0	+0	+0	+0	+0	+0	+64	-128
000000E8	-256	+64	+256	+256	-128	+0	+0	-64
000000F0	+0	+0	+0	+0	+0	+0	+0	+0
000000F8	+64	+0	-256	-64	+0	+0	+0	+0

## 4.2.4.3.2.3 LH2

The following is a dump of the HL2 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	+0	+0	+0	+0	+0	+0
8000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	-128	-64	+64	+64	-64	-192	+0	-128
00000018	-192	+0	+0	+0	+0	+0	+0	+0
00000020	-128	-128	+0	+64	-64	+128	+0	+0
00000028	+0	+64	-64	+64	+0	+64	-512	-64
00000030	+0	+0	+64	-192	+0	+0	-64	+192
00000038	+0	+0	+64	-192	-192	-192	+192	-256
00000040	+0	+0	+0	+64	+0	+0	+192	-192
00000048	+192	-64	+64	+64	+0	+64	-320	+1280
00000050	+0	+0	+0	-64	+128	+448	-64	+0
00000058	+192	-128	+64	+0	+256	-64	+0	+64
00000060	+0	+64	-192	+128	-576	-768	-1216	+640
00000068	-64	+128	+0	-64	+64	+576	-832	+0
00000070	+0	+64	-256	-832	+0	+0	+1024	-448
00000078	+0	+1024	-192	+64	-128	-64	+128	-64
0800000	+0	+0	+0	+64	+64	+0	+0	+256
00000088	-192	-1088	-896	+128	-256	-896	-64	+0
00000090	-64	+64	+0	-64	+0	+64	+64	-128
00000098	+64	+192	+1088	+832	+960	+576	-128	+0
000000A0	+128	-192	+128	+128	-128	+128	+64	-64
8A000000	+64	+0	+0	-128	+320	+448	-64	+0
000000B0	+64	+256	-448	-896	-448	+128	-128	+0
000000B8	+0	+0	+0	+0	+0	-64	+64	+0
000000C0	-192	+1088	+512	-64	+256	+512	-576	+384
000000C8	+0	+64	+0	+0	+0	+0	+0	+0
000000D0	-64	+64	+0	+0	+0	+0	+0	-128
8D000000	-128	+128	+0	+0	+320	-64	+0	+0
000000E0	-64	+0	+0	+0	+0	+0	+0	+0
000000E8	-320	-256	-128	-384	-64	+0	+0	+0
000000F0	+0	+0	+0	+0	+0	+0	+0	+0

## 4.2.4.3.2.4 HH2

The following is a dump of the HH2 sub-band, as shown in figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	+0	+0	+0	+0	+0	+0
8000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+128	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0
00000028	+0	+0	+0	+0	-128	+0	-512	-128
00000030	+0	+0	+0	+0	+0	+0	-128	-128
00000038	+128	-128	+0	+0	+0	+0	+256	+256
00000040	+0	+0	+0	+384	+0	+0	+128	+128
00000048	-128	+128	+0	+0	+0	+0	-512	-1024
00000050	+0	+0	+0	-128	+0	+0	-128	-128
00000058	-128	+0	+0	+0	+0	+0	+0	+0
00000060	+0	+0	+0	+128	+128	-128	-384	+384
00000068	+0	+0	+0	-128	+128	+0	+0	+0
00000070	+0	+128	-256	+0	+0	-128	+384	+128
00000078	+256	-128	+0	+0	+0	-256	-128	+0
08000000	+0	+0	+0	+0	+0	+0	+0	+0
00000088	+128	+0	+128	+128	+0	-384	+0	+0
00000090	+0	+0	+0	+0	+0	+0	+128	+0
00000098	-128	+256	+0	-128	+128	+0	+0	+0
0A00000A0	+128	+128	+0	+0	+0	+0	+0	-128
8A000000	+0	+0	+0	-128	+0	-256	+0	+0
000000B0	+256	+256	+128	-128	+0	-128	+0	+0
000000B8	+0	+0	+0	+0	+0	+0	+0	+0
000000C0	-256	+256	+0	+0	+128	-256	+128	-128
000000C8	-128	+0	+0	+0	+0	+0	+0	+0
000000D0	+0	+0	+0	+0	+0	+0	+128	+0
000000D8	+0	+0	+0	-128	-256	+0	+0	+0
000000E0	+0	+0	+0	+0	+0	+0	+0	+0
000000E8	+128	+128	-128	-128	+0	+0	+0	+0
000000F0	+0	+0	+0	+0	+0	+0	+0	+0
000000F8	+0	+0	+128	+0	+0	+0	+0	+0

## 4.2.4.3.2.5 Inverse DWT-X (LL2 - HL2)

The following is a dump of the L1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	+128	+32	+0	-32	-16	+0	-48
80000008	-96	-84	-72	-124	-176	-208	-240	-272
00000010	-304	-304	-304	-368	-432	-468	-504	-540
00000018	-576	-620	-664	-708	-752	-784	-816	-816
00000020	+304	+386	+212	+230	+248	+200	+152	+248
00000028	+88	+20	-48	-52	-56	-13	-226	-199
00000030	-172	-181	-190	-215	-240	-290	-340	-406
00000038	-472	-518	-564	-706	-592	-664	-736	-736
00000040	+1024	+788	+808	+492	+432	+480	+528	-368
00000048	+16	+892	+1000	+804	+1120	+1158	+940	+594

00000050	+248	+6	+20	-78	-176	-192	-208	-256
00000058	-304	-352	-400	-400	-656	-1088	-496	-624
00000060	+712	+680	+648	+664	+680	+606	+276	-150
00000068	+704	+1128	+2064	+2216	+2112	+2374	+2380	+2178
00000070	+1720	+1716	+176	-116	+104	-219	-286	-321
00000078	-356	-192	-284	-456	+396	+2172	-1428	-660
08000000	+976	+924	+872	+836	+800	+652	+1784	+1332
00000088	+1136	+1828	+2264	+2956	+3136	+3366	+2572	+3426
00000090	+3256	+1794	-436	+1526	+2208	+1866	+1524	+1214
00000098	+904	+512	+376	+800	+200	-344	+1160	-248
0A00000	+1176	+1106	+1036	+998	+960	+530	+612	+2502
8A000000	+2344	+2633	+3178	+3339	+3500	+3620	+2972	+3684
000000B0	+4140	-106	+256	+3786	+3220	+3316	+3156	+2820
000000B8	+2740	+2586	+1920	+1142	+364	-236	+188	-324
000000C0	+1248	+1224	+1200	+1080	+960	+184	+944	+1800
000000C8	+2400	+1838	+2044	+2410	+3032	+3810	+4332	+4742
000000D0	+1568	-438	+3444	+3710	+3720	+3758	+3796	+3578
000000D8	+3104	+2660	+2216	+1500	+528	-240	-240	-368
000000E0	+1440	+1354	+1268	+1294	+1320	+883	+446	+9
000000E8	+852	+805	+1270	+1463	+888	+286	-60	+1434
000000F0	+112	+1592	+5120	+4136	+3920	+3845	+3770	+3855
000000F8	+3684	+3393	+3102	+2939	+3032	+944	-376	-248
00000100	+1504	+1420	+1336	+1364	-2192	-1314	-692	+730
00000108	+2152	+2556	+3216	+3732	+4248	+4442	+4636	+622
00000110	+448	+294	+652	+3074	+3704	+4012	+4064	+3284
00000118	+2760	+1966	+916	+26	-96	-240	-128	-256
00000120	+1640	+1530	+1932	-1202	<del>-</del> 752	-170	+412	+1602
00000128	+2536	+3103	+3670	+3709	+3748	+3718	+2408	+26
00000130	+2252	+4438	+3040	+730	+212	-64	-84	-88
00000138	+164	+355	+1058	+2081	-224	-56	-144	-272
00000140	+1712	+1688	+896	-1672	-656	-2	+396	+970
00000148	+2056	+2674	+2780	+2790	+3056	+3266	+660	+486
00000150	+4408	+3974	+4052	+4466	+4368	+4180	+4248	+4284
00000158	+4064	+3928	+3792	+680	-128	-128	-128	-256
00000160	+1624	+2491	-1506	-1039	-828	-417	-262	+5
00000168	+16	+495	+974	+1597	+1708	+1239	+258	+3133
00000170	+3960	+3894	+3828	+3778	+3728	+3595	+3462	+3297
00000178	+3132	+2911	+2434	-443	+8	-56	-120	-120
00000180	+2368	-642	-2116	-1350	+184	+592	+1256	+896
00000188	+536	-404	-832	-1004	-664	+1004	+1136	+4036
00000190	+3608	+3558	+3508	+3474	+3440	+3314	+3188	+3030
00000198	+2616	+2502	+84	+178	+16	-64	-144	-144
000001A0	+1680	+1741	+2058	+2103	+1636	+1419	+1202	+1225
000001A8	+1248	+1393	+1282	+979	+676	+741	+2086	+2407
000001B0	+2728	+2859	+2990	+2897	+3060	+2944	+2828	+2552
000001B8	+2276	+1178	-176	+54	+28	-36	-100	-100
000001C0	+1760	+1628	+1496	+1428	+1360	+1302	+1244	+1186
000001C8	+1128	+1062	+996	+946	+896	+878	+604	+922
000001D0	+1752	+1104	+1480	+1776	+1816	+1934	+1028	+1258
000001D8	+464	+30	+108	+58	+8	-40	-88	-216
000001E0	+1504	+1476	+1448	+1356	+1264	+1230	+1196	+1162
000001E8	+1128	+1046	+964	+914	+864	+806	+748	+578
000001F0	+408	+512	+360	+672	+984	+70	+180	+50
000001F8	+176	+142	+108	+58	+8	-56	-120	-120

# 4.2.4.3.2.6 Inverse DWT-X (LH2 - HH2)

The following is a dump of the H1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	+0	+0	+0	+0	+0	+0
8000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	-128	-96	-64	+0	+64	+32	+0	+192
00000028	-128	-160	-192	-96	+0	-64	-128	-160
00000030	-192	-96	+0	+0	+0	+0	+0	+0
00000038	+0	+0	+0	+0	+0	+0	+0	+0
00000040	-128	-128	-128	-64	+0	+32	+64	+0
00000048	-64	+32	+128	+64	+0	+0	+0	+0
00000050	+0	+32	+64	+0	-64	+0	+64	+64
00000058	+64	-160	+128	-64	-256	-1024	+256	+0
00000060	+0	+0	+0	+32	+64	-64	-192	-96
00000068	+0	+0	+0	+0	+0	-96	+320	-96
00000070	+0	+256	+0	-192	+128	-32	-192	-192
00000078	-192	-192	-192	-64	+64	+288	-512	+0
08000000	+0	+0	+0	+0	+0	-64	-128	+608
00000088	-192	-96	+0	+64	+128	+160	-320	+192
00000090	+192	-192	-64	+224	+0	+32	+64	+32
00000098	+0	+32	+64	+0	-64	-32	+2048	+0
000000A0	+0	+0	+0	+0	+0	+0	+0	-160
000000A8	+192	+320	+448	+224	+0	-192	+128	-32
000000B0	+320	-128	-64	+0	+64	+32	+0	+128
000000B8	+256	+96	-64	-32	+0	+32	+64	+64
000000C0	+0	+32	+64	-64	-192	-64	+64	-64
000000C8	-704	-480	-768	-1120	-960	-928	+640	+960
000000D0	-256	-64	+128	+64	+0	+0	+0	-224
000000D8	+64	+544	+512	-160	-832	-416	+0	+0
000000E0	+0	+0	+0	+160	-192	-960	-704	-352
000000E8	+0	+32	+64	+224	+896	+864	-704	-192
000000F0	-192	+896	+960	+160	-128	-32	+64	-32
000000F8	-128	-32	+64	-320	+320	-96	+0	+0
00000100	+0	+0	+0	+0	+0	+32	+64	+64
00000108	+64	+32	+0	+0	+0	+128	+256	+0
00000110	-256	-448	-1152	-1056	-960	-224	+0	+96
00000118	-320	-512	-704	-1056	+128	+64	+0	+0
00000120	-64	+0	+64	+32	+0	-32	-64	-32
00000128	+0	+32	+64	+32	+0	+160	-192	-32
00000130	+128	-128	+128	+1056	+960	+928	+896	+672
00000138	+960	+992	+512	+192	-128	-64	+0	+0
00000140	+0	+96	-320	+128	+64	+96	+128	+0
00000148	-128	+0	+128	+96	+64	+32	+0	-192
00000150	+128	+64	+0	+0	+0	-32	-64	-96
00000158	+384	+480	+576	-192	+64	+32	+0	+0
00000160	-192	+416	+0	+192	-640	-512	-896	-896
00000168	-384	-96	+192	-192	-64	-32	+0	+0
00000170	+0	+0	+0	+0	+0	+0	+0	+0
00000178	+0	-32	-64	+0	+64	+32	+0	+0
00000180	+64	+64	+1088	+1248	+384	+160	-64	+64
00000188	+192	+640	+576	-480	-512	+192	+384	+0
00000190	+128	-128	+128	+64	+0	+0	+0	+0
00000198	+0	+0	+0	+0	+0	+0	+0	+0
000001A0	-64	+0	+64	+32	+0	+0	+0	+0
000001A8	+0	+0	+0	-32	-64	+128	-192	-160

000001B0	-128	+0	+128	+64	+0	+32	+64	+32
000001B8	+512	-224	+64	+32	+0	+0	+0	+0
000001C0	-64	-32	+0	+0	+0	+0	+0	+0
000001C8	+0	+0	+0	+0	+0	+0	+0	-192
000001D0	-384	-128	-384	+0	-128	-448	-256	-384
000001D8	+0	+0	+0	+0	+0	+0	+0	+0
000001E0	+0	+0	+0	+0	+0	+0	+0	+0
000001E8	+0	+0	+0	+0	+0	+0	+0	+0
000001F0	+0	+0	+0	-256	-512	+0	+0	+0
000001F8	+0	+0	+0	+0	+0	+0	+0	+0

# 4.2.4.3.2.7 Inverse DWT-Y (L1 - H1)

The following is a dump of the LL1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	+128	+32	+0	-32	-16	+0	-48
80000008	-96	-84	-72	-124	-176	-208	-240	-272
00000010	-304	-304	-304	-368	-432	-468	-504	-540
00000018	-576	-620	-664	-708	-752	-784	-816	-816
00000020	+168	+281	+138	+115	+92	+84	+76	+52
00000028	+28	+8	-12	-64	-116	-95	-201	-195
00000030	-190	-218	-247	-291	-336	-379	-422	-473
00000038	-524	-569	-614	-707	-672	-724	-776	-776
00000040	+368	+434	+244	+230	+216	+184	+152	+152
00000048	+152	+100	+48	-4	-56	+19	-162	-119
00000050	-76	-133	-190	-215	-240	-290	-340	-406
00000058	-472	-518	-564	-706	-592	-664	-736	-736
00000060	+504	+475	+446	+377	+436	+380	+324	+228
00000068	-124	+208	+156	+216	+532	+476	+165	-42
00000070	-250	-239	-101	-146	-192	-241	-290	-347
00000078	-404	-395	-514	-537	-560	-620	-680	-680
0800000	+1152	+900	+904	+524	+400	+448	+496	-464
00000088	+112	+956	+1032	+820	+1120	+1190	+1004	+674
00000090	+344	+38	-12	-78	-144	-192	-240	-288
00000098	-336	-272	-464	-368	-528	-576	-624	-624
0A00000	+708	+566	+552	+474	+524	+599	+546	-283
8A000000	+296	+1098	+1772	+1630	+1616	+1806	+1612	+1450
000000B0	+1032	+869	+194	-49	-164	-197	-103	-144
000000B8	-186	-464	-102	-508	-530	-1066	-450	-642
000000C0	+776	+744	+712	+680	+648	+622	+340	-102
000000C8	+736	+1112	+2000	+2184	+2112	+2422	+2220	+2226
000000D0	+1720	+1572	+144	-20	+72	-203	-222	-257
000000D8	-292	-16	-252	-392	+492	+2540	-1300	-660
000000E0	+876	+834	+792	+814	+836	+541	+758	+295
000000E8	+984	+1494	+2132	+2554	+2592	+2686	+3036	+2610
000000F0	+2440	+2179	-130	+361	+1364	+768	+299	+135
000000F8	-30	-96	-290	+92	+474	+1610	-1478	-454
00000100	+976	+924	+872	+820	+768	+716	+1944	+1076
00000108	+1232	+1876	+2264	+2924	+3072	+3334	+2572	+3378
00000110	+3160	+1762	-404	+1510	+2144	+1866	+1588	+1294
00000118	+1000	+592	+440	+832	+200	-472	+392	-248
00000120	+1076	+1015	+954	+909	+864	+511	+1054	+2893
00000128	+1404	+2006	+2609	+3187	+3510	+3805	+2180	+3875
00000130	+3906	+524	-170	+3040	+2666	+2639	+2484	+2081
00000138	+1806	+1621	+1308	+995	+170	-418	+3858	-302
00000140	+1176	+1106	+1036	+998	+960	+562	+676	+2278

00000148	+2344	+2521	+2954	+3195	+3436	+3636	+3068	+3604
00000150	+3884	+54	+320	+3674	+3188	+3284	+3124	+2740
00000158	+2612	+2522	+1920	+1158	+396	-236	-868	-356
00000160	+1212	+1157	+1102	+1055	+1008	+389	+794	+1775
00000168	+2884	+2859	+3475	+3474	+3474	+3619	+3764	+3877
00000170	+3350	-400	+1738	+3676	+3566	+3577	+3460	+3439
00000178	+3290	+2623	+1828	+1313	+670	-78	-442	-250
00000180	+1248	+1208	+1168	+1112	+1056	+216	+912	+1912
00000188	+2656	+1918	+2204	+2858	+3512	+4370	+3948	+4278
00000190	+1536	-342	+3412	+3678	+3688	+3742	+3796	+3626
00000198	+2944	+2340	+1992	+1596	+944	-48	-272	-400
000001A0	+1344	+1337	+1330	+1051	+900	+677	+967	+936
000001A8	+522	+513	+377	+144	+296	+488	+3240	+4584
000001B0	+424	+289	+4250	+3979 +2067	+3836	+3801	+3767	+3356
000001B8 000001C0	+3458 +1440	+3826 +1338	+3427 +1236	+2067	+452 +1512	-256 +1395	-324 +766	-324 +217
000001C0 000001C8	+1204	+1029	+1622	+1911	+920	+318	-28	+1050
000001C8	+336	+1176	+4576	+4024	+3984	+3861	+3738	+3983
000001D0	+3716	+3137	+2814	+3179	+3288	+1200	-376	-248
000001E0	+1472	+1379	+1286	+1585	-676	-1648	-1211	-159
000001E0	+1662	+1840	+2531	+3213	+4152	+3860	+1008	+500
000001E0	+120	+2415	+4582	+4093	+3860	+3936	+4013	+3553
000001F8	+3094	+2623	+2153	+1306	+2124	+296	-252	-252
00000200	+1504	+1420	+1336	+1284	-2096	-850	-372	+874
00000208	+2120	+2524	+3184	+3620	+3800	+3946	+4860	+718
00000210	+672	+70	+748	+3522	+4248	+4140	+4032	+3252
00000218	+2984	+2238	+1236	+714	-320	-224	-128	-256
00000220	+1588	+1475	+1618	+33	-1424	-446	+148	+1358
00000228	+2440	+2861	+3411	+3656	+3774	+4016	+4130	+380
00000230	+982	+1502	-154	+14	+310	+1414	+1750	+1582
00000238	+774	+152	-213	-499	-16	-12	-136	-264
00000240	+1672	+1530	+1900	-1218	-752	-170	+412	+1586
00000248	+2504	+3071	+3638	+3693	+3748	+3574	+2376	+42
00000250	+2316	+4726	+3552	+730	+212	-416	-532	-472
00000258	-156	+115	+1154	+2513	-224	-56	-144	-272
00000260	+1580	+1585	+1590	-1421	-720	-166	+260	+1222
00000268	+2312	+2928	+3289	+3273	+3386	+3692	+1182	+256
00000270	+3554	+4110	+4026	+4446	+3970	+3514	+3442	+3106
00000278	+3538	+3637	+3225	+1980	-416	-212	-136	-264
00000280	+1744	+1640	+1024	-1752	-688	-34	+364	+986
00000288	+2120	+2658	+2684	+2726	+3024	+3170	+756	+598
00000290	+4280	+4006	+3988	+3938	+3888	+3732	+3832	+3996
00000298	+3392	+3192	+3248	+680	-96	-112	-128	-256
000002A0	+1732	+2129	-801	-1219	-486	+71	+499	+719
000002A8	+940	+1600	+2005	+2377	+2494	+2268	+507	+1529
000002B0	+4344	+4062	+3908	+3858	+3808	+3607	+3535	+3478
000002B8	+3934	+3899	+3865	-217	+52	-36	-124	-188
000002C0 000002C8	+1720 +272	+2235 +543	-1346	-1199	-540	-209	+122 +258	+453 +3229
000002C8	+3896	+3862	+814 +3828	+1645 +3778	+1708 +3728	+1239 +3611	+3494	+3345
000002D0	+2940	+2687	+2178	-347	-56	-88	-120	-120
000002D8	+1692	+1508	-2003	-1250	-1394	-744	-120 -863	-120 -910
000002E0	-316	-259	+183	+104	+538	+1017	+601	+3632
000002E0	+3720	+3742	+3636	+3610	+3584	+3462	+3341	+3187
000002F8	+2778	+2538	+1019	-84	+92	-20	-132	-132
00000310	+2432	-882	-2660	-2070	+312	+768	+1736	+1312
00000308	+632	-676	-1216	-668	-376	+924	+944	+4036
00000310	+3544	+3622	+3444	+3442	+3440	+3314	+3188	+3030
00000318	+2616	+2518	+116	+178	-16	-80	-144	-144

00000320	+2184	+541	+1587	+2192	+1646	+1373	+1357	+1380
00000328	+1276	+1478	+1041	-677	-730	+1136	+2235	+3261
00000330	+3392	+3016	+3409	+3265	+3250	+3121	+2992	+2783
00000338	+2318	+1904	-46	+108	+6	-58	-122	-122
00000340	+1680	+1709	+1482	+1463	+1444	+1339	+1234	+1193
00000348	+1152	+1073	+994	+1235	+964	+581	+1990	+2487
00000350	+2728	+2923	+2862	+2833	+3060	+2928	+2796	+2536
00000358	+2020	+1290	-208	+38	+28	-36	-100	-100
00000360	+1624	+1676	+1601	+1501	+1402	+1320	+1239	+1189
00000368	+1140	+1067	+995	+1034	+818	+953	+961	+1472
00000370	+2112	+2045	+2491	+2416	+2470	+2599	+2088	+2049
00000378	+2138	+268	+62	+104	+18	-38	-94	-158
00000380	+1824	+1644	+1464	+1412	+1360	+1302	+1244	+1186
00000388	+1128	+1062	+996	+962	+928	+814	+700	+1098
00000390	+2008	+1168	+1608	+1744	+1880	+2142	+1124	+1434
00000398	+208	+142	+76	+42	+8	-40	-88	-216
000003A0	+1552	+1504	+1456	+1384	+1312	+1266	+1220	+1174
000003A8	+1128	+1054	+980	+938	+896	+810	+724	+502
000003B0	+536	+616	+312	+1272	+1336	+322	+204	+70
000003B8	+192	+142	+92	+50	+8	-48	-104	-168
000003C0	+1536	+1492	+1448	+1356	+1264	+1230	+1196	+1162
000003C8	+1128	+1046	+964	+914	+864	+806	+748	+674
000003D0	+600	+576	+552	+800	+1304	+294	+308	+242
000003D8	+176	+142	+108	+58	+8	-56	-120	-120
000003E0	+1536	+1492	+1448	+1356	+1264	+1230	+1196	+1162
000003E8	+1128	+1046	+964	+914	+864	+806	+748	+674
000003F0	+600	+576	+552	+288	+280	+294	+308	+242
000003F8	+176	+142	+108	+58	+8	-56	-120	-120
00000400	+0	+128	+0	+0	+0	+0	+0	+0
00000408	+0	+0	+0	+0	+0	+0	+0	+0

#### 4.2.4.3.3 Level 1 Sub-bands

The following are the dumps of the four level 1 de-quantized sub-bands (LL1, LH1, HL1, and HH1). LL1 is reconstructed from level 2 sub-bands. LH1, HL1 and HH1 are generated by de-quantizing the corresponding decoded sub-bands, as shown in sections <u>4.2.4.2</u> and <u>4.2.4.2.1</u>.

All the coefficients are displayed in 11.5 fixed-point representation.

## 4.2.4.3.3.1 LL1

The LL1 sub-band is the same as that shown in section 4.2.4.3.2.7.

#### 4.2.4.3.3.2 HL1

The following is a dump of the HL1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+128	+0	+0	+0	+0	+0	+0
80000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0
00000028	+0	+0	+0	+0	+0	+0	+0	+0
00000030	+0	+0	+0	+0	+0	+0	+0	+0
00000038	+0	+0	+0	+0	+0	+0	+0	+0

00000040	+0	+0	+0	+0	+0	+0	+0	+0
00000048	+0	+0	+0	+0	+0	+0	+0	+0
00000050	+0	+0	+0	+0	+0	+0	+0	+0
00000058	+0	+0	+0	+0	+0	+0	+0	+0
00000060	+128	+0	+256	+0	+0	+0	+0	-128
00000068	+0	+0	+0	+0	+0	+0	+0	+0
00000070	+0	+0	+0	+0	+0	+0	+0	+0
00000078	+0	+0	+0	+128	+0	+0	+0	+0
08000000	+0	+0	+128	+0	+0	+0	+256	+0
00000088	+0	+0	+0	+0	+0	+0	+0	+0
00000090	+0	+0	+0	+0	+0	+0	+0	+0
00000098	+0	+0	+0	+0	+0	+0	+0	+0
000000A0	+0	+0	+0	+0	+0	+0	+0	+0
8A000000	+0	+128	+0	+0	+0	+0	+0	+0
000000B0	+0	+0	-128	+0	+0	+0	+0	+0
000000B8	+0	+0	+0	+0	-128	+128	+0	+0
000000C0	+0	+0	+0	+0	+0	+0	-384	+0
000000C8	+0	+0	+128	+0	+0	+0	+0	+0
000000D0	+0	+256	+0	+0	+0	+0	+0	+0
000000D8	+0	+128	+0	-256	+512	-640	-128	+0
000000E0	+0	+0	+0	+0	+0	-128	-384	+0
000000E8	+0	+0	+0	+0	+0	+0	+0	+0
000000F0	+0	-384	+0	+384	+0	+0	+0	+0
000000F8	+0	+0	-128	+512	+512	-640	-128	+0
00000100	+0	+0	+0	+0	+0	-256	+640	+0
00000108	+0	+0	+0	+0	+0	+256	+128	+0
00000110	+256	-640	-512	+128	+0	+0	+0	+0
00000118	+0	+0	+128	+384	-128	+640	+0	-128
00000120	+0	+0	+0	+0	+0	-256	-256	-384
00000128	+0	+0	+0	+0	+0	+384	+0	+0
00000130	+896	+0	-512	+0	+0	+0	+0	+0
00000138	+0	+0	+0	-128	+0	-128	+256	-128
00000140	+0	+0	+0	+0	+0	-384	+128	+640
00000148	+0 +0	+0	+0	+0	+0	+0	-128 +0	+0
00000150 00000158	+0	+128 +0	+896 +0	+0 +0	+0 +0	+0 -128	+0	+0 +0
00000138	+0	+0	+0	+0	+256	+0	+0	+0
00000160	-256	+0	+0	+0	+0	+0	+128	+0
00000108	-1152	-384	+640	+0	+0	+0	+120	+0
00000170	+0	+0	+040	+0	+0	-128	+0	+0
00000178	+0	+0	+0	+0	+0	+0	-128	-128
00000180	-128	+0	+0	+0	+0	+0	+0	+768
00000190	-256	-1024	-128	+0	+0	+0	+0	+0
00000190	+0	+0	+0	+0	+0	-128	+0	+0
00000130	+0	+0	+0	+0	-384	+0	+0	+0
000001110	+0	+0	+0	-128	+0	-128	+0	+640
000001H0	+256	+384	+0	+0	+0	+0	+0	+0
000001B0	+0	+0	+128	+0	+256	+0	+0	+0
000001C0	+0	+0	+0	-128	+128	+0	+0	-128
000001C8	+256	+0	+0	+128	+0	+0	-128	+0
000001D0	-128	+896	+0	+0	+0	+0	+0	+0
000001D8	+0	+0	+0	+0	-384	-256	+0	+0
000001E0	+0	+0	+0	+384	-128	+0	-128	+0
000001E8	+128	+0	+0	+0	+128	+256	-128	+0
000001F0	-640	+128	+0	+0	+0	+0	+0	+0
000001F8	+0	+0	+0	-384	-512	+0	+0	+0
00000200	+0	+0	-128	-768	+128	+0	-128	+0
00000208	+0	+0	+0	+0	+0	+0	+768	+0
00000210	-128	+0	+128	+0	+0	+128	-128	+0

00000218	+0	+0	+0	+0	+0	+0	+0	+0
00000220	+0	+0	+384	-640	+0	+0	+0	+0
00000228	+0	+0	+0	+0	+0	-128	-128	+128
00000230	+1280	+0	+0	+0	-128	+128	+0	+0
00000238	+0	+0	-128	+128	+0	+0	+0	+0
00000240	+0	+0	+896	+0	+0	+0	+0	+0
00000248	+0	+0	+0	+0	+0	+128	-640	-640
00000250	+384	+0	+0	+0	+0	+0	+0	+0
00000258	+0	-128	+0	-128	+0	+0	+0	+0
00000260	+0	-128	-256	+0	+0	+0	-128	+0
00000268	+0	+0	+0	+0	+0	+384	-128	-896
00000270	+0	+0	+0	+0	+0	+0	+0	+0
00000278	+0	+0	+128	-768	+0	+0	+0	+0
00000280	+0	+0	-1024	+0	+0	+0	+0	+0
00000288	+0	+0	+0	+0	+0	+384	+256	+512
00000290	+0	+0	+0	+0	+0	-128	+0	+0
00000298	+0	+0	+768	-128	+0	+0	+0	+0
000002A0	-128	+896	-128	+0	+0	+0	-128	-128
000002A8	+0	+0	+0	+0	+0	-384	-128	+768
000002B0	+0	+0	+0	+0	+0	+0	+0	+0
000002B8	+0	+0	+384	+128	+0	+0	+0	+0
000002C0	+0	+512	+128	+256	-256	-256	+0	-128
000002C8	+0	+0	+0	+0	+128	-128	-896	+128
000002D0	+0	+0	+0	+0	+0	+0	+0	+0
000002D8	+0	+0	-768	+0	+0	+0	+0	+0
000002E0	-128	-1280	+384	+128	+256	+0	-256	+128
000002E8	+128	+0	+0	+0	+0	+0	-128	+0
000002F0	+0	+0	-128	+0	+0	+0	+0	+0
000002F8	+0	+384	-256	+0	+0	+0 +128	+0	+0
00000300	+768	-1024	-256	+0	-256		+0	+0
00000308 00000310	-128 +0	-128 +0	-128 +0	+128	+128	+128	+768	+0
00000310	+0	+512	+128	+0 +0	+0 +0	+0 +0	+0 +0	+0
00000318	+384	+312	+128	+128	+0	+0	+128	+128
00000320	+0	+236	+128	-256	+640	-384	+256	+120
00000328	+0	+0	+120	+128	+040	+0	+230	+0
00000330	+0	-256	+0	+0	+0	+0	+0	+0
00000330	+0	+0	+0	+0	+0	+0	+0	+0
00000340	+0	+0	-128	+0	+0	-384	+0	+128
00000340	+0	+0	+128	+128	+0	+0	+0	+0
00000350	+0	-512	+0	+0	+0	+0	+0	+0
00000330	+0	+0	+0	+0	+0	+0	+0	+0
00000368	+0	+0	+0	+0	+0	+0	-128	+128
00000370	-128	-128	+0	+0	+128	+0	+0	+0
00000370	+384	+0	+0	+0	+0	+0	+0	+0
00000370	+0	+0	+0	+0	+0	+0	+0	+0
00000388	+0	+0	+0	+0	+0	+0	-128	+0
00000390	+0	+0	+128	+128	+128	-256	+0	+128
00000398	+0	+0	+0	+0	+0	+0	+0	+0
000003A0	+0	+0	+0	+0	+0	+0	+0	+0
000003A8	+0	+0	+0	+0	+0	+0	+0	+0
000003H0	-128	+0	-256	+128	+128	+0	+0	+0
000003B0	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0
000003C8	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+384	-128	+0	+0	+0
000003D8	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0
000003E8	+0	+0	+0	+0	+0	+0	+0	+0
30000000	. 0	. 0	. 0	. 0	. 0	. 0	. 0	. 0

000003F0	+0	+0	+0	-128	+0	+0	+0	+0
000003F8	+0	+0	+0	+0	+0	+0	+0	+0

## 4.2.4.3.3.3 LH1

The following is a dump of the LH1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	+0	+0	+0	+0	+0	+0
8000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0
00000028	+0	+0	+0	+0	+0	+0	+0	+0
00000030	+0	+0	+0	+0	+0	+0	+0	+0
00000038	+0	+0	+0	+0	+0	+0	+0	+0
00000040	+0	+0	+0	+0	+0	+0	+0	+0
00000048	+128	+0	-128	-128	+0	+0	-128	-128
00000050	+128	+0	+0	+0	+0	+0	+0	+0
00000058	+0	+0	+0	+0	+0	+0	+0	+0
00000060	-128	-128	-128	+0	+0	+0	+0	-128
00000068	+0	+0	+0	+0	+0	+0	+0	+0
00000070	+0	-128	+0	+0	+0	+0	+0	+0
00000078	+0	+0	+0	+0	+0	+0	+0	+0
08000000	-128	-128	-128	+0	+0	+0	+0	+0
00000088	+0	+0	+0	+0	+0	+0	+0	+0
00000090	+0	+0	+0	+0	+0	+0	+0	+0
00000098	+0	+0	+0	+0	+0	+0	+0	+0
0A000000	+0	+0	+0	+0	+0	+0	+0	+0
8A000000	+0	+0	+0	+0	+0	+0	+0	+0
000000B0	+0	+0	+0	+0	-128	+128	+0	+0
000000B8	+0	+0	+0	+0	-256	-1024	+256	+0
000000C0	+0	+0	+0	+0	+0	+0	-128	+0
000000C8	+0	+0	+0	+0	+0	+0	+0	+0
000000D0	+0	+0	+0	+0	+0	+0	-128	+0
000000D8	+0	+128	+0	-256	+512	+512	-128	+0
000000E0	+0	+0	+0	+0	+0	-128	+384	-128
000000E8	+0	+0	+0	+0	+0	+0	+128	+0
000000F0	+0	+128	+0	+0	+0	+0	+0	+0
000000F8	+0	+0	-128	+384	+384	-896	-128	+0
00000100	+0	+0	+0	+0	+0	+0	+0	+128
00000108	+0	+0	+0	+0	+0	+0	+0	+0
00000110	+0	+0	-128	+128	+0	+0	+0	+0
00000118	+0	+0	+0	+128	+0	+0	+768	+384
00000120	+0	+0	+0	+0	+0	+0	+0	+0
00000128	+0	+0	+0	+128	+0	+0	+0	+0
00000130	+128	+0	+0	+0	+0	+0	+0	+0
00000138	+0	+0	+0	+0	+0	+0	-1024	+0
00000140	+0	+0	+0	+0	+0	+0	+0	+0
00000148	+0	+0	+0	+128	-256	-256	+256	-128
00000150	+0	+0	-128	+0	+0	+0	+0	+0
00000158	+0	+0	+0	+0	+0	+0	+0	+0
00000160	+0	+0	+0	+0	+0	-128	+0	+0
00000168	+128	+128	+384	+128	+0	+0	+0	+0
00000170	+0	+0	+0	+0	+0	+0	+0	+128
00000178	+0	+0	+0	+0	+0	+0	+0	+0
00000180	+0	+0	+0	+0	+0	-128	+0	-128

00000188	-640	-384	-512	-768	-768	+896	+128	+128
00000190	-128	+0	+0	+0	+0	+0	+0	+0
00000198	-128	-256	-384	+0	+128	+0	+0	+0
000001A0	+0	+0	+0	+0	+0	+128	+0	+256
000001A8	-128	+0	-256	-384	+128	+128	-1024	+768
000001B0	+0	-128	+128	+0	+0	+0	+0	+128
000001B8	+128	+0	+0	+768	-384	-128	+0	+0
000001C0	+0	+0	+0	-128	+640	+256	-768	-256
000001C8	+0	+0	+0	+256	+896	-768	-128	+0
000001D0	+0	+128	+0	+0	+0	+0	+0	+0
000001D8	+0	+0	-128	-128	+128	+768	+0	+0
000001E0	+0	+0	+0	+0	-256	+128	+0	+0
000001E8	+0	+0	+0	+0	+0	-128	+768	-128
000001F0	+128	-768	+896	+0	+0	+0	+0	+0
000001F8	+0	+0	+0	+128	-128	-128	+0	+0
00000200	+0	+0	+0	+128	+0	+0	+0	+0
00000208	+0	+0	+0	+0	+0	+0	+0	+0
00000210	-128	-256	+0	-1024	+768	+768	+512	+384
00000218	+384	+512	-128	-256	+0	+0	+0	+0
00000220	+0	+0	+0	+0	+0	+0	+0	+0
00000228	+0	+0	+0	+0	+0	+0	+256	-128
00000230	-128	+896	-1024	+0	+128	-256	-512	-384
00000238	-128	+128	-384	-512	+128	+0	+0	+0
00000240	+0	+0	+0	+0	+0	+0	+0	+0
00000248	+0	+0	+128	+0	+128	-384	-640	+0
00000250	+128	+0	+0	+1024	-128	-896	-1152	-896
00000258	-256	+768	+384	+0	+0	+0	+0	+0
00000260	+0	+0	+128	+0	+0	+0	-128	-128
00000268	+0	+0	+0	+0	+0	+128	-128	+0
00000270	+0	+0	+0	+0	+0	+0	+0	+0
00000278	+0	+0	+0	+0	+0	+0	+0	+0
00000280	+0	+0	+0	+0	+0	+0	+128	+0
00000288	+0	+0	+0	+0	+0	+0	+0	-128
00000290	+128	+0	+0	+0	+0	+0	-128	+128
00000298	+0	+0	+128	-128	+0	+0	+0	+0
000002A0	-128	+128	-128	+128	+128	+0	+0	+0
000002A8	+0	+0	+0	+0	+0	+0	+0	+0
000002B0	+0	+0	+0	+0	+0	+0	+0	+0
000002B8	-128	+128	-128	+0	+0	+0	+0	+0
000002C0	+0	+128	+128	+384	+384	+0	+128	+128
000002C8	-128	+128	+0	+0	+0	+0	+0	+0
000002D0	+0	+0	+0	+0	+0	+0	+0	+0
000002D8	+0	+0	+128	+0	+0	+0	+128	+0
000002E0	+0	+0	+256	+128	-512	-640	-1024	-768
000002E8	-512	+128	+0	+0	-128	+0	+0	+0
000002F0	+0	+0	+0	+0	+0	+0	+0	+0
000002F8	+0	+0	+0	+128	+0	+0	+0	+0
00000300	+384	-1152	-640	+1280	+256	+256	+0	-128
00000308	+256	+768	-512	-128	+0	+0	+0	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0
00000318	+0	+0	+0	+0	+0	+0	+0	+0
00000320	-128	+256	-128	-128	+128	+0	+0	+0
00000328	+0	+0	-128	+512	-256	-128	+128	-128
00000330	+128	-128	+0	+0	+0	+0	+0	+0
00000338	+0	+128	+0	+0	+0	+0	+0	+0
00000340	+0	+0	+0	+0	+0	+0	+0	+0
00000348	+0	+0	+0	+0	+0	+0	+0	+128
00000350	-128	+128	+0	+0	+0	+0	+0	+0
00000358	+0	+0	+0	+0	+0	+0	+0	+0

00000360	+0	+128	+0	+0	+0	+0	+0	+0
00000368	+0	+0	+0	+0	+0	+0	-128	-128
00000370	+0	-128	+128	+128	+0	+128	+0	-128
00000378	+384	-128	+0	+0	+0	+0	+0	+0
00000380	+0	+0	+0	+0	+0	+0	+0	+0
00000388	+0	+0	+0	+0	+0	+0	+0	-128
00000390	-128	-128	+128	+128	+128	+0	-256	-384
00000398	+0	+0	+0	+0	+0	+0	+0	+0
000003A0	+0	+0	+0	+0	+0	+0	+0	+0
000003A8	+0	+0	+0	+0	+0	+0	+0	+0
000003B0	+0	+0	-128	+512	+256	+128	+0	+0
000003B8	+0	+0	+0	+0	+0	+0	+0	+0
000003C0	+0	+0	+0	+0	+0	+0	+0	+0
000003C8	+0	+0	+0	+0	+0	+0	+0	+0
000003D0	+0	+0	+0	+0	-256	+0	+0	+0
000003D8	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0
000003E8	+0	+0	+0	+0	+0	+0	+0	+0
000003F0	+0	+0	+0	+0	+0	+0	+0	+0
000003F8	+0	+0	+0	+0	+0	+0	+0	+0
00000400	+0	+0	+0	+0	+0	+0	+0	+0
00000408	+0	+0	+0	+0	+0	+0	+0	+0

# 4.2.4.3.3.4 HH1

The following is a dump of the HL1 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	+0	+0	+0	+0	+0	+0	+0	+0
80000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0
00000028	+0	+0	+0	+0	+0	+0	+0	+0
00000030	+0	+0	+0	+0	+0	+0	+0	+0
00000038	+0	+0	+0	+0	+0	+0	+0	+0
00000040	+0	+0	+0	+0	+0	+0	+0	+0
00000048	+0	+0	+0	+0	+0	+0	+0	+0
00000050	+0	+0	+0	+0	+0	+0	+0	+0
00000058	+0	+0	+0	+0	+0	+0	+0	+0
00000060	+0	+0	+0	+0	+0	+0	+0	+0
00000068	+0	+0	+0	+0	+0	+0	+0	+0
00000070	+0	+0	+0	+0	+0	+0	+0	+0
00000078	+0	+0	+0	+0	+0	+0	+0	+0
08000000	+0	+0	+0	+0	+0	+0	+0	+0
00000088	+0	+0	+0	+0	+0	+0	+0	+0
00000090	+0	+0	+0	+0	+0	+0	+0	+0
00000098	+0	+0	+0	+0	+0	+0	+0	+0
0A00000	+0	+0	+0	+0	+0	+0	+0	+0
8A000000	+0	+0	+0	+0	+0	+0	+0	+0
000000B0	+0	+0	+0	+0	+0	+0	+0	+0
000000B8	+0	+0	+0	+0	-256	+256	+0	+0
000000C0	+0	+0	+0	+0	+0	+0	+0	+0
000000C8	+0	+0	+0	+0	+0	+0	+0	+0
000000D0	+0	+0	+0	+0	+0	+0	+0	+0
000000D8	+0	+0	+0	-512	-256	+256	+0	+0
000000E0	+0	+0	+0	+0	+0	-256	-256	+0

000000E8	+0	+0	+0	+0	+0	+0	+0	+0
000000F0	+0	-256	+0	+0	+0	+0	+0	+0
000000F8	+0	+0	-256	+256	-512	+0	+0	+0
00000100	+0	+0	+0	+0	+0	+0	+0	+0
00000108	+0	+0	+0	+0	+0	+0	+0	+0
00000110	+0	+0	-256	+0	+0	+0	+0	+0
00000118	+0	+0	+0	-256	+0	+0	+256	-256
00000120	+0	+0	+0	+0	+0	-256	+0	+0
00000128	+0	+0	+0	+0	+0	+0	+0	+0
00000130	+0	+0	+0	+0	+0	+0	+0	+0
00000138	+0	+0	+0	+0	+0	+0	+0	+0
00000140	+0	+0	+0	+0	+0	+0	+0	+0
00000148	+0	+0	+0	+0	+0	+0	+0	+0
00000150	+0	+0	+0	+0	+0	+0	+0	+0
00000158	+0	+0	+0	+0	+0	+0	+0	+0
00000160 00000168	+0 +0							
00000188	+0	+0	+0	+0	+0	+0	+0	+0
00000170	+0	+0	+0	+0	+0	+0	+0	+0
00000178	+0	+0	+0	+0	+0	+0	+0	+0
00000180	+0	+0	+0	-256	+0	+0	+0	+256
00000100	+0	+0	+0	+0	+0	+0	+0	+0
00000190	+0	+0	+0	+0	+0	+0	+0	+0
00000130	+0	+0	+0	+0	+256	+0	+0	+0
000001110 000001A8	+0	+0	+0	+0	+0	+0	+0	-256
000001H0	+0	+256	+0	+0	+0	+0	+0	+0
000001B8	+0	+0	+0	+0	+256	+0	+0	+0
000001C0	+0	+0	+0	+0	+256	+0	+0	+0
000001C8	+0	+0	+0	+0	+0	-256	+0	+0
000001D0	+0	+0	+0	+0	+0	+0	+0	+0
000001D8	+0	+0	+0	+256	+256	+0	+0	+0
000001E0	+0	+0	+0	+0	+0	+0	+0	+0
000001E8	+0	+0	+0	+0	+0	+0	-256	+0
000001F0	+256	+0	+0	+0	+0	+0	+0	+0
000001F8	+0	+0	+0	+256	+0	+0	+0	+0
00000200	+0	+0	+0	-256	+0	+0	+0	+0
00000208	+0	+0	+0	+0	+0	+0	+0	+0
00000210	-512	+0	+0	+0	+0	+0	+0	+0
00000218	+0	+0	+0	+0	+0	+0	+0	+0
00000220	+0	+0	+0	+0	+0	+0	+0	+0
00000228	+0	+0	+0	+0	+0	+0	-256	+0
00000230	-256	+0	+0	+0	+0	+0	+0	+0
00000238	+0	+0	+0	+256	+0	+0	+0	+0
00000240	+0	+0	+0	+0	+0	+0	+0	+0
00000248	+0	+0	+0	+0	+0	-256	+256	+0
00000250	+0	+0	+0	+0	+0	+0	+0	+0
00000258	+0	+0	+0	-256	+0	+0	+0	+0
00000260	+0	+0	+0	+0	+0	+0	+0	+0
00000268	+0 +0	+0	+0	+0	+0	+256	+0	+0
00000270 00000278	+0	+0	+0	+0	+0	+0	+0	+0
00000278	+0	+0 +0						
00000280	+0	+0	+0	+0	+0	+0	+0	+256
00000288	+0	+0	+0	+0	+0	+0	+0	+230
00000298	+0	+0	+256	+0	+0	+0	+0	+0
00000230	+0	+256	+0	+0	+0	+256	+0	+0
000002A8	+0	+0	+0	+0	+0	+0	+0	+0
000002H0	+0	+0	+0	+0	+0	+0	+0	+0
000002B8	+0	+0	+0	+0	+0	+0	+0	+0

000002C0	+0	+0	-256	+0	+0	+256	+256	+0
000002C8	+0	+0	+0	+0	+0	+0	+0	+0
000002D0	+0	+0	+0	+0	+0	+0	+0	+0
000002D8	+0	+0	+0	+0	+0	+0	+0	+0
000002E0	+0	-256	-256	+512	+0	-256	+0	+0
000002E8	+0	+0	+0	+0	+0	+0	+0	+0
000002F0	+0	+0	+0	+0	+0	+0	+0	+0
000002F8	+0	+0	+0	+0	+0	+0	+0	+0
00000300	+256	-256	+0	+0	+0	+0	+0	+0
00000308	+0	+256	-256	+0	+0	+0	+0	+0
00000310	+0	+0	+0	+0	+0	+0	+0	+0
00000318	+0	+0	+0	+0	+0	+0	+0	+0
00000320	+0	+0	+0	+0	+0	+0	+0	+0
00000328	+0	+0	+0	+0	+0	+0	+256	+0
00000330	+0	+0	+0	+0	+0	+0	+0	+0
00000338	+0	+0	+0	+0	+0	+0	+0	+0
00000340	+0	+0	+0	+0	+0	+0	+0	+0
00000348	+0	+0	+0	+0	+0	+0	+0	+0
00000350	+0	+0	+0	+0	+0	+0	+0	+0
00000358	+0	+0	+0	+0	+0	+0	+0	+0
00000360	+0	+0	+0	+0	+0	+0	+0	+0
00000368	+0	+0	+0	+0	+0	+0	+0	+0
00000370	-256	+0	+0	+0	+0	+0	+0	+0
00000378	+0	+0	+0	+0	+0	+0	+0	+0
00000380	+0	+0	+0	+0	+0	+0	+0	+0
00000388	+0	+0	+0	+0	+0	+0	+0	+0
00000390	-256	+0	+0	+0	+0	+0	+0	+0
00000398	+0	+0	+0	+0	+0	+0	+0	+0
000003A0	+0	+0	+0	+0	+0	+0	+0	+0
000003A8	+0	+0	+0	+0	+0	+0	+0	+0
000003B0	+0	+0	-256	-256	+256	+0	+0	+0
000003B8	+0	+0	+0	+0	+0	+0	+0	+0
000003C0	+0	+0	+0	+0	+0	+0	+0	+0
000003C8	+0	+0	+0	+0	+0	+0	+0	+0
000003D0	+0	+0	+0	-256	+0	+0	+0	+0
000003D8	+0	+0	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+0
000003E8	+0	+0	+0	+0	+0	+0	+0	+0
000003F0	+0	+0	+0	+0	+0	+0	+0	+0
000003F8	+0	+0	+0	+0	+0	+0	+0	+0

# 4.2.4.3.3.5 Inverse DWT-X (LL1 - HL1)

The following is a dump of the L0 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	+16	+64	+272	-32	-16	+0	-16
80000000	-32	-24	-16	-8	+0	-24	-48	-72
00000010	-96	-90	-84	-78	-72	-98	-124	-150
00000018	-176	-192	-208	-224	-240	-256	-272	-288
00000020	-304	-304	-304	-304	-304	-336	-368	-400
00000028	-432	-450	-468	-486	-504	-522	-540	-558
00000030	-576	-598	-620	-642	-664	-686	-708	-730
00000038	-752	-768	-784	-800	-816	-816	-816	-816
00000040	+168	+224	+281	+209	+138	+126	+115	+103
00000048	+92	+88	+84	+80	+76	+64	+52	+40
00000050	+28	+18	+8	-2	-12	-38	-64	-90

00000058	-116	-105	-95	-148	-201	-198	-195	-192
00000060	-190	-204	-218	-232	-247	-269	-291	-313
00000068	-336	-357	-379	-400	-422	-447	-473	-498
00000070	-524	-546	-569	-591	-614	-660	-707	-689
00000078	-672	-698	-724	-750	-776	-776	-776	-776
08000000	+368	+401	+434	+339	+244	+237	+230	+223
00000088	+216	+200	+184	+168	+152	+152	+152	+152
00000090	+152	+126	+100	+74	+48	+22	-4	-30
00000098	-56	-18	+19	-71	-162	-140	-119	-97
0A00000	-76	-104	-133	-161	-190	-202	-215	-227
8A000000	-240	-265	-290	-315	-340	-373	-406	-439
000000B0	-472	-495	-518	-541	-564	-635	-706	-649
000000B8	-592	-628	-664	-700	-736	-736	-736	-736
000000C0	+376	+649	+411	+364	+318	+795	+249	+342
000000C8	+436	+408	+380	+352	+324	+308	+292	-140
000000D0	-60	+74	+208	+182	+156	+186	+216	+374
000000D8	+532	+504	+476	+320	+165	+61	-42	-146
00000E0	-250	-244	-239	-170	-101	-123	-146	-169
000000E8	-192	-216	-241	-265	-290	-318	-347	-375
000000F0	-404	-399	-395	-454	-514	-557	-601	-356
000000F8	-624	-622	-620	-650	-680	-680	-680	-680
00000100	+1152	+1026	+900	+870	+840	+906	+460	+430
00000108	+400	+424	+448	+408	+368	+400	-592	-240
00000110	+112	+534	+956	+994	+1032	+926	+820	+970
00000118	+1120	+1155	+1190	+1097	+1004	+839	+674	+509
00000120	+344	+191	+38	+13	-12	-45	-78	-111
00000128	-144	-168	-192	-216	-240	-264	-288	-312
00000130	-336	-304	-272	-368	-464	-416	-368	-448
00000138	-528	-552	-576	-600	-624	-624	-624	-624
00000140	+708	+637	+566	+559	+552	+513	+474	+499
00000148	+524	+561	+599	+572	+546	+131	-283	+6
00000150 00000158	+296 +1616	+665	+1034 +1806	+1627	+1708	+1669	+1630 +1450	+1623 +1241
00000158	+1010	+1711 +950	+1806	+1709 +563	+1612 +258	+1531 -120	+1450	+1241 -74
00000160	-164	-180	-197	-150	-103	-120 -123	-144	-74 -165
00000188	-186	-325	-464	-283	-103 -102	-123 -305	-508	-183
00000170	-466	-1022	-1066	-534	-514	-578	-642	-642
00000178	+776	+760	+744	+728	+712	+696	+680	+664
00000180	+648	+635	+622	+577	+532	-457	+90	+413
00000188	+736	+924	+1112	+1524	+1936	+2284	+2120	+2116
00000190	+2112	+2267	+2422	+2321	+2220	+2223	+2120	+1973
00000130	+1720	+1582	+1444	+1242	+16	-2	-20	+26
000001710	+72	-65	-203	-212	-222	-239	-257	-274
000001710	-292	-186	-80	+58	-316	-290	-264	-462
000001B0	+364	+2508	+2604	-436	-916	-1012	-596	-596
000001B0	+876	+855	+834	+813	+792	+803	+814	+825
000001C0	+836	+720	+605	+553	+1014	-18	+487	+735
000001C0	+984	+1239	+1494	+1813	+2132	+2343	+2554	+2573
000001D0	+2592	+2639	+2686	+2861	+3036	+2823	+2610	+2525
000001E0	+2440	+2405	+2371	+448	+62	+115	+169	+1438
000001E0	+1172	+970	+768	+533	+299	+217	+135	+52
000001E0	-30	-63	-96	-161	-226	-419	-100	+955
000001F8	-38	+1842	+1674	-990	-1094	-998	-390	-390
00000110	+976	+950	+924	+898	+872	+846	+820	+794
00000200	+768	+806	+844	+786	+1752	+2534	+756	+994
00000200	+1232	+1554	+1876	+2070	+2264	+2594	+2924	+2998
00000210	+3072	+3139	+3206	+3305	+2380	+3103	+3314	+3173
00000210	+3032	+3005	+1954	-217	+172	-87	+1702	+2147
00000228	+2080	+1973	+1866	+1727	+1588	+1441	+1294	+1147
00000220	. 2000	. 10,0	. 2000	. = / = /	. 1000			1

00000230	+1000	+796	+592	+484	+376	+732	+576	+1092
00000238	+72	-584	-728	+952	+72	-56	-184	-440
00000240	+1076	+1045	+1015	+984	+954	+931	+909	+886
00000248	+864	+751	+639	+462	+1310	+1749	+3213	+1636
00000250	+1596	+1801	+2006	+2307	+2609	+2898	+3187	+3348
00000258	+3510	+3561	+3613	+3568	+1988	+2931	+3875	+3666
00000260	+3458	+3559	+76	+81	+86	+667	+3296	+2981
00000268	+2666	+2652	+2639	+2561	+2484	+2282	+2081	+1943
00000270	+1806	+1713	+1621	+1464	+1308	+1183	+1059	+390
00000278	+234	-60	-354	+1464	+3794	+2226	-366	-622
00000280	+1176	+1141	+1106	+1071	+1036	+1017	+998	+979
00000288	+960	+857	+754	+11	+804	+1605	+1894	+3239
00000290	+2024	+2272	+2521	+2737	+2954	+3074	+3195	+3315
00000298	+3436	+3536	+3636	+3384	+3132	+3144	+3668	+3776
0AC00002A0	+3884	+1937	-10	+155	-192	+3309	+3226	+3207
000002A8	+3188	+3236	+3284	+3204	+3124	+2932	+2740	+2676
000002B0 000002B8	+2612 +396	+2567 +112	+2522 -172	+2221 -744	+1920 -804	+1539 -580	+1158	+777 -356
000002B8	+1212	+112	+1157	+1129	+1102	+1078	-356 +1055	-356 +967
000002C0	+880	+1104	+261	+527	+794	+1076	+1775	+2393
000002C8	+3012	+2487	+2987	+3231	+3475	+3474	+3474	+3474
000002D0	+3474	+3546	+3619	+3659	+3473	+4012	+3474	+3869
000002E0	+3926	-157	+368	+221	+1610	+3763	+3356	+3461
000002E8	+3566	+3571	+3577	+3518	+3460	+3449	+3439	+3364
000002E0	+3290	+2956	+2623	+2225	+1828	+1570	+1313	+991
000002F8	+670	+328	-14	-452	-378	-314	-250	-250
00000300	+1248	+1228	+1208	+1188	+1168	+1140	+1112	+1084
00000308	+1056	+636	+216	+596	+976	+1252	+2040	+2156
00000310	+2784	+2127	+1982	+2093	+2204	+2531	+2858	+3185
00000318	+3512	+3941	+4370	+4159	+3948	+3921	+3894	+4123
00000320	+1280	+277	+298	+95	+3988	+3609	+3742	+3715
00000328	+3688	+3715	+3742	+3769	+3796	+3711	+3626	+3285
00000330	+2944	+2642	+2340	+2166	+1992	+1794	+1596	+1270
00000338	+944	+480	+16	-352	-208	-304	-400	-400
00000340	+1344	+1340	+1337	+1333	+1330	+1190	+1051	+1071
00000348	+1092	+212	+869	+918	+967	+951	+936	+729
00000350	+522	+517	+513	+445	+377	+292	+208	+28
00000358	+360	+456	+552	+1672	+3304	+3784	+4264	+3400
00000360	-24	+485	-31	+2781	+4058	+4018	+3979	+3907
00000368	+3836	+3818	+3801	+3784	+3767	+3561	+3356	+3407
00000370	+3458	+3642	+3826	+3594	+3363	+2939	+2003	+1163
00000378	+324	+482	-384	-354	-324	-324	-324	-324
00000380	+1440	+1389	+1338	+1287	+1236	+1273	+1310	+1155
00000388	+1512	+1677	+1331	+1048	+766	+523	+281	+454
00000390	+1140	+1532	+901	+1261	+1622	+1734	+1847	+1607
00000398	+856	+587	+318	+177	+36	+319	+1114	+757
000003A0	+400	+340	+792	+4252	+4128	+4076	+4024	+4004
000003A8	+3984	+3922	+3861	+3799	+3738	+3860	+3983	+3849
000003B0 000003B8	+3716	+3426	+3137	+2975	+2814	+2996	+3179	+3329
	+3480	+1732	+1520	+124	-248	-248	-248	-248
000003C0 000003C8	+1472 -804	+1425 -1450	+1379 -1584	+1332 -1365	+1286	+1339	+1393 <b>-</b> 95	+1062 +751
000003C8	-804 +1598	+1943	-1584 +1776	+2153	-1147 +2531	-877 +2872	-95 +3213	+3650
000003D0	+1598	+1943	+1776	+2153	+2531	+2872	+3213	+3650
000003D8	+440	+275	+2671	+3850	+4518	+4305	+4093	+3976
000003E0	+3860	+3898	+3936	+3974	+4013	+3783	+3553	+3376
000003E8	+3094	+2858	+2623	+2388	+2153	+1825	+1498	+1267
000003F0	+2572	+538	+552	+150	-252	-252	-252	-252
00000310	+1504	+1462	+1420	+1410	+1400	+1310	+1732	-1558
30000100	. 1001	. 1 1 0 2	120	. 1 110	100	. 1010	. 1 , 52	1000

00000408	-1776	-1089	-914	-611	-308	+59	+938	+1529
00000410	+2120	+2322	+2524	+2854	+3184	+3402	+3620	+3710
00000418	+3800	+3873	+3946	+4211	+4476	+3941	+334	+535
00000420	+736	+179	+134	+409	+684	+2327	+3458	+3853
00000428	+4248	+4162	+4076	+4310	+4032	+3418	+3316	+3150
00000430	+2984	+2611	+2238	+1737	+1236	+975	+714	+197
00000438	-320	-272	-224	-176	-128	-192	-256	-256
00000440	+1588	+1531	+1475	+1450	+1426	+1561	+161	-1751
00000448	-1104	-775	-446	-149	+148	+753	+1358	+1899
00000450	+2440	+2650	+2861	+3136	+3411	+3533	+3656	+3715
00000458	+3774	+3927	+4080	+3913	+4258	+2063	+380	+585
00000460	+278	+3130	+862	+354	-154	-70	+14	+194
00000468	+374	+638	+1414	+1806	+1686	+1634	+1582	+1178
00000470	+774	+463	+152	+1	-149	-580	-499	-33
00000478	-80	-46	-12	-74	-136	-200	-264	-264
00000480 00000488	+1672	+1601	+1530 -170	+1491	+1452	+1685	-1666	-1209
	-752 +2504	-461 +2787	+3071	+121 +3354	+412 +3638	+999 +3665	+1586	+2045
00000490 00000498	+3748	+3629	+3510	+3327	+2632	+377	+3693 +682	+3720 +283
00000498	+2444	+4257	+4534	+4043	+3552	+2141	+730	+471
000004A0	+212	-102	-416	-474	-532	-502	-472	-314
000004A8	-156	+11	+179	+442	+1218	+1897	+2577	+952
000004B0	-160	-108	-56	-100	-144	-208	-272	-272
000001E0	+1580	+1614	+1649	+1459	+1782	-268	-1293	-1006
00000100	-720	-443	-166	+79	+324	+549	+1286	+1799
00000100	+2312	+2620	+2928	+3108	+3289	+3281	+3273	+3329
000004D8	+3386	+3443	+3500	+3045	+1054	+655	+768	+593
000004E0	+4002	+4056	+4110	+4068	+4026	+4236	+4446	+4208
000004E8	+3970	+3742	+3514	+3478	+3442	+3274	+3106	+3322
000004F0	+3538	+3587	+3637	+3399	+3161	+2986	+2300	-402
000004F8	-32	-122	-212	-174	-136	-200	-264	-264
00000500	+1744	+1692	+1640	+1588	+1536	-1900	-1240	-964
00000508	-688	-361	-34	+165	+364	+675	+986	+1553
00000510	+2120	+2389	+2658	+2671	+2684	+2705	+2726	+2875
00000518	+3024	+3001	+2978	+2475	+436	+837	+214	+3143
00000520	+4024	+4015	+4006	+3997	+3988	+3963	+3938	+3913
00000528	+3888	+3842	+3796	+3590	+3896	+3946	+3996	+3694
00000530	+3392	+3292	+3192	+3028	+2864	+3148	+360	-92
00000538	-32	-72	-112	-120	-128	-192	-256	-256
00000540	+1860	+1546	+1745	+2072	-1185	-1426	-1155	-820
00000548	-486	-207	+71	+317	+563	+449	+847	+669
00000550	+1004	+1302	+1600	+1802	+2005	+2191	+2377	+2435
00000558	+2494	+2477	+2460	+843	+763	+730	+1209	+4120
00000560	+3960	+4011	+4062	+3985	+3908	+3883	+3858	+3833
00000568	+3808	+3707	+3607	+3571	+3535	+3506	+3478	+3706
00000570	+3934	+3916	+3899	+3786	+3673	+2368	-473	+14
00000578	-12	-24	-36	-80	-124	-156	-188	-188
00000580	+1720	+1849	+1979	+1180	-1666	-1272	-1391	-453
00000588 00000590	-540	-758	+47	-364	+250	+383	+517	+170
00000598	+336	+439	+543	+678	+814	+1229	+1645	+1644 +3978
00000598	+1644	+1697	+1239	+748	+770	+399	+3613 +3778	
000005A0	+3832 +3728	+3847 +3669	+3862 +3611	+3845 +3552	+3828 +3494	+3803 +3419	+3778	+3753 +3142
000005A8	+3728	+3669	+3611	+3552	+3494	-237	+3345	+3142 -9
000005B0	-56	<del>-</del> 72	-88	-104	-120	-120	-120	-120
000005B8	+1820	+1760	+2212	-2232	-1555	-762	-1506	-1290
000005C8	-1586	-717	-872	-803	-735	-1302	-846	-389
000005E0	-444	-127	-323	-70	+183	+143	+104	+321
000005D8	+538	+777	+1017	+841	+665	+1924	+3696	+3708
00000000	. 550				. 5 0 5	. 1721	. 5 5 5 5	. 5 / 00

000005E0	+3720	+3731	+3742	+3721	+3700	+3431	+3674	+3629
000005E8	+3584	+3523	+3462	+3401	+3341	+3264	+3187	+2982
000005F0	+2778	+2562	+2346	+2418	+955	-13	+44	+68
000005F8	+92	+36	-20	-76	-132	-132	-132	-132
00000600	+1664	+1991	-754	-3435	-2020	-2493	-1942	-751
00000608	+440	+124	+832	+1508	+1672	+1492	+1312	+1004
00000610	+696	-182	-548	-1074	-1088	-1134	-668	-330
00000618	-504	+402	+796	+902	+496	+3610	+3652	+3598
00000620	+3544	+3583	+3622	+3533	+3444	+3443	+3442	+3441
00000628	+3440	+3377	+3314	+3251	+3188	+3109	+3030	+2823
00000630	+2616	+2439	+2262	+2053	-204	+211	+114	+49
00000638	-16	-48	-80	-112	-144	-144	-144	-144
00000640	+1800	+1778	+221	+1352	+1459	+1793	+2128	+2111
00000648	+1582	+1477	+1373	+1333	+1293	+1528	+1252	+1488
00000650	+1212	+1345	+1478	+1227	+977	+438	-613	-1279
00000658	-922	+1323	+1008	+885	+2299	+3228	+3133	+3262
00000660	+3392	+3204	+3016	+3212	+3409	+3305	+3201	+3449
00000668	+3186	+3153	+3121	+3056	+2992	+2887	+2783	+2550
00000670	+2318	+2175	+2032	+545	+82	+95	+108	+57
00000678	+6	-26	-58	-90	-122	-122	-122	-122
00000680	+1680	+1694	+1709	+1595	+1482	+1472	+1463	+1453
00000688	+1444	+1391	+1339	+1286	+1234	+1213	+1193	+1172
00000690	+1152	+1112	+1073	+1065	+1058	+922	+1299	+1131
00000698	+964	+868	+773	+709	+2182	+2302	+2423	+2799
000006A0	+2664	+2793	+2923	+2860	+2798	+3007	+2705	+3106
000000A8	+2996	+2962	+2928	+2862	+2796	+2666	+2536	+2278
000006B0	+2020	+1783	+1546	-227	+48	+43	+38	+33
000006B8	+28	-4	-36	-68	-100	-100	-100	-100
000006C0	+1624	+1650	+1676	+1638	+1601	+1551	+1501	+1451
000006C8	+1402	+1361	+1320	+1279	+1239	+1214	+1189	+1164
000006D0	+1140	+1103	+1067	+1031	+995	+1014	+1034	+926
000006D8	+818	+885	+953	+989	+1025	+992	+1472	+2048
000006E0	+2112	+1886	+2173	+2108	+2555	+2485	+2416	+2411
000006E8	+2406 +1946	+2726 +1779	+2535 +76	+2311 +69	+2088 +62	+2068	+2049	+1997
000006F0	+1946	-10	-38	-66	-94	+83 <b>-</b> 126	+104 -158	+61 <b>-</b> 158
000006F8 00000700	+1824	+1734	+1644	+1554	+1464	+1438	+1412	+1386
00000700	+1360	+1331	+1302	+1273	+1244	+1215	+1186	+1157
00000708	+1128	+1095	+1062	+1029	+996	+979	+962	+945
00000710	+928	+871	+814	+789	+764	+707	+1162	+1585
00000718	+2008	+1588	+1168	+1356	+1544	+1836	+1616	+1940
00000720	+1752	+2235	+2206	+1217	+1252	+1311	+1370	+1013
00000720	+144	+143	+142	+109	+76	+59	+42	+25
00000738	+8	-16	-40	-64	-88	-152	-216	-216
00000730	+1552	+1528	+1504	+1480	+1456	+1420	+1384	+1348
00000748	+1312	+1289	+1266	+1243	+1220	+1197	+1174	+1151
00000740	+1128	+1091	+1054	+1017	+980	+959	+938	+917
00000758	+896	+853	+810	+767	+724	+613	+502	+551
00000750	+600	+384	+680	+560	+440	+376	+1336	+1528
00000768	+1208	+989	+258	+231	+204	+137	+70	+131
00000770	+192	+167	+142	+117	+92	+71	+50	+29
00000778	+8	-20	-48	-76	-104	-136	-168	-168
00000770	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
00000788	+1264	+1247	+1230	+1213	+1196	+1179	+1162	+1145
00000790	+1128	+1087	+1046	+1005	+964	+939	+914	+889
00000798	+864	+835	+806	+777	+748	+711	+674	+637
00000730	+600	+588	+576	+564	+552	+580	+608	+1660
000007H0	+1176	+511	+358	+333	+308	+275	+242	+209
000007H0	+176	+159	+142	+125	+108	+83	+58	+33

000007B8	+8	-24	-56	-88	-120	-120	-120	-120
000007C0	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
000007C8	+1264	+1247	+1230	+1213	+1196	+1179	+1162	+1145
000007D0	+1128	+1087	+1046	+1005	+964	+939	+914	+889
000007D8	+864	+835	+806	+777	+748	+711	+674	+637
000007E0	+600	+588	+576	+564	+552	+452	+352	+92
000007E8	+344	+319	+294	+301	+308	+275	+242	+209
000007F0	+176	+159	+142	+125	+108	+83	+58	+33
000007F8	+8	-24	-56	-88	-120	-120	-120	-120

# 4.2.4.3.3.6 Inverse DWT-X (LH1 - HH1)

The following is a dump of the H0 sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

0000000	+0	+0	+0	+0	+0	+0	+0	+0
8000000	+0	+0	+0	+0	+0	+0	+0	+0
00000010	+0	+0	+0	+0	+0	+0	+0	+0
00000018	+0	+0	+0	+0	+0	+0	+0	+0
00000020	+0	+0	+0	+0	+0	+0	+0	+0
00000028	+0	+0	+0	+0	+0	+0	+0	+0
00000030	+0	+0	+0	+0	+0	+0	+0	+0
00000038	+0	+0	+0	+0	+0	+0	+0	+0
00000040	+0	+0	+0	+0	+0	+0	+0	+0
00000048	+0	+0	+0	+0	+0	+0	+0	+0
00000050	+0	+0	+0	+0	+0	+0	+0	+0
00000058	+0	+0	+0	+0	+0	+0	+0	+0
00000060	+0	+0	+0	+0	+0	+0	+0	+0
00000068	+0	+0	+0	+0	+0	+0	+0	+0
00000070	+0	+0	+0	+0	+0	+0	+0	+0
00000078	+0	+0	+0	+0	+0	+0	+0	+0
0800000	+0	+0	+0	+0	+0	+0	+0	+0
88000000	+0	+0	+0	+0	+0	+0	+0	+64
00000090	+128	+64	+0	-64	-128	-128	-128	-64
00000098	+0	+0	+0	-64	-128	-128	-128	+0
0A00000	+128	+64	+0	+0	+0	+0	+0	+0
8A000000	+0	+0	+0	+0	+0	+0	+0	+0
000000B0	+0	+0	+0	+0	+0	+0	+0	+0
000000B8	+0	+0	+0	+0	+0	+0	+0	+0
000000C0	-128	-128	-128	-128	-128	-64	+0	+0
000000C8	+0	+0	+0	+0	+0	-64	-128	-64
000000D0	+0	+0	+0	+0	+0	+0	+0	+0
000000D8	+0	+0	+0	+0	+0	+0	+0	+0
000000E0	+0	-64	-128	-64	+0	+0	+0	+0
000000E8	+0	+0	+0	+0	+0	+0	+0	+0
000000F0	+0	+0	+0	+0	+0	+0	+0	+0
000000F8	+0	+0	+0	+0	+0	+0	+0	+0
00000100	-128	-128	-128	-128	-128	-64	+0	+0
00000108	+0	+0	+0	+0	+0	+0	+0	+0
00000110	+0	+0	+0	+0	+0	+0	+0	+0
00000118	+0	+0	+0	+0	+0	+0	+0	+0
00000120	+0	+0	+0	+0	+0	+0	+0	+0
00000128	+0	+0	+0	+0	+0	+0	+0	+0
00000130	+0	+0	+0	+0	+0	+0	+0	+0
00000138	+0	+0	+0	+0	+0	+0	+0	+0
00000140	+0	+0	+0	+0	+0	+0	+0	+0

00000148	+0	+0	+0	+0	+0	+0	+0	+0
00000150	+0	+0	+0	+0	+0	+0	+0	+0
00000158	+0	+0	+0	+0	+0	+0	+0	+0
00000160	+0	+0	+0	+0	+0	+0	+0	-64
00000168	-128	+0	+128	+64	+0	+0	+0	+0
00000170	+0	+0	+0	+0	+0	+0	+0	-64
00000178	-128	-1088	-1024	+64	+128	+64	+0	+0
00000180	+0	+0	+0	+0	+0	+0	+0	+0
00000188	+0	+0	+0	-64	-128	-64	+0	+0
00000190	+0	+0	+0	+0	+0	+0	+0	+0
00000198	+0	+0	+0	+0	+0	+0	+0	+0
000001A0	+0	+0	+0	+0	+0	+0	+0	+0
000001A8	+0	+0	+0	-64	-128	-64	+0	+0
000001B0	+0	+64	+128	+64	+0	+0	+0	-576
000001B8	+896	+192	+512	+640	-256	-128	+0	+0
000001C0	+0	+0	+0	+0	+0	+0	+0	+0
000001C8	+0	+0	+0	-192	+640	-192	+0	+0
000001D0	+0	+0	+0	+0	+0	+0	+0	+0
000001D8	+0	+0	+0	+64	+128	+64	+0	+0
000001E0	+0	+128	+256	-320	+128	+64	+0	+0
000001E0	+0	+0	+0	+0	+0	+0	+0	+0
000001E8	+0	+0	+0	+0	+0	-320	+384	+960
000001F0	+512	-1088	-640	-384	-128	-64	+00+	+900
000001F8	+312	+0	+0	+0	+0	+0	+0	+0
00000200	+0	+0	+0	+0	+0	+64	+128	+64
00000210	+0	+0	+0	+0	+0	+0	+0	+0
00000218	+0	+0	+0	+0	+0	+0	+0	+0
00000220	+0	+0	+0	+0	+0	-384	+256	+128
00000228	+0	+0	+0	+0	+0	+0	+0	+0
00000230	+0	+0	+0	+0	+0	+128	+256	-320
00000238	+128	+64	+0	+320	+640	+1024	+384	-128
00000240	+0	+0	+0	+0	+0	+0	+0	+0
00000248	+0	+64	+128	-384	+128	+64	+0	+0
00000250	+0	+0	+0	+0	+0	+64	+128	+64
00000258	+0	+0	+0	+0	+0	+0	+0	+64
00000260	+128	+64	+0	+0	+0	+0	+0	+0
00000268	+0	+0	+0	+0	+0	+0	+0	+0
00000270	+0	+0	+0	+0	+0	+0	+0	+0
00000278	+0	+0	+0	-512	-1024	-512	+0	+0
00000280	+0	+0	+0	+0	+0	+0	+0	+0
00000288	+0	+0	+0	+0	+0	+0	+0	+0
00000290	+0	+0	+0	+0	+0	+64	+128	-64
00000298	-256	-256	-256	+0	+256	+64	-128	-64
000002A0	+0	+0	+0	-64	-128	-64	+0	+0
000002A8	+0	+0	+0	+0	+0	+0	+0	+0
000002B0	+0	+0	+0	+0	+0	+0	+0	+0
000002B8	+0	+0	+0	+0	+0	+0	+0	+0
000002C0	+0	+0	+0	+0	+0	+0	+0	+0
000002C8	+0	-64	-128	-64	+0	+0	+0	+64
000002D0	+128	+128	+128	+256	+384	+256	+128	+64
000002D8	+0	+0	+0	+0	+0	+0	+0	+0
000002E0	+0	+0	+0	+0	+0	+0	+0	+0
000002E8	+0	+0	+0	+0	+0	+64	+128	+64
000002F0	+0	+0	+0	+0	+0	+0	+0	+0
000002F8	+0	+0	+0	+0	+0	+0	+0	+0
00000300	+0	+0	+0	+0	+0	+0	+0	+0
00000308	+0	-64	-128	-64	+0	-64	-128	-384
00000310	-640	-512	-384	-448	-512	-576	-640	-1152
00000318	-640	+128	+896	+512	+128	+64	+0	+384

00000320	-256	-128	+0	+0	+0	+0	+0	+0
00000328	+0	+0	+0	+0	+0	+0	+0	-64
00000330	-128	-192	-256	-320	-384	-192	+0	+64
00000338	+128	+64	+0	+0	+0	+0	+0	+0
00000340	+0	+0	+0	+0	+0	+0	+0	-64
00000348	-128	+448	+0	+0	+0	+128	+256	+64
00000350	-128	-64	+0	-128	-256	-320	-384	-128
00000358	+128	+128	+128	-448	-1024	-64	+896	+0
00000360	+128	-64	-256	+384	+0	+0	+0	+0
00000368	+0	+0	+0	+0	+0	+64	+128	+128
00000370	+128	+64	+0	+0	+0	+384	+768	+128
00000378	-512	+128	-256	-128	+0	+0	+0	+0
00000380	+0	+0	+0	+0	+0	-64	-128	+192
00000388	+512	+832	+128	-320	-768	-512	-256	-128
00000390	+0	+0	+0	+0	+0	+128	+256	+576
00000398	+896	+128	-640	-832	+0	+0	+0	+0
000003A0	+0	+64	+128	+64	+0	+0	+0	+0
000003A8	+0	+0	+0	+0	+0	+0	+0	+0
000003B0	+0	+0	+0	-64	-128	-192	-256	+320
000003B8	-128	+768	+640	+320	+0	+0	+0	+0
000003C0 000003C8	+0 -256	+0 -64	+0 +128	+0 +64	+0 +0	+0 +0	+0 +0	-128 +0
000003C8	+0	+0	+120	+04	+0	+0	+0	+0
000003D0	+0	-64	-128	+384	+896	-64	+0	+0
000003D8	+0	+64	-128 -896	+384	+896	+448	+0	+0
000003E0	+0	+04	+0	+0	+0	+0	+0	+0
000003E0	+0	+0	+0	+0	+0	+0	+0	+384
000003F0	-256	-192	-128	-64	+0	+0	+0	+0
00000310	+0	+0	+0	+0	+0	+128	+256	-320
00000400	+128	+64	+0	+0	+0	+0	+0	+0
00000410	+0	+0	+0	+0	+0	+0	+0	+0
00000418	+0	+0	+0	+0	+0	+0	+0	+64
00000420	+128	-960	+0	+0	+0	-512	-1024	-128
00000428	+768	+768	+768	+640	+512	+448	+384	+384
00000430	+384	+448	+512	+192	-128	-192	-256	-128
00000438	+0	+0	+0	+0	+0	+0	+0	+0
00000440	+0	+0	+0	+0	+0	+0	+0	+0
00000448	+0	+0	+0	+0	+0	+0	+0	+0
00000450	+0	+0	+0	+0	+0	+0	+0	+0
00000458	+0	+0	+0	+192	+384	-320	+0	+0
00000460	+0	+0	+1024	+0	-1024	-512	+0	+64
00000468	+128	-64	-256	-384	-512	-448	-384	-256
00000470	-128	+0	+128	-128	-384	-512	-640	+192
00000478	+0	+0	+0	+0	+0	+0	+0	+0
00000480	+0	+0	+0	+0	+0	+0	+0	+0
00000488	+0	+0	+0	+0	+0	+0	+0	+0
00000490	+0	+0	+0	+64	+128	+64	+0	+64
00000498	+128	-64	-256	-960	-640	+128	-128	+0
000004A0	+128	+64	+0	+0	+0	+512	+1024	+448
000004A8	-128	-512	-896	-1024	-1152	-1024	-896	-576
000004B0	-256	+256	+768	+576	+384	+256	+128	-384
000004B8	+128	+64	+0	+0	+0	+0	+0	+0
000004C0	+0	+0	+0	+64	+128	+64	+0	+0
000004C8	+0	+0	+0	-64	-128	-128	-128	-64
000004D0	+0	+0	+0	+0	+0	+0	+0	+0
000004D8	+0	+0	+0	+384	-256	-128	+0	+0
000004E0	+0	+0	+0	+0	+0	+0	+0	+0
000004E8	+0	+0	+0	+0	+0	+0	+0	+0
000004F0	+0	+0	+0	+0	+0	+0	+0	+0

000004F8	+0	+0	+0	+0	+0	+0	+0	+0
00000500	+0	+0	+0	+0	+0	+0	+0	+0
00000508	+0	+0	+0	+64	+128	+64	+0	+0
00000510	+0	+0	+0	+0	+0	+0	+0	+0
00000518	+0	+0	+0	+0	+0	-128	-256	+384
00000520	+0	+0	+0	+0	+0	+0	+0	+0
00000528	+0	+0	+0	-64	-128	+0	+128	+64
00000530	+0	+0	+0	+0	+0	+384	-256	-128
00000538	+0	+0	+0	+0	+0	+0	+0	+0
00000540	-128	-64	+0	+384	-256	-64	+128	+128
00000548	+128	+0	-128	+384	-128	-64	+0	+0
00000550	+0	+0	+0	+0	+0	+0	+0	+0
00000558	+0	+0	+0	+0	+0	+0	+0	+0
00000560	+0	+0	+0	+0	+0	+0	+0	+0
00000568	+0	+0	+0	+0	+0	+0	+0	-64
00000570	-128	+0	+128	+0	-128	-64	+0	+0
00000578	+0	+0	+0	+0	+0	+0	+0	+0
00000580	+0	+64	+128	+192	+256	-128	+512	+448
00000588	+384	+128	-128	+384	-128	+448	+0	-64
00000590	-128	+0	+128	+64	+0	+0	+0	+0
00000598 000005A0	+0 +0	+0 +0	+0 +0	+0 +0	+0 +0	+0 +0	+0 +0	+0 +0
000005A0	+0	+0	+0	+0	+0	+0	+0	+0
000005A0	+0	+0	+0	+64	+128	+64	+0	+0
000005B8	+0	+0	+0	+64	+128	+64	+0	+0
000005B0	+0	+64	+128	-192	+512	-256	+0	+640
000005C8	-768	-640	-512	-1216	-896	-236 -832	-768	-640
000005D0	-766 -512	-192	+128	+64	+0	+0	+0	-64
000005D8	-128	-64	+0	+0	+0	+0	+0	+0
000005E0	+0	+0	+0	+0	+0	+0	+0	+0
000005E8	+0	+0	+0	+0	+0	+0	+0	+0
000005E0	+0	+0	+0	+0	+0	+64	+128	+64
000005F8	+0	+0	+0	+0	+0	+0	+0	+0
00000610	+128	+0	-1152	-1344	-512	+384	+1280	+768
00000608	+256	+256	+256	+128	+0	-64	-128	+64
00000610	+256	+448	+640	+576	-512	-768	+0	+0
00000618	+0	+0	+0	+0	+0	+0	+0	+0
00000620	+0	+0	+0	+0	+0	+0	+0	+0
00000628	+0	+0	+0	+0	+0	+0	+0	+0
00000630	+0	+0	+0	+0	+0	+0	+0	+0
00000638	+0	+0	+0	+0	+0	+0	+0	+0
00000640	-128	+64	+256	+64	-128	-128	-128	+0
00000648	+128	+64	+0	+0	+0	+0	+0	+0
00000650	+0	+0	+0	-64	-128	+192	+512	+128
00000658	-256	-192	-128	-64	+0	+384	-256	-64
00000660	+128	+0	-128	-64	+0	+0	+0	+0
00000668	+0	+0	+0	+0	+0	+0	+0	+0
00000670	+0	+64	+128	+64	+0	+0	+0	+0
00000678	+0	+0	+0	+0	+0	+0	+0	+0
00000680	+0	+0	+0	+0	+0	+0	+0	+0
00000688	+0	+0	+0	+0	+0	+0	+0	+0
00000690	+0	+0	+0	+0	+0	+0	+0	+0
00000698	+0	+0	+0	+0	+0	+64	+128	+0
000006A0	-128	+0	+128	+64	+0	+0	+0	+0
000006A8	+0	+0	+0	+0	+0	+0	+0	+0
000006B0	+0	+0	+0	+0	+0	+0	+0	+0
000006B8	+0	+0	+0	+0	+0	+0	+0	+0
000006C0	+0	+64	+128	+64	+0	+0	+0	+0
000006C8	+0	+0	+0	+0	+0	+0	+0	+0

000006D0	+0	+0	+0	+0	+0	+0	+0	+0
000006D8	+0	+0	+0	-64	-128	-128	-128	+0
000006E0	+128	-448	+0	+64	+128	+128	+128	+64
000006E8	+0	+64	+128	+64	+0	-64	-128	+128
000006F0	+384	+128	-128	-64	+0	+0	+0	+0
000006F8	+0	+0	+0	+0	+0	+0	+0	+0
00000700	+0	+0	+0	+0	+0	+0	+0	+0
00000708	+0	+0	+0	+0	+0	+0	+0	+0
00000710	+0	+0	+0	+0	+0	+0	+0	+0
00000718	+0	+0	+0	+0	+0	-64	-128	-64
00000720	+0	-512	+0	+64	+128	+128	+128	+128
00000728	+128	+64	+0	-128	-256	-320	-384	-192
00000730	+0	+0	+0	+0	+0	+0	+0	+0
00000738	+0	+0	+0	+0	+0	+0	+0	+0
00000740	+0	+0	+0	+0	+0	+0	+0	+0
00000748	+0	+0	+0	+0	+0	+0	+0	+0
00000750	+0	+0	+0	+0	+0	+0	+0	+0
00000758	+0	+0	+0	+0	+0	+0	+0	+0
00000760	+0	+0	+0	+0	+0	-128	+768	+0
00000768	+256	+640	+0	+0	+0	+0	+0	+0
00000770	+0	+0	+0	+0	+0	+0	+0	+0
00000778	+0	+0	+0	+0	+0	+0	+0	+0
00000780	+0	+0	+0	+0	+0	+0	+0	+0
00000788	+0	+0	+0	+0	+0	+0	+0	+0
00000790	+0	+0	+0	+0	+0	+0	+0	+0
00000798	+0	+0	+0	+0	+0	+0	+0	+0
000007A0	+0	+0	+0	+0	+0	+64	+128	-512
000007A8	-128	-64	+0	+0	+0	+0	+0	+0
000007B0	+0	+0	+0	+0	+0	+0	+0	+0
000007B8	+0	+0	+0	+0	+0	+0	+0	+0
000007C0	+0	+0	+0	+0	+0	+0	+0	+0
000007C8	+0	+0	+0	+0	+0	+0	+0	+0
000007D0	+0	+0	+0	+0	+0	+0	+0	+0
000007D8	+0	+0	+0	+0	+0	+0	+0	+0
000007E0	+0	+0	+0	+0	+0	+0	+0	+0
000007E8	+0	+0	+0	+0	+0	+0	+0	+0
000007F0	+0	+0	+0	+0	+0	+0	+0	+0
000007F8	+0	+0	+0	+0	+0	+0	+0	+0

# 4.2.4.3.3.7 Inverse DWT-Y (L0 - H0)

The following is a dump of the LLO sub-band, as shown in the figure illustrating three-level DWT decomposition in section 3.1.8.1.4.

00000000	-32	+16	+64	+272	-32	-16	+0	-16
8000000	-32	-24	-16	-8	+0	-24	-48	-72
00000010	-96	-90	-84	-78	-72	-98	-124	-150
00000018	-176	-192	-208	-224	-240	-256	-272	-288
00000020	-304	-304	-304	-304	-304	-336	-368	-400
00000028	-432	-450	-468	-486	-504	-522	-540	-558
00000030	-576	-598	-620	-642	-664	-686	-708	-730
00000038	<del>-</del> 752	-768	-784	-800	-816	-816	-816	-816
00000040	+68	+120	+172	+240	+53	+55	+57	+43
00000048	+30	+32	+34	+36	+38	+20	+2	-16
00000050	-34	-36	-38	-40	-42	-68	-94	-120
00000058	-146	-148	-151	-186	-220	-227	-233	-240
00000060	-247	-254	-261	-268	-275	-302	-329	-356

00000068	-384	-403	-423	-443	-463	-484	-506	-528
00000070	-550	-572	-594	-616	-639	-673	-707	-709
00000078	-712	-733	-754	-775	-796	-796	-796	-796
08000000	+168	+224	+281	+209	+138	+126	+115	+103
00000088	+92	+88	+84	+80	+76	+64	+52	+40
00000090	+28	+18	+8	-2	-12	-38	-64	-90
00000098	-116	-105	-95	-148	-201	-198	-195	-192
0A00000	-190	-204	-218	-232	-247	-269	-291	-313
8A000000	-336	-357	-379	-400	-422	-447	-473	-498
000000B0	-524	-546	-569	-591	-614	-660	-707	-689
000000B8	-672	-698	-724	-750	-776	-776	-776	-776
000000C0	+268	+312	+357	+273	+191	+181	+172	+162
00000008	+154	+144	+134	+124	+114	+108	+102	+80
000000D0	+58	+56	+54	+52	+50	+24	-2	-44
000000D8 000000E0	-86 -165	-61 -170	-38 175	-93 -196	-149 -218	-137 -235	-124 -252	-144 -269
000000E0	-183	-310	-175 -334	-357	-381	-233 -409	-232 -439	-269 -468
000000E8	-498	-520	-543	-565	-589	-647	-706	-668
000000F0	-632	-663	-694	-725	-756	-756	-756	-756
0000010	+368	+401	+434	+339	+244	+237	+230	+223
00000100	+216	+200	+184	+168	+152	+152	+152	+120
00000100	+88	+94	+100	+106	+112	+86	+60	+2
00000118	-56	-18	+19	-39	-98	-76	-55	-97
00000120	-140	-136	-133	-161	-190	-202	-215	-227
00000128	-240	-265	-290	-315	-340	-373	-406	-439
00000130	-472	-495	-518	-541	-564	-635	-706	-649
00000138	-592	-628	-664	-700	-736	-736	-736	-736
00000140	+404	+556	+454	+383	+313	+531	+239	+282
00000148	+326	+304	+282	+260	+238	+246	+254	+118
00000150	+238	+196	+154	+32	-90	-88	-86	+76
00000158	+238	+243	+247	+29	-191	-232	-272	-121
00000160	+29	-62	-153	-149	-145	-162	-180	-197
00000168	-216	-240	-265	-289	-315	-345	-376	-406
00000170	-438	-446	-456	-497	-539	-595	-653	-502
00000178	-608	-625	-642	-675	-708	-708	-708	-708
00000180	+440	+713	+475	+428	+382	+827	+249	+342
00000188	+436	+408	+380	+352	+324	+340	+356	-140
00000190	-124	+42	+208	+214	+220	+250	+280	+406
00000198	+532	+504	+476	+352	+229	+125	+22	-146
000001A0	-314	-244	-175	-138	-101	-123	-146	-169
000001A8	-192	-216	-241	-265	-290	-318	-347	-375
000001B0	-404	-399	-395	-454	-514	-557	-601	-356
000001B8	-624	-622	-620	-650	-680	-680	-680	-680
000001C0	+604	+677	+495	+457	+419	+770	+354	+386
000001C8	+418	+416	+414	+380	+346	+258	-342	-302
000001D0 000001D8	-6 +826	+288	+582	+604	+626	+588	+550	+688
000001D8 000001E0	+826	+829 <b>-</b> 139	+833 -292	+724 -175	+616 <b>-</b> 56	+481 -83	+348 -112	+181 -139
000001E0	-168	-192	-216	-240	-265	-291	-317	-343
000001E0	-370	-351	-333	-411	-489	-486	-484	-402
000001F8	-576	-587	-598	-625	-652	-652	-652	-652
00000110	+1280	+1154	+1028	+998	+968	+970	+460	+430
00000200	+400	+424	+448	+408	+368	+432	-528	-208
00000200	+112	+534	+956	+994	+1032	+926	+820	+970
00000218	+1120	+1155	+1190	+1097	+1004	+839	+674	+509
00000220	+344	+223	+102	+45	-12	-45	-78	-111
00000228	-144	-168	-192	-216	-240	-264	-288	-312
00000230	-336	-304	-272	-368	-464	-416	-368	-448
00000238	-528	-552	-576	-600	-624	-624	-624	-624

00000240	+770	+671	+573	+554	+536	+629	+467	+464
00000248	+462	+492	+523	+490	+457	+281	-405	-101
00000250	+204	+599	+995	+1310	+1370	+1297	+1225	+1296
00000258	+1368	+1432	+1498	+1402	+1308	+1184	+1062	+874
00000260	+688	+586	+485	+303	+123	-82	-32	-76
00000268	-122	-174	-226	-199	-171	-193	-216	-238
00000270	-261	-314	-368	-325	-283	-360	-438	-451
00000278	-465	-515	-565	-583	-601	-617	-633	-633
00000280	+772	+701	+630	+623	+616	+545	+474	+499
00000288	+524	+561	+599	+572	+546	+131	-283	+6
00000290	+296	+665	+1034	+1627	+1708	+1669	+1630	+1623
00000298	+1616	+1711	+1806	+1709	+1612	+1531	+1450	+1241
000002A0	+1032	+950	+869	+563	+258	-120	+15	-42
000002A8	-100	-180	-261	-182	-103	-123	-144	-165
000002B0	-186	-325	-464	-283	-102	-305	-508	-455
000002B8	-402	-478	-554	-566	-578	-610	-642	-642
000002C0	+774	+730	+687	+675	+664	+620	+577	+581
000002C8	+586	+597	+610	+590	+571	-147	-96	+209
000002D0	+516	+794	+1073	+1575	+1822	+1976	+1875	+1869
000002D8	+1864	+1988	+2114	+2014	+1916	+1876	+1838	+1606
000002E0	+1376	+1266	+1156	+902	+137	-61	-3	-120
000002E8 000002F0	-238	-122	-7 -304	-69	-130	-164	-200	-219 -426
000002F0 000002F8	-239 -467	-271 -937	-304 -895	-128 -549	-209 -459	-297 -667	-386 -619	-619
00000218								
00000300	+776 +648	+760 +635	+744 +622	+728 +609	+712 +596	+696 <b>-</b> 425	+680 +90	+664 +413
00000308	+736	+924	+1112	+1524	+1936	+2284	+2120	+2116
00000310	+2112	+2267	+2422	+2321	+2220	+2223	+2120	+1973
00000310	+1720	+1582	+1444	+1242	+16	-2	-20	+58
00000328	+136	-65	-267	-212	-158	-207	-257	-274
00000320	-292	-218	-144	+26	-316	-290	-264	-142
00000338	-20	+2956	+2860	-788	-852	-980	-596	-596
00000340	+826	+807	+789	+770	+752	+749	+747	+744
00000348	+742	+677	+613	+516	+421	-285	+288	+573
00000350	+860	+1081	+1303	+1668	+2034	+2313	+2337	+2344
00000358	+2352	+2452	+2554	+2574	+2596	+2506	+2418	+2248
00000360	+2080	+1961	+1843	+925	+7	+40	+74	+748
00000368	+654	+453	+251	+48	-154	-107	-61	-111
00000370	-161	-28	+104	+45	-271	-274	-278	-842
00000378	+1411	+3007	+3323	+327	-1389	-1197	-493	-493
00000380	+876	+855	+834	+813	+792	+803	+814	+825
00000388	+836	+720	+605	+681	+758	+110	+487	+735
00000390	+984	+1239	+1494	+1813	+2132	+2343	+2554	+2573
00000398	+2592	+2639	+2686	+2829	+2972	+2791	+2610	+2525
000003A0	+2440	+2341	+2243	+608	-2	+83	+169	+1438
000003A8	+1172	+970	+768	+565	+363	+249	+135	+52
000003B0	-30	-95	-160	-193	-226	-259	-292	+763
000003B8	-742	+2290	+1738	-1118	-902	-902	-390	-390
000003C0	+926	+902	+879	+855	+832	+824	+817	+809
000003C8	+802	+763	+724	+397	+2375	+970	+589	+848
000003D0	+1108	+1396	+1685	+1941	+2198	+2468	+2739	+2785
000003D8	+2832	+2888	+2946	+3178	+2900	+3058	+2962	+2848
000003E0	+2736	+2896	+2546	-364	+309	+205	+871	+1760
000003E8	+1626	+1471	+1317	+1145	+975	+844	+714	+599
000003F0	+485	+351	+216	+146	+75	-355	+750	+2687
000003F8	+529	-1067	-615	-835	-799	-847	-383	-383
00000400	+976	+950	+924	+898	+872	+846	+820	+794
00000408	+768	+806	+844	+882	+1432	+2598	+692	+962
00000410	+1232	+1554	+1876	+2070	+2264	+2594	+2924	+2998

00000418	+3072	+3139	+3206	+3273	+2316	+3071	+3314	+3173
00000420	+3032	+2941	+1826	-57	+108	+73	+1574	+2083
00000428	+2080	+1973	+1866	+1727	+1588	+1441	+1294	+1147
00000430	+1000	+796	+592	+484	+376	+828	+256	+772
00000438	-248	-72	-408	+984	-184	-536	-376	-376
00000440	+1026	+997	+969	+941	+913	+888	+864	+840
00000448	+816	+762	+709	+768	+1339	+2269	+2176	+1411
00000450	+1414	+1677	+1941	+2188	+2436	+2730	+3023	+3157
00000458	+3291	+3349	+3409	+3420	+2152	+3000	+3594	+3403
00000460	+3213	+3233	+951	+12	+97	-303	+2883	+2755
00000468	+2373	+2312	+2252	+2143	+2036	+1861	+1687	+1544
00000470	+1403	+1254	+1106	+974	+842	+1229	+1105	+21
00000478	+217	+46	-381	+1912	+3181	+2765	+301	-723
00000480	+1076	+1045	+1015	+984	+954	+931	+909	+886
00000488	+864	+719	+575	+654	+1246	+1685	+3149	+1604
00000490	+1596	+1801	+2006	+2307	+2609	+2866	+3123	+3316
00000498	+3510	+3561	+3613	+3568	+1988	+2931	+3875	+3634
000004A0	+3394	+3527	+76	+81	+86	+859	+3168	+2917
000004A8	+2666	+2652	+2639	+2561	+2484	+2282	+2081	+1943
000004B0	+1806	+1713	+1621	+1464	+1308	+1119	+931	+550
000004B8	+170	-92	-354	+1560	+3986	+1970	-558	-558
000004C0	+1126	+1092	+1060	+1027	+995	+973	+953	+932
000004C8	+912	+899	+888	-340	+1249	+1756	+2521	+2421
000004D0	+1810	+2036	+2263	+2521	+2781	+3066	+3350	+3443
000004D8	+3537	+3612	+3688	+3476	+2496	+3021	+3803	+3833
000004E0	+3863	+2843	+33	+133	-21	+2099	+3197	+3061
000004E8	+2927	+2944	+2961	+2882	+2804	+2607	+2410	+2309
000004F0	+2209	+2139	+2071	+1842	+1614	+1328	+1044	+663
000004F8	+283	+10	-263	-488	-201	-201	-457	-457
00000500	+1176	+1141	+1106	+1071	+1036	+1017	+998	+979
00000508	+960	+825	+690	+203	+740	+1573	+1894	+3239
00000510	+2024	+2272	+2521	+2737	+2954	+3010	+3067	+3315
00000518	+3564	+3664	+3764	+3384	+3004	+3112	+3732	+3776
00000520	+3820	+1905	-10	+187	-128	+3341	+3226	+3207
00000528	+3188	+3236	+3284	+3204	+3124	+2932	+2740	+2676
00000530	+2612	+2567	+2522	+2221	+1920	+1539	+1158	+777
00000538	+396	+112	-172	-488	-292	-324	-356	-356
00000540	+1194	+1162	+1131	+1099	+1069	+1047	+1026	+972
00000548	+920	+969	+507	+380	+767	+1428	+1834	+2799
00000550	+2486	+2347	+2721	+2919	+3118	+3290	+3462	+3266
00000558	+3071	+3157	+3243	+3521	+3800	+3674	+3548	+3710
00000560	+3873	+874	+179	+91	+517	+3439	+3291	+3333
00000568	+3377	+3403	+3430	+3361	+3292	+3174	+3057	+3004
00000570	+2951	+2761	+2572	+2222	+1874	+1554	+1235	+883
00000578	+533	+220	-93	-470	-335	-319	-303	-303
00000580	+1212	+1184	+1157	+1129	+1102	+1078	+1055	+967
00000588	+880	+1114	+325	+559	+794	+1284	+1775	+2361
00000590	+2948	+2423	+2923	+3103	+3283	+3314	+3346	+3474
00000598	+3602	+3674	+3747	+3659	+3572	+3980	+3877	+3901
000005A0	+3926	-157	+368	+253	+1674	+3795	+3356	+3461
000005A8	+3566	+3571	+3577	+3518	+3460	+3417	+3375	+3332
000005B0	+3290	+2956	+2623	+2225	+1828	+1570	+1313	+991
000005B8	+670	+328	-14	-452	-378	-314	-250	-250
000005C0	+1230	+1206	+1182	+1158	+1135	+1109	+1083	+1025
000005C8	+968	+779	+78	+481	+885	+1284	+1939	+2466
000005D0	+3250	+2626	+2772	+3157	+3543	+3514	+3486	+3729
000005D8	+3717	+3775	+3834	+3780	+3728	+3934	+3885	+3915
000005E0	+2667	+92	+333	+173	+2831	+3701	+3549	+3587
000005E8	+3627	+3642	+3659	+3643	+3628	+3675	+3724	+3436

0000065P									
00000600	000005F0	+3149	+2847	+2545	+2275	+2006	+1730	+1454	+1114
00000608	000005F8	+775	+388	+1		-293		-325	-325
00000610	00000600	+1248	+1228	+1208	+1188	+1168	+1140	+1112	+1084
00000618	00000608	+1056	+700	+344	+660	+976	+1284	+2104	+2316
00000620	00000610	+3040	+2319	+2110	+2189	+2268	+2691	+3114	+3729
00000628	00000618	+3832	+3877	+3922	+3903	+3884	+3889	+3894	+3931
00000630	00000620	+1408	+341	+298	+95	+3988	+3609	+3742	+3715
00000638	00000628	+3688	+3715	+3742	+3769	+3796	+3679	+3562	+3285
00000640	00000630	+3008	+2738		+2326	+2184	+1890	+1596	+1238
00000648	00000638						-304	-400	-400
00000650	00000640								+1093
00000658									+834
00000660									-106
00000668									+4337
00000670									+3810
00000678         +954         +545         -120         -321         -266         -314         -362           00000680         +1344         +1340         +1337         +1333         +1330         +1190         +1051         +           00000690         +906         +805         +705         +733         +761         +740         +720           00000690         +906         +805         +705         +733         +761         +740         +720           000006A0         +40         +581         +97         +2589         +4058         +4018         38799         +           000006B0         +3458         +3706         +3954         +3754         +3555         +2843         +1619         +           000006C8         +382         +1364         +1337         +1309         +1283         +1247         +1212           000006C0         +1392         +1364         +1337         +1309         +1283         +1247         +1212           000006C0         +392         +1424         +1099         +1079         +1058         +1072         +1088           000006D0         +799         +1056         +802         +772         +743         +64									+3201
00000680									+1280
00000688									-362
00000690									+1103
00000698									+889
000006A0									+668
00000688									+3208
000006B0 +3458 +3706 +3954 +3754 +3555 +2843 +1619 + 000006B8 +516 +386 -256 -290 -324 -324 -324 -324 000006C0 +1392 +1364 +1337 +1309 +1283 +1247 +1212 000006C8 +982 +1424 +1099 +1079 +1058 +1072 +1088 000006D0 +799 +1056 +802 +772 +743 +645 +547 000006B0 +799 +1056 +649 +563 +332 +102 +1939 +4033 + 000006E0 +444 +332 -36 +4076 +4093 +4047 +4001 + 000006E0 +444 +332 -36 +4076 +4093 +4047 +4001 + 000006E0 +3811 +3678 +3545 +3380 +3216 +3639 +3806 +3861 + 000006F0 +3811 +3678 +3545 +3380 +3216 +3639 +3806 + 00000700 +1440 +1389 +1338 +1287 +1236 +1305 +1374 + 00000708 +1320 +1037 +1267 +1208 +1150 +715 +281 + 00000710 +1204 +1564 +901 +1325 +1750 +1830 +1911 + 00000712 +336 +340 +856 +4028 +1128 +4076 +4024 + 00000728 +3984 +3922 +3861 +3799 +3738 +3828 +3919 + 00000728 +3984 +3922 +3861 +3799 +3738 +3828 +3919 + 00000738 +3800 +1284 +1328 +1287 +2878 +2900 +2923 + 00000738 +3800 +1284 +1328 +28 -248 -248 -248 + 00000740 +1456 +1406 +1358 +1309 +1261 +1209 +1159 + 00000738 +3800 +1284 +1328 +28 -248 -248 -248 + 00000748 +1218 +1265 +33 -654 -1342 -977 -356 +30000758 +3784 +2536 +1033 +2265 +522 +440 +615 +30000768 +3822 +3910 +3898 +3886 +3875 +3805 +3735 +30000778 +3026 +2303 +2291 +4051 +4099 +4078 +4058 +400000778 +3026 +2303 +2291 +4051 +4099 +4078 +4058 +400000778 +3364 +403 +2211 +4051 +4099 +4078 +4058 +400000778 +3364 +4102 +4125 +1379 +1332 +1286 +1371 +1457 +400000778 +3026 +2303 +2292 +665 -250 -250 -250 -250 -250 -250 -250 -25									+3907
000006B8         +516         +386         -256         -290         -324         -324         -324           000006C0         +1392         +1364         +1337         +1309         +1283         +1247         +1212           000006C8         +982         +1424         +1099         +1079         +1058         +1072         +1088           000006D0         +799         +1056         +802         +772         +743         +645         +547           000006D0         +736         +649         +563         +332         +102         +1939         +4033         +           000006E0         +444         +332         -36         +4076         +4093         +4047         +4001         +           000006E0         +3811         +3678         +3545         +3380         +3791         +3639         +3806         +3806         +3639         +3806         +3806         +3639         +3806         +3639         +3806         +3806         +3600         +3806         +3806         +3639         +3806         +3806         +3600         +3806         +3639         +3806         +3606         +3609         +3806         +3806         +3806         +3806         +3806									+3375
000006C0 +1392 +1364 +1337 +1309 +1283 +1247 +1212 +100006C8 +982 +1424 +1099 +1079 +1058 +1072 +1088 +1072 +1088 +100006D0 +799 +1056 +802 +772 +743 +645 +547 +100006D8 +736 +649 +563 +332 +102 +1939 +4033 +100006E0 +444 +332 -36 +4076 +4093 +4047 +4001 +100006E8 +3910 +3870 +3830 +3791 +3752 +3806 +3861 +100006E0 +3811 +3678 +3545 +3380 +3216 +3639 +3806 +100006E0 +3811 +3678 +3545 +3380 +3216 +3639 +3806 +100000F0 +1440 +1389 +1338 +1287 +1236 +1305 +1374 +100000700 +1440 +1389 +1338 +1287 +1236 +1305 +1374 +100000700 +1440 +1389 +1338 +1287 +1236 +1305 +1374 +100000700 +1204 +1564 +901 +1325 +1750 +1830 +1911 +100000718 +344 +459 +574 +817 +548 +351 +666 +100000720 +336 +340 +856 +4028 +4128 +4076 +4024 +100000728 +3984 +3922 +3861 +3799 +3738 +3828 +3919 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +3137 +3007 +2878 +2900 +2923 +100000730 +3652 +3394 +31338 +1738 +2140 +2575 +3009 +100000730 +1456 +1406 +1358 +1309 +1261 +1209 +1159 +1000000000000000000000000000000000000									+1067
000006C8         +982         +1424         +1099         +1079         +1058         +1072         +1088           000006D0         +799         +1056         +802         +772         +743         +645         +547           000006D0         +736         +649         +563         +332         +102         +1939         +4033         +           000006E0         +444         +332         -36         +4076         +4093         +4001         +           000006E0         +3811         +3678         +3545         +3380         +3216         +3639         +3806         +3861         +           000006F0         +3811         +3678         +3545         +3380         +3216         +3639         +3806         +3861         +           00000700         +1440         +1389         +1338         +1287         +286         -286         -286         -286         00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +         00000700         +1440         +1564         +901         +1325         +1750         +1830         +1911         +         00000718         +344         +459         +574									-324
000006D0									+968
000006D8         +736         +649         +563         +332         +102         +1939         +4033         +000006E0         +4444         +332         -36         +4076         +4093         +4047         +4001         +000006E8         +3910         +3870         +3830         +3791         +3752         +3806         +3861         +3668         +3669         +3866         +3867         +1236         +1305         +1374         +         +400000718         +3444         +459         +574         +817         +588         +39191         +         +30000728         +3384         +3922         +3861         +3799         +3738         +3828         +3919         +         +30000738         +3800         +1284 <t< td=""><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td>+815</td></t<>									+815
000006E0									+769
000006E8         +3910         +3870         +3830         +3791         +3752         +3806         +3861         +3000           00006F0         +3811         +3678         +3545         +3380         +3216         +3639         +3806         +3806           00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +           00000708         +1320         +1037         +1267         +1208         +1150         +715         +281           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000718         +344         +459         +574         +817         +548         +351         +666           00000728         +3364         +3922         +3861         +3799         +3738         +3828         +3919         +           00000738         +3800         +1284         +1328         +288         -248         -248         -248           00000738         +3800         +1284									+1982
000006F0         +3811         +3678         +3545         +3380         +3216         +3639         +3806         +3000006F8         +1134         +1091         +24         -387         -286         -286         -286         -286         -00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +           00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000718         +344         +459         +574         +817         +548         +351         +666           00000720         +336         +340         +856         +4028         +4128         +4076         +4024         +           00000738         +3894         +3922         +3861         +3799         +3738         +3828         +3919         +           00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000740         +1456         +1406         +1358									+3955
000006F8         +1134         +1091         +24         -387         -286         -286         -286           00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000718         +344         +459         +574         +817         +548         +351         +666           00000720         +336         +340         +856         +4028         +4128         +4076         +4024         +           00000728         +3384         +3922         +3861         +3799         +3738         +3828         +3919         +           00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000738         +3800         +1284         +1328         +28         -248         -248         -248           00000748         +1218         +1265         +33         -654         -1342         -977         -356           00000750         +1401         +1753         +1338         +1738<									+3835
00000700         +1440         +1389         +1338         +1287         +1236         +1305         +1374         +           00000708         +1320         +1037         +1267         +1208         +1150         +715         +281           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000718         +344         +459         +574         +817         +548         +351         +666         -           00000720         +336         +340         +856         +4028         +4128         +4076         +4024         +           00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000738         +3800         +1284         +1328         +28         -248         -248         -248         -248         -248         -248         -248         -248         +28         -248         +159         +1159         +         -4159         +1159         +         -4159         +1159         +         -4159         +1159         +         -248         -248         -248         -248         -248         -									+2341
00000708         +1320         +1037         +1267         +1208         +1150         +715         +281           00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +           00000718         +344         +459         +574         +817         +548         +351         +666         -           00000720         +336         +340         +856         +4028         +4128         +4076         +4024         +           00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000738         +3800         +1284         +1328         +28         -248									-286
00000710         +1204         +1564         +901         +1325         +1750         +1830         +1911         +00000718         +344         +459         +574         +817         +548         +351         +666         +666         +4028         +4128         +4076         +4024         +400000728         +3984         +3922         +3861         +3799         +3738         +3828         +3919         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +200000738         +3800         +1284         +1328         +28         -248									+1091
00000718       +344       +459       +574       +817       +548       +351       +666         00000720       +336       +340       +856       +4028       +4128       +4076       +4024       +         00000728       +3984       +3922       +3861       +3799       +3738       +3828       +3919       +         00000730       +3652       +3394       +3137       +3007       +2878       +2900       +2923       +         00000738       +3800       +1284       +1328       +28       -248       -248       -248         00000740       +1456       +1406       +1358       +1309       +1261       +1209       +1159       +         00000748       +1218       +1265       +33       -654       -1342       -977       -356         00000750       +1401       +1753       +1338       +1738       +2140       +2575       +3009       +         0000768       +3784       +2536       +1033       +265       +522       +440       +615         00000768       +3922       +3910       +3898       +3886       +3875       +3805       +3735       +         00000770       +3373									+486
00000720       +336       +340       +856       +4028       +4128       +4076       +4024       +         00000728       +3984       +3922       +3861       +3799       +3738       +3828       +3919       +         00000730       +3652       +3394       +3137       +3007       +2878       +2900       +2923       +         00000740       +1456       +1406       +1358       +1309       +1261       +1209       +1159       +         00000748       +1218       +1265       +33       -654       -1342       -977       -356       +         00000750       +1401       +1753       +1338       +1738       +2140       +2575       +3009       +         00000758       +3784       +2536       +1033       +265       +522       +440       +615         00000760       +388       +403       +2211       +4051       +4099       +4078       +4058       +         00000770       +3373       +3126       +2879       +2585       +2291       +2026       +1762       +         00000780       +1472       +1425       +1379       +1332       +1286       +1371       +1457       +     <									+1383
00000728       +3984       +3922       +3861       +3799       +3738       +3828       +3919       +         00000730       +3652       +3394       +3137       +3007       +2878       +2900       +2923       +         00000740       +1456       +1406       +1358       +1309       +1261       +1209       +1159       +         00000748       +1218       +1265       +33       -654       -1342       -977       -356       +         00000750       +1401       +1753       +1338       +1738       +2140       +2575       +3009       +         00000758       +3784       +2536       +1033       +265       +522       +440       +615       +615       +4051       +4099       +4078       +4058       +         00000760       +388       +403       +2211       +4051       +4099       +4078       +4058       +         0000770       +3373       +3126       +2879       +2585       +2291       +2026       +1762       +         00000780       +1472       +1425       +1379       +1332       +1286       +1371       +1457       +         0000788       -932       -1834									+757
00000730         +3652         +3394         +3137         +3007         +2878         +2900         +2923         +           00000738         +3800         +1284         +1328         +28         -248         -248         -248           00000740         +1456         +1406         +1358         +1309         +1261         +1209         +1159         +           00000748         +1218         +1265         +33         -654         -1342         -977         -356         -           00000750         +1401         +1753         +1338         +1738         +2140         +2575         +3009         +           00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000788         -93									+4004
00000738         +3800         +1284         +1328         +28         -248         -248         -248           00000740         +1456         +1406         +1358         +1309         +1261         +1209         +1159         +           00000748         +1218         +1265         +33         -654         -1342         -977         -356         -           00000750         +1401         +1753         +1338         +1738         +2140         +2575         +3009         +           00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000778         +3026         +2303         +2092         +665         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           0000790         +1598         +194									+3785
00000740         +1456         +1406         +1358         +1309         +1261         +1209         +1159         +           00000748         +1218         +1265         +33         -654         -1342         -977         -356           00000750         +1401         +1753         +1338         +1738         +2140         +2575         +3009         +           00000758         +3784         +2536         +1033         +265         +522         +440         +615         +           00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000778         +3026         +2303         +2092         +665         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000790         +1598         +1									+3105
00000748         +1218         +1265         +33         -654         -1342         -977         -356           00000750         +1401         +1753         +1338         +1738         +2140         +2575         +3009         +           00000758         +3784         +2536         +1033         +265         +522         +440         +615         +           00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000778         +3026         +2303         +2092         +665         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000788         -932         -1834         -1712         -1237         -763         -621         +33           00000790         +1598         +1943         +17									-248 +1444
00000750 +1401 +1753 +1338 +1738 +2140 +2575 +3009 + 00000758 +3784 +2536 +1033 +265 +522 +4440 +615 00000760 +388 +403 +2211 +4051 +4099 +4078 +4058 + 00000768 +3922 +3910 +3898 +3886 +3875 +3805 +3735 + 00000770 +3373 +3126 +2879 +2585 +2291 +2026 +1762 + 00000778 +3026 +2303 +2092 +665 -250 -250 -250 00000780 +1472 +1425 +1379 +1332 +1286 +1371 +1457 + 00000788 -932 -1834 -1712 -1237 -763 -621 +33 00000790 +1598 +1943 +1776 +2153 +2531 +2808 +3085 + 00000798 +3640 +4102 +4052 +3042 +496 +530 +564 00000780 +3898 +3860 +3898 +3936 +3974 +4013 +3783 +3553 + 00000780 +3094 +2858 +2623 +2420 +2217 +1921 +1626 00000788 +2764 +250 +296 +22 -252 -252 -252									+394
00000758         +3784         +2536         +1033         +265         +522         +440         +615           00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000778         +3026         +2303         +2092         +665         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000788         -932         -1834         -1712         -1237         -763         -621         +33           00000790         +1598         +1943         +1776         +2153         +2531         +2808         +3085         +           00000780         +3640         +4102         +4052         +3042         +496         +530         +564           000007A0         +440         +211         +3055 <td< td=""><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td>+3524</td></td<>									+3524
00000760         +388         +403         +2211         +4051         +4099         +4078         +4058         +           00000768         +3922         +3910         +3898         +3886         +3875         +3805         +3735         +           00000770         +3373         +3126         +2879         +2585         +2291         +2026         +1762         +           00000778         +3026         +2303         +2092         +665         -250         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000788         -932         -1834         -1712         -1237         -763         -621         +33           00000790         +1598         +1943         +1776         +2153         +2531         +2808         +3085         +           00000798         +3640         +4102         +4052         +3042         +496         +530         +564           000007A0         +440         +211         +3055         +3818         +4070         +4081         +4093         +           000007B0         +3094									+629
00000768       +3922       +3910       +3898       +3886       +3875       +3805       +3735       +         00000770       +3373       +3126       +2879       +2585       +2291       +2026       +1762       +         00000778       +3026       +2303       +2092       +665       -250       -250       -250       -250         00000780       +1472       +1425       +1379       +1332       +1286       +1371       +1457       +         00000788       -932       -1834       -1712       -1237       -763       -621       +33         00000790       +1598       +1943       +1776       +2153       +2531       +2808       +3085       +         00000798       +3640       +4102       +4052       +3042       +496       +530       +564         000007A0       +440       +211       +3055       +3818       +4070       +4081       +4093       +         000007B0       +3094       +2858       +2623       +2420       +2217       +1921       +1626         000007B8       +2764       +250       +296       +22       -252       -252       -252       -252									
00000770       +3373       +3126       +2879       +2585       +2291       +2026       +1762       +:00000778       +3026       +2303       +2092       +665       -250									+3990
00000778         +3026         +2303         +2092         +665         -250         -250         -250           00000780         +1472         +1425         +1379         +1332         +1286         +1371         +1457         +           00000788         -932         -1834         -1712         -1237         -763         -621         +33         -           00000790         +1598         +1943         +1776         +2153         +2531         +2808         +3085         +           00000798         +3640         +4102         +4052         +3042         +496         +530         +564           000007A0         +4440         +211         +3055         +3818         +4070         +4081         +4093         +           000007A8         +3860         +3898         +3936         +3974         +4013         +3783         +3553         +           000007B0         +3094         +2858         +2623         +2420         +2217         +1921         +1626           000007B8         +2764         +250         +296         +22         -252         -252         -252									+3553 +2649
00000780     +1472     +1425     +1379     +1332     +1286     +1371     +1457     +       00000788     -932     -1834     -1712     -1237     -763     -621     +33       00000790     +1598     +1943     +1776     +2153     +2531     +2808     +3085     +       00000798     +3640     +4102     +4052     +3042     +496     +530     +564       000007A0     +440     +211     +3055     +3818     +4070     +4081     +4093     +       000007A8     +3860     +3898     +3936     +3974     +4013     +3783     +3553     +       000007B0     +3094     +2858     +2623     +2420     +2217     +1921     +1626       000007B8     +2764     +250     +296     +22     -252     -252     -252     -252									-250
00000788         -932         -1834         -1712         -1237         -763         -621         +33         -930         +1598         +1943         +1776         +2153         +2531         +2808         +3085         +         -930         +3640         +4102         +4052         +3042         +496         +530         +564 <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td> <td></td>									
00000790     +1598     +1943     +1776     +2153     +2531     +2808     +3085     +       00000798     +3640     +4102     +4052     +3042     +496     +530     +564       000007A0     +440     +211     +3055     +3818     +4070     +4081     +4093     +       000007A8     +3860     +3898     +3936     +3974     +4013     +3783     +3553     +       000007B0     +3094     +2858     +2623     +2420     +2217     +1921     +1626       000007B8     +2764     +250     +296     +22     -252     -252     -252									+1030 +815
00000798     +3640     +4102     +4052     +3042     +496     +530     +564       000007A0     +440     +211     +3055     +3818     +4070     +4081     +4093     +       000007A8     +3860     +3898     +3936     +3974     +4013     +3783     +3553     +       000007B0     +3094     +2858     +2623     +2420     +2217     +1921     +1626       000007B8     +2764     +250     +296     +22     -252     -252     -252									+815
000007A0     +440     +211     +3055     +3818     +4070     +4081     +4093     +       000007A8     +3860     +3898     +3936     +3974     +4013     +3783     +3553     +       000007B0     +3094     +2858     +2623     +2420     +2217     +1921     +1626       000007B8     +2764     +250     +296     +22     -252     -252     -252									+3362
000007A8     +3860     +3898     +3936     +3974     +4013     +3783     +3553     +       000007B0     +3094     +2858     +2623     +2420     +2217     +1921     +1626       000007B8     +2764     +250     +296     +22     -252     -252     -252									+302
000007B0 +3094 +2858 +2623 +2420 +2217 +1921 +1626 000007B8 +2764 +250 +296 +22 -252 -252 -252									+3323
000007B8 +2764 +250 +296 +22 -252 -252									+3323
									-252
00000,00 11400 11440 11000 T1000 T10									-232 -408
	00000700	T1400	T1443	T1333	T13/1	T1343	T1300	±1330	-400

000007C8	-1834	-1589	-1089	-811	-535	-281	+485	+1171
000007D0	+1859	+2132	+2150	+2503	+2857	+3105	+3352	+3536
000007D8	+3720	+3875	+3775	+4298	+4054	+2123	+449	+502
000007E0	+556	+546	+26	+2113	+3945	+4115	+4031	+3946
000007E8	+3862	+3838	+3814	+3982	+3894	+3488	+3338	+3140
000007F0	+2943	+2622	+2302	+2030	+1758	+1495	+1234	+1259
000007F8	+774	-347	-188	-189	-190	-222	-254	-254
00000800	+1504	+1462	+1420	+1410	+1400	+1246	+1604	-1334
00000808	-1712	-1089	-978	-643	-308	+59	+938	+1529
00000810	+2120	+2322	+2524	+2854	+3184	+3402	+3620	+3710
00000818	+3800	+3905	+4010	+4019	+4028 +236	+3973	+334	+503
00000820	+672 +3864	+627 +3778	+582 +3692	+409		+2359	+3970	+3917 +2958
00000828	+2792	+2387	+1982	+3990 +1641	+3776 +1300	+3194 +1071	+3124 +842	+69
00000838	-192	-176	-160	-144	-128	-192	-256	-256
00000838	+1546	+1496	+1447	+1430	+1413	+1627	+1330	-2102
00000848	-1184	-819	-712	-395	-80	+405	+1148	+1713
00000850	+2280	+2486	+2692	+2995	+3297	+3467	+3638	+3712
00000858	+3787	+3915	+4045	+3917	+4047	+3097	+357	+655
00000860	+699	+198	+466	+381	+297	+376	+200	+1815
00000868	+3431	+3568	+3961	+4114	+3755	+3310	+3121	+2804
00000870	+2487	+2208	+1931	+1189	+447	+37	-116	-254
00000878	-136	-111	-86	-109	-132	-196	-260	-260
00000880	+1588	+1531	+1475	+1450	+1426	+1497	+33	-1591
00000888	-1168	-807	-446	-149	+148	+753	+1358	+1899
00000890	+2440	+2650	+2861	+3136	+3411	+3533	+3656	+3715
00000898	+3774	+3927	+4080	+3817	+4066	+2223	+380	+553
000008A0	+214	+3610	+350	+354	+358	+442	+526	+226
8A800000	-74	+286	+1158	+1678	+1686	+1634	+1582	+1114
000008B0	+646	+239	-168	-31	+107	-228	-51	-65
000008B8	-80	-46	-12	-74	-136	-200	-264	-264
000008C0	+1630	+1565	+1502	+1470	+1439	+1590	-817	-1399
000008C8	-960	-633	-308	-14	+280	+875	+1472	+1971
000008D0	+2472	+2718	+2965	+3229	+3492	+3582	+3674	+3701
000008D8	+3729	+3793	+3859	+4147	+4181	+707	+563	+417
000008E0	+1297	+3917	+4234	+2198	+163	+267	+372	+348
000008E8	+325	+108	+147	+186	-31	+38	+107	+96
000008F0	+85	+61	+38	-162	-106	-126	+111	+876
000008F8	-152	-93	-34	-87	-140	-204	-268	-268
00000900	+1672	+1601	+1530	+1491	+1452	+1685	-1666	-1209
00000908	-752	-461	-170	+121	+412	+999	+1586	+2045
00000910	+2504	+2787	+3071	+3322	+3574	+3633	+3693	+3688
00000918 00000920	+3684 +2380	+3661 +4225	+3638 +4022	+3711 +4043	+2760 +4064	+473 +2141	+746 +218	+283 +215
00000920	+212	+186	+160	+230	+3004	+2141	+168	+102
00000928	+36	-117	-269	+218	+1218	+2025	+2833	+1048
00000930	-224	-140	-56	-100	-144	-208	-272	-272
00000938	+1626	+1607	+1589	+1458	+1585	+692	-1479	-1107
00000948	-736	-451	-168	+115	+400	+805	+1468	+1937
00000950	+2408	+2703	+2999	+3327	+3655	+3568	+3482	+3620
00000958	+3759	+3439	+3121	+1601	+851	+819	+533	+437
00000960	+3415	+4252	+4066	+4055	+4045	+4084	+4124	+2995
00000968	+1867	+1068	+269	+62	-145	-38	+69	+704
00000970	+1339	+2183	+3028	+2816	+2861	+2953	+2790	-349
00000978	+96	-19	-134	-137	-140	-204	-268	-268
00000980	+1580	+1614	+1649	+1427	+1718	-300	-1293	-1006
00000988	-720	-443	-166	+111	+388	+613	+1350	+1831
00000990	+2312	+2620	+2928	+3076	+3225	+3249	+3273	+3297
00000998	+3322	+3475	+3628	+3333	+1502	+655	+832	+593

000009A0	+3938	+4024	+4110	+4068	+4026	+3980	+3934	+3984
000009A8	+4034	+3998	+3962	+3990	+4018	+3786	+3554	+3610
000009B0	+3666	+3459	+3253	+3111	+2969	+2858	+2236	-210
000009B8	-96	-154	-212	-174	-136	-200	-264	-264
000009C0	+1662	+1653	+1644	+1619	+1851	-988	-1266	-985
000009C8	-704	-401	-100	+9	+120	+403	+944	+1579
000009D0	+2216	+2504	+2793	+2873	+2954	+2976	+2999	+3085
000009D8	+3173	+3237	+3303	+3575	+521	+553	+587	+1771
000009E0	+3981	+4019	+4058	+4032	+4007	+3971	+3936	+3948
000009E8	+3961	+3920	+3879	+3806	+3989	+3866	+3743	+3636
000009F0	+3529	+3375	+3222	+3069	+2916	+2907	+1362	-119
000009F8	-64	-113	-162	-147	-132	-196	-260	-260
00A0000	+1744	+1692	+1640	+1556	+1472	-1932	-1240	-964
00000A08	-688	-361	-34	+165	+364	+707	+1050	+1585
00000A10	+2120	+2389	+2658	+2671	+2684	+2705	+2726	+2875
00000A18	+3024	+3001	+2978	+2283	+564	+965	+342	+2951
00000A20	+4024	+4015	+4006	+3997	+3988	+3963	+3938	+3913
00000A28	+3888	+3842	+3796	+3622	+3960	+3946	+3932	+3662 -28
00000A30 00000A38	+3392 -32	+3292 -72	+3192	+3028 -120	+2864 -128	+2956 <b>-</b> 192	+488 -256	-28 -256
00000A38	+1834	+1635	-112 +1692	+1718	+208	-1663	-1229	-236 -924
00000A40	-619	-283	+1092	+256	+719	+705	+948	+1126
00000A40	+1562	+1845	+2129	+2236	+2344	+2447	+2551	+2654
00000A58	+2759	+2738	+2719	+1562	+663	+623	+327	+4207
00000A60	+3992	+4012	+4034	+3990	+3948	+3922	+3898	+3872
000007100	+3848	+3774	+3701	+3484	+3523	+3726	+3929	+3812
00000A70	+3695	+3604	+3513	+3407	+3300	+3350	-440	-231
00000A78	-22	-48	-74	-100	-126	-174	-222	-222
08A00000	+1924	+1578	+1745	+1880	-1057	-1394	-1219	-884
00000A88	-550	-207	+135	+93	+563	+449	+847	+669
00000A90	+1004	+1302	+1600	+1802	+2005	+2191	+2377	+2435
00000A98	+2494	+2477	+2460	+843	+763	+794	+1337	+3928
00000AA0	+3960	+4011	+4062	+3985	+3908	+3883	+3858	+3833
8AA00000	+3808	+3707	+3607	+3603	+3599	+3506	+3414	+3706
00000AB0	+3998	+3916	+3835	+3786	+3737	+2208	-345	+78
00000AB8	-12	-24	-36	-80	-124	-156	-188	-188
00000AC0	+1598	+1585	+1829	+2154	-1873	-1413	-1208	-556
00000AC8	-417	-514	-102	+440	+214	+191	+681	+435
00000AD0	+702	+870	+1039	+1224	+1409	+1709	+2010	+2039
00000AD8	+2069	+2086	+1849	+795	+766	+596	+2474	+3953
00000AE0	+3896	+3928	+3962	+3914	+3868	+3842	+3818	+3792
00000AE8	+3768	+3687	+3608	+3577	+3546	+3462	+3379	+3312
00000AF0	+3245	+3364	+3484	+3189	+2893	+858	-154	+35
00000AF8	-34	-48	-62	-108	-154	-154	-154	-154
00000B00	+1784	+1849	+1915	+892	-1666	-1176	-1711	-741
00000B08	-796	-822	+175	-748	+378	+191	+517	+202
00000B10	+400	+439	+479	+646	+814	+1229	+1645	+1644
00000B18	+1644	+1697	+1239	+748	+770	+399	+3613	+3978
00000B20	+3832	+3847	+3862	+3845	+3828	+3803	+3778	+3753
00000B28	+3728	+3669	+3611	+3552	+3494	+3419	+3345	+3174
00000B30	+3004	+2813	+2623	+2592	+2562	-237	+37	-9 100
00000B38	-56	-72	-88	-136	-184	-152	-120	-120
00000B40	+1802	+1900	+2255	-286	-1290 170	-1129	-712	-391
00000B48	-327	-385	-445	+201	-178	+436	+27	-45
00000B50	-118 +1123	+204	+270 +1127	+384 +794	+498 +717	+685 +1161	+874	+998
00000B58	+1123	+1252	+1127		+717 +3764	+1161 +3616	+3654	+3843
00000B60 00000B68	+3776 +3656	+3788 +3595	+3802 +3536	+3782 +3476	+3764 +3417	+3616 +3341	+3726 +3265	+3690 +3078
00000B68	+3656	+3595		+3476 +2617	+3417	+3341		
000000870	TZÖÐI	TZ00/	+2484	+2617	+1982	-28	+8	+14

00000B78	+18	-18	-54	+6	+66	-30	-126	-126
00000B80	+1820	+1696	+2084	-2232	-1939	-570	-1762	-1834
00000B88	-1394	-461	-552	-387	-223	-1110	-462	-37
00000B90	-124	-31	-451	-134	+183	+143	+104	+353
00000B98	+602	+809	+1017	+841	+665	+1924	+3696	+3708
00000BA0	+3720	+3731	+3742	+3721	+3700	+3431	+3674	+3629
00000BA8	+3584	+3523	+3462	+3401	+3341	+3264	+3187	+2982
00000BB0	+2778	+2562	+2346	+2386	+891	-77	-20	+36
00000BB8	+92	+36	-20	-108	-196	-164	-132	-132
00000BC0	+1710	+1955	+1177	-2833	-955	-2075	-2172	-364
00000BC8	-1885	-1352	-820	-1599	-843	-1249	-887	-652
00000BD0	-674	-554	-435	-636	-325	-304	-282	-101
00000BD8	-175	+493	+906	+871	+580	+2767	+3674	+3653
00000BE0	+3632	+3656	+3682	+3626	+3572	+3436	+3558	+3534
00000BE8 00000BF0	+3512 +2697	+3449 +2500	+3388 +2304	+3325 +2219	+3264 +343	+3186 +179	+3108 +271	+2902 +154
00000BF0	+38	-6	-50	-110	-170	-154	-138	-138
00000BF8	+1600	+1959	-242	-2667	-2020	-2557	-2582	-1455
00000000	+696	+316	+960	+2052	+2120	+1940	+1760	+1292
00000C08	+824	-310	-932	-1394	-832	-750	-668	-298
00000C10	-440	+434	+796	+902	+496	+3610	+3652	+3598
00000C10	+3544	+3583	+3622	+3533	+3444	+3443	+3442	+3441
00000028	+3440	+3377	+3314	+3251	+3188	+3109	+3030	+2823
00000020	+2616	+2439	+2262	+2053	-204	+179	+50	+17
00000C38	-16	-48	-80	-112	-144	-144	-144	-144
00000C40	+1956	+1852	-2091	-3025	-1145	+322	+2045	+1672
00000C48	+1555	+1328	+1614	+1916	+1706	+1622	+1282	+1502
00000C50	+1466	+1301	+1393	+940	-792	-1548	-768	-820
00000C58	-617	+926	+934	+909	+1397	+3323	+3456	+3446
00000060	+3436	+3393	+3351	+3388	+3426	+3373	+3321	+3444
00000C68	+3313	+3264	+3217	+3153	+3090	+2997	+2906	+2686
00000C70	+2467	+2290	+2115	+1282	-61	+136	+79	+36
00000C78	-5	-37	-69	-101	-133	-133	-133	-133
00000C80	+1800	+1746	+669	+1992	+1779	+1665	+1552	+1727
00000C88	+1390	+1317	+1245	+1269	+1293	+1560	+1316	+1456
00000C90	+1084	+1121	+1158	+971	+1297	+726	-869	-1343
00000C98	-794	+1419	+1072	+917	+2299	+3036	+3261	+3294
00000CA0	+3328	+3204	+3080	+3244	+3409	+3305	+3201	+3449
00000CA8	+3186	+3153	+3121	+3056	+2992	+2887	+2783	+2550
00000CB0	+2318	+2143	+1968	+513	+82	+95	+108	+57
00000CB8	+6	-26	-58	-90	-122	-122	-122	-122
00000CC0	+1516	+1832	+1636	+1905	+1406	+1344	+1283	+1589
00000CC8	+1641	+1465	+1291	+1277	+1263	+1386	+1254	+1314
00000CD0	+1118	+1116	+1115	+905	+953	+1160	+1111	+118
00000CD8	-363	+807	+698	+700	+2240	+3325	+2361	+2934
00000CE0	+3252	+2998	+2745	+2924	+3103	+3155	+2952	+3277
00000CE8	+3091	+3057	+3024	+2959	+2894	+2776	+2659	+2414
00000CF0	+2169	+2074	+1981	+255	+65	+68	+73	+44
00000CF8	+17	-15	-47	-79	-111 +1546	-111	-111	-111
00000D00	+1744	+1662	+1581 +1339	+1563		+1536	+1527	+1453
00000D08 00000D10	+1380 +1152	+1359 +1112	+1339	+1286 +1097	+1234 +1122	+1213 +826	+1193 +1043	+1172 +1067
00000D10	+1152	+1112	+1073	+1097	+1122	+826	+1043	+1067
00000D18	+2664	+2793	+2923	+2860	+2102	+3007	+2705	+3106
00000D20	+2996	+2793	+2923	+2862	+2796	+2666	+2703	+2278
00000D20	+2020	+1751	+1482	-259	+48	+43	+38	+33
00000D30	+28	-4	-36	-68	-100	-100	-100	-100
00000D30	+1684	+1640	+1596	+1584	+1573	+1543	+1513	+1451
00000D40	+1391	+1359	+1329	+1282	+1236	+1213	+1190	+1168
000000010	. 1001	. 1000	. 1025	. 1202	. 1200	. 1210	. 1100	. 1100

00000D50	+1146	+1107	+1069	+1063	+1058	+920	+1038	+996
00000D58	+955	+924	+894	+880	+1635	+1679	+2235	+2439
00000D60	+2132	+2451	+2771	+2580	+2644	+2713	+2528	+2742
00000D68	+2701	+2828	+2699	+2570	+2442	+2383	+2324	+2105
00000D70	+1887	+1732	+811	-79	+55	+62	+71	+46
00000D78	+23	-7	-37	-67	-97	-113	-129	-129
00000D80	+1624	+1618	+1612	+1606	+1601	+1551	+1501	+1451
00000D88	+1402	+1361	+1320	+1279	+1239	+1214	+1189	+1164
00000D90	+1140	+1103	+1067	+1031	+995	+1014	+1034	+926
00000D98	+818	+885	+953	+1021	+1089	+1024	+1472	+2048
00000DA0	+2112	+2110	+2109	+2044	+2491	+2421	+2352	+2379
00000DA8	+2406	+2694	+2471	+2279	+2088	+2100	+2113	+1933
00000DB0	+1754	+1715	+140	+101	+62	+83	+104	+61
00000DB8	+18	-10	-38	-66	-94	-126	-158	-158
00000DC0	+1724	+1788	+1852	+1692	+1532	+1494	+1456	+1418
00000DC8	+1381	+1345	+1311	+1275	+1241	+1214	+1187	+1160
00000DD0	+1134	+1098	+1064	+1029	+995	+996	+998	+935
00000DD8	+873	+877	+883	+792	+702	+657	+1125	+1832
00000DE0	+2284	+1193	+1638	+1796	+2209	+2320	+2176	+2239
00000DE8	+2047	+2560	+2562	+1891	+1734	+1673	+1613	+1744
00000DF0	+1621	+1152	-83	-8	+69	+70	+73	+42
00000DF8	+13	-13	-39	-65	-91	-139	-187	-187
00000E00	+1824	+1702	+1580	+1522	+1464	+1438	+1412	+1386
00000E08	+1360	+1331	+1302	+1273	+1244	+1215	+1186	+1157
00000E10	+1128	+1095	+1062	+1029	+996	+979	+962	+945
00000E18	+928	+871	+814	+821	+828	+803	+1290	+1617
00000E20	+1944	+2068	+1168	+1292	+1416	+1708	+1488	+1844
00000E28	+1688	+2171	+2142	+1249	+1380	+1503	+1626	+1045
00000E30	-48	+79	+206	+141	+76	+59	+42	+25
00000E38 00000E40	+8	-16 +1615	-40	-64	-88	-152	-216	-216
00000E40	+1688		+1542	+1501 +1257	+1460 +1232	+1429 +1205	+1398 +1180	+1367
00000E48	+1336 +1128	+1309 +1092	+1284 +1058	+1237	+1232	+1203	+1180	+1153 +930
00000E50	+1128	+1092	+1058	+1022	+988	+595	+950	+930
00000E58	+1272	+330	+812	+1038	+1152	+1298	+1444	+1910
00000E60	+1272	+1531	+1200	+515	+344	+259	+176	+251
00000E00	+72	+122	+174	+128	+84	+64	+46	+251
00000E70	+8	-18	-44	-70	-96	-144	-192	-192
00000E78	+1552	+1528	+1504	+1480	+1456	+1420	+1384	+1348
00000E88	+1312	+1289	+1266	+1243	+1220	+1197	+1174	+1151
00000E88	+1128	+1091	+1200	+1017	+980	+959	+938	+917
00000E98	+896	+853	+810	+767	+724	+645	+566	+583
00000E30	+600	+640	+680	+528	+376	+376	+888	+1464
00000EA8	+1016	+637	+258	+295	+332	+297	+262	+227
00000ER0	+192	+167	+142	+117	+92	+71	+50	+29
00000EB8	+8	-20	-48	-76	-104	-136	-168	-168
00000EB0	+1544	+1521	+1498	+1475	+1452	+1411	+1370	+1329
00000EC8	+1288	+1267	+1248	+1227	+1208	+1187	+1168	+1147
00000ED0	+1128	+1088	+1050	+1010	+972	+948	+926	+902
00000ED8	+880	+843	+808	+771	+736	+677	+620	+609
00000EE0	+600	+614	+628	+546	+464	+238	+2060	+1690
00000EE8	+1576	+1709	+308	+313	+320	+285	+252	+217
00000EE0	+184	+162	+142	+120	+100	+76	+54	+30
00000EF0	+8	-22	-52	-82	-112	-128	-144	-144
00000E10	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
00000F08	+1264	+1247	+1230	+1213	+1196	+1179	+1162	+1145
00000F00	+1128	+1087	+1046	+1005	+964	+939	+914	+889
00000F10	+864	+835	+806	+777	+748	+711	+674	+637
00000F10	+600	+588	+576	+564	+552	+612	+160	+1916
00000120	1000	1000	1370	1001	1002	1012	1 ± 00	. + > + 0

00000F28	+1112	+223	+358	+333	+308	+275	+242	+209
00000F30	+176	+159	+142	+125	+108	+83	+58	+33
00000F38	+8	-24	-56	-88	-120	-120	-120	-120
00000F40	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
00000F48	+1264	+1246	+1230	+1212	+1196	+1178	+1162	+1144
00000F50	+1128	+1086	+1046	+1004	+964	+938	+914	+888
00000F58	+864	+834	+806	+776	+748	+710	+674	+636
00000F60	+600	+588	+576	+564	+552	+644	+480	+108
00000F68	+504	+158	+326	+316	+308	+274	+242	+208
00000F70	+176	+158	+142	+124	+108	+82	+58	+32
00000F78	+8	-24	-56	-88	-120	-120	-120	-120
00000F80	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
00000F88	+1264	+1247	+1230	+1213	+1196	+1179	+1162	+1145
00000F90	+1128	+1087	+1046	+1005	+964	+939	+914	+889
00000F98	+864	+835	+806	+777	+748	+711	+674	+637
00000FA0	+600	+588	+576	+564	+552	+420	+288	+348
00000FA8	+408	+351	+294	+301	+308	+275	+242	+209
00000FB0	+176	+159	+142	+125	+108	+83	+58	+33
00000FB8	+8	-24	-56	-88	-120	-120	-120	-120
00000FC0	+1536	+1514	+1492	+1470	+1448	+1402	+1356	+1310
00000FC8	+1264	+1246	+1230	+1212	+1196	+1178	+1162	+1144
00000FD0	+1128	+1086	+1046	+1004	+964	+938	+914	+888
00000FD8	+864	+834	+806	+776	+748	+710	+674	+636
00000FE0	+600	+588	+576	+564	+552	+420	+288	+348
00000FE8	+408	+350	+294	+300	+308	+274	+242	+208
00000FF0	+176	+158	+142	+124	+108	+82	+58	+32
00000FF8	+8	-24	-56	-88	-120	-120	-120	-120

#### 4.2.4.3.4 Reconstructed Y Component

The reconstructed Y component is the same as the LLO band shown in section 4.2.4.3.3.7.

## 4.2.4.3.5 Reconstructed Cb Component

The following is a dump of the reconstructed Cb component. All the coefficients are displayed in 11.5 fixed-point representation.

0	0000000	+1728	+1730	+1732	+1734	+1736	+1738	+1740	+1742
0	8000000	+1744	+1740	+1736	+1732	+1728	+1796	+1864	+1804
0	0000010	+1744	+1754	+1764	+1774	+1784	+1794	+1804	+1814
0	0000018	+1824	+1774	+1724	+1802	+1880	+1814	+1748	+1810
0	0000020	+1872	+1878	+1884	+1890	+1896	+1910	+1924	+1938
0	0000028	+1952	+1938	+1924	+1910	+1896	+1914	+1932	+1950
0	0000030	+1968	+1974	+1980	+1986	+1992	+1998	+2004	+2010
0	0000038	+2016	+2016	+2016	+2016	+2016	+2016	+2016	+2016
0	0000040	+1710	+1697	+1684	+1704	+1723	+1726	+1730	+1733
0	0000048	+1737	+1738	+1740	+1741	+1743	+1758	+1774	+1757
0	0000050	+1741	+1762	+1783	+1788	+1793	+1774	+1755	+1784
0	0000058	+1813	+1817	+1821	+1825	+1829	+1857	+1885	+1881
0	0000060	+1877	+1849	+1821	+1857	+1894	+1904	+1914	+1924
0	0000068	+1935	+1928	+1922	+1915	+1909	+1922	+1936	+1949
0	0000070	+1963	+1974	+1985	+1997	+2008	+2009	+2011	+2012
0	0000078	+2014	+2017	+2020	+2023	+2026	+2026	+2026	+2026
0	0800000	+1692	+1664	+1637	+1674	+1711	+1715	+1720	+1725
0	8800000	+1730	+1737	+1744	+1751	+1758	+1721	+1684	+1711
0	0000090	+1738	+1770	+1802	+1802	+1802	+1754	+1706	+1754

00000098	+1802	+1860	+1918	+1848	+1778	+1900	+2022	+1952
0A000000	+1882	+1820	+1759	+1825	+1892	+1898	+1905	+1911
8A000000	+1918	+1919	+1920	+1921	+1922	+1931	+1940	+1949
000000B0	+1958	+1974	+1991	+2008	+2025	+2021	+2018	+2015
000000B8	+2012	+2018	+2024	+2030	+2036	+2036	+2036	+2036
000000C0	+1674	+1631	+1589	+1644	+1698	+1703	+1710	+1716
000000C8	+1723	+1735	+1748	+1760	+1773	+1763	+1754	+1760
000000D0	+1767	+1794	+1821	+1800	+1779	+1830	+1881	+1900
000000D8	+1919	+2047	+2175	+2015	+1855	+1879	+1903	+1927
000000E0	+1951	+1759	+1824	+1856	+1890	+1892	+1895	+1897
000000E8	+1901	+1909	+1918	+1926	+1935	+1939	+1944	+1948
000000F0	+1953	+1974	+1996	+2019	+2041	+2032	+2025	+2017
000000F8	+2010	+2019	+2028	+2037	+2046	+2046	+2046	+2046
00000100	+1656	+1599	+1543	+1614	+1686	+1693	+1701	+1708
00000108	+1716	+1734	+1752	+1770	+1788	+1806	+1824	+1810
00000110	+1796	+1818	+1840	+2054	+2268	+1650	+1032	+510
00000118	-12	-70	-128	+390	+908	+1602	+2296	+2158
00000120	+2020	+1699	+1890	+1889	+1888	+1887	+1886	+1885
00000128	+1884	+1900	+1916	+1932	+1948	+1948	+1948	+1948
00000130 00000138	+1948 +2008	+1975 +2020	+2003 +2032	+2030 +2044	+2058 +2056	+2045 +2056	+2033 +2056	+2020 +2056
00000138	+1590	+2020	+1551	+1612	+1673	+1579	+1742	+1713
00000140	+1685	+1672	+1660	+1711	+1763	+1694	+1626	+1941
00000140	+2001	+2060	+583	-654	-1891	-2046	-2201	-2084
00000150	-1967	-2049	-2131	-2053	-1975	-1751	-1527	+41
00000130	+1609	+2374	+1859	+2000	+1886	+1898	+1912	+1909
00000168	+1907	+1900	+1894	+1919	+1945	+1944	+1944	+1943
00000170	+1943	+1967	+1992	+2017	+2042	+2032	+2023	+2014
00000178	+2006	+2017	+2028	+2039	+2050	+2050	+2050	+2050
00000180	+1524	+1542	+1560	+1610	+1661	+1467	+1785	+1719
00000188	+1654	+1611	+1568	+1653	+1738	+1839	+1940	+793
00000190	-866	-2050	-2210	-2082	-1954	-1902	-1850	-1862
00000198	-1874	-1980	-2086	-1936	-1786	-1776	-1766	-1820
000001A0	-1874	-534	+1829	+2112	+1884	+1911	+1939	+1934
000001A8	+1930	+1901	+1872	+1907	+1942	+1941	+1940	+1939
000001B0	+1938	+1960	+1982	+2004	+2027	+2021	+2015	+2009
000001B8	+2004	+2014	+2024	+2034	+2044	+2044	+2044	+2044
000001C0	+1586	+1641	+1697	+1704	+1712	+1577	+1699	+1660
000001C8	+1623	+1613	+1604	+1642	+1681	+1791	-402	-2036
000001D0	-1877	-2144	-1899	-1942	-1985	-1918	-1851	-1880
000001D8	-1909	-1959	-2009	-1931	-1853	-1801	-1749	-1617
000001E0	-1485	-1939	-1882	+96	+2074	+1971	+1869	+1895
000001E8	+1921	+1885	+1850	+1894	+1939	+1937	+1936	+1934
000001F0	+1933	+1952	+1972	+1991	+2011	+2008	+2006	+2003
000001F8	+2002	+2011	+2020	+2029	+2038	+2038	+2038	+2038
00000200	+1136	+1229	+1322	+1287	+1252	+1433	+1614	+1603
00000208	+1592	+1616	+1640	+1632	+1624	+2256	-1720	-1792
00000210	-1864	-1982	-2100	-2058	-2016	-1934	-1852	-1898
00000218	-1944	-1938	-1932	-1926	-1920	-1826	-1732	-1670
00000220	-1608	-1552	-1496	-1664	-1320	+2288	+1800	+1856
00000228	+1912	+1870	+1828	+1882	+1936	+1934	+1932	+1930
00000230	+1928	+1945	+1962	+1979	+1996	+1997	+1998	+1999
00000238	+2000	+2008	+2016	+2024	+2032	+2032	+2032	+2032
00000240	+1552	+1624	+1698	+1674	+1652	+1644	+1638	+1614
00000248 00000250	+1592	+1611	+1630	+1681	+1733	+1146	-2000 -1903	-1787 -1995
	-1830 -1830	-1924 -1996	-2019 -1904	-2049 -1860	-2080 -1927	-1986 -1779	-1893 -1731	-1895 -1667
00000258 00000260	-1898 -1604	-1896 -1615	-1894 -1626	-1860 -1979	-1827 -594	-1779 +2063	-1731 +1903	-1667 +2016
00000260	+1873	-1615 +2132	-1626 +1880	-1878 +1884		+2063 +1921	+1903 +1955	+2016
00000268	T10/3	TZ13Z	+1880	+1884	+1888	T1921	<b>サエダン</b> ン	T1941

00000270	+1927	+1925	+1925	+1955	+1987	+2005	+2025	+2043
00000278	+2063	+1995	+1927	+2099	+2015	+2095	+2175	+2175
00000280	+1456	+1509	+1562	+1551	+1540	+1601	+1662	+1627
00000288	+1592	+1606	+1621	+1731	+1842	+37	-2281	-1782
00000290	-1796	-1867	-1938	-2041	-2144	-2039	-1934	-1893
00000298	-1852	-1854	-1857	-1795	-1734	-1732	-1731	-1665
000002A0	-1600	-1678	-1757	-1836	+645	+2094	+2007	+1920
000002A8	+1322	+2139	+1933	+1886	+1840	+1909	+1979	+1952
000002B0	+1926	+1907	+1888	+1933	+1978	+2015	+2052	+2089
000002B8	+2126	+1982	+1838	+2174	+1998	+2158	+2318	+2318
000002C0	+1488	+1520	+1554	+1554	+1556	+1588	+1622	+1606
000002C8	+1592	+1569	+1547	+1700	+1855	-993	-2049	-1825
000002D0	-1858	-1905	-1953	-2016	-2080	-1995	-1911	-1858
000002D8	-1806	-1812	-1819	-1729	-1641	-1685	-1730	-1678
000002E0	-1628	-1677	-1727	-2194	+1947	+2125	+2046	+945
000002E8	-2205	+114	+2177	+2144	+1856	+1912	+1970	+1963
000002F0	+1957	+1935	+1915	+1925	+1937	+1991	+2047	+2181
000002F8	+2061	+2337	+2613	+1817	+2301	+2157	+2269	+2397
00000300	+1520	+1533	+1546	+1559	+1572	+1577	+1582	+1587
00000308	+1592	+1533	+1474	+1671	+1868	-2023	-1818	-1869
00000310	-1920	-1944	-1968	-1992	-2016	-1952	-1888	-1824
00000318	-1760	-1771	-1782	-1665	-1548	-1639	-1730	-1693
00000320	-1656	-1677	-1699	-1017	+2226	+1644	+2087	-286
00000328	-2148	-2167	-1674	+611	+2384	+2173	+1962	+1975
00000330	+1988	+1965	+1942	+1919	+1896	+1969	+2042	+2019
00000338	+1484	-1916	-1220	+2484	+1068	-916	+1708	+1964
00000340	+1504	+1514	+1526	+1536	+1548	+1550	+1554	+1556
00000348	+1560	+1581	+1604	+1786	+689	-2138	-1894	-1905
00000350	-1918	-1926	-1935	-1943	-1952	-1878	-1805	-1731
00000358	-1658	-1626	-1596	-1549	-1503	-1507	-1513	-1518
00000360	-1524	-1526	-1785	+148	+2080	+1995	+2422	-2094
00000368	-2003	-2033	-1809	-1665	-1776	-189	+1398	+2536
00000370	+2139	+2122	+2105	+2327	+2295	+2204	+2113	+2870
00000378	-213	-1669	-1077	-1237	-1653	-1589	+2059	+1931
00000380	+1488	+1497	+1506	+1515	+1524	+1525	+1526	+1527
00000388	+1528	+1631	+1735	+1902	-490	-2254	-1971	-1943
00000390	-1916	-1909	-1902	-1895	-1888	-1805	-1722	-1639
00000398	-1556	-1483	-1411	-1434	-1458	-1377	-1297	-1344
000003A0	-1392	-1376	-1872	+1312	+1935	+1834	+1734	-2622
000003A8	-2370	-2157	-1945	-1892	-1840	-2039	-2239	-2022
000003B0	-782	-281	+220	+433	+134	-377	-888	-1655
000003B8	-1398	-1166	-934	-1374 +1492	-1302	-726 +1498	+2410	+1898
000003C0	+1472	+1478	+1486		+1500		+1498	+1496
000003C8	+1496	+1600	+1705	+1666	-933	-1474	-2015	-1964
000003D0	-1914	-1891	-1869 -1321	-1846	-1824	-1731	-1639	-1546
000003D8 000003E0	-1454	-1387 -1545		-1191	-1317	-1150	-1240	-1250
000003E0	-1260 -2225		-1575 -1952	+2459	+1885 -1904	+2057	+182 -1907	-2429
		-2088		-1928 1670		-1905		-2149
000003F0 000003F8	-1879 -1239	-1835 -1335	-1793	-1670 -1335	-1803	-1645	-1489	-1491
			-1431		-1495	+681	+2345	+2089
00000400 00000408	+1456 +1464	+1461 +1570	+1466 +1676	+1471 +1174	+1476 -1888	+1473 -950	+1470 -2060	+1467
00000408	+1464 -1912	+1570 -1874	+1676 -1836	+1174 -1798	-1888 -1760	-950 -1658		-1986 -1454
00000410	-1912 -1352	-1874 -1292	-1836 -1232	-1798 -1204	-1760 -1688	-1658 -1180	-1556 -1184	-1454 -1156
00000418	-1332 -1128	-1292 -1203	-1232 -254	+2071	+1836	+2281	-1184	-1136 -2237
00000420	-2080	-2020	-254 -1960	-1964	-1968	-2028	-2088	-2020
00000428	-2000 -1952	-2020 -1855	-1960 -1758	-1964 -1725	-1900 -1692	-2026 -1635	-2000 -1578	-1329
00000430	-1592 -1592	-1504	-1416	-1040	-1688	+2088	+2280	+2280
00000438	+1428	+1438	+1450	+1460	+1472	+1463	+1454	+1493
000000440	11120	11100	11400	1 1 1 0 0	1 ± 1 / 2	11100	11101	11170

00000448	+1533	+1512	+1748	-160	-2068	-1346	-1137	-1775
00000450	-1902	-1848	-1794	-1708	-1622	-1544	-1466	-1356
00000458	-1247	-1198	-1149	-1196	-1755	-1246	-993	-1012
00000460	-1032	-1202	+930	+2023	+1837	+2238	-2480	-2286
00000468	-1838	-1799	-1761	-1835	-1909	-1954	-2000	-1982
00000470	-1964	-1908	-1853	-1829	-1807	-1749	-1692	-1538
00000478	-1642	-1526	-1410	-638	-122	+774	+1926	+1926
00000480	+1400	+1417	+1434	+1451	+1469	+1454	+1439	+1520
00000488	+1602	+1455	+1820	-1239	-1737	-1743	<del>-</del> 726	-1821
00000490	-1892	-1822	-1752	-1618	-1485	-1431	-1377	-1259
00000498	-1142	-1104	-1066	-1188	-1823	-1313	-803	-869
000004A0 000004A8	-936 -1596	-1203 -1579	+2115 -1563	+1976 -1706	+1838 -1850	+916 -1881	-2055 -1913	-1569 -1944
000004A8	-1396	-1379 -1962	-1949	-1706	-1922	-1864	-1913	-1749
000004B0	-1692	-1548	-1404	-1004	-1922 -92	+996	+2084	+2084
000004B0	+1372	+1394	+1418	+1441	+1465	+1444	+1423	+1483
000001C0	+1543	+1765	+1732	-2204	-1533	-1611	-1179	-1274
000004D0	-1882	-1764	-1646	-1560	-1475	-1301	-1127	-1113
000004D8	-1101	-994	-887	-1052	-1730	-1395	-804	-709
000004E0	-872	-306	+2051	+1929	+2063	-151	-1597	-1347
000004E8	-1354	-1326	-1300	-1417	-1535	-1599	-1665	-1730
000004F0	-1796	-1824	-1852	-1880	-1909	-1883	-1857	-1767
000004F8	-1678	-1570	-1462	-1434	+1154	+2402	+1858	+1858
00000500	+1344	+1373	+1403	+1432	+1462	+1435	+1409	+1446
00000508	+1484	+1564	+621	-1890	-1842	-1737	-1633	-728
00000510	-1872	-1706	-1541	-1503	-1466	-1428	-1391	-1225
00000518	-1060	-884	-709	-917	-1638	-1478	-807	-551
00000520	-808	+590	+1988	+1882	+2288	-1218	-1140	-1126
00000528	-1112	-1075	-1038	-1129	-1220	-1319	-1418	-1517
00000530	-1616	-1686	-1756	-1826	-1896	-1902	-1908	-1786
00000538	-1664	-1592	-1520	-1864	+2400	+2016	+2144	+2144
00000540	+1348	+1372	+1398	+1424	+1450	+1463	+1477	+1491
00000548	+1505	+1729	-607	-1838	-1790	-1735	-1681	-1003
00000550	-1350	-1710	-1558	-1519	-1480	-1382	-1285	-1379
00000558	-1475	-1208	-941	-611	-793	-796	-800	-611
00000560 00000568	-680 -886	+1364 -868	+1872 -851	+1932 -929	+1481 -1009	-1150 -1061	-966 -1114	-926 -1230
00000570	-1348	-1521	-1695	-1805	-1915	-1900	-1886	-1792
00000578	-1698	-1604	-1766	-744	+2326	+2134	+2198	+2198
00000570	+1352	+1373	+1395	+1417	+1439	+1492	+1546	+1536
00000588	+1526	+1894	-1835	-1787	-1739	-1735	-1731	-1279
00000590	-828	-1714	-1577	-1536	-1495	-1337	-1180	-1023
00000598	-866	-764	-663	-562	-973	-371	-282	-417
000005A0	-552	+2138	+1757	+1983	+674	-1083	-793	-726
000005A8	-660	-662	-665	-731	-798	-804	-811	-945
000005B0	-1080	-1357	-1635	-1784	-1934	-1899	-1865	-1798
000005B8	-1732	-1616	-2012	+376	+2252	+2252	+2252	+2252
000005C0	+1356	+1373	+1391	+1409	+1427	+1425	+1423	+1501
000005C8	+1579	+907	-1814	-1702	-1847	-1909	-1716	-1634
000005D0	-786	-1686	-1819	-1712	-1605	-1371	-1139	-921
000005D8	-705	-656	-608	-384	-416	-233	-308	-477
000005E0	+376	+1968	+1769	+2033	<b>-</b> 5	-839	-651	-606
000005E8	-562	-584	-606	-660	-715	-739	-763	-963
000005F0	-1164	-1432	-1702	-1843	-1985	-1977	-1971	-1884
000005F8	-1798	-2012	-2226	+2152	+2178	+2194	+2210	+2210
00000600	+1360	+1374	+1388	+1402	+1416	+1358	+1300	+1466
00000608	+1632	-81	-1794	-1619	-1956	-2085	-1702	-1991
00000610	-744	-891	-526 554	-353	-180	-383	-586	-821
00000618	-1056	-805	-554	-463	-372	-353	-334	-539

00000620	+1304	+1799	+1782	+2085	-684	-597	-510	-487
00000628	-464	-506	-548	-590	-632	-674	-716	-982
00000630	-1248	-1509	-1770	-1903	-2036	-2057	-2078	-1971
00000638	-1864	-1896	-1416	+2392	+2104	+2136	+2168	+2168
00000640	+1346	+1358	+1371	+1383	+1396	+1395	+1393	+1552
00000648	+1711	-1177	-1762	-2203	-1364	-465	+690	+1942
00000650	+1913	+1747	+1837	+1816	+1794	+1889	+1983	+1774
00000658	+1564	+548	-468	-299	-386	-391	-398	-147
00000660	+1895	+1920	+1946	+1284	-401	-397	-393	-421
00000668	-450	-478	-507	-568	-629	-722	-815	-1068
00000670	-1321	-1697	-2074	-2082	-2091	-2129	-2168	-2030
00000678	-1894	-2028	+142	+2280	+2114	+2082	+2050	+2050
00000680	+1332	+1343	+1354	+1365	+1377	+1432	+1487	+1382
00000688	+1278	-1763	-195	+1308	+1788	+1667	+1547	+1522
00000690	+1498	+1569	+1641	+1681	+1721	+1600	+1480	+1552
00000698	+1624	+1901	+2179	+1145	-401	-431	-462	-12
000006A0	+1974	+1786	+2111	+484	-119	-198	-277	-356
000006A8	-436	-451	-467	-547	-627	-770	-914	-898
000006B0	-882	-606	-330	-470	-611	-1435	-2259	-2091
000006B8	-1924	-2160	+1700	+2168	+2124	+2028	+1932	+1932
000006C0	+1318	+1327	+1337	+1346	+1357	+1405	+1452	+1420
000006C8	+1389	+1381	+1629	+1748	+1356	+1495	+1635	+1631
000006D0	+1627	+1551	+1732	+1689	+1647	+1728	+1809	+1730
000006D8	+1652	+1686	+1721	+1948	+1921	+874	-430	+363
000006E0	+1925	+1764	+1859	+148	-28	-95	-160	-291
000006E8	-422	-423	-426	-557	-688	-370	-309	-280
000006F0 000006F8	-251 -1858	-570 -1636	-890 +2170	-858 +2296	-826 +2166	-563	-301	-1079 +2070
000000700	+1304	+1312	+1321	+1329	+1338	+2118 +1378	+2070 +1419	+1459
00000700	+1504	+1452	+1404	+1329	+1436	+1570	+1724	+1484
00000708	+1244	+1022	+1313	+1187	+1062	+1088	+1115	+1397
00000710	+1680	+1728	+1777	+1729	+1682	+1922	+1651	+1763
00000710	+1876	+1742	+1609	-189	+62	+8	-45	-226
00000728	-408	-397	-387	-568	-750	-227	-217	-430
00000720	-644	-1047	-1451	-1502	-1554	-1229	-905	-580
00000738	-256	-856	+1616	+1912	+2208	+2208	+2208	+2208
00000740	+1290	+1304	+1319	+1334	+1350	+1377	+1404	+1271
00000748	+1395	+1525	+1655	+1769	+1884	+1802	+1720	+1430
00000750	+1141	+1026	+1168	+1037	+908	+700	+491	+331
00000758	+172	+873	+1575	+1524	+1731	+1991	+1738	+1774
00000760	+1811	+1914	+993	-119	+48	-74	-196	-271
00000768	-346	-407	-470	-324	-179	-213	-503	-810
00000770	-1117	-1273	-1430	-1636	-1841	-1823	-1551	-1246
00000778	-686	+1194	+1026	+1610	+2194	+2194	+2194	+2194
00000780	+1276	+1297	+1319	+1341	+1363	+1376	+1390	+1340
00000788	+1802	+1854	+1907	+1863	+1820	+1768	+1717	+1377
00000790	+1038	+1031	+1024	+889	+755	+568	+381	+290
00000798	+200	+19	-162	+553	+1781	+2060	+1827	+1786
000007A0	+1746	+2086	+378	-50	+35	-156	-348	-316
000007A8	-284	-419	-554	-337	-121	-456	-791	-934
000007B0	-1078	-1244	-1411	-1514	-1617	-1907	-1686	-1657
000007B8	-1116	+1964	+1972	+2076	+2180	+2180	+2180	+2180
000007C0	+1262	+1289	+1318	+1346	+1375	+1359	+1344	+1632
000007C8	+1921	+1927	+1934	+1876	+1820	+1702	+1585	+1259
000007D0	+935	+907	+880	+724	+569	+436	+302	+217
000007D8	+132	+44	-43	-99	+102	+801	+2011	+1878
000007E0	+1745	+1426	+2131	+916	-43	-191	-340	-393
000007E8	-446	-461	-478	-237	-254	-522	-790	-962
000007F0	-1135	-1519	-1647	-1760	-1872	-1446	-2045	-1827

000007F8	-1354	+2254	+2278	+2222	+2166	+2166	+2166	+2166
00800000	+1248	+1283	+1318	+1353	+1388	+1343	+1298	+1925
00000808	+2040	+2001	+1962	+1891	+1820	+1637	+1454	+1143
00000810	+832	+784	+736	+560	+384	+304	+224	+144
00000818	+64	+70	+76	+18	-40	+54	+1684	+1714
00000820	+1744	+1790	+1836	+1882	+1928	+798	-332	-470
00000828	-608	-505	-402	-139	-388	-589	-790	-991
00000830	-1192	-1794	-1884	-2006	-2128	-2266	-868	+818
00000838	+2504	+2288	+2072	+2112	+2152	+2152	+2152	+2152
00000840	+1238	+1263	+1290	+1332	+1375	+1301	+1484	+2002
00000848	+2009	+1973	+1939	+1871	+1805	+1608	+1411	+1118
00000850	+826	+751	+676	+505	+334	+273	+212	+151
00000858	+91	+69	+48	+11	-26	+482	+1758	+1771
00000860	+1784	+2033	+1771	+1860	+1950	+1989	+2029	+884
00000868	-260	-1156	-261	-309	-614	-922	-975	-1411
00000870 00000878	-1848 +2076	-2062 +2051	-2019 +2026	-697 +2081	+626 +2136	+2060 +2136	+2471 +2136	+2273 +2136
00000878	+1228	+1245	+1263	+1313	+1363	+1260	+1670	+2130
00000888	+1226	+1243	+1203	+1853	+1791	+1580	+1369	+1094
00000880	+820	+718	+616	+450	+285	+243	+201	+159
00000898	+118	+69	+20	+430	-13	+910	+1833	+1828
00000030	+1824	+229	+1706	+1839	+1972	+1901	+1830	+1983
00000010	+2136	+2032	+1416	+1056	+696	+280	+376	+728
000008B0	+1080	+1767	+2454	+2405	+2356	+2035	+2226	+2193
000000B8	+2160	+2070	+1980	+2050	+2120	+2120	+2120	+2120
000008C0	+1218	+1226	+1235	+1292	+1350	+1235	+1888	+2061
000008C8	+1979	+1935	+1893	+1834	+1776	+1551	+1326	+1070
000008D0	+814	+685	+556	+395	+235	+212	+189	+166
000008D8	+145	+116	+88	-68	+33	+1306	+1811	+1949
000008E0	+1576	-200	-183	+905	+1994	+1956	+1919	+1881
000008E8	+1844	+2004	+1909	+2005	+2102	+2042	+2239	+2195
000008F0	+2152	+2043	+1935	+2370	+2038	+2697	+1821	+368
000008F8	+2244	+2121	+1998	+2051	+2104	+2104	+2104	+2104
00000900	+1208	+1208	+1209	+1273	+1338	+1210	+2107	+2043
00000908	+1980	+1925	+1871	+1816	+1762	+1523	+1285	+1046
00000910	+808	+652	+497	+341	+186	+182	+179	+175
00000918	+172	+164	+157	+117	+590	+1958	+1791	+1815
00000920	+816	+140	-24	-28	-32	+988	+2008	+2036
00000928	+2064	+1977	+1890	+1931	+1972	+2013	+2054	+2127
00000930	+2200	+2320	+2440	+2080	+184	-1760	-3192	+336
00000938	+2328	+2172	+2016	+2052	+2088	+2088	+2088	+2088
00000940	+1222	+1215	+1209	+1266	+1325	+1459	+2104	+2046
00000948	+1989	+1945	+1903	+1861	+1819	+1612	+1406	+1136
00000950	+866	+715	+564	+446	+328	+295	+263	+230
00000958	+199	+481	+764	+711	+1427	+2086	+1721	+1692
00000960	+128	-37	+55	-14	-82	-108	-135	+335
00000968	+804	+1293	+1783	+2272	+2250	+2197	+1889	+1356
00000970	+568	-763	-2095	-3010	-2646	-2931	-2705	+2305
00000978	+2196	+2159	+2122	+2117	+2112	+2112	+2112	+2112
00000980	+1236	+1223	+1210	+1261	+1313	+1708	+2103	+2050
00000988	+1998	+1967	+1937	+1907	+1877	+1702	+1528	+1226
00000990 00000998	+924	+778	+633	+552	+471	+409	+348	+287
00000998 000009A0	+226 -48	+287	+349 +134	+283 +1	+1241 -132	+1702	+1652 -230	+1826 -343
000009A0 000009A8	-48 -456	+43 -670	+134 -884	-202	-132 -544	-181 -946	-230 -1860	-343 -1718
000009A8	-456 -2088	-670	-884 -2534	-202 -2469	-2404	-946 -2311	-1860 -1706	+2483
000009B0	+2064	+2146	+2228	+2182	+2136	+2136	+2136	+2403
000009B8	+1250	+1230	+1211	+1255	+1300	+1957	+2101	+2150
000009C8	+2007	+1956	+1906	+1856	+1806	+1696	+1586	+1284
33333353	. 2007	. 1000	. 1000	. 1000	. 1000	. 1000	. 1000	. 1204

000009D0	+982	+841	+701	+657	+613	+554	+497	+438
000009D8	+381	+412	+445	+717	+1758	+1782	+1807	+1095
000009E0	-128	-70	-11	-97	-182	-253	-325	-428
000009E8	-532	-761	-991	-580	-170	-1033	-873	-1976
000009F0	-1800	-2018	-2237	-2343	-2450	-2650	-35	+2308
000009F8	+2092	+2117	+2142	+2151	+2160	+2160	+2160	+2160
00A0000	+1264	+1238	+1212	+1250	+1288	+2206	+2100	+2058
00000A08	+2016	+1946	+1876	+1806	+1736	+1690	+1644	+1342
00000A10	+1040	+905	+770	+763	+756	+701	+646	+591
00000A18	+536	+539	+542 -156	+897 -194	+1764	+1607	+1962	+365
00000A20 00000A28	-208 -608	-182 -853	-1098	-194 -1471	-232 -820	-326 -97	-420 -910	-514 -955
00000A28	-2024	-2238	-2452	-2474	-2496	-2990	+1636	+2134
00000A30	+2120	+2088	+2056	+2120	+2184	+2184	+2184	+2184
00000A30	+1198	+1191	+1185	+1227	+1525	+2065	+2093	+2009
00000A48	+1925	+1887	+1850	+1781	+1712	+1682	+1653	+1464
00000A50	+1275	+1130	+986	+937	+889	+840	+792	+743
00000A58	+696	+684	+674	+1335	+1741	+1839	+1939	+54
00000A60	-294	-295	-297	-298	-300	-414	-527	-641
00000A68	<del>-</del> 755	-947	-1140	-1732	-1813	-733	-166	-1038
00000A70	-887	-1234	-1581	-1609	-1636	-1158	+2392	+2279
00000A78	+2166	+2119	+2072	+2121	+2170	+2170	+2170	+2170
08A00000	+1132	+1145	+1159	+1205	+1763	+1924	+2086	+1960
88A00000	+1834	+1829	+1825	+1756	+1688	+1675	+1663	+1586
00000A90	+1510	+1356	+1202	+1112	+1023	+981	+939	+897
00000A98	+856	+831	+807	+1774	+1718	+1817	+1405	-512
00000AA0	-380	-409	-438	-403	-369	-502	-635	-768
8AA00000	-902	-1042	-1182	-1482	-1782	-2138	-1982	-610
00000AB0	-262	-486	-711	-744	-777	+162	+2125	+1912
00000AB8	+2212	+2150	+2088	+2122	+2156	+2156	+2156	+2156
00000AC0	+1194	+1146	+1100	+1182	+1776	+1927	+2079	+1863
00000AC8	+1903	+1978	+1799	+1843	+1632	+1619	+1608	+1612
00000AD0	+1617	+1517	+1418	+1351	+1284	+1216	+1149	+1098
00000AD8	+1048	+945	+1099	+1781	+1695	+1954	+422	-566
00000AE0	-530	-554	-579	-571 -1679	-565	-686	-806	-927
00000AE8	-1049 -2773	-1232 -2074	-1416		-1943 -2221	-2342	-2486 +2369	-2501 +2137
00000AF0 00000AF8	+2162	+2133	-1376 +2104	-1671 +2123	+2142	+458 +2142	+2142	+2137
00000AF8	+1256	+1149	+1043	+1160	+1790	+1931	+2142	+1766
00000B00	+1230	+2129	+1774	+1931	+1576	+1565	+1554	+1639
00000B00	+1724	+1679	+1635	+1590	+1546	+1453	+1361	+1300
00000B18	+1240	+1060	+1392	+1788	+1672	+2092	-560	-620
00000B20	-680	-700	-721	-741	-762	-870	-979	-1087
00000B28	-1196	-1423	-1650	-1877	-2104	-2291	-2478	-2857
00000B30	-2724	-2895	-3067	-3110	-3666	+2547	+2103	+2107
00000B38	+2112	+2116	+2120	+2124	+2128	+2128	+2128	+2128
00000B40	+1214	+1170	+1128	+1453	+1779	+1692	+1861	+1807
00000B48	+1753	+1732	+1712	+1803	+1640	+1759	+1623	+1710
00000B50	+1799	+1666	+1790	+1755	+1719	+1628	+1539	+1497
00000B58	+1456	+1352	+1504	+1752	+1745	+1445	-902	-898
00000B60	-894	-907	-921	-935	-950	-1070	-1190	-1310
00000B68	-1431	-1641	-1852	-2062	-2273	-2431	-2590	-2812
00000B70	-2779	-2929	-3080	-3279	-2198	+2298	+2187	+2124
00000B78	+2062	+2081	+2100	+2119	+2138	+2138	+2138	+2138
00000B80	+1172	+1193	+1214	+1747	+1769	+1710	+2163	+2360
00000B88	+2046	+1592	+1651	+1677	+1704	+1954	+1693	+1783
00000B90	+1874	+1654	+1947	+1920	+1893	+1805	+1718	+1695
00000B98	+1672	+1644	+1617	+1717	+1818	+798	-1245	-1176
00000BA0	-1108	-1115	-1123	-1131	-1139	-1270	-1402	-1534

00000BA8	-1666	-1860	-2054	-2248	-2442	-2572	-2702	-2768
00000BB0	-2834	-2964	-3094	-3192	-219	+2306	+2272	+2142
00000BB8	+2012	+2046	+2080	+2114	+2148	+2148	+2148	+2148
00000BC0	+1194	+1150	+1364	+1784	+1694	+1983	+2272	+1441
00000BC8	+2147	+1980	+1813	+1838	+1864	+1909	+1698	+1823
00000BD0	+1949	+1818	+1943	+1989	+2034	+1933	+1833	+1812
00000BD8	+1792	+1712	+1633	+1649	+1923	-536	-1459	-1390
00000BE0	-1322	-1354	-1388	-1421	-1455	-1566	-1678	-1789
00000BE8	-1901	-2078	-2256	-2433	-2611	-2744	-2878	-2915
00000BF0	-2953	-2998	-3044	-3777	+1633	+2298	+1941	+2015
00000BF8	+2090	+2107	+2124	+2141	+2158	+2158	+2158	+2158
00000C00	+1216	+1109	+1514	+1823	+1620	+2001	+1870	+1803
00000C08	+1224	+1600	+1464	+1232	+1000	+1096	+1192	+1352
00000C10	+1512	+1726	+1940	+2058	+2176	+2062	+1948	+1930
00000C18	+1912	+1781	+1650	+1583	+2028	-1871	-1674	-1605
00000C20	-1536	-1595	-1654	-1713	-1772	-1863	-1954	-2045
00000C28	-2136	-2297	-2458	-2619	-2780	-2917	-3054	-3063
00000C30	-3072	-3033	-2994	-2827	+2460	+2035	+2122	+2145
00000C38	+2168	+2168	+2168	+2168	+2168	+2168	+2168	+2168
00000C40 00000C48	+1190	+1271	+1610	+1756	+1647	+1523	+1144	+1324
00000C48	+1249 +1294	+1364 +1404	+1224 +1514	+1211 +1800	+1199 +2087	+1255 +2075	+1566 +2063	+1430 +2003
00000C58	+1944	+1654	+1621	+1811	+979	-1997	-1903	-1888
00000C58	-1874	-1927	-1982	-2036	-2091	-2163	-2236	-2308
00000C68	-2381	-2513	-2646	-2778	-2911	-3005	-3100	-3114
00000C70	-3129	-3039	-3206	-1084	+2317	+2104	+2148	+2159
00000C78	+2171	+2175	+2179	+2183	+2187	+2187	+2187	+2187
00000C80	+1164	+1179	+1195	+1179	+1163	+1302	+1442	+1358
00000C88	+1274	+1385	+1496	+1447	+1399	+1158	+1429	+1508
00000090	+1588	+1594	+1601	+1543	+1486	+1832	+2179	+2077
00000098	+1976	+1528	+1593	+1785	-582	-2381	-2133	-2172
00000CA0	-2212	-2261	-2311	-2361	-2411	-2464	-2518	-2572
00000CA8	-2626	-2730	-2834	-2938	-3042	-3094	-3146	-3166
00000CB0	-3186	-3046	-3418	+658	+2174	+2174	+2174	+2174
00000CB8	+2174	+2182	+2190	+2198	+2206	+2206	+2206	+2206
00000CC0	+1202	+1230	+1259	+1272	+1286	+1321	+1356	+1343
00000CC8	+1331	+1405	+1480	+1474	+1470	+1349	+1483	+1522
00000CD0	+1562	+1576	+1591	+1573	+1557	+1589	+1622	+1718
00000CD8	+1816	+1690	+1820	+1694	-2015	-2556	-2330	-2376
00000CE0	-2422	-2610	-2799	-2700	-2602	-2669	-2736	-2803
00000CE8	-2871	-2946	-3022	-3097	-3173	-3182	-3192	-3153
00000CF0	-3115	-3324	-3278	+2256	+2159	+2147	+2136	+2156
00000CF8	+2177	+2189	+2201	+2213	+2225	+2225	+2225	+2225
00000D00	+1240	+1282	+1325	+1367	+1410	+1340	+1271	+1329
00000D08	+1388	+1426	+1465	+1503	+1542	+1540	+1539	+1537
00000D10	+1536	+1559	+1582	+1605	+1628	+1603	+1578	+1617
00000D18	+1656	+1596	+1536	+1604	-2936	-2476	-2528	-2580
00000D20	-2632	-2704	-2777	-2785	-2794	-2874	-2955	-3035
00000D28	-3116	-3163	-3210	-3257	-3304	-3271	-3238	-3141
00000D30	-3044	-3091	-2114	+2319	+2144	+2121	+2098	+2139
00000D38	+2180	+2196	+2212	+2228	+2244	+2244	+2244	+2244
00000D40 0000D48	+1230	+1255	+1281	+1306	+1333	+1303	+1272	+1338
00000D48 00000D50	+1405 +1542	+1436 +1562	+1468 +1584	+1500 +1605	+1533 +1627	+1535 +1601	+1537 +1577	+1539 +1616
00000D50	+1656	+1302	+1959	-417	-2793	-2797	-2545	-2581
00000D38	-2618	-2687	-2757	-417 -2794	-2793 -2833	-2797	-2343 -2968	-3036
00000D60	-3105	-3145	-3186	-3178	-3171	-3149	-3128	-3058
00000D00	-2989	-3221	-126	+2281	+2129	+2084	+2040	+2107
00000D78	+2175	+2189	+2203	+2217	+2231	+2231	+2231	+2231
0000010	.21/5	. 2100	.2200	/	, 2291		. 2291	. 2251

00000D80	+1220	+1229	+1238	+1247	+1257	+1266	+1275	+1348
00000D88	+1422	+1447	+1473	+1499	+1525	+1530	+1536	+1542
00000D90	+1548	+1567	+1587	+1606	+1626	+1601	+1577	+1616
00000D98	+1656	+1763	+1871	+1658	-2138	-2862	-2563	-2583
00000DA0	-2604	-2671	-2738	-2805	-2873	-2928	-2983	-3038
00000DA8	-3094	-3128	-3162	-3100	-3038	-3028	-3018	-2976
00000DB0	-2934	-3352	+1862	+2244	+2114	+2048	+1982	+2076
00000DB8	+2170	+2182	+2194	+2206	+2218	+2218	+2218	+2218
00000DC0	+1210	+1234	+1259	+1283	+1308	+1325	+1341	+1390
00000DC8	+1439	+1457	+1477	+1496	+1516	+1525	+1535	+1544
00000DD0	+1554	+1571	+1589	+1607	+1625	+1616	+1608	+1632
00000DD8	+1656	+1718	+1782	+1685	+1845	+528	-2836	-2728
00000DE0	-2622	-2654	-2687	-2719	-2752	-2763	-2773	-2992
00000DE8	-2955	-3030	-3106	-2813	-2777	-3226	-2908	-3134
00000DF0	-3359	-971	+2186	+2270	+2099	+2075	+2052	+2108
00000DF8	+2165	+2175	+2185	+2195	+2205	+2205	+2205	+2205
00000E00	+1200	+1240	+1280	+1320	+1360	+1384	+1408	+1432
00000E08	+1456	+1469	+1482	+1495	+1508	+1521	+1534	+1547
00000E10	+1560	+1576	+1592	+1608	+1624	+1632	+1640	+1648
00000E18 00000E20	+1656	+1675 -2638	+1694	+1713	+1732	+1871	+986	-827
00000E20	-2640 -2816	-2038 -2933	-2636 -3050	-2634 -2783	-2632 -3028	-2598 -3169	-2564 -1774	-2946 +293
00000E28	+2360	+2179	+1998	+2041	+2084	+2103	+2122	+2141
00000E30	+2360	+2179	+2176	+2184	+2192	+2103	+2122	+2141
00000E30	+1232	+1266	+1300	+1334	+1368	+1390	+1412	+1434
00000E48	+1456	+1468	+1482	+1494	+1508	+1520	+1534	+1546
00000E10	+1560	+1578	+1596	+1614	+1632	+1640	+1648	+1656
00000E58	+1664	+1645	+1628	+1705	+1784	+2101	+1908	+1298
00000E60	+688	+1071	-594	-1587	-2580	-2891	-3202	-2281
00000E68	-2640	-2058	-1476	-94	+1032	+2278	+2244	+2209
00000E70	+2176	+2131	+2088	+2091	+2096	+2111	+2128	+2143
00000E78	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000E80	+1264	+1292	+1320	+1348	+1376	+1396	+1416	+1436
00000E88	+1456	+1469	+1482	+1495	+1508	+1521	+1534	+1547
00000E90	+1560	+1580	+1600	+1620	+1640	+1648	+1656	+1664
00000E98	+1672	+1617	+1562	+1699	+1836	+1821	+1806	+1887
00000EA0	+1968	+1964	+1960	+2020	+2080	+1936	+1792	+1200
00000EA8	+1632	+1889	+2146	+2083	+2020	+2093	+2166	+2079
00000EB0	+1992	+2085	+2178	+2143	+2108	+2121	+2134	+2147
00000EB8	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000EC0	+1296	+1318	+1340	+1362	+1384	+1402	+1420	+1438
00000EC8	+1456	+1468	+1482	+1494	+1508	+1520	+1534	+1546
00000ED0	+1560	+1582	+1604	+1626	+1648	+1656	+1664	+1672
00000ED8	+1680	+1667	+1656	+1739	+1824	+1811	+1800	+1835
00000EE0	+1872	+1881	+1890	+1819	+1748	+1995	+450	+937
00000EE8	+912	+715	+2056	+2019	+1984	+2035	+2088	+2059
00000EF0	+2032	+2085	+2140	+2129	+2120	+2129	+2140	+2149
00000EF8	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000F00 00000F08	+1328	+1344 +1469	+1360	+1376	+1392	+1408	+1424	+1440
00000F08	+1456 +1560		+1482	+1495	+1508	+1521	+1534	+1547
00000F10	+1560	+1584 +1719	+1608 +1750	+1632 +1781	+1656 +1812	+1664 +1803	+1672 +1794	+1680 +1785
00000F18	+1088	+1719	+1730	+1781	+1812	+1803	+1794	+1785
00000F20	+1776	+2103	+1966	+1074	+1928	+1790	+2100	+2041
00000F20	+2072	+2087	+2102	+2117	+2132	+2139	+2146	+2153
00000F38	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000F40	+1328	+1344	+1360	+1376	+1392	+1408	+1424	+1440
00000F48	+1456	+1468	+1482	+1494	+1508	+1520	+1534	+1546
00000F50	+1560	+1584	+1608	+1632	+1656	+1664	+1672	+1680
							* · <del>-</del>	

00000F58	+1688	+1718	+1750	+1780	+1812	+1802	+1794	+1784
00000F60	+1776	+1798	+1820	+1858	+1896	+1750	+1860	+2338
00000F68	+1792	+2134	+1966	+1956	+1948	+1978	+2010	+2040
00000F70	+2072	+2086	+2102	+2116	+2132	+2138	+2146	+2152
00000F78	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000F80	+1328	+1344	+1360	+1376	+1392	+1408	+1424	+1440
00000F88	+1456	+1469	+1482	+1495	+1508	+1521	+1534	+1547
00000F90	+1560	+1584	+1608	+1632	+1656	+1664	+1672	+1680
00000F98	+1688	+1719	+1750	+1781	+1812	+1803	+1794	+1785
00000FA0	+1776	+1798	+1820	+1842	+1864	+1958	+2052	+1954
00000FA8	+1856	+1911	+1966	+1957	+1948	+1979	+2010	+2041
00000FB0	+2072	+2087	+2102	+2117	+2132	+2139	+2146	+2153
00000FB8	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192
00000FC0	+1328	+1344	+1360	+1376	+1392	+1408	+1424	+1440
00000FC8	+1456	+1468	+1482	+1494	+1508	+1520	+1534	+1546
00000FD0	+1560	+1584	+1608	+1632	+1656	+1664	+1672	+1680
00000FD8	+1688	+1718	+1750	+1780	+1812	+1802	+1794	+1784
00000FE0	+1776	+1798	+1820	+1842	+1864	+1958	+2052	+1954
00000FE8	+1856	+1910	+1966	+1956	+1948	+1978	+2010	+2040
00000FF0	+2072	+2086	+2102	+2116	+2132	+2138	+2146	+2152
00000FF8	+2160	+2168	+2176	+2184	+2192	+2192	+2192	+2192

## 4.2.4.3.6 Reconstructed Cr Component

The following is a dump of the reconstructed Cb component. All the coefficients are displayed in 11.5 fixed-point representation.

00000000	-2112	-2114	-2116	-2118	-2120	-2122	-2124	-2126
8000000	-2128	-2118	-2108	-2098	-2088	-2150	-2212	-2146
00000010	-2080	-2100	-2120	-2140	-2160	-2164	-2168	-2172
00000018	-2176	-2092	-2008	-2052	-2096	-2132	-2168	-2076
00000020	-1984	-2088	-2192	-2168	-2144	-2136	-2128	-2120
00000028	-2112	-2126	-2140	-2154	-2168	-2150	-2132	-2114
00000030	-2096	-2096	-2096	-2096	-2096	-2096	-2096	-2096
00000038	-2096	-2080	-2064	-2048	-2032	-2032	-2032	-2032
00000040	-2128	-2113	-2098	-2115	-2132	-2133	-2134	-2135
00000048	-2137	-2127	-2117	-2107	-2097	-2117	-2137	-2125
00000050	-2114	-2134	-2154	-2159	-2163	-2135	-2108	-2128
00000058	-2149	-2132	-2116	-2116	-2115	-2115	-2114	-2098
00000060	-2082	-2112	-2142	-2141	-2139	-2133	-2128	-2122
00000068	-2117	-2127	-2137	-2147	-2158	-2146	-2134	-2122
00000070	-2111	-2108	-2106	-2104	-2102	-2101	-2101	-2101
00000078	-2101	-2087	-2073	-2059	-2045	-2045	-2045	-2045
08000000	-2144	-2112	-2080	-2112	-2145	-2145	-2145	-2145
00000088	-2146	-2136	-2126	-2116	-2107	-2085	-2063	-2105
00000090	-2148	-2168	-2189	-2178	-2167	-2107	-2048	-2085
00000098	-2122	-2173	-2225	-2180	-2135	-2098	-2061	-2120
0A00000	-2180	-2136	-2093	-2114	-2135	-2131	-2128	-2125
8A000000	-2122	-2128	-2135	-2141	-2148	-2142	-2137	-2131
000000B0	-2126	-2121	-2117	-2112	-2108	-2107	-2107	-2106
000000B8	-2106	-2094	-2082	-2070	-2058	-2058	-2058	-2058
000000C0	-2160	-2111	-2062	-2109	-2157	-2156	-2155	-2154
000000C8	-2155	-2145	-2135	-2125	-2116	-2132	-2148	-2132
000000D0	-2118	-2154	-2191	-2181	-2170	-2494	-2308	-2393
000000D8	-2479	-2470	-2461	-2243	-2282	-2353	-2167	-2174

000000E0	-2182	-2160	-2139	-2135	-2130	-2128	-2128	-2127
000000E8	-2127	-2129	-2132	-2134	-2138	-2138	-2139	-2139
000000F0	-2141	-2133	-2127	-2120	-2114	-2112	-2112	-2111
000000F8	-2111	-2101	-2091	-2081	-2071	-2071	-2071	-2071
00000100	-2176	-2110	-2045	-2107	-2170	-2168	-2167	-2165
00000108	-2164	-2154	-2145	-2135	-2126	-2180	-2235	-2161
00000110	-2088	-2141	-2195	-2440	-2686	-2371	-1033	-398
00000118	+236	+305	+375	-3	-894	-2096	-2787	-2485
00000120	-2184	-2185	-2187	-2156	-2126	-2127	-2129	-2130
00000128	-2132	-2131	-2130	-2129	-2128	-2135	-2142	-2149
00000130	-2156	-2147	-2138	-2129	-2120	-2119	-2118	-2117
00000138	-2116	-2108	-2100	-2092	-2084	-2084	-2084	-2084
00000140	-2112	-2085	-2058	-2112	-2166	-2067	-2225	-2190
00000148	-2157	-2107	-2057	-2104	-2151	-2119	-2088	-2632
00000150	-2666	-2263	-837	+844	+2526	+3327	+2847	+2847
00000158	+2847	+2726	+2606	+2967	+3070	+2968	+2867	+397
00000160	-2074	-2745	-2137	-2281	-2169	-2202	-2236	-2190
00000168	-2145	-2145	-2147	-2148	-2150	-2152	-2156	-2159
00000170	-2163	-2159	-2156	-2152	-2150	-2130	-2111	-2123
00000178	-2137	-2127 -2060	-2117	-2107	-2097	-2097 -1967	-2097	-2097
00000180 00000188	-2048 -2150	-2060 -2060	-2073 -1971	-2118 -2074	-2163 -2177	-1967 -2315	-2284 -2454	-2217 -1057
00000188	+1364	+2990	+2568	+2593	+2619	+2369	+2631	+2508
00000190	+2386	+2332	+2300	+2352	+2427	+2913	+2888	+3022
00000130	+3156	+1302	-2088	-2406	-2213	-2279	-2345	-2251
000001A0	-2158	-2161	-2165	-2168	-2172	-2171	-2171	-2170
000001N0	-2170	-2172	-2175	-2177	-2180	-2142	-2105	-2131
000001B0	-2158	-2146	-2134	-2122	-2110	-2110	-2110	-2110
000001C0	-2112	-2163	-2215	-2235	-2255	-1994	-2247	-2194
000001C8	-2143	-2109	-2076	-2123	-2170	-2270	+700	+3527
000001D0	+2770	+2035	+2325	+2293	+2263	+2178	+2350	+2265
000001D8	+2181	+2129	+2078	+2154	+2231	+2521	+2557	+2559
000001E0	+2562	+3221	+3113	+140	-2832	-2034	-2261	-2199
000001E8	-2139	-2160	-2182	-2188	-2194	-2189	-2185	-2181
000001F0	-2177	-2185	-2193	-2201	-2210	-2154	-2098	-2138
000001F8	-2179	-2165	-2151	-2137	-2123	-2123	-2123	-2123
00000200	-1664	-1755	-1846	-1841	-1836	-1767	-2210	-2173
00000208	-2136	-2159	-2182	-2173	-2164	-2739	+2830	+2735
00000210	+2640	+2361	+2082	+1995	+1908	+1989	+2070	+2023
00000218	+1976	+1927	+1878	+1957	+2036	+2131	+2226	+2353
00000220	+2480	+2581	+2682	+2943	+2692	-2815	-2178	-2149
00000228	-2120	-2160	-2200	-2208	-2216	-2208	-2200	-2192
00000230	-2184	-2198	-2212	-2226	-2240	-2166	-2092	-2146
00000238	-2200	-2184	-2168	-2152	-2136	-2136	-2136	-2136
00000240	-2096	-2166	-2238	-2228	-2220	-2087	-2210	-2173
00000248	-2137	-2189	-2243	-2152	-2318	-2031	+3375	+2861
00000250	+2605	+2305	+2007	+1851	+1697	+1756	+1815	+1810
00000258	+1806	+1756	+1707	+1754	+1801	+1911	+2023	+2149
00000260	+2277	+2299	+2323	+2729	+1345	-2439	-2129	-2217
00000268	-2307	-2349	-2136	-2179	-2222	-2223	-2224	-2193
00000270	-2162	-2171	-2180	-2190 2170	-2199	-2198	-2198	-2213
00000278	-2229 -2016	-2172 -2067	-2115 -2119	-2170 -2105	-2225 -2003	-2113 -2152	-2257 -2211	-2257 -2174
00000280 00000288	-2016 -2138	-2067 -2221	-2118 -2305	-2105 -2132	-2093 -2472	-2152 +212	-2211 +2897	-2174 +2477
00000288	+2570	+2251	+1932	+1709	+1487	+1524	+1561	+1598
00000290	+1636	+1586	+1537	+1709	+1567	+1524	+1301	+1947
00000296 000002A0	+2074	+2019	+1964	+2261	-514	-2321	-2080	-2031
000002A0	-1982	-2283	-2073	-2151	-2229	-2321	-2248	-2194
000002R0	-2140	-2144	-2149	-2154	-2159	-2231	-2304	-2281
00000200	2110	2177	2117	2101	2100	2231	2504	2201

000002B8	-2258	-2160	-2062	-2188	-2314	-2090	-2378	-2378
000002C0	-2064	-2094	-2126	-2125	-2125	-2152	-2179	-2159
000002C8	-2139	-2204	-2270	-2144	-2530	+1688	+2834	+2460
000002D0	+2343	+2147	+1953	+1678	+1404	+1387	+1370	+1418
000002D8	+1466	+1416	+1366	+1349	+1332	+1442	+1553	+1663
000002E0	+1775	+1817	+1861	+2415	-2405	-2457	-1999	-2035
000002E8	-281	-1464	-2393	-2378	-2363	-2301	-2240	-2195
000002F0	-2150	-2165	-2181	-2182	-2182	-2199	-2218	-2188
000002F8	-2159	-2756	-2329	-1934	-2307	-2627	-2179	-2307
00000300	-2112	-2123	-2135	-2146	-2158	-2153	-2149	-2144
00000308	-2140	-2188	-2236	-2156	-2588	+3164	+2772	+2444
00000310	+2116	+2045	+1975	+1648	+1322	+1251	+1181	+1238
00000318	+1296	+1246	+1197	+1147	+1098	+1192	+1287	+1381
00000320	+1476	+1617	+1758	+1291	-2760	-2083	-2430	-1273
00000328	-628	-647	-667	-1582	-2498	-2365	-2233	-2196
00000330	-2160	-2187	-2215	-2210	-2206	-2169	-2133	-2096
00000338	-2060	-280	-548	-2448	-1788	-860	-1980	-2236
00000340	-2112	-2120	-2130	-2140	-2150	-2145	-2141	-2137
00000348	-2133	-2147	-2161	-2079	-718	+3207	+2525	+2291
00000350	+2057	+1941	+1827	+1553	+1279	+1174	+1070	+1094
00000358	+1118	+1044	+970	+976	+983	+1001	+1019	+1165
00000360	+1313	+1305	+1555	-212	-2491	-2189	-2401	-867
00000368	-615	-642	-671	-603	-536	-1354	-2172	-2271
00000370	-2370	-2340	-2311	-2330	-2349	-2315	-2282	-2697
00000378	-1321	-420	-543	-394	-757	-741	-2261	-2261
00000380	-2112	-2119	-2127	-2135	-2143	-2138	-2134	-2130
00000388	-2126 +1998	-2106	-2087	-2259	+640	+2995	+2279	+2138 +950
00000390 00000398	+940	+1839 +842	+1681 +744	+1459 +806	+1237 +869	+1098 +811	+960 +753	+951
00000398 000003A0	+1150	+995	+1352	-1715	-2222	-2297	-2372	-463
000003A0	-602	-639	-676	-649	-623	-600	-2372 -577	-810
000003A0	-1044	-1214	-1384	-1426	-1469	-1183	-897	-483
000003B0	-582	-560	-538	-900	-750	-1134	-2542	-2286
000003B0	-2112	-2117	-2123	-2129	-2135	-2131	-2127	-2123
000003C8	-2119	-2017	-1916	-2886	+1262	+2014	+2256	+2097
000003D0	+1939	+1736	+1534	+1364	+1194	+1022	+850	+806
000003D8	+762	+736	+710	+508	+818	+604	+646	+752
000003E0	+859	+1131	+1149	-2865	-2273	-2339	-1639	-425
000003E8	-493	-522	-553	-566	-581	-677	-773	-661
000003F0	-550	-567	-585	-586	-588	-657	-727	-572
000003F8	-675	-668	-661	-798	-679	-1799	-2407	-2151
00000400	-2112	-2116	-2120	-2124	-2128	-2124	-2120	-2116
00000408	-2112	-2185	-2258	-1723	+1884	+1035	+2234	+2057
00000410	+1880	+1634	+1388	+1270	+1152	+946	+740	+662
00000418	+584	+630	+676	+466	+1280	+654	+540	+554
00000420	+568	+757	-78	-2481	-2324	-2383	-906	-389
00000428	-384	-407	-430	-485	-540	-499	-458	-513
00000430	-568	-689	-810	-771	-732	-645	-558	-663
00000438	-768	-776	-784	-696	-608	-2464	-2272	-2016
00000440	-2104	-2110	-2116	-2122	-2129	-2105	-2081	-2105
00000448	-2130	-2204	-2536	-84	+1856	+1148	+1209	+1701
00000450	+1683	+1507	+1332	+1188	+1045	+837	+630	+518
00000458	+407	+489	+572	+398	+1249	+662	+330	+383
00000460	+436	+589	-1304	-2350	-2117	-2615	+213	-12
00000468	-239	-265	-293	-320	-348	-377	-407	-484
00000470	-562	-626	-691	-675	-661	-625	-590	-682
00000478	-776	-804	-832	-540	-248	-664	-1848	-2616
00000480	-2096	-2104	-2113	-2121	-2130	-2086	-2043	-2095
00000488	-2148	-2225	-2815	+1555	+1829	+1519	+697	+1603

00000490	+1486	+1381	+1276	+1107	+938	+729	+520	+375
00000498	+230	+349	+468	+331	+1219	+670	+121	+212
000004A0	+304	+423	-2531	-2477	-2423	-1569	+309	-149
000004A8	-94	-125	-157	-157	-157	-256	-356	-456
000004B0	-556	-564	-573	-581	-590	-606	-623	-703
000004B8	-784	-832	-880	-384	+112	-1424	-2448	-2192
000004C0	-2088	-2098	-2109	-2119	-2131	-2099	-2068	-2100
000004C8	-2134	-2485	-2325	+2921	+2025	+1536	+1048	+1088
000004D0	+1385	+1270	+1156	+993	+831	+700	+570	+407
000004D8	+245	+256	+268	+343	+932	+662	+135	+185
000004E0	+236	-337	-2445	-2346	-2504	-793	+149	-75
000004E8	-45	-64	-84	-88	-93	-183	-273	-363
000004F0	-454	-454	-454	-518	-583	-619	-655	-723
000004F8	-792	-796	-800	-868	-1960	-2296	-2376	-2248
00000500	-2080	-2093	-2106	-2119	-2132	-2113	-2094	-2107
00000508	-2120	-2234	-813	+2752	+2222	+1555	+1401	+574
00000510	+1284	+1160	+1036	+880	+724	+672	+620	+440
00000518	+260	+164	+69	+357	+646	+654	+151	+159
00000520	+168	-1096	-2361	-2217	-2586	-18	-11	-3
00000528	+4	-4	-13	-21	-30	-110	-191	-271
00000530	-352	-344	-336	-456	-576	-632	-688	-744
00000538	-800	-760	-720 -2102	-584	-2496	-2400	-2304	-2304
00000540 00000548	-2072 -2130	-2086 -2462	+1045	-2117 +2615	-2133 +2138	-2171 +1656	-2211 +1432	-2170 +807
00000550	+951	+1193	+1045	+2015	+2138	+1656	+1432	
00000558	+723	+569	+416	+311	+207	+384	+305	+486 +242
00000558	+180	-1825	-2295	-2348	-1891	+69	-19	-10
00000568	-3	-1023 -7	-12	-16	-22	-65	-107	-182
00000570	-258	-309	-361	-477	-593	-640	-688	-736
00000578	-784	-752	-720	-1200	-2448	-2384	-2320	-2320
00000580	-2064	-2081	-2099	-2116	-2134	-2231	-2329	-2234
00000588	-2140	-2691	+2902	+2478	+2055	+1759	+1464	+1041
00000590	+618	+1227	+812	+589	+366	+379	+392	+277
00000598	+162	+207	+253	+267	+281	+114	-52	+70
000005A0	+192	-2555	-2230	-2481	-1197	+156	-28	-19
000005A8	-10	-11	-12	-13	-15	-20	-25	-94
000005B0	-164	-275	-387	-498	-610	-649	-689	-728
000005B8	-768	-744	-720	-1816	-2400	-2368	-2336	-2336
000005C0	-2056	-2075	-2095	-2115	-2135	-2178	-2222	-2138
000005C8	-2310	-1319	+2743	+2293	+2099	+1893	+1432	+1242
000005D0	+541	+1036	+1020	+699	+379	+376	+374	+275
000005D8	+177	+196	+217	+189	+162	+100	+39	+153
000005E0	-756	-2420	-2293	-2549	-502	+131	-4	-10
000005E8	-17	-14	-12	-9	-7	-7	-6	-102
000005F0	-198	-320	-444	-519	-595	-641	-689	-720
000005F8	-752	-768	-784	-2192	-2320	-2336	-2352	-2352
00000600	-2048	-2070	-2092	-2114	-2136	-2126	-2116	-2042
00000608	-2480	+52	+2584	+2108	+2144	+2028	+1400	+1444
00000610	+464	+78	-308	-470	-632	-394	-156	+18
00000618	+192	+187	+182	+113	+44	+87	+130	+237
00000620	-1704	-2286	-2356	-2618	+192	+106	+20	-2
00000628	-24	-18	-12	-6	+0	+6	+12	-110
00000630	-232	-367	-502	-541	-580	-635	-690	-713
00000638	-736	-792	-848	-2568	-2240	-2304	-2368	-2368
00000640	-2046	-2068	-2091	-2113	-2136	-2121	-2105	-2186
00000648	-2523	+1999	+2681	+2740	+1518	+117	-1541	-2639
00000650	-2457	-2465	-2474	-2466	-2459	-2498	-2536	-2303
00000658	-2070	-995	+81	-76	+24	+35	+47	-150
00000660	-2394	-2422	-2450	-1806	+117	+85	+53	+21

00000668	-11	-11	-11	-11	-11	-11	-11	-107
00000670	-203	-404	-606	-615	-625	-610	-596	-693
00000678	-791	-757	-1491	-2401	-2287	-2303	-2319	-2319
00000680	-2044	-2067	-2090	-2113	-2137	-2116	-2095	-2074
00000688	-2054	+2923	+219	-1748	-2692	-2563	-2435	-2114
00000690	-2306	-2193	-2080	-2159	-2239	-2298	-2357	-2320
00000698	-2284	-2432	-2580	-1544	+4	-16	-36	-280
000006A0	-2572	-2302	-2544	-994	+43	+64	+86	+44
000006A8	+2	-4	-10	-16	-22	-28	-34	-104
000006B0	-174	-186	-198	-178	-158	-330	-502	-674
000006B8	-846	-722	-2134	-2234	-2334	-2302	-2270	-2270
000006C0	-2042	-2065	-2089	-2112	-2137	-2159	-2180	-2154
000006C8	-2129	-2458	-2532	-2604	-2166	-2218	-2272	-2293
000006D0	-2315	-2000	-2198	-2219	-2242	-2322	-2401	-2385
000006D8	-2370	-2285	-2201	-2452	-2704	-1411	+137	-1402
000006E0	-2174	-2502	-2830	+250	+0	+28	+55	+35
000006E8	+15	+3	-9	-21	-33	-45	-57	-101
000006F0	-145	-175	-206	-220	-235	-177	-120	-414
000006F8	-709	-191	-2489	-2547	-2349	-2349	-2349	-2349
00000700	-2040	-2064	-2089	-2113	-2138	-2202	-2267	-2235
00000708	-2204	-2207	-2210	-2181	-2152	-2131	-2110	-2217
00000710	-1812	-1552	-2317	-2025	-1734	-1578	-1423	-1939
00000718	-2456	-2395	-2334	-2081	-2340	-2551	-2250	-2013
00000720	-2288	-2446	-2093	-43	-42	-8	+25	+26
00000728	+28 <b>-</b> 116	+10	-8	-26	-44	-62	-80	-98
00000730 00000738	-116	-165 -940	-214 -1820	-263 -2348	-312 -2364	-281 -2396	-250 -2428	-155 -2428
00000738	-2038	-2058	-2079	-2340	-2304	-2123	-2420	-2420
00000740	-2191	-2056	-1940	-1910	-1882	-2123	-2327	-2149
00000748	-1717	-1485	-2022	-1759	-1497	-1242	-2327 -987	-716
00000750	-446	-1226	-2007	-2723	-2160	-2330	-2245	-2175
00000750	-2362	-2338	-1034	+109	-28	-19	-10	+15
00000768	+41	+19	-3	-25	-47	-89	-131	-141
00000770	-151	-208	-266	-355	-445	-458	-472	-405
00000778	-83	-1135	-1163	-1895	-2371	-2387	-2403	-2403
00000780	-2036	-2053	-2071	-2089	-2107	-2044	-1982	-2080
00000788	-1666	-1668	-1671	-1897	-2124	-2590	-2545	-2083
00000790	-1622	-1419	-1729	-1495	-1261	-1162	-1064	-774
00000798	-484	-314	-144	-806	-2492	-2366	-2240	-2338
000007A0	-2436	-2486	-489	+4	-15	-30	-45	+4
000007A8	+54	+28	+2	-24	-50	-116	-182	-184
000007B0	-186	-252	-318	-448	-578	-636	-694	-656
000007B8	-106	-2098	-2042	-2210	-2378	-2378	-2378	-2378
000007C0	-2034	-2047	-2062	-2076	-2091	-2093	-2096	-1650
000007C8	-1461	-1687	-1913	-2155	-2398	-2676	-2442	-2016
000007D0	-1591	-1448	-1563	-1341	-1120	-986	-853	-623
000007D8	-394	-265	-137	+200	+24	-1554	-2363	-2324
000007E0	-2286	-2122	-2727	-1220	+31	+136	-15	+25
000007E8	+67	+37	+7	-7	-21	-111	-201	-211
000007F0	-221	-295	-370	-460	-551	-509	-468	-634
000007F8	-545	-2805	-2249	-2301	-2353	-2353	-2353	-2353
00000800	-2032	-2043	-2054	-2065	-2076	-2143	-2210	-1477
80800000	-1768	-1962	-2156	-2414	-2672	-2762	-2340	-1950
00000810	-1560	-1479	-1398	-1189	-980	-811	-642	-473
00000818	-304	-217	-130	-75	-20	+27	-2486	-2311
00000820	-2136	-2527	-2406	-2445	-2484	-979	+14	+47
00000828	+80	+46	+12	+10	+8	-106	-220	-238
00000830	-256	-339	-422	-473	-524	-639	-754	-1637
00000838	-2520	-2232	-2456	-2392	-2328	-2328	-2328	-2328

00000840	-2012	-2030	-2049	-2052	-2055	-2191	-2073	-1585
00000848	-1867	-2081	-2296	-2526	-2757	-2653	-2294	-1886
00000850	-1479	-1380	-1282	-1087	-893	-748	-604	-491
00000858	-379	-243	-109	-181	+1	-606	-2493	-2283
00000860	-2331	-2481	-2376	-2413	-2452	-2308	-2421	-1350
00000868	-278	-124	+30	+88	+145	+127	+109	+27
00000870	-56	-278	-501	-1107	-1714	-2162	-2612	-2532
00000878	-2453	-2297	-2397	-2369	-2341	-2341	-2341	-2341
00000880	-1992	-2018	-2045	-2040	-2035	-2241	-1936	-1695
00000888	-1966	-2201	-2436	-2639	-2842	-2545	-2248	-1823
00000890	-1398	-1282	-1166	-986	-806	-686	-566	-510
00000898 000008A0	-454 -2526	-271 -388	-88 -2346	-289 -2383	+22 <b>-</b> 2421	-1239 -2358	-2500 -2296	-2257 -2490
000008A0	-2526	-2342	-2001	-2363 -1627	-1254	-2336 -1176	-1099	-1501
000008A8	-1904	-2342	-2628	-2510	-2393	-2407	-2422	-2404
000008B8	-2386	-2362	-2338	-2316	-2354	-2354	-2354	-2354
000008C0	-1972	-2006	-2040	-2043	-2046	-2194	-1831	-1835
000008C8	-2097	-2336	-2576	-2735	-2895	-2564	-2234	-1839
000000000	-1445	-1279	-1114	-916	-719	-623	-528	-528
000008D8	-529	-425	-323	-59	-53	-2527	-2443	-2517
000008E0	-2081	+170	-140	-1312	-2485	-2440	-2395	-2382
000008E8	-2370	-2400	-2431	-2509	-2589	-2559	-2530	-2500
000008F0	-2472	-2429	-2387	-2489	-2335	-2939	-2008	-1331
000008F8	-2447	-2395	-2343	-2355	-2367	-2367	-2367	-2367
00000900	-1952	-1994	-2037	-2047	-2058	-2148	-1727	-1977
00000908	-2228	-2472	-2716	-2832	-2948	-2584	-2220	-1856
00000910	-1492	-1277	-1062	-847	-632	-561	-490	-547
00000918	-604	-581	-558	-343	-1152	-2281	-2386	-2523
00000920	-1124	-40	+19	+15	+10	-1242	-2495	-2531
00000928	-2568	-2459	-2350	-2369	-2388	-2407	-2426	-2477
00000930	-2528	-2593	-2659	-2212	-1254	+369	+967	-1026
00000938	-2508	-2428	-2348	-2364	-2380	-2380	-2380	-2380
00000940	-1948	-1996	-2044	-2060	-2077	-1957	-1837	-2069
00000948	-2303	-2545	-2788	-2918	-3049	-2873	-2442	-2026
00000950	-1611 -743	-1374 -847	-1138 -953	-965 -2017	-793	-732	-672 -2313	-707 -2327
00000958 00000960	-743 -295	+99	-955 -19	+23	-2059 +65	-2441 +26	-2313 -13	-2327 -629
00000968	-1246	-1795	-2345	-2509	-2675	-2540	-2406	-1887
00000970	-1368	-467	+434	+439	+699	+1162	+856	-2695
00000978	-2409	-2413	-2417	-2389	-2361	-2361	-2361	-2361
00000980	-1944	-1998	-2052	-2074	-2097	-1767	-1949	-2163
00000988	-2378	-2619	-2860	-3005	-3150	-3163	-2664	-2197
00000990	-1730	-1472	-1214	-1084	-954	-904	-854	-868
00000998	-882	-859	-836	-877	-1942	-2091	-2240	-2389
000009A0	+22	-18	-57	+32	+121	+14	-93	-9
000009A8	+76	+149	+221	+166	+110	+143	+175	+239
000009B0	+304	+379	+455	+530	+605	+676	+235	-2573
000009B8	-2310	-2398	-2486	-2414	-2342	-2342	-2342	-2342
000009C0	-1940	-2000	-2060	-2072	-2084	-1640	-1964	-2144
000009C8	-2325	-2532	-2740	-2899	-3059	-3052	-2790	-2319
000009D0	-1849	-1569	-1290	-1202	-1115	-1075	-1036	-1028
000009D8	-1021	-1077	-1135	-503	-2689	-2395	-2359	-1553
000009E0	+19	-6	-30	+25	+80	+34	-12	+37
000009E8	+86	+124	+162	+137	+111	+137	+163	+237
000009F0	+312	+393	+475	+525	+574	+654	-803	-2466
000009F8	-2339 -1936	-2383 -2002	-2427	-2375	-2323	-2323	-2323	-2323
00000A00	- I Y 1 h	ーノロロン	-2068	-2070	-2072	-1514	-1980	-2126
00000700				_2704		-2012	_2016	
00000A08 00000A10	-2272 -1968	-2446 -1667	-2620 -1366	-2794 -1321	-2968 -1276	-2942 -1247	-2916 -1218	-2442 -1189

00000A18	-1160	-1041	-922	-1411	-2412	-2189	-2478	-719
00000A20	+16	+6	-4	+18	+40	+54	+68	+82
00000A28	+96	+100	+104	+108	+112	+132	+152	+236
00000A30	+320	+408	+496	+520	+544	+632	-1840	-2360
00000A38	-2368	-2368	-2368	-2336	-2304	-2304	-2304	-2304
00000A40	-1898	-1921	-1944	-2111	-1766	-1551	-1848	-1985
00000A48	-2122	-2318	-2515	-2664	-2813	-3074	-3079	-2828
00000A50	-2321	-2024	-1729	-1608	-1489	-1457	-1425	-1393
00000A58	-1362	-1246	-1131	-1879	-2372	-2532	-2693	+331
00000A60	+25	+40	+55	+54	+54	+71	+88	+105
00000A68	+123	+151	+180	+208	+237	+83	-70	+48
00000A70	+167	+248	+329	+346	+363	+733	-2738	-2577
00000A78	-2416	-2395	-2374	-2353	-2332	-2332	-2332	-2332
08A00000	-1860	-1840	-1820	-2152	-1460	-1588	-1716	-1844
88A00000	-1972	-2191	-2411	-2535	-2659	-2950	-2730	-2958
00000A90	-2674	-2383	-2092	-1897	-1703	-1668	-1633	-1598
00000A98	-1564	-1452	-1340	-2348	-2333	-2365	-1885	-157
0AA00000	+34	+74	+115	+91	+68	+88	+109	+129
00000AA8	+150	+203	+256	+309	+362	+291	+220	+117
00000AB0	+14	+88	+162	+172	+183	-702	-2612	-2282
00000AB8 00000AC0	-2464	-2422	-2380	-2370	-2360 1314	-2360	-2360 1712	-2360
	-2110	-1967	-1824 -2242	-1953	-1314	-1513	-1712	-1815
00000AC8	-1918 -2707	-2207 -2692	-2242 -2679	-2453 -2409	-2408	-2602 -2054	-2541 -1968	-2752 -1867
00000AD0	-2707 -1766	-2692 -1721	-2679 -1677	-2409 -2369	-2140 -2293			
00000AD8 00000AE0	+75	+92			+82	-2516	-948 +129	-53 +152
00000AE0	+177	+222	+110 +268	+95 +313	+359	+105 +354	+350	+441
00000AE0	+533	+472	+411	+414	+674	-1689	-2518	-2339
00000AF0	-2416	-2401	-2386	-2387	-2388	-2388	-2388	-2388
00000RF0	-1848	-1838	-1828	-1754	-1168	-1438	-1708	-1786
00000B08	-1864	-2225	-2075	-2372	-2158	-2255	-2353	-2546
00000B10	-2740	-2747	-2755	-2666	-2578	-2441	-2305	-2136
00000B18	-1968	-1991	-2015	-2390	-2254	-2669	-13	+51
00000B20	+116	+111	+106	+101	+96	+123	+150	+177
00000B28	+204	+242	+280	+318	+356	+418	+480	+510
00000B30	+540	+600	+661	+657	+1166	-2677	-2425	-2396
00000B38	-2368	-2380	-2392	-2404	-2416	-2416	-2416	-2416
00000B40	-1882	-1711	-1796	-1369	-1198	-1419	-1640	-1749
00000B48	-1858	-1977	-1842	-2058	-2019	-2113	-2207	-2366
00000B50	-2525	-2478	-2689	-2836	-2983	-2759	-2536	-2393
00000B58	-2250	-2194	-2139	-2357	-2318	-2018	+72	+113
00000B60	+157	+150	+145	+139	+134	+159	+186	+212
00000B68	+239	+273	+308	+342	+377	+439	+502	+548
00000B70	+595	+632	+669	+931	+170	-2666	-2430	-2403
00000B78	-2376	-2385	-2394	-2403	-2412	-2412	-2412	-2412
00000B80	-1916	-1840	-2276	-1240	-1228	-1400	-1572	-1712
00000B88	-1852	-1731	-1610	-1745	-1881	-1972	-2063	-2186
00000B90	-2310	-2211	-2625	-2751	-2877	-2822	-2768	-2650
00000B98	-2532	-2398	-2265	-2324	-2383	-1369	+156	+177
00000BA0	+198	+191	+185	+178	+172	+197	+223	+248
00000BA8	+274	+305	+336	+367	+398	+461	+524	+587
00000BB0	+650	+664	+679	+1206	-827	-2656	-2437	-2410
00000BB8	-2384	-2390	-2396	-2402	-2408	-2408	-2408	-2408
00000BC0	-1950	-1953	-1956	-1063	-1194	-1317	-1440	-1435
00000BC8	-1430	-1499	-1314	-1431	-1550	-1638	-1726	-1798
00000BD0	-1871	-1927	-2240	-2409	-2578	-2597	-2616	-2731
00000BD8	-2846	-2554	-2262	-2259	-2511	-527	+176	+207
00000BE0	+239	+231	+224	+217	+210	+234	+259	+284
00000BE8	+309	+336	+364	+391	+419	+482	+546	+609

00000BF0	+673	+744	+816	+936	-2015	-2485	-2187	-2289
00000BF8	-2392	-2395	-2398	-2401	-2404	-2404	-2404	-2404
00000C00	-1984	-2066	-1636	-886	-1160	-1234	-1308	-1414
00000C08	-1520	-2037	-2042	-1887	-1732	-1817	-1902	-1923
00000C10	-1944	-1900	-1856	-2068	-2280	-2372	-2464	-2556
00000C18	-2648	-2454	-2260	-2194	-2640	+314	+196	+238
00000C20	+280	+272	+264	+256	+248	+272	+296	+320
00000C28	+344	+368	+392	+416	+440	+504	+568	+632
00000C30	+696	+825	+954	+923	-2692	-2315	-2450	-2425
00000C38	-2400	-2400	-2400	-2400	-2400	-2400	-2400	-2400
00000C40	-2252	-1953	-1142	-1035	-1441	-1826	-2211	-2244
00000C48	-2278	-2220	-1908	-1914	-1922	-2001	-2336	-2095
00000C50	-2111	-2171	-2231	-2131	-2031	-2143	-2255	-2303
00000C58	-2352	-2306	-2260	-2359	-1689	+442	+269	+305
00000C60	+341	+333	+325	+317	+309	+329	+349	+369
00000C68	+389	+415	+441	+468	+494	+536	+579	+669
00000C70	+760	+797	+1091	-248	-2610	-2406	-2459	-2431
00000C78 00000C80	-2404 -2008	-2400 -2096	-2396 -1673	-2392 -1953	-2388 -2234	-2388 -2162	-2388 -2091	-2388 -2051
00000C88	-2008	-2096 -2149	-2286	-2199	-2234	-1930	-2091 -2259	-2011
00000C88	-2012 -2278	-2149 -2186	-2200	-2199 -2194	-2113 -2295	-1930	-2239	-2012 -2051
00000C98	-2056	-2158	-2094	-2524	-2293 -739	+570	+343	+372
00000C30	+402	+394	+386	+378	+370	+386	+402	+418
00000CA8	+434	+462	+491	+520	+549	+569	+590	+707
00000CH0	+824	+770	+1228	-1418	-2528	-2498	-2468	-2438
00000CB8	-2408	-2400	-2392	-2384	-2376	-2376	-2376	-2376
00000CC0	-1988	-2191	-2139	-2150	-2163	-2130	-2098	-2081
00000CC8	-2066	-2140	-2216	-2179	-2143	-2066	-2245	-2137
00000CD0	-2285	-2233	-2181	-2225	-2270	-2326	-2382	-2166
00000CD8	-1952	-2250	-2549	-2465	+180	+394	+352	+407
00000CE0	+463	+455	+447	+423	+399	+523	+391	+547
00000CE8	+447	+493	+540	+572	+603	+633	+665	+792
00000CF0	+920	+1094	+1269	-2764	-2446	-2429	-2413	-2412
00000CF8	-2412	-2400	-2388	-2376	-2364	-2364	-2364	-2364
00000D00	-1968	-2031	-2094	-2093	-2092	-2099	-2106	-2113
80000000	-2120	-2133	-2147	-2160	-2174	-2203	-2233	-2262
00000D10	-2292	-2280	-2269	-2257	-2246	-2226	-2207	-2283
00000D18	-2360	-2343	-2327	-2406	+586	-38	+363	+443
00000D20	+524	+516	+508	+468	+428	+660	+380	+676
00000D28	+460	+525	+591	+624	+658	+699	+741	+878
00000D30	+1016	+907	+286	-2575	-2364	-2361	-2358	-2387
00000D38	-2416	-2400	-2384	-2368	-2352	-2352	-2352	-2352
00000D40	-2020	-2071	-2124	-2080	-2037	-2062	-2089	-2115
00000D48	-2142	-2152	-2164	-2176	-2188	-2211	-2235	-2259
00000D50	-2283	-2275	-2267	-2260	-2253	-2249	-2246	-2290
00000D58	-2336	-2337	-2339	-1205	-71	-16	+296	+496
00000D60	+441	+469	+497	+381	+521	+635	+493	+735
00000D68	+465	+544	+624	+640	+656	+747	+839	+899
00000D70	+960	+1115	-1033	-2493	-2418	-2378	-2339	-2379
00000D78	-2420	-2408	-2396	-2384	-2372	-2372	-2372	-2372
08D0000	-2072	-2113	-2155	-2068	-1982	-2027	-2073	-2118
00000D88	-2164	-2173	-2183	-2193	-2203	-2220	-2238	-2256
00000D90	-2274 -2312	-2270 -2332	-2267 -2352	-2264 -2052	-2261 -729	-2273	-2286	-2299 +550
00000D98	-2312 +350	-2332	-2352 +496	-2052 +204	-729 +614	+7 +610	+230	+550 +704
00000DA0 00000DA8	+358 +470	+422 +564	+486 +658	+294 +656	+614 +655	+610 +797	+606 +939	+794 +921
00000DA8	+470	+1324	-2352	-2412	-2472	+797 -2396	-2320	+921 <b>-</b> 2372
00000DB0	-2424	-2416	-2352 -2408	-2412 -2400	-2472 -2392	-2396 -2392	-2320 -2392	-2372 -2392
00000000								
00000DC0	-1996	-1930	-1865	-1960	-2055	-2087	-2120	-2153

00000DC8	-2186	-2193	-2201	-2209	-2217	-2229	-2241	-2253
00000DD0	-2265	-2265	-2266	-2267	-2268	-2280	-2294	-2306
00000DD8	-2320	-2342	-2365	-2707	-2538	-1491	-188	+172
00000DE0	+275	+327	+379	+287	+451	+505	+559	+773
00000DE8	+475	+551	+628	+512	+653	+909	+654	+1007
00000DF0	+1104	-739	-2583	-2506	-2430	-2397	-2365	-2396
00000DF8	-2428	-2424	-2420	-2416	-2412	-2412	-2412	-2412
00000E00	-1920	-2004	-2088	-2108	-2128	-2148	-2168	-2188
00000E08	-2208	-2214	-2220	-2226	-2232	-2238	-2244	-2250
00000E10	-2256	-2261	-2266	-2271	-2276	-2289	-2302	-2315
00000E18	-2328	-2353	-2378	-2339	-2300	-2477	-1630	-719
00000E20	+192	+232	+272	+280	+288	+400	+512	+752
00000E28	+480	+539	+598	+369	+652	+767	-142	-1211
00000E30	-2792	-2547	-2302	-2345	-2388	-2399	-2410	-2421
00000E38	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000E40	-2024	-2070	-2116	-2130	-2144	-2164	-2184	-2204
00000E48	-2224	-2228	-2232	-2236	-2240	-2244	-2248	-2252
00000E50	-2256	-2262	-2270	-2276	-2284	-2296	-2310	-2322
00000E58	-2336	-2319	-2304	-2287	-2272	-2559	-2336	-1855
00000E60	-1376	-2264	-1104	-520	+64	+384	+704	+704
00000E68	+192	-44	-280	-1236	-1936	-3018	-2564	-2349
00000E70 00000E78	-2392 -2432	-2390 -2432	-2390 -2432	-2388 -2432	-2388 -2432	-2398 -2432	-2410 -2432	-2420
00000E78	-2432 -2128	-2432 -2136	-2432 -2144	-2432 -2152	-2432 -2160	-2432 -2180	-2432 -2200	-2432 -2220
00000E80	-2128 -2240	-2136	-2144	-2152 -2246	-2160	-2180 -2250	-2250 -2252	-2254
00000E88	-2240 -2256	-2242 -2265	-2244	-2246	-2246 -2292	-2230 -2305	-2232 -2318	-2331
00000E90	-2344	-2283 -2287	-2274	-2203 -2237	-2292	-2303 -2387	-2510 -2530	-2331 -2481
00000E98	-2432	-2456	-2480	-2600	-2720	-2448	-2176	-1904
00000EA0	-2144	-2419	-2694	-2585	-2476	-2451	-2426	-2465
00000ER0	-2504	-2491	-2478	-2433	-2388	-2399	-2410	-2421
00000EB0	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000EC0	-2104	-2122	-2140	-2158	-2176	-2196	-2216	-2236
00000EC8	-2256	-2256	-2256	-2256	-2256	-2256	-2256	-2256
00000ED0	-2256	-2266	-2278	-2288	-2300	-2312	-2326	-2338
00000ED8	-2352	-2317	-2284	-2281	-2280	-2357	-2436	-2417
00000EE0	-2400	-2408	-2416	-2360	-2304	-2480	-864	-1648
00000EE8	-1408	-1225	-2580	-2509	-2440	-2427	-2416	-2435
00000EF0	-2456	-2446	-2438	-2412	-2388	-2398	-2410	-2420
00000EF8	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000F00	-2080	-2108	-2136	-2164	-2192	-2212	-2232	-2252
00000F08	-2272	-2270	-2268	-2266	-2264	-2262	-2260	-2258
00000F10	-2256	-2269	-2282	-2295	-2308	-2321	-2334	-2347
00000F18	-2360	-2349	-2338	-2327	-2316	-2329	-2342	-2355
00000F20	-2368	-2360	-2352	-2376	-2400	-2256	-2624	-1392
00000F28	-1696	-2593	-2466	-2435	-2404	-2405	-2406	-2407
00000F30	-2408	-2403	-2398	-2393	-2388	-2399	-2410	-2421
00000F38	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000F40	-2080	-2108	-2136	-2164	-2192	-2212	-2232	-2252
00000F48	-2272	-2270	-2268	-2266	-2264	-2262	-2260	-2258
00000F50	-2256	-2268	-2282	-2294	-2308	-2320	-2334	-2346
00000F58	-2360	-2348	-2338	-2326	-2316	-2328	-2342	-2354
00000F60	-2368	-2360	-2352	-2360	-2368	-2352	-2592	-2192
00000F68	-2560	-2768	-2466	-2434	-2404	-2404	-2406	-2406
00000F70	-2408	-2402	-2398	-2392	-2388	-2398	-2410	-2420
00000F78	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000F80	-2080	-2108	-2136	-2164	-2192	-2212	-2232	-2252
00000F88	-2272	-2270	-2268	-2266	-2264	-2262	-2260	-2258
00000F90	-2256	-2269	-2282	-2295	-2308	-2321	-2334	-2347
00000F98	-2360	-2349	-2338	-2327	-2316	-2329	-2342	-2355

00000FA0	-2368	-2360	-2352	-2344	-2336	-2448	-2560	-2480
00000FA8	-2400	-2433	-2466	-2435	-2404	-2405	-2406	-2407
00000FB0	-2408	-2403	-2398	-2393	-2388	-2399	-2410	-2421
00000FB8	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432
00000FC0	-2080	-2108	-2136	-2164	-2192	-2212	-2232	-2252
00000FC8	-2272	-2270	-2268	-2266	-2264	-2262	-2260	-2258
00000FD0	-2256	-2268	-2282	-2294	-2308	-2320	-2334	-2346
00000FD8	-2360	-2348	-2338	-2326	-2316	-2328	-2342	-2354
00000FE0	-2368	-2360	-2352	-2344	-2336	-2448	-2560	-2480
00000FE8	-2400	-2432	-2466	-2434	-2404	-2404	-2406	-2406
00000FF0	-2408	-2402	-2398	-2392	-2388	-2398	-2410	-2420
00000FF8	-2432	-2432	-2432	-2432	-2432	-2432	-2432	-2432

#### 4.2.4.4 Inverse Color Conversion

The following is a dump of the decoded 64x64 XRGB image obtained by using the <u>Color Conversion transform matrix (section 3.1.8.2.5)</u> on the reconstructed Y, Cb, and Cr component data. The Y, Cb, and Cr component data, presented in earlier sections, is in 11.5 fixed-point representation. This should be converted to floating-point representation before using the transform matrix given in section <u>3.1.8.2.5</u>. Alternatively, the transform matrix can be appropriately modified to handle fixed-point data.

```
00000000 00229cdf 00249de0 00259fe2 002ca5e8 00229cdf 00229ce0 00239de0 00229ce0
00000008 00229cdf 00229cdf 00239ce0 00249ce0 00249ce0 00219ce3 001e9ce6 00209ae2
00000010 002299dd 002199de 00209adf 00209ae0 001f9be0 001e9ae0 001d99e0 001c98e0
00000018 001b97df 001e96dc 002194d9 001f93dd 001d93e0 001b94dc 001895d8 001c92db
00000020 00208fde 001b91de 001693df 001793df 001992df 001891df 00178fdf 00178edf
00000028 00168dde 00158cdd 00148cdc 00128cda 00118cd9 00118bd9 00128ada 001289da
00000030 001288db 001187da 001186da 001085da 000f85d9 000f84d9 000e83d9 000d82d8
00000038 000d82d8 000d81d8 000d80d7 000d7fd7 000d7ed6 000d7ed6 000d7ed6 000d7ed6
00000040 00259fe1 0027a1e2 0029a2e3 002ba4e6 00249fe1 00249fe1 00249fe1 00249ee1
00000048 00239ee1 00249ee1 00249ee1 00259de1 00259de2 00249de2 00229de2 00229ce1
00000050 00229bdf 00219ce0 00209ce1 00209ce2 00209ce2 00209ae0 002199de 001f99df
00000058 001d98e0 001e97e0 001f97e0 001d96df 001c95de 001c94e0 001c94e1 001d93e1
00000060 001d92e0 001b93de 001a94dc 001a93de 001a93e0 001992e0 001891df 00188fdf
00000068 00178edf 00168ede 00158edd 00148ddc 00138ddb 00138cdb 00138bdb 00128adb
00000070 001289db 001288db 001187db 001186db 001085db 000f84da 000e83d9 000e83d9
00000078 000e83d9 000e82d9 000e81d8 000e80d8 000d7fd7 000d7fd7 000d7fd7 000d7fd7
00000080 0027a3e3 002aa4e3 002ea6e3 002aa4e3 0026a2e3 0026a1e3 0025a1e3 0025a0e3
00000088 0025a0e3 0025a0e3 00259fe3 00269fe3 00269ee4 00279ee1 00279edf 00259ee0
00000090 00239ee1 00219ee2 00209ee4 00209de4 00219de3 00229be0 002499dc 002299de
00000098 001f98e0 001d99e4 001b9ae7 001c98e2 001c96dc 001e94e3 002092ea 001d94e6
0000000A0 001a96e2 001c96de 001d95da 001c94de 001b94e1 001a93e0 001a92e0 001991e0
0000000A8 001890e0 001790df 00178fde 00168fde 00158edd 00148ddd 00138cdc 00138bdc
000000B0 00128adc 001289dc 001188dc 001187dd 001086dd 000f85db 000e83d9 000e84da
000000B8 000f84da 000e83da 000e82d9 000e81d9 000e80d8 000e80d8 000e80d8 000e80d8
000000C0 002aa7e5 002da7e4 0031a8e3 002ca6e3 0027a4e4 0027a3e4 0027a3e4 0027a3e4
000000C8 0026a2e4 0026a2e4 0027a1e5 0027a0e5 0027a0e6 0026a0e5 0025a0e4 00259fe4
000000D0 00259ee3 00239ee5 00229fe6 00229fe5 00229fe4 0013a5e6 001b9fe8 0016a0e8
000000D8 0011a0e7 00129fef 00139ef7 001b99ec 00179ae2 00149ce4 001d98e5 001c97e6
000000E0 001b96e7 001c98dc 001d97df 001c96e1 001c94e2 001b94e1 001b93e1 001a93e0
000000E8 001a92e0 001991e0 001890e0 001790df 00168fdf 00158ede 00158dde 00148cdd
000000F0 00138bdc 00128add 001289dd 001188de 001187de 000f85dc 000d83da 000f85db
000000F8 001086db 000f84db 000f83da 000e82da 000e81da 000e81da 000e81da 000e81da
00000100 002caae7 0030aae5 0034abe3 002ea8e4 0029a6e5 0028a6e5 0028a5e5 0028a5e5
00000108 0028a5e6 0028a4e6 0028a3e7 0028a2e7 0028a1e8 0025a2e9 0023a3ea 0025a0e8
00000110 00279ee6 00259fe7 0023a0e9 0018a4f5 000ea7ff 001ba6de 00558ebb 006f839c
```

00000118	0089797e	008d797c	00917979	007f7b94	005687af	00229bd6	0004a4fd	00109df4
							001c94e2	
							00158edf	
							000d83da	
							000e81db	
							0026a6e8	
							002ca5e2	
							002ca5e2	
							00f54823	
							00134623 001898e4	
							001696e4	
							000f85db	
							000e83db	
							0024a7ea	
							0020adf6	
							00fc6222	
							00ff531f	
							00159be7	
							001691e0	
							001186dd	
							000e84dc	
							0029abe9	
							00946a5f	
							00f8712b	
							00fb652a	
							00199be4	
							001692e1	
000001F0	001590df	001591e1	001591e3	00138fe1	00108ce0	00128be0	00158ae0	00168de2
000001F8	000f89dd	000f88dd	000f88dd	000f86dd	000f85dc	000f85dc	000f85dc	000f85dc
00000200	005fc1e7	0057bee8	004fbbe9	004ebae6	004ebae3	0051b6ee	002eaee8	002eade6
00000208	002fabe5	002face7	002eade9	002eace7	002daae5	0015b2ff	00ec4310	00f15016
00000210	00f75d1c	00f87123	00f9862a	00f6882d	00f48b31	00f48532	00f47f33	00f78535
00000218	00fa8c37	00f88e39	00f7903a	00f88b38	00f98635	00f87e35	00f77635	00f76d34
00000220	00f76532	00f85e31	00f95730	00ff5125	00f65237	0003a5fd	001e9be1	001e98e3
00000228	001f96e5	001c97e2	001a97df	001896e1	001795e4	001794e3	001793e2	001692e1
00000230	001692e0	001693e2	001794e4	001391e2	000f8ee0	00148ee1	00198ee3	00148ce1
00000238	000f8bde	000f8ade	000f89de	000f88dd	000f86dd	000f86dd	000f86dd	000f86dd
00000240	003cb6ee	0036b4ef	0030b2f0	0030blee	002fb1ec	0038b0ef	002eaee9	002faee8
00000248	0031ade6	002fafe8	002eb1ea	0031adec	0029afee	0030aac8	00ff3d05	00fa501a
00000250	00f96021	00f87428	00f7882f	00fa9638	00f59b38	00f5973b	00f6923e	00f89440
00000258	00fa9742	00fa9a44	00fa9d46	00f99845	00f89444	00f98d43	00fa8641	00f97d3f
00000260	00f9743d	00f77039	00f56d35	00ff6122	00bf6c63	00129eef	00229ae8	001c99ed
00000268	00179ce4	001498f0	001b94e1	001a96e2	001998e3	001897e4	001896e5	001895e4
00000270	001993e2	001792e1	001590df	001692e2	001793e5	001490e4	00128ee2	00118de3
00000278	00108de3	00118bde	001289d9	000f88e2	000c89dd	001085e0	000987e4	000987e4
00000280	0040b5e9	003bb4e9	0037b2ea	0037b2e9	0038b1e8	0033b0ea	002eaeeb	0030afe9
00000288	0033afe8	0030b2ea	002eb5ec	0034aff2	0025b4f7	008d7f86	00f64f00	00ed5c1e
00000290	00fa6326	00f7762d	00f58a35	00fea242	00f7ab3f	00f7a843	00f7a548	00f9a34a
00000298	00faa24c	00fba64f	00fcaa52	00f9a652	00f7a252	00fa9c50	00fd974e	00fc8d4b
000002A0	00fb8348	00f68341	00f1823a	00f5732c	00718cac	00179af0	002599ef	002697e9
000002A8	00269bc6	001696f1	001d91e3	001c96e3	001b9be3	001a99e6	001998e9	001b97e7
000002B0	001c95e5	001891df	00138dda	001992e2	001e98ea	001592e6	000b8de2	000e8ee5
000002B8	00108fe9	00128cdf	001489d4	000e88e6	00088cdc	001184e4	000488ec	000488ec
000002C0	003eb6ea	003bb5eb	0038b4eb	0038b4eb	0038b3eb	0035b2eb	0033b1ec	0034b1eb
000002C8	0035b1ea	0032b3e9	0030b5e9	0034b0f0	0023b6f8	00c56044	00f9540c	00f26322
							00f7b051	
							00fda95a	
00000200								
						00129ef4	002896f1	
000002E0	00f99551	00f7914b	00f68d45	00ff7e23	001ba5f0		002896f1 001897e7	00239fb1

000002F0	001a93e5	001993e3	001793e0	001c98e6	001a95e5	001692e5	00138fe5	00138ceb
000002F8	00138be3	000087e4	00007cf5	001a86d3	000d8cf1	00008fe2	000d85ea	000886f1
00000300	003cb7ec	003bb7ed	003ab6ed	0039b6ed	0038b5ed	0037b5ed	0037b4ed	0037b3ed
00000308	0036b3ec	0034b4e9	0031b5e5	0035b1ef	0021b8fa	00fd4203	00fc581e	00f86a26
00000310	00f47c2d	00f78431	00f98c36	00f8a041	00f6b54d	00fec05b	00f6bc5a	00f8ba5d
00000318	00fbb861	00fdbe65	00ffc469	00fbc16c	00f5bd70	00fabc6b	00febb66	00fab160
		00f89f55						
00000328	0069a90d	0062a406	005a981b	0034969b	000e99ff	001297f2	001695e4	001793e5
00000330	001892e5	001995e6	001a98e7	00209deb	001593df	001892e4	001a91e9	002095eb
		00d0f772						
00000340	003db9ed	003cb8ed	003bb8ed	003ab7ed	0039b7ed	0039b7ed	0039b6ed	003ab6ed
00000348	003ab6ed	0037b4ed	0034b2ec	0035abf3	006e96b3	00ff4601	00f86520	00f67329
		00f78b37						
00000358	00fac26e	00fac773	00facb77	00fbcb7b	00fccb7e	00fac87b	00f8c578	00f9bc72
00000360	00fbb46d	00f6b069	00feaa57	0094a0a5	0013a1f3	00219df0	00199eff	0071c124
00000368	0079b826	0072b21e	006aaa24	0067a125	00649a19	00419d72	001f9fcb	001994ff
00000370	001399f1	00199cf4	001ea0f8	001b9cff	001193f6	001293f1	001393ec	000083ff
00000378	0072cca0	00cbf982	00d0ffac	0079a046	00337700	003a7c03	000d8de2	000d8edb
00000380	003fbbee	003ebaed	003db9ed	003cb9ed	003bb8ed	003bb8ed	003cb9ee	003cb9ee
00000388	003db9ef	003ab4f1	0037aff3	0032b3fe	00b48f7d	00ff5907	00f37122	00f57c2b
00000390	00f68735	00f7923d	00f89d45	00f9ac50	00f9bb5a	00f9c465	00facd71	00facd76
00000398	00facd7b	00f7cf80	00f4d286	00fcd689	00ffd98c	00fbd48b	00f3cf8a	00f9c885
		00f5c27d						
		0082c427						
		00489b6d						
		00afe187						
		003fbcee						
		003fb4f0						
		00f89943						
		00fbd98e						
		00ffd285						
		0097d03a						
		0072ab25						
		00417c15						
		0041bdee 0039b9f0						
		0059b910 00f8a049						
		0016a049						
		00fdd899						
		00acdc4e						
		007bbc32						
		007bbc32						
		0043bfef						
		0037b9eb						
		00f6a64e						
		00feeaa6						
		00ffe5a3						
00000468	00c0e364	00bde165	00bae065	00b5de5d	00b0dc56	00aad74e	00a3d346	009bd043
00000470	0093cd3f	008cc93e	0084c63c	0081c139	007dbc36	008bc746	0089c245	0063a02c
00000478	0065aa2c	005ea42d	00509626	00a4cf98	00d9eadd	00b9ddff	00389ef4	00008fd4
00000480	0046c1ef	0044c0ef	0043bfef	0042beef	0040bdef	0042bced	0043baec	0040baf0
00000488	003dbaf4	0035b8e7	0017bdf7	00d97f50	00f79147	00f7a554	00ffdbba	00f8a24d
00000490	00f3a549	00f5ad53	00f7b55e	00f9c16f	00fbcc7f	00f9d88a	00f8e595	00f8eda2
00000498	00f8f5ae	00fff3b2	00fff2b6	00fef5ae	00f4b659	00f9db93	$00 {\sf feffcd}$	00fbf6c1
000004A0	00f7edb6	00fff2ac	0013a4f7	0016a5f0	0018a5e8	0056b4cd	00f1f271	00d5ef84
		00cde77c						
		009dd749						
		0059a028						
000004C0	0048c3ef	0046c2ef	0045c1f0	0043c0f0	0042bff0	0042beee	0043bdec	0041bcef

000004C8	003fbcf2	002fc0fe	0036bdfc	00f54c00	00ff8a52	00faa65e	00fdc48e	00fbc185
000004D0	00f5ae50	00f7b65e	00f9be6c	00fac978	00fbd485	00fede98	00ffe8aa	00fdeeae
							00fdfcca	
							00eaf28c	
							00bfe36f	
							0084c33a	
							000993d8	
							0043bfed	
							00f9ad61	
							00fbe193	
00000518	00fbf5b5	00faf8c2	00f9fcce	00f9ecb7	00fae183	00fee290	00fbfac8	00fdf8d8
00000520	00fffccb	008bcedc	00189fee	0025a3ee	000b9dfb	00e8f6a5	00e4f1a6	00e4f0a6
00000528	00e4efa6	00e5flaa	00e6f2ad	00e3f1a6	00e0ef9e	00d7ec93	00cde987	00c8ea80
00000530	00c2eb78	00c1ea73	00c0e96e	00b1e360	00a3dd53	0094d247	0086c83b	0078bc35
00000538	0069b030	0062a52b	005b9b27	0057920a	000995fc	000d96e5	001091eb	001091eb
00000540	004ac5f0	0049c4f0	0047c3f1	0045c2f1	0044c1f2	0041c1f2	003fc1f2	003fbff1
00000548	003fbcf0	0032c3fe	00be7f6e	00fe6526	00f67b35	00f59a4d	00f8ab5c	00fbd0a0
00000550	00f7c783	00fec16b	00fdd17f	00fbdb87	00f9e590	00f8ed9a	00f7f4a5	00fbea9a
							00fcf1c3	
							00e6f2b1	
							00dbeea2	
							0088ca3e	
							001193f0	
							00119310 003bc4f6	
							00f8a958	
							00faeca7	
							00f7fdea	
							00e8f2bd	
							00e8f3bd	
							008bcc42	
000005B8	0073b935	006aac31	0060a510	00229687	000b91f1	000e93f3	001294f5	001294f5
000005C0	004cc6f1	004bc5f2	0049c5f2	0047c4f2	0046c4f2	0043c4f1	0040c4f0	0042c0f3
000005C8	0039c1f6	005eacca	00fb591e	00f36e31	00f88135	00fb923f	00fbaf5e	00ffc373
000005D0	00fde2ba	00ffcd75	00ffd372	00ffe584	00fff796	00fef4a2	00fdflae	00fff8c2
000005D8	00fcf8cd	00fef8d2	00fff9d6	00fef6e1	00fcf5dd	00fffbee	00fbfce8	00fffce0
000005E0	00b2e0e8	0019a4f0	0026abec	0016a8f6	00c2e4d8	00f9fac5	00eff6cb	00f0f7ce
000005E8	00f1f8d2	00f1f8d1	00f2f9d1	00f1f9cd	00f1f9ca	00f2fbca	00f4fdca	00e7f8b6
000005F0	00daf3a2	00cbef8a	00bcec71	00b0e661	00a5e151	009ad949	008fd240	0083c73b
000005F8	0077bc35	006ab31d	005ea905	00138dea	001193ef	001093f0	000f93f0	000f93f0
00000600	004dc6f2	004cc6f2	004ac5f3	0048c5f3	0047c5f3	0046c4ef	0046c4eb	0048c0f3
00000608	0034c7fb	00989591	00fc6428	00f1773b	00fc8432	00ff9135	00ffb564	00ffbe5a
							00daebc1	
							00fffae7	
							00f6fad9	
							00f0f7c8	
							0094d83f	
							000c91eb	
							000C91eb	
							0063c1cd	
							0025b7ff	
							00fafce2	
							00fbfce3	
							00ebf4be	
							0098d73a	
							000f92e6	
							0045c0f3	
00000688	004ac4eb	00ff521f	00a79a92	0051b7e6	0028c7ff	002cc4f9	0031c1f1	003fbbf0
00000690	0037c0ef	0039b9f0	003bb3f1	0038b5f4	0036b7f7	0032b9f0	002fbbe8	002fb8eb
00000698	002fb5ed	0020acf3	0010a3fa	0070c9f3	00f5f9df	00 f6fbde	00f6fdde	00d8ebe4

00	0006A0	0011a5ee	002db2f5	0014a5f8	00a5e2ec	00fffff8	00fffef3	00fffded	00fcfde6
00	0006A8	00f8fce0	00f7fcde	00f6fcdd	00f6fcd8	00f5fdd3	00edf7c4	00e5f1b4	00e5f5b8
0.0	0006B0	00e4f9bb	00ecfed2	00f3ffe9	00edfedb	00e8f9cd	00caef89	009cd636	0084c72e
			006cb315						
			0050caf4						
			0041d4f9						
			0049bdf7						
			0030b5f2						
			001dafec						
			00f9fde1						
00	0006F0	00f1fde9	00ebfdd3	00e6fdbe	00e0f8ba	00daf2b7	00eafcd2	00f2fde6	00b7de8d
00	0006F8	0084c73d	009ab848	0014a1f9	000494f3	001094ef	001095ec	001095e9	001095e9
00	000700	0054ccf5	0051cbf4	004ecaf3	004cc9f2	0049c8f1	0048cbf5	0048cef9	0040c4f3
00	000708	0049cafc	0040c2f1	0047caf5	0046c7f4	0046c4f3	0039b5ee	002ca5e8	002eb1e1
00	000710	0056c1ea	006dc9e9	0037c2e5	0051caeb	006bd2f1	0074d1f5	007dcff9	0056c7f8
00	000718	001fafe8	0025b1ee	002cb3f4	003eb5f9	002bb3ee	001baff5	0032b5f0	003fb2f9
00	000720	0026a9f2	001faeeb	003fb8f4	00fcfff3	00ffffff	00ffffff	00fffefb	00fefff1
0.0	000728	00feffe6	00fbffe5	00f8fde3	00f5fdd7	00f3fecb	00f5fbeb	00f7feee	00f2fdde
			00e3f9b0						
			007fc679						
			0071c073						
			004dc5fc						
			0076cdef						
			009ae1ff						
			0026acf6						
			00fbfee4						
			00d9f49b						
00	000778	00dbe8b9	0096d4ff	008ed0fa	0042aeee	001095f1	001096f1	000f96f1	000f96f1
00	000780	0055cef5	0053ccf4	0050cbf4	004ecaf4	004cc8f4	0051caf7	0057cbfa	0045c0ea
00	000788	001a75c7	000058ad	00015bb4	00066fc0	000b84cd	000093ce	0011a7e0	003eb9e6
00	000790	006bcbeb	007ed1f6	006cd3f0	0082dbf4	0098e3f9	00a5ecf7	00b2f4f5	00c7f7f9
00	000798	00ddfafd	00f2ffff	00f8fff6	00bcebfe	0022b4f2	0029afff	002fb0f7	0029b1f2
00	0007A0	0023b1ee	001aa7fa	00cae6f4	00f7f8f4	00feffff	00fefff7	00feffed	00fcffeb
00	0007A8	00fbfae9	00fbfee3	00fbffdc	00fbffe9	00fbfff7	00f1fedd	00e7fbc3	00e0f6b4
00	0007B0	00d8f0a5	00ceec94	00c4e884	00b8e678	00ace36c	00a0df53	0094d455	0080bd41
00	0007B8	00d2e599	002ca1f4	0030a2f6	00209cf3	001096f1	001096f1	001096f1	001096f1
00	0007C0	0055cef4	0053cdf4	0051cbf5	0050cbf5	004ecaf6	004dc9f4	0054d0fa	002b86ce
			00045fb9						
			0083d9f5						
			00edfefb						
			0034b1e0						
			0054B1C0						
			00c5e97e						
			00009bf2						
			0054cdf5						
			000874cd						
									00dffdfc
									002ab1ee
			0025b9f7						
			00f8fada						
00	000830	00ccea95	00bce567	00abdb56	009fd344	0092cb33	0085c824	0079b46a	003a9eaf
00	000838	000c97ff	001994f9	000f9bee	00139af0	001699f3	001497f1	001295ef	001295ef
00	000840	0058d0f5	0056cef5	0053cdf4	0053ccf6	0052cbf8	0053d6fb	004fc8fc	00004cad
00	000848	00096fca	000b80d4	000588d5	000598db	0005a8e1	0018b6e6	003fc8f2	0063d3f3
00	000850	0086dff5	0091e4f7	009ce9fa	00aef0f9	00c0f7f9	$00 {\rm cbfafb}$	00d7fdfd	00defdfc
00	000858	00e6fefb	00f0fffe	00faffff	00f2fefb	00fefffd	00c6e9fb	001eb0ec	0030b4f6
00	000860	0030b7f8	0019a8f7	0026b0f0	0022aef3	001eabf5	0027aafa	001ca6f6	007dcdea
			00eaffb0						
			00b9e153						

00000878	00109cef	00189aee	00149ded	00159bf0	001599f2	001397f0	001195ee	001195ee
00000880	005ad1f6	0057cff5	0054cef4	0054cdf6	0053cbf8	004dd3f4	002c9add	00045ec1
00000888	000572c9	000683d2	000794dc	0008a2e2	0008b1e8	0028bfef	0048cef6	006bd8f8
00000890	008fe3fa	009be8fa	00a6edfb	00b7f3fb	00c7f9fa	00d0fbfc	00d9fdfd	00defefd
00000898	00e2fffc	00effffe	00fcffff	00ebfef7	00fffffe	008fd7f8	001eb0f1	002eb0f6
000008A0	0018abec	00e0f7fd	0024ade9	0023acf1	0021acf8	0026aef7	002cb0f6	001aa9f5
000008A8	0008a3f4	0022a7f9	004cc2f2	006dcdef	007ec9db	007fcac2	0081c6c6	0061bccb
000008B0	0041b3d0	0024a7e9	00089bff	00119dff	001a9fff	000f99e9	00149cf9	00159cf7
000008B8	00159cf5	00179df1	00199eed	00179cef	001599f1	001397ef	001195ed	001195ed
000008C0	005cd2f6	0059d0f5	0055cff3	0054cdf5	0053ccf8	0051d5f6	00167bcf	000467c6
000008C8	00067bcf	00068bd7	00059cdf	0008a9e5	000ab6eb	002bc4f1	004cd2f7	006ddbf9
000008D0	008ee5fa	009deafb	00 aceffb	00bdf5fb	00cefbfa	00d5fbfc	00dcfcfd	$00 {\tt dcfefd}$
000008D8	00ddfffd	00e4fffd	00eafffd	00fffffe	00ffffff	0027c0de	0026b5f6	001fb0f9
		00fff9ef						
		001aa3f2						
		0017a2f3						
		00149cf2						
		005bd2f5						
		000594dc						
		009fecfb						
		00d9fdfb						
		00ffffff						
		001aa7f3 000b9dfd						
		00119af4 005bd2f5						
		000296dd						
		000236dd						
		00c6f9ff						
		OOSSISSIS						
		0053bbe9						
		00b0d79a						
		00169ef7						
00000980	005ccff6	005bd2f6	005ad4f6	0052cdf2	005ad6fe	00298cd5	00026ccc	00027bd2
00000988	000189d8	000097df	0000a6e6	0000b2ed	0002bef4	0009c7f1	0035d5ff	0059ddfd
00000990	007ce5fb	0091eafd	00a6f0ff	00b1f2ff	00bbf5ff	00bef5fc	00c1f6f9	00c1f7f7
00000998	00c1f9f4	00c7fdfc	00cdffff	00c2f9f8	005acdf4	0039b1f3	0038baf5	002ab4f7
000009A0	00fcfbf8	00fdfeff	00feffff	00fffeff	OOfffcf6		005755	005-55
000009A8					OOTITCIO	00fdfef2	001/1166	UUICIIea
	00ffffe5	00ffffd8	$00 {\it ffffcb}$	00fffbf1				
		00ffffd8 00fdfc6c			00ffffdf	00fdfdc2	00f7ff88	00fbfe92
000009B0 000009B8	00ffff7f 00189aef	00fdfc6c 00129af2	00faf759 000c99f5	00f8f059 001199f3	00ffffdf 00f7e958 001599f2	00fdfdc2 00f7e359 001397f0	00f7ff88 00d0d368 001195ee	00fbfe92 000998ff 001195ee
000009B0 000009B8 000009C0	00ffff7f 00189aef 005fd2f9	00fdfc6c 00129af2 005cd3f8	00faf759 000c99f5 0059d4f6	00f8f059 001199f3 0058d3f8	00ffffdf 00f7e958 001599f2 005edaff	00fdfdc2 00f7e359 001397f0 001971cd	00f7ff88 00d0d368 001195ee 00026ecd	00fbfe92 000998ff 001195ee 00037bd3
000009B0 000009B8 000009C0 000009C8	00ffff7f 00189aef 005fd2f9 000488d9	00fdfc6c 00129af2 005cd3f8 000497e0	00faf759 000c99f5 0059d4f6 0005a6e6	00f8f059 001199f3 0058d3f8 0001ade7	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8	00fdfdc2 00f7e359 001397f0 001971cd 0007beea	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8
000009B0 000009B8 000009C0 000009C8 000009D0	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9
000009B0 000009B8 000009C0 000009C8 000009D0 000009D8	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4
000009B0 000009B8 000009C0 000009C8 000009D0 000009D8	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4
000009B0 000009B8 000009C0 000009C8 000009D0 000009B0 000009E8	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84
000009B0 000009B8 000009C0 000009C8 000009D0 000009B0 000009E0 000009E8	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0 00fbf67a	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc
000009B0 000009C0 000009C8 000009D0 000009D8 000009E0 000009E8 000009F0	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0 00fbf67a 00149bf1	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef
000009B0 000009C0 000009C8 000009D0 000009D8 000009E0 000009E8 000009F0 000009F8	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0 00fbf67a 00149bf1 005dd4f9	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4
000009B0 000009C0 000009C8 000009D0 000009B0 000009E0 000009E8 000009F0 000009F8 00000A00	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0 00fbf67a 00149bf1 005dd4f9 000996e0	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6 000ca5e7	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc
000009B0 000009C0 000009C8 000009D0 000009B8 000009E0 000009E8 000009F0 000009F8 00000A00 00000A08	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00ffffd0 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6 000ca5e7	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa
000009B0 000009C0 000009C8 000009D0 000009B8 000009E0 000009F0 000009F8 000000A00 00000A08 00000A10	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0
000009B0 000009C0 000009C8 000009D0 000009B8 000009E0 000009F0 000009F8 000000A00 00000A08 00000A10 00000A18	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc 00fefff2	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc 00fefff3	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9 00fefef2	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3 00fefef0	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb 003ebef7 00fefeea	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7 00fefee4	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0 00fefede
000009B0 000009C0 000009C8 000009D0 000009B8 000009E0 000009F0 000009F8 000000A00 00000A08 00000A10 00000A18 00000A20 00000A28	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc 00fefff2 00fefed8	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc 00fefff3	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb 00fdfff4	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9 00fefef2 00f6fea0	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3 00fffce	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb 003ebef7 00fefeea 00fff9f6	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7 00fefee4 00ffffc9	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0 00fefede 00fdf7be
000009B0 000009C0 000009C0 000009D0 000009B0 000009E0 000009F0 000009F8 00000A00 00000A00 00000A10 00000A18 00000A20 00000A28	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc 00fefff2 00fefed8 00f8f87a	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc 00fefff3	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb 00fdfff4 00fbffba 00f9f35c	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9 00fefef2 00f6fea0 00f5ee56	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3 00fefef0 00ffffce 00f1e84f	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb 003ebef7 00fefeea 00fff9f6 00f8ee37	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7 00fefee4 00ffffc9 003fa7ea	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0 00fefede 00fdf7be 00189df5
000009B0 000009C8 000009D0 000009D0 000009E0 000009E0 000009F0 000009F8 00000A00 00000A10 00000A18 00000A20 00000A28 00000A30 00000A38	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc 00fefff2 00fefed8 00f8f87a 00179df4	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc 00fefff3 00fcffc9	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00ffffc2 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb 00fdfff4 00fdfffba 00f9f35c 00159bee	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9 00fefef2 00f6fea0 00f5ee56 00169af2	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3 00fefef0 00ffffce 00ffffce	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb 003ebef7 00fefeea 00fff9f6 00f8ee37 001596f3	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7 00fefee4 00ffffc9 003fa7ea 001394f1	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fdffe4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0 00fefede 00fdf7be 00189df5 001394f1
000009B0 000009C0 000009C0 000009D0 000009B0 000009E0 000009F0 000009F8 00000A00 00000A10 00000A18 00000A20 00000A28 00000A30 00000A38 00000A38	00ffff7f 00189aef 005fd2f9 000488d9 0074e4fc 00b6f6f8 00fdfdf5 00ffffde 00fcfb8b 00179cf2 0062d4fc 000787da 006ce3fc 00acf3fc 00fefff2 00fefed8 00f8f87a 00179df4 0066d7fc	00fdfc6c 00129af2 005cd3f8 000497e0 0089e8fd 00b6f9fc 00fdfefa 00fbf67a 00149bf1 005dd4f9 000996e0 0082e6fd 00b0effc 00fefff3 00fcffc9 00f9f66b 00169cf1	00faf759 000c99f5 0059d4f6 0005a6e6 009fecfe 00b5fcff 00fdfffe 00f9f269 00119af1 0059d4f6 000ca5e7 0097e9fe 00b5ecfb 00fdfff4 00fdfff4 00fdfff4 00fdfffba 00f9f35c 00159bee 0060d4f6	00f8f059 001199f3 0058d3f8 0001ade7 00a5edfe 00daf3ff 00fffef9 00fdfad7 00f7ed5e 001399f2 0056d1f6 000bb0e9 0099e9fe 0089ddf9 00fefef2 00f6fea0 00f5ee56 00169af2 0059d8f9	00ffffdf 00f7e958 001599f2 005edaff 0000b5e8 00abeffe 001ab9f1 00fffdf3 00fffcf3 00f4e954 001698f3 0053cef5 0009bbeb 009ce8fe 0028b4f3 00fefef0 00ffffce 00ffffce 00f1e84f 001798f5 00399ddb	00fdfdc2 00f7e359 001397f0 001971cd 0007beea 00aeeffc 0028b3f4 00fdfeee 00ffffc0 00f7e948 001496f1 00014ebe 0015c5f3 009ee9fb 003ebef7 00fefeea 00fff9f6 00f8ee37 001596f3 000858be	00f7ff88 00d0d368 001195ee 00026ecd 0023cbf5 00b0eff9 002bb3f6 00faffe9 00fcfbc5 0087bda9 001294ef 00026fcd 0021d0fc 00a0e9f9 001eadf7 00fefee4 00ffffc9 003fa7ea 001394f1 00096ccd	00fbfe92 000998ff 001195ee 00037bd3 004cd7f8 00b3f3f9 0073cef4 00fcff84 00109afc 001294ef 00057bd4 0046dafc 00a6eefa 00bde8f0 00fefede 00fdf7be 00189df5 001394f1 000c7ad2

00000A50	004bd7f7	0061dbf8	0077def9	007fe0fa	0088e1fa	008de4fb	0091e7fb	0096eafc
		009feafb						
		00ffffed						
		00fcfdc1						
		00fbf8ac						
		00169df4						
		00105d14						
		0001CE11						
		001997d1 0040cff4						
		0040C114						
		00ffffe7						
		00fdfaba						
		00fefedf						
		00159ef6						
		005bd1f1						
		000f8cdd						
		0025c7ef						
		0076ddf5						
		00ffffdc						
		00fdfbaf						
00000AF0	00fdf74c	00fef576	00fff2a1	00f6ec87	00f8e360	0051bbb4	000d9afe	001a9ef7
00000AF8	00159ef6	00159df4	00159df2	00149bf2	001299f2	001299f2	001299f2	001299f2
00000B00	0067d4fd	0069d6f9	006cd9f5	004fb7dc	001953af	001c67c6	00005abd	001a7eca
00000B08	00157bd4	000581dc	002aa1e7	000189d3	002dabe3	0023a7dc	0029b4e6	0017ade1
00000B10	0014b7ec	0015b9ea	0016bbe9	001fbfec	0028c2ef	003bcdf7	004ed8ff	0056d5fb
00000B18	005dd2f8	005ed6f0	004ec5f4	002fb9fa	0035b8f4	0017b1ff	00f0f7d2	00feffda
00000B20	00fdfcd2	00fdfdd1	00fdfed1	00fdfecf	00fcfecd	00fcfdc7	00fdfdc0	00fdfdb9
00000B28	00fdfdb2	00fdfca4	00fdfc95	00fdfc87	00fdfc79	00fdfa6c	00fef85f	00f9f645
00000B30	00f6ef47	00f2e938	00efe428	00eee425	00ffdd05	000399ff	0017a1f5	00179ef4
00000B38	00169cf3	00159cf3	00149cf3	00129bf1	001099f0	00119af1	00129bf2	00129bf2
00000B40	0066d5fb	0070d5fc	0078e2ff	003b86c7	00235fba	001e6aba	00227ad1	002787d8
00000B48	00248cd7	001d8dd4	002189d1	002ca1ea	002296d5	0031aaef	0020a1db	0017a1dd
00000B50	000ea1e0	001aace3	0013b1eb	0010b8ed	000dc0ef	001cclef	002cc3f0	0036c4f2
00000B58	0040c5f4	0047c9f2	0045c3f6	0031bafa	0031b7f7	004cc2f4	00f5fac0	00fdffc6
00000B60	00fdfcc5	00fdfdc4	00fdfdc4	00fcfdc2	00fbfdc1	00f8f9b6	00fdfdb3	00fdfdab
00000B68	00fdfca3	00fcfc95	00fcfb88	00fcfb7b	00fbfb6d	00fcf962	00fcf757	00f8f245
		00f0e532						
		00179ef2						
		0064d1f7						
		002687ca						
		001e9eda						
		0030bdf4						
		00fdfcb7						
		00fbfb87						
		00ede12c						
		0018a0f2						
		0010d012						
		001462c3						
		001402C3						
		001fb6ee						
		00fcfca7						
		00fafa79						
		00efde28						
		00179ef4						
		0063dffa						
		0031a6e2						
		00238ed6						
		0022b1f0						
UUUU0C20	UUfbf99a	00fcfb98	UUfdfd96	UUfafb90	UU16f98a	UU171984	UU18fa7f	UUfafa7a

00000C28	00fbfb75	00fafa6a	00f9f960	00f8f855	00f7f84a	00f7f540	00f8f336	00f4eb2f
00000C30	00f0e328	00f0da24	00f0d121	00e9ca24	00049bff	0020a3f6	0016a1f7	0016a0f7
00000C38	00169ef7	00159df6	00149cf5	00139bf4	00129af3	00129af3	00129af3	00129af3
00000C40	005ae3ff	0064d8ff	000d4798	00002682	001d6bb7	003aa2de	005fe5ff	0052d8fd
00000C48	004dd6f6	0048ccf5	005fd0f6	0068d9ff	0061d3f8	005bd2f8	0042cbff	0053cefe
00000C50	0051cff5	0049caf6	004acdff	0040baff	000e7edb	000069c2	000584da	000184d5
00000C58	00068cd8	0038bef8	003abef7	0035beff	0062c7e2	00fbf379	00f8fa83	00f9f983
00000C60	00faf884	00f9f77f	00f7f77b	00f8f979	00f9fa77	00f8f972	00f7f86c	00fcfc6c
00000C68	00f9f864	00f8f85b	00f8f752	00f7f649	00f6f53f	00f5f237	00f4ef2f	00f1e628
00000C70	00eede20	00ead61f	00f2cc11	009db96c	000c9ffe	001ba3f9	0017a2f9	0017a0f9
00000C78	00169ef8	00169df7	00159cf6	00149bf5	00139af5	00139af5	00139af5	00139af5
00000C80	0060d8f9	005bd9f8	004cadd7	0069ddff	0056ddf8	0055d6fc	0055d0ff	005cd5ff
		004bcaf6						
		0043c3fb						
		004eccff						
		00f5f467						
		00f7f54c						
		00e5d21a						
		00169df8						
		0059ddfd						
		0050cefb						
		0041c4fa						
		0037b9f7 00f2ef4d						
		00f5f43d						
		00f1cc09						
		0011CC09						
		00103d13						
		004dcbf9						
		003fc5f9						
		0037c1f6						
		00eee942						
		00f4f32e						
00000D30	00ecc917	00dec40c	00bbbe39	000798f8	001a9ff8	001a9ff7	001a9ff5	00189ff7
00000D38	00179ff9	00179ef9	00169cf9	00169bf9	001699f9	001699f9	001699f9	001699f9
00000D40	005cd4f9	0058d4f9	0055d3f9	0056d2fa	0058d0fb	0056d0f8	0054d0f6	0051cef7
00000D48	004dccf9	004ccbfa	004bcafb	0049c8fb	0047c7fb	0045c7fb	0043c6fa	0041c6fa
00000D50	0040c6f9	003fc4f9	003ec3f9	003ec2fa	003ec2fb	003abef5	003ec2f8	003bc1f9
00000D58	0037c0f9	0036beff	0035bbff	0067bb84	00b0d219	00b4d31a	00d3da39	00e2dd3d
00000D60	00d6d532	00e1df38	00ece93e	00e1e636	00e9e536	00f1e634	00e5e42b	00f6e62e
00000D68	00e9eb29	00f0ee2a	00f0e824	00ece420	00e9e01d	00ebdb1c	00edd71c	00e9ce19
		00e7c004						
		00169ef9						
		0056d4f6						
		004bcbfb						
		003fc4f9						
		0035bdfd						
		00d4d52e						
		00ede927						
		00f0bc00						
		00169ef8						
		0063d6fc 004acbfb						
		004acbib						
		0031C419						
		0055bd1a						
	50454450	5 0 D 1 D U 1 Z						
00000DE8	00d5d51c	00e8e428	00ece324	00d1ce1f	00d3c51d	00dcc302	00cfc312	00e3c209
		00e8e428 0084bf6e						
00000DF0	00e3be00	00e8e428 0084bf6e 00159ef8	000ca0f6	00129ffd	0018a2f6	0019a1f5	001ba1f4	0018a0f6

00000E00	0065d7fb	005dd4fa	0056d2f8	0053d0f9	0050cff9	004fcef9	004dcdfa	004bcdfa
00000E08	004accfb	0048cbfb	0047cafb	0046c9fa	0045c8fa	0044c7fa	0043c7fa	0042c6fa
00000E10	0040c5fa	003fc4f9	003ec3f9	003dc1f9	003bc0f9	003ac0f9	0039c0f9	0038bff9
00000E18	0037bff9	0034bef8	0031bcf7	0033bbf8	0035bbfa	002cbcff	0061c2df	0093cb85
00000E20	00c5d52b	00cbd82f	00b0bb13	00b5be17	00b9c21b	00c7c826	00c5bf21	00dbc817
00000E28	00cac819	00dbd722	00ddd61a	00b7bd0d	00c8bd04	00d0c000	00adc951	006cb8b1
00000E30	0004a3ff	0013a4fb	0021a4f5	001ea3f5	001aa1f6	0019a1f6	0018a0f7	0017a0f7
00000E38	00169ff8	00159ef7	00149ef7	00139df7	00139cf6	00119af4	000f98f2	000f98f2
		0058d3f8						
		0047cbfa						
		003fc4f9						
		0035bdf6						
		0027b1c5						
		00aec73e						
		001ba2fa						
		00159ef7						
		0052d1f7						
		0046caf9						
		003fc4f9 0036bcf4						
		0038b6ff						
		0020b011						
		0018a6f8						
		001546F7						
		0052d1f8						
		0045caf9						
		003fc4f9						
00000ED8	0034bef8	0035bcf6	0035baf5	0034b8f8	0033b6fc	002eb6f9	0029b6f7	0029b5f8
00000EE0	002ab4fa	002ab5fb	002ab5fc	002ab2f6	002aafef	001ba9f6	009bcfd9	006dcfe9
00000EE8	0074c7e4	0080c9dd	0019adfb	001cacf9	001fabf8	001fa9f9	001ea7fb	001ca7f9
00000EF0	001aa7f6	001aa5f8	001aa4fb	001aa3fa	001aa2f8	0019a1f8	0018a0f8	0017a0f8
00000EF8	00169ff8	00159ef7	00149df7	00139cf6	00129bf6	00119bf5	00119af5	00119af5
00000F00	0055d0f9	0053d0fa	0051d0fa	004fcffa	004dcffa	004bcefa	0049cdf9	0046ccf9
00000F08	0044caf8	0043caf8	0043c9f8	0043c8f9	0042c8f9	0042c7f9	0041c6f9	0041c6f9
		003ec3f9						
		0033bcf9						
		002bb4f6						
		0015aafb						
		001ca4f8						
		00159ef7						
		0053d0fa 0043caf8						
		0045Ca10						
		003ecs19						
		0035bc13						
		000cacfb						
		001ca4f8						
		00159ef7						
		0053d0fa						
		0043caf8						
00000F90	0040c5fa	003ec3f9	003dc2fa	003bc1fa	0039c0fa	0038bff9	0036bff9	0035bef9
00000F98	0034bdf8	0033bcf9	0033bafa	0032b9fb	0032b8fc	0030b7fa	002eb6f8	002db5f7
00000FA0	002bb4f5	002bb4f6	002bb3f7	002bb2f8	002bb1f8	0022aff9	0019acfa	001eadf7
00000FA8	0024aef3	0020adf5	001dabf6	001fabf6	0020aaf5	001fa9f6	001ea8f7	001da6f7
00000FB0	001ca5f8	001ca4f8	001ba3f9	001ba3f9	001ba2f9	0019a1f9	0018a0f8	0017a0f8
		00159ef7						
		0053d0fa						
		0043caf8						
U0000FD0	0040c5fa	003ec3f9	003dc2fa	003bc1fa	0039c0fa	U038bff9	0036bff9	0035bef9

```
00000FD8 0034bdf8 0033bcf9 0033bafa 0032b9fb 0032b8fc 0030b7fa 002eb6f8 002db5f7 00000FE0 002bb4f5 002bb4f6 002bb3f7 002bb2f8 002bb1f8 0022aff9 0019acfa 001eadf7 00000FE8 0024aef3 0020adf5 001dabf6 001fabf6 0020aaf5 001fa9f6 001ea8f7 001da6f7 00000FF0 001ca5f8 001ca4f8 001ba3f9 001ba3f9 001ba2f9 0019alf9 0018a0f8 0017a0f8 00000FF8 00169ff8 00159ef7 00149df7 00139cf6 00129bf5 00129bf5 00129bf5 00129bf5
```

#### 4.2.4.5 Decoded Image

The following is the decoded image that is represented by the XRGB data given in section 4.2.4.4.



Figure 20: Decoded image

# **5** Security

# **5.1 Security Considerations for Implementers**

None.

# **5.2 Index of Security Parameters**

None.

### 6 Appendix A: Product Behavior

The information in this specification is applicable to the following Microsoft products or supplemental software. References to product versions include released service packs:

- Windows 7 Enterprise operating system with Service Pack 1 (SP1)
- Windows 7 Ultimate operating system with Service Pack 1 (SP1)
- Windows Server 2008 R2 Standard operating system with Service Pack 1 (SP1)
- Windows Server 2008 R2 Enterprise operating system with Service Pack 1 (SP1)
- Windows Server 2008 R2 Datacenter operating system with Service Pack 1 (SP1)
- Microsoft Hyper-V Server 2008 R2 Service Pack 1
- Windows 8 operating system
- Windows Server 2012 operating system
- Windows 8.1 operating system
- Windows Server 2012 R2 operating system

Exceptions, if any, are noted below. If a service pack or Quick Fix Engineering (QFE) number appears with the product version, behavior changed in that service pack or QFE. The new behavior also applies to subsequent service packs of the product unless otherwise specified. If a product edition appears with the product version, behavior is different in that product edition.

Unless otherwise specified, any statement of optional behavior in this specification that is prescribed using the terms SHOULD or SHOULD NOT implies product behavior in accordance with the SHOULD or SHOULD NOT prescription. Unless otherwise specified, the term MAY implies that the product does not follow the prescription.

<1> Section 1.5: Microsoft RDP 8.0 RemoteFX servers require that the TS FRAME ACKNOWLEDGE CAPABILITYSET (section 2.2.1.3) be sent by the client.

<a href="#"><2> Section 1.5:</a> Microsoft RDP 8.0 RemoteFX servers do not require that the **connectionType** field of the Client Core Data ([MS-RDPBCGR] section 2.2.1.3.2) be set to CONNECTION\_TYPE\_LAN (0x06).

<3> Section 2.2.2.1.3: Microsoft RDP 7.1 RemoteFX clients validate the width field.

<4> Section 2.2.2.1.3: Microsoft RDP 7.1 RemoteFX clients validate the height field.

<5> Section 2.2.3.1: Microsoft RDP 8.0 RemoteFX servers do not check for the special **frameID** value of 0xFFFFFFFF.

# 7 Change Tracking No table of changes is available. The document is either new or has had no changes since its last release.

# 8 Index

A	synopsis 7
Abstract data model 30 Applicability 11	P
c	Parameters - security index 138 Preconditions 10 Prerequisites 10
Capability negotiation 11 Change tracking 140	Product behavior 139
D	R
<u>Data model - abstract</u> 30	References <u>informative</u> 7 normative 6
E	Relationship to other protocols 10 RemoteFX algorithm
Event processing 32 Examples - sample use case 51	decoding 47 encoding 33 overview 33
F	stream 48
Fields - vendor-extensible 11	RemoteFX codec - overview 7
G	S
Glossary 6	Sample use case 51 Security implementer considerations 138
н	parameter index 138 Sequencing rules 32
<u>Higher-layer triggered events</u> 32	Standards assignments 11 Syntax - messages 12
I	Т
<u>Implementer - security considerations</u> 138	
Implementer - security considerations 138 Index of security parameters 138 Informative references 7	Timer events 33 Timers 32
Implementer - security considerations 138 Index of security parameters 138	Timer events 33 Timers 32 Tracking changes 140 Transport 12
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32	Timer events 33 Timers 32 Tracking changes 140
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELS packet 18
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELS packet 21 TS RFX CHANNELT packet 18 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC QUANT packet 18
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12  N	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELT packet 18 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC QUANT packet 18 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONS packet 18
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12  N Normative references 6	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELS packet 21 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 21 TS RFX CODEC VERSIONT packet 21 TS RFX CONTEXT packet 21 TS RFX FRAME BEGIN packet 22
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12  N Normative references 6  O	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELS packet 21 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC QUANT packet 18 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 18
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12  N Normative references 6  O Overview message flows 8	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELT packet 18 TS RFX CODEC CHANNELT packet 17 TS RFX CODEC QUANT packet 18 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 20 TS RFX CODEC VERSIONT packet 21 TS RFX FRAME BEGIN packet 22 TS RFX FRAME BEGIN packet 23
Implementer - security considerations 138 Index of security parameters 138 Informative references 7 Initialization 32 Introduction 6  L Local events 33  M Message flows - overview 8 Messages syntax 12 transport 12  N Normative references 6  O Overview	Timer events 33 Timers 32 Tracking changes 140 Transport 12 Triggered events 32 TS FRAME ACKNOWLEDGE CAPABILITYSET packet 15 TS FRAME ACKNOWLEDGE PDU packet 27 TS RFX BLOCKT packet 16 TS RFX CAPS packet 13 TS RFX CAPS CONTAINER packet 12 TS RFX CAPSET packet 13 TS RFX CHANNELS packet 21 TS RFX CHANNELS packet 21 TS RFX CODEC CHANNELT packet 18 TS RFX CODEC CHANNELT packet 18 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONS packet 20 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 18 TS RFX CODEC VERSIONT packet 20 TS RFX CODEC VERSIONT packet 21 TS RFX FRAME BEGIN packet 22 TS RFX FRAME BEGIN packet 23 TS RFX ICAP packet 14 TS RFX RECT packet 19

Release: Thursday, May 15, 2014

TS RFX SYNC packet 20
TS RFX TILE packet 26
TS RFX TILESET packet 24

#### U

Use case example 51

#### V

<u>Vendor-extensible fields</u> 11 <u>Versioning</u> 11