# **RIGAL** manual page

• NAME

**SYNOPSIS** 

**COMPILATION TARGET (Pascal and C)** 

**DESCRIPTION OF rc** 

**OPTIONS** 

DESCRIPTION OF *executable* file (compilation result)

**OPTION** 

**DESCRIPTION OF ic** 

**OPTIONS** 

DESCRIPTION of v

**DESCRIPTION** of rig crf

**DESCRIPTION** of rig\_lint

**ERROR MESSAGES** 

**ENVIRONMENT** 

**INSTALLATION of RIGAL from sources** 

**FILES** 

PRINTED DOCUMENTATION

**AUTHORS** 

#### **NAME**

**rc** - checks and compiles RIGAL file

**ic** - interprets intermediate RIGAL code

v - viewer for RIGAL data saved in file

**rig crf** - RIGAL cross -referencer

rig\_lint - RIGAL Lint (data type checker)

#### **SYNOPSIS**

rc filename [-c] [-D] [-P parameter]...

ic codefilename [ -p printfilename] [ -d][ parameter...]

**v** filename

**rig\_crf** filename

rig\_lint filename executable [ -p printfilename] [ parameter...]

(!) the options and parameters must be separated by one or more spaces.

## **COMPILATION TARGET (Pascal and C)**

There are two variants of RIGAL implementation: RIGAL/Pascal in UNIX Pascal and RIGAL/C in UNIX C. The differences between them are mentioned below.

### **DESCRIPTION OF rc**

rc filename [-c][-D][-P parameter]...

rc - checks source file written in RIGAL language. The source code file must have suffix .rig, but in the

command *filename* is specified without the suffix. **rc** reports error messages if any appear; file name, row, column and message text are reported to standard output. **rc** creates intermediate code *filename*.**rsc** which can be used for interpretation.

#### **OPTIONS**

-C

creates an executable file *filename* (without suffix). In RIGAL/Pascal variant an intermediate Pascal code is generated and then Pascal compiler (**pc**) and linker are invoked. In RIGAL/C variant an intermediate C code is generated and then C compiler (**cc**) and linker are invoked. Some intermediate files, among them script file **xd**, also appear.

- **-D** does not remove intermediate files after the compilation.
- -**P**parameter

passes option to Pascal or C compiler. You can use **-P** several times or use **-P** 'param1 param2' syntax. Typically you may be need to compile with statically linked standard libraries, e.g. **\$rig/rc rigcrf -c -P - Bstatic** 

## **DESCRIPTION OF** *executable* file (compilation result)

executable [ -p printfilename] [parameter...]

The parameters are passed to RIGAL program and can be received through #PARM built -in rule which returns list of parameters. The execution is identical to the interpreted program.

#### **OPTION**

-p printfilename - name of file for statement PRINT output. By default output is written to standard output.

#### DESCRIPTION OF ic

**ic** *codefilename* [ **-p** *printfilename*] [ **-d**] [parameter...]

**ic** - interprets the intermediate code, created by **rc**. The intermediate code must have suffix **.rsc**, but in the command it is specified without the suffix. Other parameters are passed to RIGAL program and can be received through #PARM built -in rule which returns list of parameters. The execution is identical to the compiled program.

#### **OPTIONS**

**-p**printfilename

name of file for statement PRINT output. By default output is written to standard output.

**-d** tracing mode is turned on. Trace of rules and branches, rule arguments and success/unsuccess messages is written to file specified by **-p** option and is mixed with output from PRINT statements. If **-p** option is absent trace is written to standard output.

## **DESCRIPTION of v**

**v** filename

**v** writes the contents of RIGAL code saved in file to standard output. The structure of code is written with indentation, in well -readable form. If the depth of some element of the structure is more than 15 levels, then characters '..' appear instead of the element. The *filename* must contain data saved by RIGAL statement SAVE \$var 'filename'

## **DESCRIPTION of rig\_crf**

rig\_crf filename

rig\_crf creates cross reference table for given RIGAL program filename. The program file must have suffix
.rig, but in the command filename is specified without the suffix. The result is written to file filename.crf.
For every rule the following is reported: rules calling this one, rules called by this one, variables, use of
global variables.

## **DESCRIPTION of rig\_lint**

**rig\_lint** *filename* 

**rig\_lint** creates warning table for given RIGAL program *filename*. The program file must have suffix .**rig**, but in the command *filename* is specified without the suffix. The result is written to file *filename*.**Int**. **rig\_lint** checks type compatibility and cases when values of different types can be assigned to the same variable.

#### ERROR MESSAGES

**Error in file** *filename* **Line**=*nn* **Message**=*text* **Column**=*mm* - checker found syntax error in your RIGAL file. Intermediate code is not created, compilation failed.

\*\*\* **ERROR** *nn xxx* - runtime warnings about dangerous manipulations with RIGAL data structures or runtime input/output errors.

rig:undefined variable

pc:command not found - see ENVIRONMENT section of this manual

**ERROR: COMPILATION** 

**ERROR IN RIGAL, rule** #name - internal compilation message, normally does not appear; try to simplify this rule.

ld() errors or warnings - try command ranlib \$rig/lib/riglib.a to remove errors.

#### **ENVIRONMENT**

For running RIGAL/Pascal you must have Sun Pascal release 2.1 (or higher). Command **pc** (Pascal compiler) must be available.

For running RIGAL/C you must have a C compiler (command **cc**) available. You must have environment variable **rig** set to the name of directory where RIGAL system binary files are located. You can set it by command **setenv rig** *full\_path/***bin** in your **.login** file It is recommended to include this directory at the start of path list by command **set path=( \$rig ... )** in your **.login** file. Then you can use RIGAL commands **rc**, **ic** etc. from any directory.

#### **INSTALLATION of RIGAL from sources**

All files are packed and compressed in file **rigs**variant.system\_version.**tar.Z** (e.g. rigsp.444.tar.Z). Here **rigsp** denotes Pascal sources, **rigsc** - C sources. **uncompress** file (without suffix **.Z**) **tar -xvf** file execute instructions in ENVIRONMENT section.

Go to RIGAL source directory (/src) and execute **make**; it takes 3-5 minutes to compile all sources by Sun Pascal (or C) compiler and perform self-test. The result is in /bin

#### **FILES**

bin/rc, bin/rig crf, bin/rig lint, bin/v basic RIGAL system executable files

**lib/riglib.a** RIGAL compiler runtime library. If you move it from one directory to another, execute command **ranlib** *new\_directory*/**riglib.a** 

include/file.inc, include/file.h m include files for compilation

bin/anrig, bin/genrig parts of RIGAL compiler

docs/rigal.1 this manual

docs/RIGAL\_language\_description.html RIGAL language description

docs/RIGAL\_programmers\_guide.html User's guide

file.rig source programs in RIGAL
file.rsc intermediate code for interpreter
xcrg\*.pas, file.RC2, file.RC4, file.TMP intermediate files, appear and by default are removed during
compilation.

# **AUTHORS**

Mikhail Auguston and Vadim Engelson, Inst. of Math. and Comp.Sci, University of Latvia, Rainis blvd. 29, Riga, LV-1459, Latvia (Lettland). Currently (1994-1995) Vadim Engelson is at IDA, S-58183, Linkoping University, Linkoping, Sweden. e -mail: vadim@mii.lu.lv , vaden@ida.liu.se.

Some info and pointers to papers are available from <u>Rigal home page</u>
Rigal and papers about it available by ftp from <u>RIGAL FTP directory</u>