# Socket Programming signal and timer

**CSEE**, Handong Univ.

Jong-won Lee

ljw@handong.edu

# Signals

#### A signal (software interrupt)

OA notification to a process that an event has occurred.

#### Signals can be sent

- OBy one process to another process (or itself)
- OBy the kernel to a process

# Signals

# Signal disposition (action associated with a signal)

- We can provide a function that is called whenever a specific signal occurs. This function is called a signal handler.
- O We can *ignore* a signal by setting its disposition to SIG IGN.
- O We can set the default disposition for a signal by setting its disposition to SIG\_DFL.



# Signal types

Signal name	Description	Default action
SIGALRM	Time-out occurs (alarm)	terminate
SIGCHLD	Change in status of a child	ignore
SIGINT	Terminal interrupt character (^C)	terminate
SIGKILL	Termination	terminate
SIGPIPE	Write to pipe with no readers	terminate
SIGSTOP	Stop (^S)	Stop process

#### Signal() function

- not recommended. Use sigaction() instead of this function.
- ODefine the action associated with a signal

```
#include <signal.h>
void (*signal(int signum, void (*func)(int))) (int);
```

- signum: the name of a signal
- func: the address of a function to be called when the signal occurs,
   SIG\_IGN or SIG\_DFL
- -Return: the previous disposition of the function if OK,
  - SIG\_ERR on error

```
#include <stdio.h>
#include <unistd.h>
#include <signal.h>
void timeout(int sig)
     if(sig==SIGALRM)
          puts("Time out!");
     alarm(2);
void keycontrol(int sig)
     if(sig==SIGINT)
          puts("CTRL+C pressed");
```

```
int main(int argc, char *argv[])
     int i;
     signal(SIGALRM, timeout);
     signal(SIGINT, keycontrol);
     alarm(2);
     for(i = 0; i < 3; i++)
          puts("wait...");
          sleep(100);
     return 0;
```

```
[ljw@localhost Chapter10]$ ./signal1
wait ...
Time out!
wait ...
^CCTRL+C pressed
wait ...
Time out!
[ljw@localhost Chapter10]$ ■
```

# Sigaction() function ODefine the action associated with a signal

- signum: the name of a signal
- act: the new action
- -oldact: the previous action

#### **Struct sigaction**

```
struct sigaction
{
    void (*sa_handler)(int);
    void (*sa_sigaction)(int, siginfo_t *, void *);
    sigset_t sa_mask;
    int sa_flags;
}
```

- sa\_handler: the address of a function to be called when the signal occurs
- sa\_sigaction: If SA\_SIGINFO is specified in sa\_flags, then sa\_sigaction (instead of sa\_handler) specifies the signal-handling function
- -sa\_mask: specifies a set of signals that will be blocked
  - when the signal handler is called.
- -sa\_flags: options. Basically 0.

#### Handling a signal mask

```
#include <stdio.h>
#include <unistd.h>
#include <signal.h>
void timeout(int sig)
{
     if(sig == SIGALRM)
          puts("Time out!");
     alarm(10);
}
void keycontrol(int sig)
     if(sig == SIGINT)
          puts("CTRL+C pressed!");
}
```

```
int main(int argc, char *argv[])
     int i;
     struct sigaction act;
     act.sa handler = timeout;
     sigemptyset(&act.sa mask);
     act.sa flags = 0;
     sigaction(SIGALRM, &act, 0);
     act.sa handler= keycontrol;
     sigemptyset(&act.sa mask);
     act.sa_flags=0;
     sigaction(SIGINT, &act, 0);kk
```

```
for(i = 0; i < 3; i++)
{
      puts("wait...");
      sleep(100);
    }
    return 0;
}</pre>
```

```
[ljw@localhost Chapter10]$ ./sigaction1
wait ...
^CCTRL+C pressed!
wait ...
Time out!
wait ...
Time out!
[ljw@localhost Chapter10]$ ■
```

#### **Functions**

```
    - clock_id: the clock that the timer uses to measure time
    : CLOCK_REALTIME, CLOCK_PROCESS_CPUTIME_ID,
    CLOCK_THREAD_CPUTIME_ID ...
```

-servp: points to a sigevent structure that specifies how the caller should be notified when the timer expires. when the signal handler is called.

*-timer\_id*: timer ID created.

- Return value: 0 on success, -1 on failure

#### **Example of timer creation**

```
int createTimer ( timer t *timerID,
                int sec, int msec)
  struct sigaction
                       sa:
  struct sigevent
                       te:
  struct itimerspec
                       its:
  /* Set up signal handler. */
  sa.sa flags = SA SIGINFO;
  sa.sa_sigaction = timer; // timer handler
  sigemptyset(&sa.sa mask);
  if (sigaction(SIGRTMIN, &sa, NULL) == -1)
     printf("sigaction error\n");
     return -1;
```

```
/* Set and enable alarm */
 te.sigev notify = SIGEV SIGNAL;
 te.sigev signo = SIGRTMIN;
 te.sigev value.sival ptr = timerID;
 timer create(CLOCK REALTIME, &te, timerID)
  its.it interval.tv sec = sec;
  its.it interval.tv nsec = msec * 1000000;
  its.it value.tv sec = sec;
  its.it value.tv nsec = msec * 1000000;
 timer_settime(*timerID, 0, &its, NULL);
 return 0;
```

#### **Functions**

```
#include <time.h>
int timer settime (timer t timerid, int flags,
                     const struct itimerspec *restrict new value,
                     struct itimerspec *restrict old value);
int timer gettime(timer t timerid, struct itimerspec *curr value);
struct timespec {
                         /* Seconds */
    time t tv sec;
                         /* Nanoseconds */
    long tv nsec;
struct itimerspec {
     struct timespec it interval; /* Timer interval for periodic timer*/
     struct timespec it value; /* Initial expiration */
 };
```

#### **Functions**

- timer\_settime() arms or disarms the timer identified by timerid. The new\_value argument specifies the new initial value and the new interval for the timer.
- If new\_value->it\_value specifies a nonzero value, then timer\_settime() arms (starts) the timer, setting it to initially expire at the given time. (If the timer was already armed, then the previous settings are overwritten.) If new\_value->it\_value specifies a zero value, then the timer is disarmed.
- The new\_value->it\_interval field specifies the period of the timer. If this field is nonzero, then each time that an armed timer expires, the timer is reloaded from the value specified in new\_value->it\_interval. If new\_value->it\_interval specifies a zero value, then the timer expires just once, that is one-shot timer.

#### **Functions**

```
int timer_gettime(timer_t timerid, struct itimerspec *curr_value);
```

- timer\_gettime() returns the time until next expiration, and the interval, for the timer specified by timerid, in the buffer pointed to by curr\_value.
- The time remaining until the next timer expiration is returned in curr value->it value.
- If the value returned in curr\_value->it\_value is zero, then the timer is currently disarmed.
- If the value returned in curr\_value->it\_interval is zero, then this is a "one-shot" timer.

#### **Functions**

```
#include <time.h>
int timer_delete(timer_t timerid);
```

timer\_delete() deletes the timer whose ID is given in timerid.
 If the timer was armed at the time of this call, it is disarmed before being deleted.

- Return value: 0 on success, -1 on failure

```
#include <unistd.h>
#include <time.h>
#include <signal.h>
#include <stdio.h>
#include <stdlib.h>
sigset t mask;
timer t timerID;
// timer handler
void timerHandler()
  printf("time-out\n");
```

```
void keycontrol(int sig)
  struct itimerspec
                        its:
  if (sig == SIGINT)
     printf("CTRL+C pressed!\n");
 // change to one-shot timer
  its.it interval.tv sec = 0;
  its.it interval.tv nsec = 0;
  its.it_value.tv_sec = 5;
  its.it value.tv nsec = 0;
  timer_settime(timerID, 0, &its, NULL);
```

```
int createTimer( timer t * timerID, I
                nt sec, int msec)
  struct sigevent
                       te:
  struct itimerspec
                       its:
  struct sigaction
                       sa:
  /* Set up signal handler. */
  sa.sa flags = SA SIGINFO;
  sa.sa_sigaction = timerHandler;
  sigemptyset(&sa.sa mask);
  if (sigaction(SIGRTMIN, &sa, NULL) == -1)
     printf("sigaction error\n");
     exit(1);
```

```
/* Set and enable alarm */
te.sigev notify = SIGEV SIGNAL;
te.sigev signo = SIGRTMIN;
te.sigev value.sival ptr = timerID;
timer_create(CLOCK_REALTIME, &te, _timerID);
its.it interval.tv sec = sec;
its.it_interval.tv_nsec = msec * 1000000;
its.it value.tv sec = sec;
its.it value.tv nsec = msec * 1000000;
timer settime(* timerID, 0, &its, NULL);
return 0;
```

```
int main()
  struct sigaction act;
  createTimer(&timerID, 3, 0);
  act.sa_handler = keycontrol;
  sigemptyset(&act.sa_mask);
  act.sa_flags = 0;
  sigaction(SIGINT, &act, 0);
  for(i = 0; i < 10; i++)
        puts("wait...");
        sleep(100);
   return 0;
```