
# Chapter 12: I/O Systems





### **Chapter 12: I/O Systems**

- Overview
- □ I/O Hardware
- □ Application I/O Interface
- Kernel I/O Subsystem
- □ Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance






### **Objectives**

- □ Explore the structure of an operating system's I/O subsystem
- □ Discuss the principles and complexities of I/O hardware
- Explain the performance aspects of I/O hardware and software

Communication between 40 device & OS



#### **Overview**

Process ⇒ [I/o request code & CPU computation code]

- I/O management is a major component of operating system design and operation
  - Important aspect of computer operation
  - I/O devices vary greatly
  - Various methods to control them
  - Performance management
  - New types of devices frequent

- " Ho controller in I/o device communicate with · Ports are connected with bushes
- Ports, busses device controllers connect to various devices
- **Device drivers encapsulate device details** 
  - Present uniform device-access interface to I/O subsystem






#### **I/O Hardware**

- □ Incredible variety of I/O devices
  - Storage
  - Transmission
  - □ Human-interface I/b device communicates with [HOFT]
- □ Common concepts signals from I/O devices interface with computer
  - Port connection point for device
  - Bus daisy chain or shared direct access
    - PCI bus common in PCs and servers, PCI Express (PCIe)
    - \* expansion bus connects relatively slow devices for human interface (keyboard, monse, ...)
    - Serial-attached <u>SCSI</u> (SAS) common disk interface for starge
  - Controller (host adapter) electronics that operate port, bus, device
    - Sometimes integrated in I/b device
    - Sometimes separate circuit board (host adapter)
    - Contains processor, microcode, private memory, bus controller, etc
      - Some talk to per-device controller with bus controller, microcode, memory, etc





### **A Typical PC Bus Structure**







### I/O Hardware (Cont.)

- 1/O instructions control devices accessed by host apr & device controller
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
  - Data-in register, data-out register, status register, control register
  - Typically 1-4 bytes, or FIFO buffer
- Devices have addresses, used by
  - Direct I/O instructions
  - □ Memory-mapped I/O By using address, CPU can provide instruction of receive result of I/o
    - Device data and command registers mapped to processor address space
    - Especially for large address spaces (graphics)






#### **Device I/O Port Locations on PCs (partial)**

I/O address range (hexadecimal)	device	
000-00F	DMA controller	
020-021	interrupt controller	
040-043	timer	
200–20F	game controller	
2F8-2FF	serial port (secondary)	
320–32F	hard-disk controller	
378–37F	parallel port	
3D0-3DF	graphics controller	
3F0-3F7	diskette-drive controller	
3F8–3FF	serial port (primary)	

\* Typical I/O port has four registers

Data-in	Data-out
Status	Control


Memory-mapped atructure





### **Polling**


- □ For each byte of I/O
  - 1. Read busy bit from status register until 0 ⇒ 1/10 device is idle
  - Host sets write bit and if write copies data into data-out register
  - 3. Host sets command-ready bit
  - 4. Controller sets busy bit,
  - Controller executes transfer
  - Controller clears busy bit, error bit, command-ready bit when transfer done



- ☐ Step 1 is **busy-wait** cycle to wait for I/O from device
  - Reasonable if device is fast
  - But inefficient if device slow
  - CPU switches to other tasks?
    - But if miss a cycle data overwritten / lost


Keyboard






### **Interrupts**

- □ Polling can happen in 3 instruction cycles
  - Read status, logical-and to extract status bit, branch if not zero
  - How to be more efficient if non-zero infrequently?
- □ CPU Interrupt-request line triggered by I/O device
  - Checked by processor after each instruction
- Interrupt handler receives interrupts
  - Maskable to ignore or delay some interrupts
- Interrupt vector to dispatch interrupt to correct handler
  - Context switch at start and end
  - Based on priority
  - □ Some <u>nonmaskable</u> interrupts are handled immediately
  - Interrupt chaining if more than one device at same interrupt number





### Interrupt-Driven I/O Cycle






### Interrupts (Cont.)

- Interrupt mechanism also used for exceptions
  - Terminate process, crash system due to hardware error
- Page fault executes when memory access error
- System call executes via trap to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
  - If operating system designed to handle it
- Used for time-sensitive processing, frequent, must be fast






### Latency

- Stressing interrupt management because even single-user systems manage hundreds or interrupts per second and servers hundreds of thousands
- For example, a quiet macOS desktop generated 23,000 interrupts over 10 seconds

Fri Nov 25 13:55:59	SCHEDULER	INTERRUPTS	0:00:10
total_samples	13	22998	
delays < 10 usecs delays < 20 usecs delays < 30 usecs delays < 40 usecs delays < 50 usecs delays < 60 usecs delays < 70 usecs delays < 80 usecs delays < 90 usecs delays < 100 usecs	12 1 0 0 0 0 0 0 0	16243 5312 473 590 61 317 2 0 0	






#### **Intel Pentium Processor Event-Vector Table**

vecto	r number	description	
nonmaskable	0	divide error	
Provide/(Adic	1	debug exception	
	2	null interrupt	
	3	breakpoint	
	4	INTO-detected overflow	
	5	bound range exception	
	6	invalid opcode	
	7	device not available	
	8	double fault	
	9	coprocessor segment overrun (reserved)	
	10	invalid task state segment	
	11	segment not present	
	12	stack fault	
	13	general protection	
	14	page fault	
	15	(Intel reserved, do not use)	
	16	floating-point error	
	17	alignment check	
	18	machine check	
19	-31	(Intel reserved, do not use)	
32-	255	maskable interrupts	







### **Direct Memory Access**





- Takes much time for large data movement (gecondary > MEM): CPU involved Used to avoid programmed I/O (one byte at a time) for large data movement
- Requires **DMA** controller
- Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
  - Source and destination addresses
  - Read or write mode
  - Count of bytes
  - Writes location of command block to DMA controller
  - Bus mastering of DMA controller grabs bus from CPU
    - Cycle stealing from CPU but still much more efficient
  - When done, interrupts to signal completion
- Version that is aware of virtual addresses can be even more efficient -





## **Six Step Process to Perform DMA Transfer**







### **Application I/O Interface**

abstraction


- □ I/O system calls encapsulate device behaviors in generic classes
- Device-driver layer hides differences among I/O controllers from kernel
- New devices talking already-implemented protocols need no extra work
- Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
  - Character-stream or block
  - Sequential or random-access
  - Synchronous or asynchronous (or both)
  - Sharable or dedicated
  - Speed of operation
  - read-write, read only, or write only




Application I/O interface



#### A Kernel I/O Structure





#### **Characteristics of I/O Devices**

aspect	variation	example
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read-write	CD-ROM graphics controller disk





### **Characteristics of I/O Devices (Cont.)**

- Subtleties of devices handled by device drivers
- ☐ Broadly I/O devices can be grouped by the OS into
  - □ Block I/O
  - Character I/O (Stream)
  - Memory-mapped file access
  - Network sockets
- For direct manipulation of I/O device specific characteristics, usually an escape / back door
  - Unix ioctl() call to send arbitrary bits to a device control register and data to device data register
- UNIX and Linux use tuple of "major" and "minor" device numbers to identify type and instance of devices (here major 8 and minors 0-4)

```
% ls -l /dev/sda*

brw-rw---- 1 root disk 8, 0 Mar 16 09:18 /dev/sda
brw-rw---- 1 root disk 8, 1 Mar 16 09:18 /dev/sda1
brw-rw---- 1 root disk 8, 2 Mar 16 09:18 /dev/sda2
brw-rw---- 1 root disk 8, 3 Mar 16 09:18 /dev/sda3
```





#### **Block and Character Devices**

- unit of write/read
- Block devices include disk drives W Support random access
  - Commands include read, write, seek
  - Raw I/O, direct I/O, or file-system access
    - Look data as they are in linear arrays
  - Memory-mapped file access possible
    - Data in consecutive addresses in memory = data in consecutive blocks
- Character devices include keyboards, mice, serial ports
  - Commands include get(), put()
  - Libraries layered on top allow line editing
  - □ Don't know what data and when they will be given as an input or output : \text{\text{\text{turner}} involved}
  - Preferable to process streaming data like a/v data or data for printers





## Network Devices

- Varying enough from block and character to have own interface
- ☐ Linux, Unix, Windows and many others include socket interface
  - Separates network protocol from network operation
  - Includes select() functionality
    - Which sockets have the received packets or available buffers to send packets
    - Prevents busy-waiting

read(fd,buf,data)




If fd is file descriptor: read data from file

If fd is socket: read data that came from the device connected through network

socket ←→ A remote program






#### **Clocks and Timers**

- Provide current time, elapsed time, timer
  - Example of timer use
    - CPU preemption in RR scheduling
    - Flushing the data in cache buffer into disks
    - Some network operations
- Normal resolution about 1/60 second
- Some systems provide higher-resolution timers
- Programmable interval timer used for timings, periodic interrupts
  - How to use a timer for many timer events?
  - 1. Set the timer for the earliest event among them
  - 2. After the interruption by the earliest event, set the timer for the second earliest event







### Nonblocking and Asynchronous I/O

- Blocking process suspended until I/O completed
  - Easy to use and understand
  - Insufficient for some needs
- Nonblocking I/O call returns as much as available
  - User interface, data copy (buffered I/O)
  - Implemented via multi-threading
  - Returns quickly with count of bytes read or written
  - select() to find if data ready then read() or write() to transfer
- Asynchronous process runs while I/O executes
  - Difficult to use
  - I/O subsystem signals process when I/O completed





#### **Two I/O Methods**





#### **Vectored I/O**

- Vectored I/O allows one system call to perform multiple I/O operations
- ☐ For example, Unix readve() accepts a vector of multiple buffers to read into or write from
- This scatter-gather method better than multiple individual I/O calls
  - Decreases context switching and system call overhead
  - Some versions provide atomicity : no context switching
    - Avoid for example worry about multiple threads changing data as reads / writes occurring





### **Kernel I/O Subsystem**

- Scheduling
  - Some I/O request ordering via per-device queue
  - Some OSs try fairness

Kernel I/O subsystem


Device drivers


- Buffering store data in memory while transferring between devices
  - To cope with device speed mismatch
  - To cope with device transfer size mismatch
  - To maintain "copy semantics"
  - Double buffering two copies of the data

\* Double buffering

\* Copy semantics


write(fd,array,100); Gystem Call memset(array,0,100); update content in MEM write CHINH array of data to buffer of the Arrow of the first asynchronous in memset of History for data the nits of write History are the sister of t






#### **Device-status Table**


To keep track of many I/O requests to support asynchronous I/O








#### **Common PC and Data-center I/O devices and Interface Speeds**






### Kernel I/O Subsystem (Cont'd)

- Caching faster device holding copy of data
  - Always just a copy
  - Key to performance
  - Sometimes combined with buffering
- ☐ Spooling hold output for a device e.g., printer
  - If device can serve only one request at a time
  - i.e., Printing
- Device reservation provides exclusive access to a device
  - System calls for allocation and de-allocation
  - Watch out for deadlock






### **Error Handling**

- ☐ OS can recover from disk read, device unavailable, transient write failures
  - Retry a read or write, for example
  - Some systems more advanced Solaris FMA, AIX
    - Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports







#### **I/O Protection**

- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
  - All I/O instructions defined to be privileged
  - I/O must be performed via system calls
    - Memory-mapped and I/O port memory locations must be protected too





### **Use of a System Call to Perform I/O**







#### **Kernel Data Structures**

- Kernel keeps state info for I/O components, including open file tables, network connections, character device state
- Many, many complex data structures to track buffers, memory allocation, "dirty" blocks
- To implement I/O,
  - Linux uses object-oriented methods
    - Supporting uniform interface to encapsulate the difference of the operations
  - Windows uses message passing
    - Message with I/O information passed from user mode into kernel
    - Message modified as it flows through to device driver and back to process





#### **UNIX I/O Kernel Structure**








### **Power Management**

- □ Not strictly domain of I/O, but much is I/O related
- Computers and devices use electricity, generate heat, frequently require cooling
- OSes can help manage and improve use
  - Cloud computing environments move virtual machines between servers
    - Can end up evacuating whole systems and shutting them down
- Mobile computing has power management as first class OS aspect






### Power Management (Cont.)

- ☐ For example, Android implements
  - Component-level power management
    - Understands relationship between components
    - Build device tree representing physical device topology
      - E.g) System bus → I/O subsystem → {flash, USB storage}
    - Device driver tracks state of device, whether in use
    - Unused component turn it off
    - All devices in tree branch unused turn off branch
  - Wake locks like other locks but prevent sleep of device when lock is held


    Power collapse put a device into very deep sleep
    - Marginal power use
    - Only awake enough to respond to external stimuli (button press, incoming call)
- Modern systems use advanced configuration and power interface (ACPI) firmware providing code that runs as routines called by kernel for device discovery, management, error and power management



### **Kernel I/O Subsystem Summary**

- In summary, the I/O subsystem coordinates an extensive collection of services that are available to applications and to other parts of the kernel
  - Management of the name space for files and devices
  - Access control to files and devices
  - Operation control (for example, a modem cannot seek())
  - File-system space allocation
  - Device allocation
  - Buffering, caching, and spooling
  - I/O scheduling
  - Device-status monitoring, error handling, and failure recovery
  - Device-driver configuration and initialization
  - Power management of I/O devices
- ☐ The upper levels of the I/O subsystem access devices via the uniform interface provided by the device drivers







#### **Transforming I/O Requests to Hardware Operations**

- Consider reading a file from disk for a process:
  - Determine device holding file
  - Translate name to device representation
  - Physically read data from disk into buffer
  - Make data available to requesting process
  - Return control to process





### Life Cycle of An I/O Request







#### **Performance**


- □ I/O a major factor in system performance:
  - Demands CPU to execute device driver, kernel I/O code
  - Context switches due to interrupts
  - Data copying
  - Network traffic especially stressful






### **Intercomputer Communications**





#### I/O Performance of Storage (and Network Latency)





# **End of Chapter 12**

