# Instalação do OpenEdge SQL Client Access ODBC drivers

Após obter o arquivo PROGRESS\_OE\_12.2\_LNX\_64\_SQLCLIENTACCESS.tar.gz

## **Pre-requisitos**

Antes de instalar o driver os pacotes abaixo:

- unixodbc
- unixodbc-dev
- xterm para equalizar o caractere SET

### Instalando requisitos

```
# Instalar unix odbc
sudo apt-get -y install unixodbc unixodbc-dev
# Instalar xterm
sudo apt-get -y install xterm
```

# Inicio da Instalação dos drivers

```
# criar um diretório test
mkdir test

# Mover o arquivo de instalação
mv PROGRESS_OE_11.7_LNX_64_SQLCLIENTACCESS.tar.gz test/
cd test

# Extrair o conteúdo
tar xzf PROGRESS_OE_11.7_LNX_64_SQLCLIENTACCESS.tar.gz
cd ..

# Ativar xterm para caracteres
export TERM=xterm
```

#### Chamar o instalador

# De dentro do diretório home
sudo ./test/proinst
# digite [Enter]

Welcome

#### WELCOME TO THE OPENEDGE INSTALLATION UTILITY

Ensure that you have your completed "Preinstallation Checklist for Unix" handy to consult. This information will facilitate your installation and ensure your choices are accurately recorded.

Copyright (c) 1984-2017 Progress Software Corporation and/or one of its subsidiaries or affiliates.

All Rights Reserved.

[Enter=OK]

## Colocar o serial e número de controle fornecido.

Product Configuration Data	
Company Name:   Serial Number:   Control Number:	[Enter=Additional] [Ctrl-E=Done] [CTRL-T=Quit] [CTRL-N=Release Notes] [CTRL-V=View] [TAB=Next Field] [CTRL-P=Help] [CTRL-A=Addendum File]
T	
Done Configuration Data Confirmation	
Are you sure that you are done entering OpenEdge products that will be installed	
[Y=YES] [N=N	O]

Escolher a mensagem [Continue with Installation] para continuar a instalação.


Type: Complete Install
|Destination pathname: /usr/dlc
|Working Dir pathname: /usr/wrk
|Management pathname: /usr/oemgmt
|Management Working Dir pathname: /usr/wrk\_oemgmt

### Escolher o local e instalação

```
Complete Installation

| The following products will be installed:
| 'OE SQL Client Access (1 USERS)'
| Disk Space Required for Products: 357,720,064 bytes
| Disk Space Required for Installation: 358,969,344 bytes
| Disk Space Remaining After Installation: 988,233,728 bytes
| Selected Destination Path: /usr/dlc
| Do you want to install the above listed product(s)?
| [Y=YES] [N=NO] [H=Help]
```

Definir o local padrão dos scripts execução



Após a instalação finalizar no valor default.

++	-
Installation of selected OpenEdge products is complete.  Refer to the installation notes for more information.	
End the OpenEdge Installation   View Release Notes   Help	
+	-+

Instalado o DRIVER ODBC!

#### Confirmando o local correto dos binários

#### Para confirmar:

```
cd /usr/dlc/odbc/lib/
ldd pgoe27.so

linux-vdso.so.1 => (0x00007ffc4eebf000)
libpthread.so.0 => /lib/x86_64-linux-gnu/libpthread.so.0 (0x00007f20f1c55000)
librt.so.1 => /lib/x86_64-linux-gnu/librt.so.1 (0x00007f20f1a4d000)
libpgicu27.so => not found
libdl.so.2 => /lib/x86_64-linux-gnu/libdl.so.2 (0x00007f20f1848000)
libstdc++.so.6 => /usr/lib/x86_64-linux-gnu/libstdc++.so.6 (0x00007f20f14c6000)
libm.so.6 => /lib/x86_64-linux-gnu/libm.so.6 (0x00007f20f1bc000)
libc.so.6 => /lib/x86_64-linux-gnu/libc.so.6 (0x00007f20f0df2000)
libgc_s.so.1 => /lib/x86_64-linux-gnu/libgc_s.so.1 (0x00007f20f0bdc000)
/lib64/ld-linux-x86-64.so.2 (0x0000559df2bed000)
```

#### "libpgicu27.so => not found"

Isso indicar que o arquivo libpgicu27.so não foi encontrado.

É necessário copia-lo para o local correto, o comando abaixo encontra o arquivo.

```
cd /
sudo find . -name libpgicu27.so
sudo cp libpgicu27.so /usr/lib

ldd pgoe27.so

linux-vdso.so.1 => (0x00007ffe951c7000)
libpthread.so.0 => /lib/x86_64-linux-gnu/libpthread.so.0 (0x00007f132a8d0000)
librt.so.1 => /lib/x86_64-linux-gnu/librt.so.1 (0x00007f132a6c8000)
libpgicu27.so => /usr/lib/libpgicu27.so (0x00007f13297cc000)
libdl.so.2 => /lib/x86_64-linux-gnu/libdl.so.2 (0x00007f13295c8000)
libstdc++.so.6 => /usr/lib/x86_64-linux-gnu/libstdc++.so.6 (0x00007f1329246000)
libr.so.6 => /lib/x86_64-linux-gnu/libr.so.6 (0x00007f1328f3c000)
libc.so.6 => /lib/x86_64-linux-gnu/libc.so.6 (0x00007f1328f3c000)
libgcc_s.so.1 => /lib/x86_64-linux-gnu/libgcc_s.so.1 (0x00007f132895c000)
/lib64/ld-linux-x86-64.so.2 (0x000055f3137c8000)
```

Agora sim o arquivo libpgicu27.so esta no local correto.

### **Configurar o ODBCINST**

Editar o arquivo /etc/odbcinst.ini e colocar os dados abaixo:

```
[Progress]
Description = Progress Driver
Driver
           = /usr/dlc/odbc/lib/pgoe27.so
FileUsage
Após isso basta criar uma entrada no arquivo /etc/odbc.ini
[AGROSYS]
Driver = Progress
DatabaseName=dbeview
PortNumber=1513
HostName=18.222.152.36
LogonID=sysprogress
Password=sysprogress
isql -v AGROSYS
 Connected!
 sql-statement
 help [tablename]
 quit
     _____
SQL>
```