# CS2100 Computer Organization Tutorial 2

#### **SUGGESTED SOLUTIONS**

## 1. Bitwise operations

Answer Omitted.

## 2. Swapping

We have discussed in lecture how to swap two variables in a function:

```
void swap(int *a, int *b) {
   int t = *a;
   *a = *b;
   *b = t;
}
```

In the above code, a temporary variable **t** is used.

A possible alternative is to use some bitwise operator to perform the swap, without using any temporary variable. Write a function to do this.

## Answer: Tut2Q2.c

```
void swap(int *a, int *b) {
    *a = *a ^ *b;
    // Now, we can recover *a_orig by applying *a XOR *b_orig
    *b = *a ^ *b;
    // So we have the following situation:
    // The value originally stored in *a, a_orig, is now in *b
    // and *a still stores a_orig XOR b_orig
    // This means that we can recover the value of b_orig by
    // applying the XOR operation to *a and a_orig.
    // Since *b stores a_orig...
    *a = *a ^ *b;
}
```

## 3. MIPS Bitwise Operations

Implement the following in MIPS assembly. Assume that integer variables **a**, **b** and **c** are mapped to registers \$s0, \$s1 and \$s2 respectively. Each part is independent of all the other parts. **For bitwise instructions (e.g. ori, andi, etc)**, any immediate values you use should be written in binary for this question. This is optional for non-bitwise instructions (e.g. addi, etc).

Note that bit 31 is the most significant bit (MSB) on the left, and bit 0 is the least significant bit (LSB) on the right, i.e.:

MSB				LSB
Bit 31	Bit 30	Bit 29	 Bit 1	Bit 0

a. Set bits 2, 8, 9, 14 and 16 of **b** to 1. Leave all other bits unchanged.

To set bits, we create a "mask" with 1's in the bit positions we want to set. Since bit 16 is in the upper 16 bits of the register, we need to use lui to set it.

```
lui $t0, 1  # Sets bit 16 of $t0.
ori $t0, $t0, 0b0100001100000100 # Set bits 14, 9, 8 and 2.
or $s1, $s1, $t0
```

b. Copy over bits 1, 3 and 7 of **b** into **a**, without changing any other bits of **a**.

```
# We use the property that x AND 1 = x to copy out the values of # bits 7, 3 and 1 of b into $t0. Note that we zero all other bits # so that they don't change anything in $s0 when we OR later on. andi $t0, $s1, 0b0000000010001010
```

# Now OR together a and \$t0 to copy over the bits or \$s0, \$s0, \$t0

c. Make bits 2, 4 and 8 of c the inverse of bits 1, 3 and 7 of b (i.e. if bit 1 of b is 0, then bit 2 of c should be 1; if bit 1 of b is 1, then bit 2 of c should be 0), without changing any other bits of c.
# We use the property that x XOR 1 = ~x to flip the values of bits 7, 3 and 1.
xori \$t0, \$s1, 0b10001010

#### 4. MIPS Arithmetic

Write the following in MIPS Assembly, using as few instructions as possible. You may rewrite the equations if necessary to minimize instructions.

In all parts you can assume that integer variables **a**, **b**, **c** and **d** are mapped to registers \$s0, \$s1, \$s2 and \$s3 respectively. Each part is independent of the others.

a. c = a + b

Answer omitted.

b. d = a + b - c

Answer omitted.

```
c. c = 2b + (a - 2)
    add $s2, $s1, $s1
                         # c = 2b (alternatively, can do a shift left 1 bit)
                         # $t0 = a - 2
    addi $t0, $s0, -2
    add $s2, $s2, $t0
                        #c = 2b + (a - 2)
d. d = 6a + 3(b - 2c)
    Rewrite:
    d = 6a + 3b - 6c
    Factorize out 3
    d = 3(2a + b - 2c)
    = 3(2a - 2c + b)
    = 3(2(a-c) + b)
    sub $t0, $s0, $s2
                         # t0 = a - c
                         # t0 = 2(a - c)
    sll $t0, $t0, 1
                         # t0 = 2(a - c) + b
    add $t0, $t0, $s1
    sll $t1, $t0, 2
                         # t1 = 4(2(a - c) + b)
    sub $s3, $t1, $t0
                         \# d = 3(2(a-c)+b)
```

5. [AY2013/14 Semester 2 Exam]

The mysterious MIPS code below assumes that \$s0 is a 31-bit binary sequence, i.e. the MSB (most significant bit) of \$s0 is assumed to be zero at the start of the code.

```
add $t0, $s0, $zero #make a copy of $s0 in $t0
lui $t1, 0x8000
lp: beq $t0, $zero, e
    andi $t2, $t0, 1
    beq $t2, $zero, s
    xor $s0, $s0, $t1
s: srl $t0, $t0, 1
    j lp
e:
```

- a) For each of the following initial values in register \$s0 at the beginning of the code, give the hexadecimal value of the content in register \$s0 at the end of the code.
  - i. Decimal value **31**.
  - ii. Hexadecimal value **0x0AAAAAA**.
- b) Explain the purpose of the code in one sentence.

#### Answers:

```
a.i. $s0 = 0x8000 001F
ii. $s0 = 0x0AAA AAAA
```

b. The code sets bit 31 of \$s0 to 1 if there are odd number of '1' in \$s0 initially, or 0 if there are even number of '1'. (This is called the even parity bit.)