

CIS Apache Tomcat 8 Benchmark

v1.1.0 - 10-21-2019

Terms of Use

Please see the below link for our current terms of use:

https://www.cisecurity.org/cis-securesuite/cis-securesuite-membership-terms-of-use/

Table of Contents

Terms of Use	1
Overview	6
Intended Audience	6
Consensus Guidance	6
Typographical Conventions	7
Scoring Information	7
Profile Definitions	8
Acknowledgements	9
Recommendations	10
1 Remove Extraneous Resources	10
1.1 Remove extraneous files and directories (Scored)	10
1.2 Disable Unused Connectors (Not Scored)	12
2 Limit Server Platform Information Leaks	14
2.1 Alter the Advertised server info String (Scored)	14
2.2 Alter the Advertised server.number String (Scored)	16
2.3 Alter the Advertised server.built Date (Scored)	18
2.4 Disable X-Powered-By HTTP Header and Rename the Server Value for all Connectors (Scored)	
2.5 Disable client facing Stack Traces (Scored)	22
2.6 Turn off TRACE (Scored)	24
2.7 Ensure Sever Header is Modified To Prevent Information Disclosure (Not Scored)	
3 Protect the Shutdown Port	28
3.1 Set a nondeterministic Shutdown command value (Scored)	28
3.2 Disable the Shutdown port (Not Scored)	30
4 Protect Tomcat Configurations	32
4.1 Restrict access to \$CATALINA_HOME (Scored)	32
4.2 Restrict access to \$CATALINA_BASE (Scored)	34
4.3 Restrict access to Tomcat configuration directory (Scored)	36
4.4 Restrict access to Tomcat logs directory (Scored)	38

4.5 Restrict access to Tomcat temp directory (Scored)	40
4.6 Restrict access to Tomcat binaries directory (Scored)	42
4.7 Restrict access to Tomcat web application directory (Scored)	44
4.8 Restrict access to Tomcat catalina.properties (Scored)	46
4.9 Restrict access to Tomcat catalina.policy (Scored)	48
4.10 Restrict access to Tomcat context.xml (Scored)	50
4.11 Restrict access to Tomcat logging.properties (Scored)	52
4.12 Restrict access to Tomcat server.xml (Scored)	54
4.13 Restrict access to Tomcat tomcat-users.xml (Scored)	56
4.14 Restrict access to Tomcat web.xml (Scored)	58
5 Configure Realms	60
5.1 Use secure Realms (Scored)	60
5.2 Use LockOut Realms (Scored)	62
6 Connector Security	63
6.1 Setup Client-cert Authentication (Scored)	63
6.2 Ensure SSLEnabled is set to True for Sensitive Connectors (Not Scored)	65
6.3 Ensure scheme is set accurately (Scored)	66
6.4 Ensure secure is set to true only for SSL-enabled Connectors (Scored)	67
6.5 Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)	69
6.6 Control the maximum size of a POST request that will be parsed for paral (Scored)	
7 Establish and Protect Logging Facilities	73
7.1 Application specific logging (Scored)	73
7.2 Specify file handler in logging.properties files (Scored)	75
7.3 Ensure className is set correctly in context.xml (Scored)	77
7.4 Ensure directory in context.xml is a secure location (Scored)	79
7.5 Ensure pattern in context.xml is correct (Scored)	81
7.6 Ensure directory in logging.properties is a secure location (Scored)	83
8 Configure Catalina Policy	85
8.1 Restrict runtime access to sensitive packages (Scored)	85
9 Application Deployment	87

9.1 Starting Tomcat with Security Manager (Scored)	87
9.2 Disabling auto deployment of applications (Scored)	89
9.3 Disable deploy on startup of applications (Scored)	90
10 Miscellaneous Configuration Settings	91
10.1 Ensure Web content directory is on a separate partition from the Tomsystem files (Not Scored)	
10.2 Restrict access to the web administration application (Not Scored)	93
10.3 Restrict manager application (Not Scored)	95
10.4 Force SSL when accessing the manager application (Scored)	97
10.5 Rename the manager application (Scored)	99
10.6 Enable strict servlet Compliance (Scored)	101
10.7 Turn off session facade recycling (Scored)	103
10.8 Do not allow additional path delimiters (Scored)	104
10.9 Do not allow custom header status messages (Scored)	105
10.10 Configure connectionTimeout (Scored)	106
10.11 Configure maxHttpHeaderSize (Scored)	108
10.12 Force SSL for all applications (Scored)	109
10.13 Do not allow symbolic linking (Scored)	111
10.14 Do not run applications as privileged (Scored)	113
10.15 Do not allow cross context requests (Scored)	114
10.16 Do not resolve hosts on logging valves (Scored)	115
10.17 Enable memory leak listener (Scored)	117
10.18 Setting Security Lifecycle Listener (Scored)	119
10.19 Use the logEffectiveWebXml and metadata-complete settings for department applications in production (Scored)	
11 Minimize Features	123
11.1 Limit HTTP Request Methods (Scored) (Scored)	123
Appendix: Summary Table	125
Appendix: Change History	128

Overview

This document, Security Configuration Benchmark for Apache Tomcat 8.0, provides prescriptive guidance for establishing a secure configuration posture for Apache Tomcat versions 8.0 running on Linux. This guide was tested against Apache Tomcat 8.0 as installed by tar packages provided by Apache, and assumes the value of CATALINA_BASE of instance is equal to its CATALINA_HOME. To obtain the latest version of this guide, please visit http://benchmarks.cisecurity.org. If you have questions, comments, or have identified ways to improve this guide, please write us at feedback@cisecurity.org.

Intended Audience

This document is intended for system and application administrators, security specialists, auditors, help desk, and platform deployment personnel who plan to develop, deploy, assess, or secure solutions that incorporate Apache Tomcat on a Linux platform.

Consensus Guidance

This benchmark was created using a consensus review process comprised of subject matter experts. Consensus participants provide perspective from a diverse set of backgrounds including consulting, software development, audit and compliance, security research, operations, government, and legal.

Each CIS benchmark undergoes two phases of consensus review. The first phase occurs during initial benchmark development. During this phase, subject matter experts convene to discuss, create, and test working drafts of the benchmark. This discussion occurs until consensus has been reached on benchmark recommendations. The second phase begins after the benchmark has been published. During this phase, all feedback provided by the Internet community is reviewed by the consensus team for incorporation in the benchmark. If you are interested in participating in the consensus process, please visit https://workbench.cisecurity.org/.

Typographical Conventions

The following typographical conventions are used throughout this guide:

Convention	Meaning
Stylized Monospace font	Used for blocks of code, command, and script examples. Text should be interpreted exactly as presented.
Monospace font	Used for inline code, commands, or examples. Text should be interpreted exactly as presented.
<italic brackets="" font="" in=""></italic>	Italic texts set in angle brackets denote a variable requiring substitution for a real value.
Italic font	Used to denote the title of a book, article, or other publication.
Note	Additional information or caveats

Scoring Information

A scoring status indicates whether compliance with the given recommendation impacts the assessed target's benchmark score. The following scoring statuses are used in this benchmark:

Scored

Failure to comply with "Scored" recommendations will decrease the final benchmark score. Compliance with "Scored" recommendations will increase the final benchmark score.

Not Scored

Failure to comply with "Not Scored" recommendations will not decrease the final benchmark score. Compliance with "Not Scored" recommendations will not increase the final benchmark score.

Profile Definitions

The following configuration profiles are defined by this Benchmark:

• Level 1

Items in this profile intend to:

- o be practical and prudent;
- o provide a clear security benefit; and
- o not inhibit the utility of the technology beyond acceptable means.

• Level 2

This profile extends the "Level 1" profile. Items in this profile exhibit one or more of the following characteristics:

- o are intended for environments or use cases where security is paramount
- o acts as defense in depth measure
- o may negatively inhibit the utility or performance of the technology

Acknowledgements

This benchmark exemplifies the great things a community of users, vendors, and subject matter experts can accomplish through consensus collaboration. The CIS community thanks the entire consensus team with special recognition to the following individuals who contributed greatly to the creation of this guide:

Contributor

Jordan Rakoske GSEC, GCWN Tim Harrison CISSP, ICP, Center for Internet Security Elizabeth Alberto

Editor

Sherif Mansour Alex Dong

Recommendations

1 Remove Extraneous Resources

1.1 Remove extraneous files and directories (Scored)

Profile Applicability:

• Level 2

Description:

The installation may provide example applications, documentation, and other directories which may not serve a production use.

Rationale:

Removing sample resources is a defense in depth measure which reduces potential exposures introduced by these resources.

Audit:

Perform the following to determine the existence of extraneous resources:

No output implies no sample resources are present.

Remediation:

Perform the following to remove extraneous resources:

```
$ rm -rf $CATALINA_HOME/webapps/docs \
    $CATALINA_HOME/webapps/examples \
    $CATALINA_HOME/webapps/ROOT
```

If the Manager and HOST-Manager application are not utilized, also remove the following resources:

```
$ rm -rf $CATALINA_HOME/webapps/host-manager \
$CATALINA_HOME/webapps/manager \
```

Default Value:

 $\verb|docs, examples, ROOT, manager| and host-manager| are default web applications shipped with Tomcat.$

1.2 Disable Unused Connectors (Not Scored)

Profile Applicability:

• Level 2

Description:

The default installation of Tomcat includes connectors with default settings. These are traditionally set up for convenience. It is best to remove these connectors and enable only what is needed.

Rationale:

Improperly configured or unnecessarily installed Connectors may lead to a security exposure.

Audit:

Execute the following command to find configured Connectors. Ensure only those required are present and not commented out:

```
$ grep "Connector" $CATALINA HOME/conf/server.xml
```

Remediation:

Within the \$CATALINA_HOME/conf/server.xml, remove, or comment out, every unused Connectors. For example, to disable an instance of the HTTPConnector, remove the following:

```
<Connector className="org.apache.catalina.connector.http.HttpConnector"
...
connectionTimeout="60000"/>
```

Default Value:

\$CATALINA HOME/conf/server.xml, has the following connectors defined by default:

- A non-SSL HTTP Connector bound to port 8080
- An AJP Connector bound to port 8009

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html#Connectors
- 2. https://tomcat.apache.org/tomcat-8.5-doc/security-howto.html#Connectors

CIS Controls:

Version 7

9.2 Ensure Only Approved Ports, Protocols and Services Are Running Ensure that only network ports, protocols, and services listening on a system with validated business needs, are running on each system.

2 Limit Server Platform Information Leaks

Limiting server platform information leaks increases the complexity for attackers to determine which vulnerabilities affect the server platform.

2.1 Alter the Advertised server.info String (Scored)

Profile Applicability:

• Level 2

Description:

The server info attribute contains the name of the application service. This value is presented to Tomcat clients when clients connect to the tomcat server.

Rationale:

Altering the server.info attribute may increase the complexity for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server.info value has been changed: Extract the ServerInfo.properties file and examine the server.info attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.info org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server platform string that gets displayed when clients connect to the tomcat server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory which was created

```
cd org/apache/catalina/util
```

3. Open ServerInfo.properties in an editor

4. Update the server.info attribute in the ServerInfo.properties file.

server.info=<SomeWebServer>

5. Update the catalina.jar with the modified ServerInfo.properties file.

\$ jar uf catalina.jar org/apache/catalina/util/ServerInfo.properties

Default Value:

The default value for the server.info attribute is Apache Tomcat/<version>. For example, Apache Tomcat/8.5.11.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html
- 2. https://tomcat.apache.org/tomcat-8.5-doc/security-howto.html

CIS Controls:

Version 7

13.2 <u>Remove Sensitive Data or Systems Not Regularly Accessed by Organization</u>
Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.2 Alter the Advertised server.number String (Scored)

Profile Applicability:

• Level 2

Description:

The server number attribute represents the specific version of Tomcat which is executing. This value is presented to Tomcat clients when connect.

Rationale:

Advertising a valid server version may provide attackers with information useful for locating vulnerabilities affecting the server platform. Altering the server version string may increase the complexity for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server.number value has been changed: Extract the ServerInfo.properties file and examine the server.number attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.number org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server version string that gets displayed when clients connect to the server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory that was created

```
$ cd org/apache/Catalina/util
```

- 3. Open ServerInfo.properties in an editor
- 4. Update the server.number attribute

```
server.number=<someversion>
```

5. Update the catalina.jar with the modified ServerInfo.properties file.

\$ jar uf catalina.jar org/apache/catalina/util/ServerInfo.properties

Default Value:

The default value for the server.number attribute is a four part version number, such as 8.5.11.0.

CIS Controls:

Version 7

13.2 <u>Remove Sensitive Data or Systems Not Regularly Accessed by Organization</u>
Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.3 Alter the Advertised server.built Date (Scored)

Profile Applicability:

• Level 2

Description:

The server.built date represents the date which Tomcat was compiled and packaged. This value is presented to Tomcat clients when clients connect to the server.

Rationale:

Altering the server.built string may increase the complexity for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server.built value has been changed: Extract the ServerInfo.properties file and examine the server.built attribute.

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
$ grep server.built org/apache/catalina/util/ServerInfo.properties
```

Remediation:

Perform the following to alter the server version string which gets displayed when clients connect to the server.

1. Extract the ServerInfo.properties file from the catalina.jar file:

```
$ cd $CATALINA_HOME/lib
$ jar xf catalina.jar org/apache/catalina/util/ServerInfo.properties
```

2. Navigate to the util directory that was created

```
$ cd org/apache/Catalina/util
```

- 3. Open ServerInfo.properties in an editor
- 4. Update the server.built attribute in the ServerInfo.properties file.

```
server.built=
```

5. Update the catalina.jar with the modified ServerInfo.properties file.

Default Value:

The default value for the server.built attribute is build date and time. For example, Jul 8 2008 11:40:35.

CIS Controls:

Version 7

13.2 <u>Remove Sensitive Data or Systems Not Regularly Accessed by Organization</u>
Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.4 Disable X-Powered-By HTTP Header and Rename the Server Value for all Connectors (Scored)

Profile Applicability:

• Level 2

Description:

The <code>xpoweredBy</code> setting determines if Apache Tomcat will advertise its presence via the <code>xpowered-By</code> HTTP header. It is recommended that this value be set to <code>false</code>. The server attribute overrides the default value that is sent down in the HTTP header further masking Apache Tomcat.

Rationale:

Preventing Tomcat from advertising its presence in this manner may increase the complexity for attackers to determine which vulnerabilities affect the server platform.

Audit:

Perform the following to determine if the server platform, as advertised in the HTTP Server header, has been changed:

- 1. Locate all Connector elements in \$CATALINA HOME/conf/server.xml.
- 2. Ensure each Connector has a server attribute and that the server attribute does not reflect Apache Tomcat. Also, make sure that the <code>xpoweredBy</code> attribute is **NOT** set to true.

Remediation:

Perform the following to prevent Tomcat from advertising its presence via the X-PoweredBy HTTP header.

1. Add the xpoweredBy attribute to each Connector specified in \$CATALINA_HOME/conf/server.xml. Set the xpoweredBy attributes value to false.

```
<Connector
...
xpoweredBy="false" />
```

Alternatively, ensure the xpoweredBy attribute for each Connector specified in \$CATALINA HOME/conf/server.xml is absent.

2. Add the server attribute to each Connector specified in \$CATALINA_HOME/conf/server.xml. Set the server attribute value to anything except a blank string.

Default Value:

The default value is false.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html
- 2. https://tomcat.apache.org/tomcat-8.5-doc/config/http.html

CIS Controls:

Version 7

13.2 Remove Sensitive Data or Systems Not Regularly Accessed by Organization Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.5 Disable client facing Stack Traces (Scored)

Profile Applicability:

• Level 1

Description:

When a runtime error occurs during request processing, Apache Tomcat will display debugging information to the requestor. It is recommended that such debug information be withheld from the requestor.

Rationale:

Debugging information, such as that found in call stacks, often contains sensitive information which may be useful to an attacker. By preventing Tomcat from providing this information, the risk of leaking sensitive information to a potential attacker is reduced.

Audit:

Perform the following to determine if Tomcat is configured to prevent sending debug information to the requestor

- 1. Ensure an <error-page> element is defined in \$CATALINA HOME/conf/web.xml.
- 2. Ensure the <error-page> element has an <exception-type> child element with a value of java.lang.Throwable.
- 3. Ensure the <error-page> element has a <location> child element.

Note: Perform the above for each application hosted within Tomcat. Per application instances of web.xml can be found at \$CATALINA_HOME/webapps/<aPP_Name>/WEB-INF/web.xml.

Remediation:

Perform the following to prevent Tomcat from providing debug information to the requestor during runtime errors:

- 1. Create a web page that contains the logic or message you wish to invoke when encountering a runtime error. For example purposes, assume this page is located at /error.jsp.
- 2. Add a child element, <error-page>, to the <web-app> element, in the \$CATALINA_HOME/conf/web.xml file.
- 3. Add a child element, <exception-type>, to the <error-page> element. Set the value of the <exception-type> element to java.lang. Throwable.

4. Add a child element <location> to the <error-page> element. Set the value of the <location> element to the location of page created in step 1.

The resulting entry will look as follows:

```
<error-page>
<span> <exception-type>java.lang.Throwable</exception-type>
  <location>/error.jsp</location>
  </error-page>
```

Default Value:

Tomcat's default configuration does not include an <error-page> element in \$CATALINA_HOME/conf/web.xml. Therefore, Tomcat will provide debug information to the requestor by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/api/org/apache/tomcat/util/descriptor/web/ErrorPage.html

CIS Controls:

Version 7

13.2 <u>Remove Sensitive Data or Systems Not Regularly Accessed by Organization</u>
Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.6 Turn off TRACE (Scored)

Profile Applicability:

• Level 1

Description:

The HTTP TRACE verb provides debugging and diagnostics information for a given request.

Rationale:

Diagnostic information, such as that found in the response to a TRACE request, often contains sensitive information which may useful to an attacker. By preventing Tomcat from providing this information, the risk of leaking sensitive information to a potential attacker is reduced.

Audit:

Perform the following to determine if the server platform, as advertised in the HTTP Server header, has been changed:

- 1. Locate all Connector elements in \$CATALINA HOME/conf/server.xml.
- 2. Ensure each Connector does not have an allowTrace attribute or, if present, the allowTrace attribute is **NOT** set true.

Note: Perform the above for each application hosted within Tomcat. Per application instances of web.xml can be found at

\$CATALINA HOME/webapps/<APP NAME>/WEBINF/web.xml.

Remediation:

Perform the following to prevent Tomcat from accepting a TRACE request: Set the allowTrace attribute for each Connector specified in \$CATALINA HOME/conf/server.xml to false.

```
<Connector ... allowTrace="false" />
```

Alternatively, ensure the allowTrace attribute is absent from each Connector specified in \$CATALINA HOME/conf/server.xml.

Default Value:

Tomcat does not allow the TRACE HTTP verb by default. Tomcat will only allow TRACE if the allowTrace attribute is present and set to true.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html
- 2. https://tomcat.apache.org/tomcat-8.5-doc/security-howto.html
- 3. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html

CIS Controls:

Version 7

13.2 Remove Sensitive Data or Systems Not Regularly Accessed by Organization Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

2.7 Ensure Sever Header is Modified To Prevent Information Disclosure (Not Scored)

Profile Applicability:

• Level 2

Description:

The server header is a vanity header developed to help identify the underlying technology in a server for troubleshooting and identification. This header is unnessesary and could be used to target your website for exploitation. Tomcat does not provide the ability to remove the server header, however, it does provide the ability to modify the header.

Rationale:

The server header may specify the underlying technology used by an application. Attackers are able to conduct reconnaissance on a website using these response headers. This header could be used to target attacks for specific known vulnerabilities associated with the underlying technology. Removing this header will prevent targeting of your application for specific exploits by non-determined attackers.

While this is not the only way to fingerprint a site through the response headers, it makes it harder and prevents some potential attackers from targeting your website.

Audit:

In \$CATALINA_HOME/conf/server.xml, check for the server directive as shown below. If the directive is not present or the directive specifies something revealing on the underlying infrastructure then the server header should be changed.

```
<Connector port="8443" server="Apache" redirectPort="8080" />
```

Remediation:

In \$CATALINA_HOME/conf/server.xml, add the server directive to the connector as shown below replacing apache with the text of your choosing. This text should not help in identifying the server.

```
<Connector port="8443" server="I am a teapot" redirectPort="8080" />
```

Scripted:

• If you do not have the header defined:

```
sed -ir 's/Connector/Connector server="I am a teapot"/g'
$CATALINA_HOME/conf/server.xml
```

• If you already have a header but it is still revealing

```
sed -ir 's/server="[^"]*"/server="I Am A Teapot"/g'
$CATALINA_HOME/conf/server.xml
```

Default Value:

The default value is Apache-Coyote/1.1.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html#server.xml
- 2. https://stackoverflow.com/questions/52637285/replacing-server-header-in-tomcat-with-sed

CIS Controls:

Version 7

13.2 Remove Sensitive Data or Systems Not Regularly Accessed by Organization

Remove sensitive data or systems not regularly accessed by the organization from the network. These systems shall only be used as stand alone systems (disconnected from the network) by the business unit needing to occasionally use the system or completely virtualized and powered off until needed.

3 Protect the Shutdown Port

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the Shutdown command, all applications within Tomcat are halted.

3.1 Set a nondeterministic Shutdown command value (Scored)

Profile Applicability:

• Level 1

Description:

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the SHUTDOWN command, all applications within Tomcat are halted. The shutdown port is not exposed to the network as it is bound to the loopback interface. It is recommended that a nondeterministic value be set for the shutdown attribute in \$CATALINA HOME/conf/server.xml.

Rationale:

Setting the shutdown attribute to a nondeterministic value will prevent malicious local users from shutting down Tomcat.

Audit:

Perform the following to determine if the shutdown port is configured to use the default shutdown command:

Ensure the shutdown attribute in \$CATALINA_HOME/conf/server.xml is not set to SHUTDOWN.

```
$ cd $CATALINA_HOME/conf
$ grep 'shutdown[[:space:]]*=[[:space:]]*"SHUTDOWN"' server.xml
```

Remediation:

Perform the following to set a nondeterministic value for the shutdown attribute. Update the shutdown attribute in \$CATALINA_HOME/conf/server.xml as follows:

```
<Server port="8005" shutdown="NONDETERMINISTICVALUE">
```

Note: NONDETERMINISTICVALUE should be replaced with a sequence of random characters.

Default Value:

The default value for the shutdown attribute is SHUTDOWN.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/server.html
- 2. https://tomcat.apache.org/tomcat-8.5-doc/config/server.html

CIS Controls:

Version 7

4.7 <u>Limit Access to Script Tools</u>

Limit access to scripting tools (such as Microsoft PowerShell and Python) to only administrative or development users with the need to access those capabilities.

3.2 Disable the Shutdown port (Not Scored)

Profile Applicability:

• Level 2

Description:

Tomcat listens on TCP port 8005 to accept shutdown requests. By connecting to this port and sending the Shutdown command, all applications within Tomcat are halted. The shutdown port is not exposed to the network as it is bound to the loopback interface. If this functionality is not used, it is recommended that the shutdown port be disabled.

Rationale:

Disabling the Shutdown port will eliminate the risk of malicious local entities using the shutdown command to disable the Tomcat server.

Audit:

Perform the following to determine if the shutdown port has been disabled: Ensure the port attribute in \$CATALINA HOME/conf/server.xml is set to -1.

```
$ cd $CATALINA_HOME/conf/
$ grep '<Server[[:space:]]\+[^>]*port[[:space:]]*=[[:space:]]*"-1"'
server.xml
```

Remediation:

Set the port to -1 in the \$CATALINA HOME/conf/server.xml to disable the shutdown port

```
<Server port="-1" shutdown="SHUTDOWN">
```

Default Value:

The shutdown port is enabled on TCP port 8005, bound to the loopback address.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/server.html

CIS Controls:

Version 7

9.2 Ensure Only Approved Ports, Protocols and Services Are Running Ensure that only network ports, protocols, and services listening on a system with validated business needs, are running on each system.

4 Protect Tomcat Configurations

The security of processes and data which traverse or depend on Tomcat may become compromised if the Tomcat configurations are not secured.

4.1 Restrict access to \$CATALINA_HOME (Scored)

Profile Applicability:

• Level 1

Description:

SCATALINA_HOME is the environment variable which holds the path to the root Tomcat directory. It is important to protect access to this in order to protect the Tomcat binaries and libraries from unauthorized modification. It is recommended that the ownership of SCATALINA_HOME be tomcat_admin:tomcat. It is also recommended that the permission on SCATALINA_HOME deny read, write, and execute for the world (o-rwx) and deny write access to the group (g-w).

Rationale:

The security of processes and data which traverse or depend on Tomcat may become compromised if the \$CATALINA HOME is not secured.

Audit:

Perform the following to ensure the permission on the \$CATALINA_HOME directory prevent unauthorized modification.

```
$ cd $CATALINA_HOME
$ find . -follow -maxdepth 0 \( -perm /o+rwx,g=w -o ! -user tomcat_admin -o !
-group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to establish the recommended state:

1. Set the ownership of the \$CATALINA HOME to tomcat admin:tomcat.

```
# chown tomcat_admin.tomcat $CATALINA_HOME
```

2. Remove write permissions for the group and read, write, and execute permissions for the world

chmod g-w,o-rwx \$CATALINA_HOME

CIS Controls:

Version 7

14.6 Protect Information through Access Control Lists

Protect all information stored on systems with file system, network share, claims, application, or database specific access control lists. These controls will enforce the principle that only authorized individuals should have access to the information based on their need to access the information as a part of their responsibilities.

4.2 Restrict access to \$CATALINA_BASE (Scored)

Profile Applicability:

• Level 1

Description:

\$CATALINA_BASE is the environment variable that specifies the base directory from which most relative paths are resolved. \$CATALINA_BASE is usually used when there are multiple instances of Tomcat running. It is important to limit access to this in order to protect the Tomcat-related binaries and libraries from unauthorized modification. It is recommended that the ownership of \$CATALINA_BASE be tomcat_admin:tomcat. It is also recommended that the permission on \$CATALINA_BASE deny read, write, and execute for the world (o-rwx) and prevent write deny to the group (g-w).

Rationale:

The security of processes and data which traverse or depend on Tomcat may become compromised if the \$CATALINA BASE is not secured.

Audit:

Perform the following to ensure the permission on the \$CATALINA_BASE directory prevent unauthorized modification.

```
$ cd $CATALINA_BASE
$ find . -follow -maxdepth 0 \( -perm /o+rwx,g=w -o ! -user tomcat_admin -o !
-group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to establish the recommended state:

1. Set the ownership of the \$CATALINA BASE to tomcat_admin:tomcat.

```
# chown tomcat_admin.tomcat $CATALINA_BASE
```

2. Remove write permissions for the group and read, write, and execute permissions for the world

```
# chmod g-w,o-rwx $CATALINA_BASE
```

CIS Controls:

Version 7

14.6 Protect Information through Access Control Lists

Protect all information stored on systems with file system, network share, claims, application, or database specific access control lists. These controls will enforce the principle that only authorized individuals should have access to the information based on their need to access the information as a part of their responsibilities.

4.3 Restrict access to Tomcat configuration directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/conf directory contains Tomcat configuration files. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory deny read, write, and execute for the world (o-rwx) and deny write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently altering Tomcat's configuration.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf are securely configured.

```
# cd $CATALINA_HOME/conf
# find . -maxdepth 0 \( -perm /o+rwx, g=w -o ! -user tomcat_admin -o ! -group
tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to Tomcat configuration files:

1. Set the ownership of the \$CATALINA HOME/conf to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf
```

2. Remove write permissions for the group and read, write, and execute permissions for the world.

```
# chmod g-w,o-rwx $CATALINA_HOME/conf
```

Default Value:

The default permissions of the top-level directories are 770.

Version 7

14.6 Protect Information through Access Control Lists

4.4 Restrict access to Tomcat logs directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/logs directory contains Tomcat logs. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory deny read, write, and execute for the world (o-rwx).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently altering Tomcat's logs.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/logs are securely configured.

```
# cd $CATALINA_HOME
# find logs -follow -maxdepth 0 \( -perm /o+rwx -o ! -user tomcat_admin -o !
-group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to Tomcat log files:

1. Set the ownership of the \$CATALINA HOME/logs to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/logs
```

2. Remove read, write, and execute permissions for the world

```
# chmod o-rwx $CATALINA_HOME/logs
```

Default Value:

The default permissions of the top-level directories are 770.

Version 7

14.6 Protect Information through Access Control Lists

4.5 Restrict access to Tomcat temp directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/temp directory is used by Tomcat to persist temporary information to disk. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permissions on this directory deny read, write, and execute for the world (o-rwx).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of Tomcat processes.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/temp are securely configured.

```
# cd $CATALINA_HOME
# find temp -follow -maxdepth 0 \( -perm /o+rwx -o ! -user tomcat_admin -o !
-group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to Tomcat temp directory:

1. Set the ownership of the \$CATALINA HOME/temp to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/temp
```

2. Remove read, write, and execute permissions for the world

```
# chmod o-rwx $CATALINA_HOME/temp
```

Default Value:

The default permissions of the top-level directories are 770.

Version 7

14.6 Protect Information through Access Control Lists

4.6 Restrict access to Tomcat binaries directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat \$CATALINA_HOME/bin directory contains executes that are part of the Tomcat run-time. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permission on this directory deny read, write, and execute for the world (o-rwx) and deny write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of Tomcat processes.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/bin are securely configured.

```
# cd $CATALINA_HOME
# find bin -follow -maxdepth 0 \( -perm /o+rwx,g=w -o ! -user tomcat_admin -o
! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to Tomcat bin directory:

1. Set the ownership of the \$CATALINA HOME/bin to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/bin
```

2. Remove read, write, and execute permissions for the world

```
# chmod g-w,o-rwx $CATALINA_HOME/bin
```

Default Value:

The default permissions of the top-level directories are 770.

Version 7

14.6 Protect Information through Access Control Lists

4.7 Restrict access to Tomcat web application directory (Scored)

Profile Applicability:

• Level 1

Description:

The Tomcat $CATALINA_HOME/webapps$ directory contains web applications that are deployed through Tomcat. It is recommended that the ownership of this directory be tomcat_admin:tomcat. It is also recommended that the permission on $CATALINA_HOME/webapps$ deny read, write, and execute for the world (o-rwx) and deny write access to the group (g-w).

Rationale:

Restricting access to these directories will prevent local users from maliciously or inadvertently affecting the integrity of web applications.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/webapps are securely configured.

```
# cd $CATALINA_HOME
# find webapps -follow -maxdepth 0 \(( -perm /o+rwx,g=w -o ! -user tomcat admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to Tomcat webapps directory:

1. Set the ownership of the \$CATALINA_HOME/webapps to tomcat_admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/webapps
```

2. Remove read, write, and execute permissions for the world.

```
# chmod g-w,o-rwx $CATALINA_HOME/webapps
```

Default Value:

The default permissions of the top-level directories are 770.

Version 7

14.6 Protect Information through Access Control Lists

4.8 Restrict access to Tomcat catalina.properties (Scored)

Profile Applicability:

• Level 1

Description:

catalina.properties is a Java properties file which contains settings for Tomcat including class loader information, security package lists, and performance properties. It is recommended that access to this file properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/catalina.properties care securely configured.

```
# cd $CATALINA_HOME/conf/
# find catalina.properties -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+x -o !
-user tomcat_admin -o ! -group tomcat \( ) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to catalina.properties:

1. Set the ownership of the \$CATALINA_HOME/conf/catalina.properties to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/catalina.properties
```

2. Set the permissions of the $CATALINA_HOME/conf/catalina.properties$ to 600

```
# chmod 600 $CATALINA_HOME/conf/catalina.properties
```

Default Value:

The default permissions of the top-level directories are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.9 Restrict access to Tomcat catalina.policy (Scored)

Profile Applicability:

• Level 1

Description:

The catalina.policy file is used to configure security policies for Tomcat. It is recommended that access to this file has the proper permissions to properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/catalina.policy care securely configured.

```
# cd $CATALINA_HOME/conf/
# find catalina.policy -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+x -o ! -
user tomcat_admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to \$CATALINA HOME/conf/catalina.policy.

1. Set the owner and group owner of the contents of \$CATALINA HOME/conf/catalina.policy to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/catalina.policy
```

2. Set the permissions of the \$CATALINA_HOME/conf/catalina.policy file to 600.

```
# chmod 600 $CATALINA_HOME/conf/catalina.policy
```

Default Value:

The default permissions of catalina.policy are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.10 Restrict access to Tomcat context.xml (Scored)

Profile Applicability:

• Level 1

Description:

The context.xml file is loaded by all web applications and sets certain configuration options. It is recommended that access to this file properly protect from unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/context.xml care securely configured.

```
# cd $CATALINA_HOME/conf
# find context.xml -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+x -o ! -user
tomcat_admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to context.xml:

1. Set the ownership of the \$CATALINA_HOME/conf/context.xml to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/context.xml
```

2. Set the permissions for the \$CATALINA HOME/conf/context.xml to 600.

```
# chmod 600 $CATALINA_HOME/conf/context.xml
```

Default Value:

The default permissions of context.xml are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.11 Restrict access to Tomcat logging.properties (Scored)

Profile Applicability:

• Level 1

Description:

logging.properties is a Tomcat file which specifies the logging configuration. It is recommended that access to this file properly protect against unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/logging.properties care securely configured.

```
# cd $CATALINA_HOME/conf
# find logging.properties -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+x -o !
-user tomcat_admin -o ! -group tomcat \( ) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to logging.properties:

1. Set the ownership of the \$CATALINA_HOME/conf/logging.properties to tomcat_admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/logging.properties
```

2. Set the permissions for the \$CATALINA HOME/conf/logging.properties file to 600.

```
# chmod 600 $CATALINA_HOME/conf/logging.properties
```

Default Value:

The default permissions are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.12 Restrict access to Tomcat server.xml (Scored)

Profile Applicability:

• Level 1

Description:

server.xml contains Tomcat servlet definitions and configurations. It is recommended that access to this file properly protect against unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/server.xml care securely configured.

```
# cd $CATALINA_HOME/conf/
# find server.xml -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+x -o ! -user
tomcat_admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to server.xml:

 Set the ownership of the \$CATALINA_HOME/conf/server.xml to tomcat_admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/server.xml
```

2. Set the permissions of the \$CATALINA HOME/conf/server.xml to 600

```
# chmod 600 $CATALINA_HOME/conf/server.xml
```

Default Value:

The default permissions of the top-level directories are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.13 Restrict access to Tomcat tomcat-users.xml (Scored)

Profile Applicability:

• Level 1

Description:

tomcat-users.xml contains authentication information for Tomcat applications. It is recommended that access to this file properly protect against unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/tomcat-users.xml care securely configured.

```
# cd $CATALINA_HOME/conf/
# find tomcat-users.xml -follow -maxdepth 0 \( -perm /o+rwx,g=rwx,u+x -o ! -
user tomcat_admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to tomcat-users.xml:

 Set the ownership of the \$CATALINA_HOME/conf/tomcat-users.xml to tomcat_admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/tomcat-users.xml
```

2. Set the permissions of the \$CATALINA HOME/conf/tomcat-users.xml to 600

```
# chmod 600 $CATALINA_HOME/conf/tomcat-users.xml
```

Default Value:

The default permissions of the top-level directories are 600.

Version 7

14.6 Protect Information through Access Control Lists

4.14 Restrict access to Tomcat web.xml (Scored)

Profile Applicability:

• Level 1

Description:

web.xml is a Tomcat configuration file that stores application configuration settings. It is recommended that access to this file properly protect against unauthorized changes.

Rationale:

Restricting access to this file will prevent local users from maliciously or inadvertently altering Tomcat's security policy.

Audit:

Perform the following to determine if the ownership and permissions on \$CATALINA HOME/conf/web.xml are securely configured.

```
# cd $CATALINA_HOME/conf/
# find web.xml -follow -maxdepth 0 \( -perm /o+rwx,g+rwx,u+wx -o ! -user
tomcat_admin -o ! -group tomcat \) -ls
```

The above command should not produce any output.

Remediation:

Perform the following to restrict access to web.xml:

1. Set the ownership of the \$CATALINA HOME/conf/web.xml to tomcat admin:tomcat.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/conf/web.xml
```

2. Set the permissions for the \$CATALINA HOME/conf/web.xml file to 400.

```
# chmod 400 $CATALINA_HOME/conf/web.xml
```

Default Value:

The default permissions for web.xml are 400.

Version 7

14.6 Protect Information through Access Control Lists

5 Configure Realms

A Tomcat realm is a database of usernames and passwords used to identify valid users of web applications.

5.1 Use secure Realms (Scored)

Profile Applicability:

• Level 2

Description:

A realm is a database of usernames and passwords used to identify valid users of web applications. Review the Realms configuration to ensure Tomcat is not configured to use MemoryRealm, JDBCRealm, UserDatabaseRealm and JAASRealm.

Rationale:

According to the Tomcat documentation: the MemoryRealm and JDBCRealm are not designed for production usage and could result in reduced availability; the UserDatabaseRealm is not intended for large-scale installations; and the JAASRealm is not widely used and therefore the code is not as mature as the other realms.

Audit:

Perform the following to ensure an improper realm is not in use:

```
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep MemoryRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep JDBCRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep
UserDatabaseRealm
# grep "Realm className" $CATALINA_HOME/conf/server.xml | grep JAASRealm
```

The above commands should not produce any output.

Remediation:

Set the Realm className setting in \$CATALINA_HOME/conf/server.xml to one of the appropriate realms.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/realm-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html

Version 7

14.6 Protect Information through Access Control Lists

5.2 Use LockOut Realms (Scored)

Profile Applicability:

• Level 2

Description:

A LockOut realm wraps around standard realms adding the ability to lock a user out after multiple failed logins.

Rationale:

Locking out a user after multiple failed logins slows down attackers from brute forcing logins.

Audit:

Perform the following to check to see if a LockOut realm is being used:

```
# grep "LockOutRealm" $CATALINA_HOME/conf/server.xml
```

Remediation:

Create a lockout realm wrapping the main realm similar to the example below:

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/realm-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/realm.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

Maintain documented, standard security configuration standards for all authorized operating systems and software.

6 Connector Security

Tomcat Connector Security will ensure applications built on Tomcat have an accurate depiction of the context and security guarantees provided to them.

6.1 Setup Client-cert Authentication (Scored)

Profile Applicability:

• Level 2

Description:

Client-cert authentication requires each client connecting to the server to have a certificate to authenticate. This is generally regarded as stronger authentication than a password as it requires the client to have the certificate and not just a password.

Rationale:

Certificate based authentication is more secure than password based authentication.

Audit:

Review the Connector configuration in server.xml and ensure the clientAuth is set to true and, in Tomcat 8.5.x, certificateVerification is set to required.

Remediation:

In the Connector element, set the clientAuth to true and, in Tomcat 8.5.x, set the certificateVerification to required

```
<Connector
    port="8443" minProcessors="5" maxProcessors="75"
    enableLookups="true" disableUploadTimeout="true"
    acceptCount="100" debug="0" scheme="https" secure="true";
    clientAuth="true" sslProtocol="TLS"/>
    ...
<Connector ...>
    <SSLHostConfig
    certificateVerification="required"
    />
```

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html

- 3. https://tomcat.apache.org/tomcat-8.5-doc/ssl-howto.html
- 4. https://tomcat.apache.org/tomcat-8.5-doc/config/http.html#SSL Support-SSLHostConfig

Version 7

16.4 Encrypt or Hash all Authentication Credentials
Encrypt or hash with a salt all authentication credentials when stored.

6.2 Ensure SSLEnabled is set to True for Sensitive Connectors (Not Scored)

Profile Applicability:

• Level 1

Description:

The SSLEnabled setting determines if SSL is enabled for a specific Connector. It is recommended that SSL be utilized for any Connector that sends or receives sensitive information, such as authentication credentials or personal information.

Rationale:

The SSLEnabled setting ensures SSL is active, which will in-turn ensure the confidentiality and integrity of sensitive information while in transit.

Audit:

Review the server.xml and ensure all Connectors sending or receiving sensitive information have the SSLEnabled attribute set to true.

Remediation:

In server.xml, set the SSLEnabled attribute to true for each Connector that sends or receives sensitive information:

```
<Connector
...
SSLEnabled="true"
...
/>
```

Default Value:

SSLEnabled is set to false.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html
- 3. https://tomcat.apache.org/tomcat-8.5-doc/security-howto.html

6.3 Ensure scheme is set accurately (Scored)

Profile Applicability:

• Level 1

Description:

The scheme attribute is used to indicate to callers of request.getScheme() which scheme is in use by the Connector. Ensure the scheme attribute is set to http for Connectors operating over HTTP. Ensure the scheme attribute is set to https for Connectors operating over HTTPS.

Rationale:

Maintaining parity between the scheme in use by the Connector and advertised by request.getScheme() will ensure applications built on Tomcat have an accurate depiction of the context and security guarantees provided to them.

Audit:

Review the server.xml to ensure the Connector's scheme attribute is set to http for Connectors operating over HTTP. Also ensure the Connector's scheme attribute is set to https for Connectors operating over HTTPS.

Remediation:

In server.xml, set the Connector's scheme attribute to http for Connectors operating over HTTP. Set the Connector's scheme attribute to https for Connectors operating over HTTPS.

```
<Connector
...
scheme="https"
...
/>
```

Default Value:

The scheme attribute is set to http.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

6.4 Ensure secure is set to true only for SSL-enabled Connectors (Scored)

Profile Applicability:

• Level 1

Description:

The secure attribute is used to convey Connector security status to applications operating over the Connector. This is typically achieved by calling request.isSecure(). Ensure the secure attribute is only set to true for Connectors operating with the SSLEnabled attribute set to true.

Rationale:

Accurately reporting the security state of the Connector will help ensure that applications built on Tomcat are not unknowingly relying on security controls that are not in place.

Audit:

Review the server.xml and ensure the secure attribute is set to true for those Connectors having SSLEnabled set to true. Also, ensure the secure attribute set to false for those Connectors having SSLEnabled set to false.

Remediation:

For each Connector defined in server.xml, set the secure attribute to true for those Connectors having SSLEnabled set to true. Set the secure attribute to false for those Connectors having SSLEnabled set to false.

Default Value:

The secure attribute is set to false.

References:

- https://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
 https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

6.5 Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)

Profile Applicability:

• Level 1

Description:

The sslProtocol setting determines which protocol Tomcat will use to protect traffic. It is recommended that sslProtocol attribute be set to TLS.

Rationale:

The TLS protocol does not contain weaknesses that affect other secure transport protocols, such as SSLv1 or SSLv2. Therefore, TLS is leveraged to protect the confidentiality and integrity of data while in transit.

Audit:

Review server.xml to ensure the sslProtocol attribute is set to TLS for all Connectors having SSLEnabled set to true.

Remediation:

In server.xml, set the sslProtocol attribute to TLS for Connectors having SSLEnabled set to true.

```
<Connector
...
sslProtocol="TLS"
...
/>
```

In Tomcat 8.5.x using JSSE, set it to TLS or alternatively remove it.

```
<Connector
...

<SSLHostConfig
...

sslProtocol="TLS"
...
/>
```

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/ssl-howto.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

3. https://tomcat.apache.org/tomcat-8.5-doc/config/http.html

CIS Controls:

Version 7

14.4 Encrypt All Sensitive Information in Transit Encrypt all sensitive information in transit.

18.5 <u>Use Only Standardized and Extensively Reviewed Encryption Algorithms</u> Use only standardized and extensively reviewed encryption algorithms.

6.6 Control the maximum size of a POST request that will be parsed for parameter (Scored)

Profile Applicability:

• Level 1

Description:

The maxPostSize attribute controls the maximum size of a POST request which will be parsed for parameters. Setting a proper size is recommended to reduce DOS attack.

Rationale:

The maxPostSize value is the maximum size in bytes of the POST which will be handled by the container FORM URL parameter parsing. The parameters are cached for the duration of the request. Limit its size to reduce exposure to a DOS attack.

Audit:

Check maxPostSize for each of connectors:

```
<Connector
...
maxPostSize=2097152
...
```

If not set within Connector, then default value 2097152 (2 MB) is used.

Remediation:

Set the ${\tt maxPostSize}$ attributes to each Connector specified in ${\tt SCATALINA_HOME/conf/server.xml}$ per requirement.

```
<Connector
...
maxPostSize=2097152
...</pre>
```

Impact:

Disabling the maxPostSize may increase the risk for a DOS attack.

Default Value:

2097152 **(2 MB)**

References:

- https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html
 https://tomcat.apache.org/tomcat-8.5-doc/security-howto.html

7 Establish and Protect Logging Facilities

Enable logging and ensure logs are properly protected

7.1 Application specific logging (Scored)

Profile Applicability:

• Level 2

Description:

By default, <code>java.util.logging</code> does not provide the capabilities to configure per-web application settings, only per VM. In order to overcome this limitation Tomcat implements JULI as a wrapper for <code>java.util.logging</code>. JULI provides additional configuration functionality so you can set each web application to have unique logging specifications.

Rationale:

Establishing per application logging profiles will help ensure that each application's logging verbosity is set to an appropriate level in order to provide appropriate information when needed for security review.

Audit:

Ensure a logging.properties file is located at \$CATALINA_HOME/webapps/<app name>/WEB-INF/classes.

Remediation:

Create a logging.properties file and place that into your application web-INF/classes directory.

Note: By default, installing Tomcat places a <code>logging.properties</code> file in ${\tt SCATALINA_HOME/conf}$. This file can be used as base for an application specific logging properties file.

Default Value:

By default, per application logging is not configured.

Version 7

6.3 Enable Detailed Logging

Enable system logging to include detailed information such as an event source, date, user, timestamp, source addresses, destination addresses, and other useful elements.

7.2 Specify file handler in logging.properties files (Scored)

Profile Applicability:

• Level 1

Description:

Handlers specify where log messages are sent. Console handlers send log messages to the Java console and File handlers specify logging to a file.

Rationale:

Utilizing file handlers will ensure that security event information is persisted to disk.

Audit:

Review each application's logging.properties file located in the applications \$CATALINA_HOME/webapps/<app name>/WEB-INF/classes directory and determine if the file handler properties are set.

```
$ grep handlers \
$CATALINA_HOME/webapps/<app name>/WEB-INF/classes/logging.properties
```

In the instance where an application specific logging has not been created, the logging.properties file will be located in \$CATALINA HOME/conf

```
$ grep handlers $CATALINA HOME/conf/logging.properties
```

Remediation:

Add the following entries to your logging.properties file if they do not exist.

```
handlers=...,<prefix>org.apache.juli.FileHandler,...
```

Ensure logging is not off and set the logging level to the desired level such as:

```
<prefix>org.apache.juli.FileHandler.level=FINEST
```

Default Value:

No value for new applications by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/logging.html

Version 7

6.3 Enable Detailed Logging

Enable system logging to include detailed information such as an event source, date, user, timestamp, source addresses, destination addresses, and other useful elements.

7.3 Ensure className is set correctly in context.xml (Scored)

Profile Applicability:

• Level 2

Description:

Ensure the className attribute is set to AccessLogValve. The className attribute determines the access log valve to be used for logging.

Rationale:

Some log valves are not suited for production and should not be used. Apache recommends org.apache.catalina.valves.AccessLogValve

Audit:

Execute the following to ensure className is set properly:

```
# grep org.apache.catalina.valves.AccessLogValve $CATALINA_HOME/webapps/<app
name>/META-INF/context.xml
```

Remediation:

Add the following statement into the \$CATALINA_HOME/webapps/<app name>/META-INF/context.xml file if it does not already exist.

```
<Valve
className="org.apache.catalina.valves.AccessLogValve"
directory="$CATALINA_HOME/logs/"
prefix="access_log"
fileDateFormat="yyyy-MM-dd.HH"
suffix=".log"
pattern="%t %H cookie:%{SESSIONID}c request:%{SESSIONID}r %m %U %s %q %r"
/>
```

Default Value:

Does not exist by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

Version 7

6.3 Enable Detailed Logging

Enable system logging to include detailed information such as an event source, date, user, timestamp, source addresses, destination addresses, and other useful elements.

7.4 Ensure directory in context.xml is a secure location (Scored)

Profile Applicability:

• Level 1

Description:

The directory attribute tells Tomcat where to store logs. It is recommended that the location referenced by the directory attribute be secured.

Rationale:

Securing the log location will help ensure the integrity and confidentiality of web application activity.

Audit:

Review the permissions of the directory specified by the directory attribute to ensure the permissions are o-rwx and owned by tomcat admin:tomcat:

```
# grep directory context.xml
# ls -ld <log location>
```

Remediation:

Perform the following:

1. Add the following statement into the \$CATALINA_HOME/webapps/<app name>/META-INF/context.xml file if it does not already exist.

```
<Valve className="org.apache.catalina.valves.AccessLogValve"
directory="$CATALINA_HOME/logs/"
prefix="access_log" fileDateFormat="yyyy-MM-dd.HH" suffix=".log"
pattern="%t %H cookie:%{SESSIONID}c
request:%{SESSIONID}r %m %U %s %q %r"/>
```

2. Set the location pointed to by the directory attribute to be owned by tomcat admin: tomcat with permissions of o-rwx.

```
# chown tomcat_admin:tomcat $CATALINA_HOME/logs
# chmod o-rwx $CATALINA_HOME/logs
```

Default Value:

Does not exist by default

Version 7

14.6 Protect Information through Access Control Lists

Protect all information stored on systems with file system, network share, claims, application, or database specific access control lists. These controls will enforce the principle that only authorized individuals should have access to the information based on their need to access the information as a part of their responsibilities.

7.5 Ensure pattern in context.xml is correct (Scored)

Profile Applicability:

• Level 1

Description:

The pattern setting informs Tomcat what information should be logged per application. At a minimum, enough information to uniquely identify a request, what was requested, where the requested originated from, and when the request occurred should be logged. The following will log the request date and time (%t), the requested URL (%U), the remote IP address (%a), the local IP address (%A), the request method (%m), the local port (%p), query string, if present, (%q), and the HTTP status code of the response (%s).

```
pattern="%t %U %a %A %m %p %q %s"
```

Rationale:

The level of logging detail prescribed will assist in identifying correlating security events or incidents.

Audit:

Review the pattern settings to ensure it contains all of the variables required by the installation.

```
# grep pattern $CATALINA HOME/webapps/<app name>/META-INF/context.xml
```

Remediation:

Add the following statement into the \$CATALINA_HOME/webapps/<app name>/META-INF/context.xml file if it does not already exist.

```
<Valve
className="org.apache.catalina.valves.AccessLogValve"
directory="$CATALINA_HOME/logs/" prefix="access_log" fileDateFormat="yyyy-MM-
dd.HH" suffix=".log"
pattern="%h %t %H cookie:%{SESSIONID}c request:%{SESSIONID}r %m %U %s %q %r"
/>
```

Default Value:

Does not exist by default.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

CIS Controls:

Version 7

1. 6.3 Enable Detailed Logging

Enable system logging to include detailed information such as an event source, date, user, timestamp, source addresses, destination addresses, and other useful elements.

7.6 Ensure directory in logging.properties is a secure location (Scored)

Profile Applicability:

• Level 1

Description:

The directory attribute tells Tomcat where to store logs. The directory value should be a secure location with restricted access.

Rationale:

Securing the log location will help ensure the integrity and confidentiality of web application activity records.

Audit:

Review the permissions of the directory specified by the directory setting to ensure the permissions are o-rwx and owned by tomcat admin:tomcat:

```
# grep directory logging.properties
# ls -ld <log_location>
```

Remediation:

Perform the following:

 $1. \ \ Add \ the \ following \ properties \ into \ your \ \texttt{logging.properties} \ file \ if \ they \ do \ not \ exist$

```
<application_name>.org.apache.juli.FileHandler.directory=<log_location>
<application_name>.org.apache.juli.FileHandler.prefix=<application_name
>
```

2. Set the location pointed to by the directory attribute to be owned by tomcat_admin:tomcat with permissions of o-rwx.

```
# chown tomcat_admin:tomcat <log_location>
# chmod o-rwx <log_location>
```

Default Value:

The directory location is configured to store logs in \$CATALINA HOME/logs.

Version 7

14.6 Protect Information through Access Control Lists

Protect all information stored on systems with file system, network share, claims, application, or database specific access control lists. These controls will enforce the principle that only authorized individuals should have access to the information based on their need to access the information as a part of their responsibilities.

8 Configure Catalina Policy

Configuring Catalina Policy prevents web applications from accessing restricted or unknown packages which may be malicious or dangerous to the application.

8.1 Restrict runtime access to sensitive packages (Scored)

Profile Applicability:

• Level 1

Description:

package.access grants or revokes access to listed packages during runtime. It is recommended that application access to certain packages be restricted.

Rationale:

Prevent web applications from accessing restricted or unknown packages which may be malicious or dangerous to the application.

Audit:

Review package.access list in $CATALINA_HOME/conf/catalina.properties$ to ensure only allowed packages are defined.

Remediation:

Edit $CATALINA_BASE/conf/catalina.properties$ by adding allowed packages to the package.access list:

```
package.access =
sun.,org.apache.catalina.,org.apache.coyote.,org.apache.tomcat.,
org.apache.jasper
```

Default Value:

The default package access value within $\texttt{SCATALINA_BASE/conf/catalina.properties}$ is:

```
package.access =
sun.,org.apache.catalina.,org.apache.coyote.,org.apache.tomcat.,
org.apache.jasper
```

CIS Controls:

Version 7

14.6 Protect Information through Access Control Lists

Protect all information stored on systems with file system, network share, claims, application, or database specific access control lists. These controls will enforce the principle that only authorized individuals should have access to the information based on their need to access the information as a part of their responsibilities.

9 Application Deployment

By running Tomcat with the Security Manager, applications are run in a sandbox which can prevent untrusted code from accessing files on the file system.

9.1 Starting Tomcat with Security Manager (Scored)

Profile Applicability:

• Level 1

Description:

Configure applications to run in a sandbox using the Security Manager. The Security Manager restricts what classes Tomcat can access thus protecting your server from mistakes, Trojans, and malicious code.

Rationale:

By running Tomcat with the Security Manager, applications are run in a sandbox which can prevent untrusted code from accessing files on the file system.

Audit:

Review the start up configuration in /etc/init.d for Tomcat to determine if Tomcat is started with the -security option,

Remediation:

The security policies implemented by the Java SecurityManager are configured in the \$CATALINA_HOME/conf/catalina.policy file. Once you have configured the catalina.policy file for use with a SecurityManager, Tomcat can be started with a SecurityManager in place by using the --security option:

On Unix:

\$ \$CATALINA_HOME/bin/catalina.sh start -security

On Windows:

C:\> %CATALINA HOME%\bin\catalina start -security

Default Value:

By default the -security option is not utilized.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/security-manager-howto.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

9.2 Disabling auto deployment of applications (Scored)

Profile Applicability:

• Level 2

Description:

Tomcat allows auto deployment of applications while Tomcat is running. It is recommended that this capability be disabled.

Rationale:

This could allow malicious or untested applications to be deployed and should be disabled.

Audit:

Perform the following to ensure autoDeploy is set to false.

grep "autoDeploy" \$CATALINA HOME/conf/server.xml

Remediation:

In the \$CATALINA HOME/conf/server.xml file, change autoDeploy to false.

autoDeploy="false"

Default Value:

autoDeploy is set to true.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/deployer-howto.html#Deploying on a running Tomcat server
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

9.3 Disable deploy on startup of applications (Scored)

Profile Applicability:

• Level 2

Description:

Tomcat allows auto deployment of applications on startup. It is recommended that this capability be disabled.

Rationale:

This could allow malicious or untested applications to be deployed and should be disabled.

Audit:

Perform the following to ensure deployOnStartup is set to false.

grep "deployOnStartup" \$CATALINA HOME/conf/server.xml

Remediation:

In the \$CATALINA_HOME/conf/server.xml file, change deployOnStartup to false.

deployOnStartup="false"

Default Value:

deployOnStartup is set to true

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/deployer-howto.html#Deployment on Tomcat startup
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html#Automatic Application Deployment
- 3. https://tomcat.apache.org/tomcat-8.0-doc/config/host.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10 Miscellaneous Configuration Settings

Store web content on a separate partition from Tomcat system files.

10.1 Ensure Web content directory is on a separate partition from the Tomcat system files (Not Scored)

Profile Applicability:

• Level 1

Description:

Store web content on a separate partition from Tomcat system files.

Rationale:

The web document directory is where the files which are served to the end user reside. In the past, directory traversal exploits have allowed malicious users to wreak havoc on a web server including executing code, uploading files, and reading sensitive data. Even if you do not have any directory traversal exploits in your server or code at this time, that doesn't mean they won't be introduced in the future. Moving your web document directory onto a different partition will prevent these kinds of attacks from doing more damage to other parts of the file system.

Audit:

Locate the Tomcat system files and web content directory. Review the system partitions and ensure the system files and web content directory are on separate partitions.

```
# df $CATALINA_HOME/webapps
# df $CATALINA_HOME
```

Note: Use the default value webapps which is defined by appBase attribute here.

Remediation:

Move the web content files to a separate partition from the tomcat system files and update your configuration.

Default Value:

Not Applicable

Version 7

2.10 Physically or Logically Segregate High Risk Applications

Physically or logically segregated systems should be used to isolate and run software that is required for business operations but incur higher risk for the organization.

10.2 Restrict access to the web administration application (Not Scored)

Profile Applicability:

• Level 2

Description:

Limit access to the web administration application to only those with a justified need.

Rationale:

Limiting access to the least privilege will ensure only those people with a justified need will have access to a resource. The web administration application should be limited to only administrators.

Audit:

Review \$CATALINA_HOME/conf/server.xml to determine whether the RemoteAddrValve option is uncommented and configured to only allow access to systems required to connect.

Remediation:

For the administration application, edit $CATALINA_HOME/conf/server.xml$ and uncomment the following:

```
<Valve className="org.apache.catalina.valves.RemoteAddrValve"
allow="127\.0\.0\.1"/>
```

Note: The RemoteAddrValve property expects a regular expression, therefore periods and other regular expression meta-characters must be escaped.

Default Value:

By default, this configuration is not present.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html

Version 7

4.7 <u>Limit Access to Script Tools</u>

Limit access to scripting tools (such as Microsoft PowerShell and Python) to only administrative or development users with the need to access those capabilities.

10.3 Restrict manager application (Not Scored)

Profile Applicability:

• Level 2

Description:

Limit access to the manager application to only those with a justified need.

Rationale:

Limiting access to the least privilege will ensure only those people with a justified need will have access to a resource The manager application should be limited to only administrators.

Audit:

Review \$CATALINA_HOME/conf/<enginename>/<hostname>/manager.xml to determine if the RemoteAddrValve option is uncommented and configured to only allow access to systems required to connect.

Remediation:

For the manager application, edit

\$CATALINA HOME/conf/<enginename>/<hostname>/manager.xml, and add the bolded line:

Add hosts, comma separated, which are allowed to access the admin application.

Note: The RemoteAddrValve property expects a regular expression, therefore periods and other regular expression meta-characters must be escaped.

Default Value:

By default this setting is not present

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/manager-howto.html

Version 7

4.7 <u>Limit Access to Script Tools</u>

Limit access to scripting tools (such as Microsoft PowerShell and Python) to only administrative or development users with the need to access those capabilities.

10.4 Force SSL when accessing the manager application (Scored)

Profile Applicability:

• Level 1

Description:

Use the transport-guarantee attribute to ensure SSL protection when accessing the manager application.

Rationale:

By default when accessing the manager application, login information is sent over the wire in plain text. By setting the transport-guarantee within web.xml, SSL is enforced.

Note: This requires SSL to be configured.

Audit:

Ensure \$CATALINA_HOME/webapps/manager/WEB-INF/web.xml has the <transport-quarantee> set to CONFIDENTIAL.

grep transport-guarantee \$CATALINA HOME/webapps/manager/WEB-INF/web.xml

Remediation:

Set <transport-guarantee> to CONFIDENTIAL in $CATALINA_HOME/webapps/manager/WEB-INF/web.xml$:

```
<security-constraint>
    <user-data-constraint>
        <transport-guarantee>CONFIDENTIAL</transport-guarantee>
        <user-data-constraint>
        </security-constraint>
```

Default Value:

By default this configuration is not present.

References:

1. https://www.owasp.org/index.php/Securing tomcat

Version 7

14.4 Encrypt All Sensitive Information in Transit Encrypt all sensitive information in transit.

10.5 Rename the manager application (Scored)

Profile Applicability:

• Level 2

Description:

The manager application allows administrators to manage Tomcat remotely via a web interface. The manager application should be renamed to make it harder for attackers or automated scripts to locate.

Rationale:

By relocating the manager applications, an attacker will need to guess its location rather than simply navigate to the standard location in order to carry out an attack.

Audit:

Ensure \$CATALINA_HOME/conf/Catalina/localhost/manager.xml, \$CATALINA_HOME/webapps/host-manager/manager.xml, \$CATALINA_HOME/webapps/manager and \$CATALINA_HOME/webapps/manager do not exist.

Remediation:

Perform the following to rename the manager application:

1. Rename the manager application XML file:

```
# mv $CATALINA_HOME/webapps/host-manager/manager.xml \
$CATALINA_HOME/webapps/host-manager/<new-name>.xml
```

- 2. Update the docBase attribute within \$CATALINA_HOME/webapps/host-manager/<new-name>.xml to \$CATALINA HOME/webapps/<new-name>
- $3. \;\; Move \ CATALINA_HOME/webapps/manager to \ CATALINA_HOME/webapps/<new-name>$

```
# mv $CATALINA_HOME/webapps/manager $CATALINA_HOME/webapps/<new-name>
```

Default Value:

The default name of the manager application is manager and is located at:

\$CATALINA_HOME/webapps/manager

References:

1. https://www.owasp.org/index.php/Securing tomcat

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.6 Enable strict servlet Compliance (Scored)

Profile Applicability:

• Level 1

Description:

The STRICT_SERVLET_COMPLIANCE influences Tomcat's behavior in several subtle ways. See the References below for the complete list. It is recommended that STRICT SERVLET COMPLIANCE be set to true.

Rationale:

When STRICT_SERVLET_COMPLIANCE is set to true, Tomcat will always send an HTTP Content-type header when responding to requests. This is significant as the behavior of web browsers is inconsistent in the absence of the Content-type header. Some browsers will attempt to determine the appropriate content-type by sniffing

Audit:

Ensure the -Dorg.apache.catalina.STRICT_SERVLET_COMPLIANCE=true parameter is present in the start up script which, by default, is located at \$CATALINA HOME/bin/catalina.sh.

Remediation:

To start Tomcat with strict compliance enabled, add -

Dorg.apache.catalina.STRICT SERVLET COMPLIANCE=true the to the startup script.

Impact:

Changing this to true will change a number of other default values which is likely to break the majority of systems as some browsers are unable to correctly handle the cookie headers that result from a strict adherence to the specifications. Please refer to the referenced documentation for a complete list of changed values. Defaults, regardless of whether or not they have been changed by setting

org.apache.catalina.STRICT_SERVLET_COMPLIANCE can always be overridden by explicitly setting the appropriate system property or element attribute.

Default Value:

By default value is false.

Refer	ences:					
1.	https://tor	ncat.apache.org	g/tomcat-8.0)-doc/confi	g/systemp	rops.html

10.7 Turn off session facade recycling (Scored)

Profile Applicability:

• Level 1

Description:

The RECYCLE_FACADES can specify if a new facade will be created for each request. If a new facade is not created there is a potential for information leakage from a prior session.

Rationale:

When RECYCLE_FACADES is set to false, Tomcat will recycle the session facade between requests which may result in information leakage.

Audit:

Ensure -Dorg.apache.catalina.connector.RECYCLE_FACADES=true is added to the start up script which, by default, is located at \$CATALINA HOME/bin/catalina.sh.

Remediation:

To start Tomcat with RECYCLE_FACADES set to true, add

Dorg.apache.catalina.connector.RECYCLE FACADES=true to your startup script.

Default Value:

The default value is false.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/systemprops.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/security-howto.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.8 Do not allow additional path delimiters (Scored)

Profile Applicability:

• Level 2

Description:

Being able to specify different path-delimiters on Tomcat creates the possibility that an attacker can access applications that were previously blocked by a proxy like mod proxy.

Rationale:

Allowing additional path-delimiters allows for an attacker to get to an application or area which was not previously visible.

Audit:

Ensure the -Dorg.apache.catalina.connector.CoyoteAdapter.ALLOW_BACKSLASH=false and -Dorg.apache.tomcat.util.buf.UDecoder.ALLOW_ENCODED_SLASH=false parameters are added to the start up script which, by default, is located at \$CATALINA HOME/bin/catalina.sh.

Remediation:

To start Tomcat with ALLOW_BACKSLASH and ALLOW_ENCODED_SLASH set to false, add - Dorg.apache.catalina.connector.CoyoteAdapter.ALLOW_BACKSLASH=false and - Dorg.apache.tomcat.util.buf.UDecoder.ALLOW_ENCODED_SLASH=false to your startup script.

Default Value:

By default both parameters are set to false.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/systemprops.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.9 Do not allow custom header status messages (Scored)

Profile Applicability:

• Level 2

Description:

The ability to specify custom status messages opens up the potential for additional headers to be injected. If custom header status messages are required make sure it is only in US-ASCII and does not include any user-supplied data.

Rationale:

Allowing user-supplied data into a header creates the potential for cross-site scripting (XSS).

Audit:

Ensure -Dorg.apache.coyote.USE_CUSTOM_STATUS_MSG_IN_HEADER=false is added to the start up script which, by default, is located at \$CATALINA_HOME/bin/catalina.sh.

Remediation:

To start Tomcat with use_custom_status_msg_in_header set to false, add - Dorg.apache.coyote.USE_CUSTOM_STATUS_MSG_IN_HEADER=false to your startup script.

Default Value:

By default this is set to false.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/systemprops.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.10 Configure connectionTimeout (Scored)

Profile Applicability:

• Level 2

Description:

The connectionTimeout setting allows Tomcat to close idle sockets after a specific amount of time to save system resources.

Rationale:

Closing idle sockets reduces system resource usage which can provide better performance and help protect against Denial of Service (Dos) attacks.

Audit:

Locate each connectionTimeout setting in \$CATALINA_HOME/conf/server.xml and verify the setting is correct.

grep connectionTimeout \$CATALINA HOME/conf/server.xml

Remediation:

Set the connectionTimeoutfor each connector in \$CATALINA_HOME/conf/server.xml to optimal number of milliseconds based on hardware resources, load, and number of concurrent connections.

connectionTimeout="60000"

Impact:

This timeout will also apply when reading any request body when disableUploadTimeout is not set to false.

Default Value:

By default this is set to 60000 (i.e. 60 seconds) but the standard server.xml which ships with Tomcat sets this set to 20000 (i.e. 20 seconds).

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

Version 7

5.1 Establish Secure Configurations

10.11 Configure maxHttpHeaderSize (Scored)

Profile Applicability:

• Level 2

Description:

The ${\tt maxHttpHeaderSize}$ limits the size of the request and response headers defined in bytes.

Rationale:

Limiting the size of the header request can help protect against Denial of Service (DoS) requests.

Audit:

Locate each maxHttpHeaderSize setting in \$CATALINA_HOME/conf/server.xml and verify that they are set to 8192.

grep maxHttpHeaderSize \$CATALINA_HOME/conf/server.xml

Remediation:

Set maxHttpHeaderSize for each connector in $CATALINA_HOME/conf/server.xml$ to the appropriate setting.

maxHttpHeaderSize="8192"

Default Value:

By default this is set to 8192.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.12 Force SSL for all applications (Scored)

Profile Applicability:

• Level 2

Description:

Use the transport-guarantee attribute to ensure SSL protection when accessing all applications. This can be overridden on a per application basis in the application configuration.

Rationale:

By default, when accessing applications SSL will be enforced to protect information sent over the network. By using the transport-guarantee attribute within web.xml, SSL is enforced.

Note: This requires SSL to be configured.

Audit:

Ensure \$CATALINA_HOME/conf/web.xml has the transport-guarantee attribute set to CONFIDENTIAL.

grep transport-guarantee \$CATALINA HOME/conf/web.xml

Remediation:

Set transport-guarantee to CONFIDENTIAL $in\$ \$CATALINA HOME/conf/web.xml:

<user-data-constraint>
 <transport-guarantee>CONFIDENTIAL</transport-guarantee>
<user-data-constraint>

Impact:

If the data protection level is set to INTEGRAL or CONFIDENTIAL, and the client is not already using SSL, then the client is redirected to the same URI, but using port 443 or the port defined for the redirectPort attribute in the <Connector> element in server.xml.

Default Value:

By default this configuration is not present.

References:

1. https://www.owasp.org/index.php/Securing tomcat

CIS Controls:

Version 7

14.4 Encrypt All Sensitive Information in Transit Encrypt all sensitive information in transit.

10.13 Do not allow symbolic linking (Scored)

Profile Applicability:

• Level 1

Description:

Symbolic links permit one application to include the libraries from another. This allows for re-use of code but also allows for potential security issues when applications include libraries from other applications to which they should not have access.

Rationale:

Allowing symbolic links makes Tomcat susceptible to directory traversal vulnerability. Also, there is a potential that an application could link to another application to which it should not be linking. On case-insensitive operating systems there is also the threat of source code disclosure.

Audit:

Ensure the allowLinking attribute in all context.xml does not exist or is set to false.

```
# find . -name context.xml | xargs grep "allowLinking"
```

Remediation:

In all context.xml, set the allowLinking attribute to false:

Default Value:

By default allowLinking has a value of false.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/resources.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/context.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.14 Do not run applications as privileged (Scored)

Profile Applicability:

• Level 1

Description:

Setting the privileged attribute for an application changes the class loader to the Server class loader instead of the Shared class loader.

Rationale:

Running an application in privileged mode allows an application to load the manager libraries.

Audit:

Ensure the privileged attribute in each context.xml file does not exist or is set to false.

```
# find . -name context.xml | xargs grep "privileged"
```

Remediation:

Set the privileged attribute in all context.xml files to false unless it is required as for the manager application:

```
<Context ... privileged="false" />
```

Default Value:

By default, privileged has a value of false.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/context.html

CIS Controls:

Version 7

4.7 <u>Limit Access to Script Tools</u>

Limit access to scripting tools (such as Microsoft PowerShell and Python) to only administrative or development users with the need to access those capabilities.

10.15 Do not allow cross context requests (Scored)

Profile Applicability:

• Level 1

Description:

Setting crossContext to false prevents an application from calling ServletConext.getContext to return a dispatcher for another application.

Rationale:

Allowing crossContext creates the possibility for a malicious application to make requests to a restricted application.

Audit:

Ensure the crossContext attribute in all context.xml does not exist or is set to false.

```
# find . -name context.xml | xargs grep "crossContext"
```

Remediation:

Set the crossContext attribute in all context.xml files to false:

```
<Context ... crossContext="false" />
```

Default Value:

By default crossContext has a value of false.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/context.html

CIS Controls:

Version 7

4.7 <u>Limit Access to Script Tools</u>

Limit access to scripting tools (such as Microsoft PowerShell and Python) to only administrative or development users with the need to access those capabilities.

10.16 Do not resolve hosts on logging valves (Scored)

Profile Applicability:

• Level 2

Description:

Setting enableLookups to true on Connector will result in a DNS look-ups to obtain the host name of the remote client before logging any information. This uses additional resources when logging.

Rationale:

Allowing enableLookups adds additional overhead to resolve the host name of a remote client which is rarely needed.

Audit:

Ensure Connector elements have the <code>enableLookups</code> attribute set to false or <code>enableLookups</code> does not exist.

grep enableLookups \$CATALINA HOME/conf/server.xml

Remediation:

In Connector elements, set the enableLookups attribute to false or remove it.

<Connector ... enableLookups="false" />

Default Value:

By default, DNS lookups are disabled.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/valve.html
- 2. https://tomcat.apache.org/tomcat-8.0-doc/config/http.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.17 Enable memory leak listener (Scored)

Profile Applicability:

• Level 1

Description:

The JRE Memory Leak Prevention Listener provides work-arounds for known places where the Java Runtime Environment uses the context class loader to load a singleton as this will cause a memory leak if a web application class loader happens to be the context class loader at the time. The work-around is to initialize these singletons when this listener starts as Tomcat's common class loader is the context class loader at that time. It also provides work-arounds for known issues that can result in locked JAR files.

Rationale:

Enabling the JRE Memory Leak Prevention Listener provides work-arounds for preventing memory leaks.

Audit:

Ensure this line is present and not commented out in the

\$CATALINA HOME/conf/server.xml:

```
<Listener
className="org.apache.catalina.core.JreMemoryLeakPreventionListener" />
```

Remediation:

Uncomment the JRE Memory Leak Prevention Listener in \$CATALINA HOME/conf/server.xml

```
<Listener
className="org.apache.catalina.core.JreMemoryLeakPreventionListener" />
```

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/listeners.html#JRE Memory Leak Prevention Listener-org.apache.catalina.core.JreMemoryLeakPreventionListener

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.18 Setting Security Lifecycle Listener (Scored)

Profile Applicability:

• Level 1

Description:

The Security Lifecycle Listener performs a number of security checks when Tomcat starts and prevents Tomcat from starting if they fail.

Rationale:

When enabled, the **Security Lifecycle Listener** can

- Enforce a blacklist of OS users that must not be used to start Tomcat.
- Set the least restrictive umask before Tomcat starts.

Audit:

Review server.xml to ensure the Security Lifecycle Listener element is uncommented with the checkedOsUsers and minimumUmask attributes set with expected values.

Remediation:

Uncomment the listener in \$CATALINA_HOME/conf/server.xml. If the operating system supports umask then the line in \$CATALINA_HOME/bin/catalina.sh that obtains the umask also needs to be uncommented.

Within Server elements add:

- checkedOsUsers: A comma separated list of OS users that must not be used to start Tomcat. If not specified, the default value of root is used.
- minimumUmask: The least restrictive umask that must be configured before Tomcat will start. If not specified, the default value of 0007 is used.

```
<Listener className="org.apache.catalina.security.SecurityListener"
checkedOsUsers="alex,bob" minimumUmask="0007" />
```

Default Value:

The Security Lifecycle Listener is not enabled by default. For <code>checkedOsUsers</code>, the default value is <code>root</code>. For <code>minimumUmask</code>, the default value is <code>0007</code>.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/config/listeners.html#Security Lifecycle Listener-org.apache.catalina.security.SecurityListener

CIS Controls:

Version 7

5.1 Establish Secure Configurations

10.19 Use the logEffectiveWebXml and metadata-complete settings for deploying applications in production (Scored)

Profile Applicability:

• Level 1

Description:

Both fragments and annotations give rise to security concerns. web.xml contains a metadata-complete attribute on the web-app element whose binary value defines whether other sources of metadata should be considered when deploying this web application, this includes annotations on class files (@WebServlet, but also @WebListener, @WebFilter, ...), web-fragment.xml as well as classes located in WEB-INF/classes. In addition, Tomcat could allow you to log the effective web.xml, when an application starts, and the effective web.xml is the result of taking the main web.xml for your application merging in all the fragments applying all the annotations. By logging that, you are able to review it, and see if that is in fact what you actually want.

Rationale:

Enable logEffectiveWebXml will allow you to log the effective web.xml and you are able to see if that is in fact what you actually want. Enable metadata-complete so that the web.xml is the only metadata considered.

Audit:

1. Review each application's web.xml file located in the applications \$CATALINA_HOME/webapps/<app name>/WEB-INF/web.xml and determine if the metadata-complete property is set.

```
<web-app
...
metadata-complete="true"
...
>
```

2. Review each application's <code>context.xml</code> file located in the applications <code>\$CATALINA_HOME/webapps/<app name>/META-INF/context.xml</code> and determine if the metadata-complete property is set.

```
<Context
...
logEffectiveWebXml="true"
```

···

Remediation:

- Set the metadata-complete value in the web.xml in each of the applications to true. Note: The metadata-complete option is not enough to disable all of annotation scanning. If there is a ServletContainerInitializer with a @HandlesTypes annotation, Tomcat has to scan your application for classes that use annotations or interfaces specified in that annotation.
- Set the logEffectiveWebXml value in the context.xml in each of the application to true.

Default Value:

If logEffectiveWebXml and/or metadata-complete is/are not specified, the default value is false.

References:

- 1. https://tomcat.apache.org/tomcat-8.0-doc/config/context.html
- 2. https://alexismp.wordpress.com/2010/07/28/servlet-3-0-fragments-and-web-xml-to-rule-them-all/
- 3. https://tomcat.apache.org/tomcat-8.5-doc/config/context.html

CIS Controls:

Version 7

6.3 Enable Detailed Logging

Enable system logging to include detailed information such as an event source, date, user, timestamp, source addresses, destination addresses, and other useful elements.

11 Minimize Features

11.1 Limit HTTP Request Methods (Scored) (Scored)

Profile Applicability:

• Level 1

Description:

Restrict unnecessary HTTP request methods such as PUT and DELETE.

Rationale:

The HTTP 1.1 protocol supports several request methods which are rarely used and potentially high risk. For example, methods such as PUT and DELETE are rarely used and should be disabled in keeping with the primary security principle of minimize features and options. Also since the usage of these methods is typically to modify resources on the Tomcat server, they should be explicitly disallowed.

Audit:

Perform the following to determine if the recommended state is implemented:

- 1. Locate web.xml under \$CATALINA HOME/conf
- 2. Find the init param readonly and ensure it is set with true

If it's not found, then it uses default value true.

Remediation:

Perform the following to prevent Tomcat from accepting PUT or DELETE methods:

- 1. Locate web.xml under \$CATALINA HOME/conf
- 2. Find the init param readonly, remove it or set its value with true

Impact:

Applications which use PUT and DELETE may be impacted by this recommendation.

Default Value:

By default, the value of readonly is true.

References:

1. https://tomcat.apache.org/tomcat-8.0-doc/default-servlet.html

CIS Controls:

Version 7

5.1 Establish Secure Configurations

Appendix: Summary Table

Control			Set Correctly	
		Yes	No	
1	Remove Extraneous Resources	1		
1.1	Remove extraneous files and directories (Scored)			
1.2	Disable Unused Connectors (Not Scored)			
2	Limit Server Platform Information Leaks			
2.1	Alter the Advertised server.info String (Scored)			
2.2	Alter the Advertised server.number String (Scored)			
2.3	Alter the Advertised server.built Date (Scored)			
2.4	Disable X-Powered-By HTTP Header and Rename the Server Value for all Connectors (Scored)			
2.5	Disable client facing Stack Traces (Scored)			
2.6	Turn off TRACE (Scored)			
2.7	Ensure Sever Header is Modified To Prevent Information Disclosure (Not Scored)			
3	Protect the Shutdown Port			
3.1	Set a nondeterministic Shutdown command value (Scored)			
3.2	Disable the Shutdown port (Not Scored)			
4	Protect Tomcat Configurations			
4.1	Restrict access to \$CATALINA_HOME (Scored)			
4.2	Restrict access to \$CATALINA_BASE (Scored)			
4.3	Restrict access to Tomcat configuration directory (Scored)			
4.4	Restrict access to Tomcat logs directory (Scored)			
4.5	Restrict access to Tomcat temp directory (Scored)			
4.6	Restrict access to Tomcat binaries directory (Scored)			
4.7	Restrict access to Tomcat web application directory (Scored)			
4.8	Restrict access to Tomcat catalina.properties (Scored)			
4.9	Restrict access to Tomcat catalina.policy (Scored)			
4.10	Restrict access to Tomcat context.xml (Scored)			
4.11	Restrict access to Tomcat logging.properties (Scored)			
4.12	Restrict access to Tomcat server.xml (Scored)			
4.13	Restrict access to Tomcat tomcat-users.xml (Scored)			
4.14	Restrict access to Tomcat web.xml (Scored)			
5	Configure Realms	-		
5.1	Use secure Realms (Scored)			
5.2	Use LockOut Realms (Scored)			
6	Connector Security			
6.1	Setup Client-cert Authentication (Scored)			

6.2	Ensure SSLEnabled is set to True for Sensitive Connectors (Not Scored)					
6.3	Ensure scheme is set accurately (Scored)					
6.4	Ensure secure is set to true only for SSL-enabled Connectors (Scored)					
6.5	Ensure SSL Protocol is set to TLS for Secure Connectors (Scored)					
6.6	Control the maximum size of a POST request that will be parsed for parameter (Scored)					
7	Establish and Protect Logging Facilities					
7.1	Application specific logging (Scored)					
7.2	Specify file handler in logging.properties files (Scored)					
7.3	Ensure className is set correctly in context.xml (Scored)					
7.4	Ensure directory in context.xml is a secure location (Scored)					
7.5	Ensure pattern in context.xml is correct (Scored)					
7.6	Ensure directory in logging.properties is a secure location (Scored)					
8	Configure Catalina Policy					
8.1	Restrict runtime access to sensitive packages (Scored)					
9	Application Deployment					
9.1	Starting Tomcat with Security Manager (Scored)					
9.2	Disabling auto deployment of applications (Scored)					
9.3	Disable deploy on startup of applications (Scored)					
10	Miscellaneous Configuration Settings	.1				
10.1	Ensure Web content directory is on a separate partition from the Tomcat system files (Not Scored)					
10.2	Restrict access to the web administration application (Not Scored)					
10.3	Restrict manager application (Not Scored)					
10.4	Force SSL when accessing the manager application (Scored)					
10.5	Rename the manager application (Scored)					
10.6	Enable strict servlet Compliance (Scored)					
10.7	Turn off session facade recycling (Scored)					
10.8	Do not allow additional path delimiters (Scored)					
10.9	Do not allow custom header status messages (Scored)					
10.10	Configure connectionTimeout (Scored)					
10.11	Configure maxHttpHeaderSize (Scored)					
10.12	Force SSL for all applications (Scored)					
10.13	Do not allow symbolic linking (Scored)					
10.14	Do not run applications as privileged (Scored)					
10.15	Do not allow cross context requests (Scored)					
10.16	Do not resolve hosts on logging valves (Scored)					
10.17	Enable memory leak listener (Scored)					

10.18	Setting Security Lifecycle Listener (Scored)		
10.19	Use the logEffectiveWebXml and metadata-complete settings for deploying applications in production (Scored)		
11	Minimize Features		
11.1	Limit HTTP Request Methods (Scored) (Scored)		

Appendix: Change History

Date	Version	Changes for this version
Mar 25, 2016	1.0.0	Initial Release
Sep 6, 2016	1.0.1	Bugfix Update
Sep 30, 2019	1.1.0	Permissions for Tomcat config files (Ticket 9142)
Sep 30, 2019	1.1.0	Contradiction between description & audi (Ticket 9140)
Sep 30, 2019	1.1.0	'Remediation' instructs one to change pe (Ticket 5003)
Oct 1, 2019	1.1.0	Map Apache Tomcat 8 Benchmark to CIS Con (Ticket 9231)
Oct 21, 2019	1.1.0	Planned Update