



Need to delete local-lvm and reuse the size

Tarek Damak · Apr 10, 2017 · local-lvm



Forums

Proxmox Virtual Environment

Proxmox VE: Installation and configuration



Tarek Damak

New Member



Apr 10, 2017

#1

Hello Evrybody ,
I don't use local-lvm , i want to delete that partition and add the free size to the root partition (local).
Any help please ?



un1x0d

Renowned Member

Apr 10, 2017

#2

Reinstall with options or go to console.

`lvremove pve/data`

and `man lvm` .. at `lvextend pve/root` ...

after boot from cd and extend ext4 volume root with `resize2fs`



Tarek Damak

New Member



Apr 10, 2017

#3

Thank You , but can you more explain please ?
i didn't understant , should i reinstall all ? so i lose my vms ?
Thank you again



ignaqui

Active Member

Aug 31, 2017

#4

@Tarek Damak

If you have VMs deployed in local-lvm - then yes, you'll lose them. If you have your VMs deployed in local - then you're safe.

You can do the following:

- `delete local-lvm storage in gui`
- `lvremove /dev/pve/data`
- `lvresize -l +100%FREE /dev/pve/root`

Then you need to boot from rescue disc and resize ext4 file system.

I always try to use xfs for similar tasks as you can extend it on the fly (no

shrinking available though!).

The link may be helpful: <https://artofawareness.wordpress.com/2017/03/06/proxmox-remove-lvm-local-data/>

Cheers

Last edited: Aug 31, 2017

👍 HPE, Pheggas, alexdelprete and 2 others



CashewCaliphate

Member

Apr 9, 2018

🔗 #5

ignaqui said:

@Tarek Damak

Then you need to boot from rescue disc and resize ext4 file system. I always try to use xfs for similar tasks as you can extend it on the fly (no shrinking available though!).

The link may be helpful: <https://artofawareness.wordpress.com/2017/03/06/proxmox-remove-lvm-local-data/>

Is there a command to accomplish this from a live rescue disc? I booted into gparted, didn't see any ext4 filesystem resizing options, so I tried the `resize2fs /sda3/dev/mapper/pve-root` command provided in your link, but my arguments or paths must not be valid.



Yuniel Leal Yanes

Active Member

Nov 1, 2018

🔗 #6

CashewCaliphate said:

Is there a command to accomplish this from a live rescue disc? I booted into gparted, didn't see any ext4 filesystem resizing options, so I tried the `resize2fs /sda3/dev/mapper/pve-root` command provided in your link, but my arguments or paths must not be valid.

Should be "resize2fs /dev/mapper/pve-root", not need to boot from live rescue disk.

👍 Pheggas and rubi2020



rubi2020

Member

May 28, 2020

🔗 #7

ignaqui said:

[Click to expand...](#)

If you have VMs deployed in local-lvm - then yes, you'll lose them. If you have your VMs deployed in local - then you're safe.

You can do the following:

- delete local-lvm storage in gui
- `lvremove /dev/pve/data`

Yuniel Leal Yanes said:

Should be "`resize2fs /dev/mapper/pve-root`", not need to boot from live rescue disk.

worked like a charm!

Thank you 😊



Mamadou
New Member

Jul 17, 2020

#8

Hello, I would know deleting the /pve/data couldn't corrupt the system? but I have same issue and my lvm /pve/data size is 2.6To, there's only 16GB free.



mikhael
New Member

Jul 10, 2021

#9

Hello,

Just installed P VE 6.3-2-on laptop logged in over https.
Need to resize my original storage from 20gb and its a 120 x 2 both might be connected inside the laptop separately ///

`#lvresize -l +100%FREE /dev/pve/root` gives me the same storage output **could it be the 25% of the total space?**

Ran the following commands successfully via shell :

1. Deleted *local-lvm* storage in hypervisor
2. Then ran the `#lvremove /dev/pve/data`
3. After running the following `#lvresize -l +100%FREE /dev/pve/root` get the exact same storage size i had before i ran all these commands)

like why does it do this ? Could it be hardware ? rebooted twice no difference help,

There are always more commands right ?
fdisk perhaps ?

```
#lvresize -l +100%FREE /dev/pve/root
```

Output = New size (28349 extents) matches existing size (28349 extents).

Last edited: Jul 10, 2021



mikhael
New Member

Jul 10, 2021

#10

Storage Update Delay? User Error ?

After about 15 mins in the Proxmox VE 6.3 Updated the storage as shown in screen shot 1 (connected via https)


Not quite sure why it would take that long, ran the command like several times;

The command `#lvresize -l +100%FREE /dev/pve/root` runs Screen shot 2 takes place instead of screen shot 3 .


Attachments



sh1.png



sh2.png



sh3.png

Last edited: Jul 11, 2021



Jun 29, 2022

#11

Yuniel Leal Yanes said:

j03man
Member

Should be "resize2fs /dev/mapper/pve-root", not need to boot from live rescue disk.

Worked! Thank you very much!

 **Yuniel Leal Yanes**



cheetoooh
New Member

Feb 19, 2024

 #12

This is very helpful! Thank you very much!

[You must log in or register to reply here.](#)

Share:



Forums

Proxmox Virtual Environment

Proxmox VE: Installation and configuration

About

The Proxmox community has been around for many years and offers help and support for Proxmox VE, Proxmox Backup Server, and Proxmox Mail Gateway.

We think our community is one of the best thanks to people like you!

Quick Navigation

[Home](#)

[Get Subscription](#)

[Wiki](#)

[Downloads](#)

[Proxmox Customer Portal](#)

[About](#)

Get your subscription!

The Proxmox team works very hard to make sure you are running the best software and getting stable updates and security enhancements, as well as quick enterprise support. Tens of thousands of happy customers have a Proxmox subscription. Get yours easily in our online shop.

Buy now!

[Cookies](#)

[Proxmox Support Forum - Light Mode](#)

[Contact us](#)

[Terms and rules](#)

[Privacy policy](#)

[Help](#)

[Home](#)

Community platform by XenForo® © 2010-2025 XenForo Ltd.

