

Note: set the registry key 'HKLM\Software\Policies\Microsoft\TPM' [REG_DWORD] 'OSManagedAuthLevel' to 4) to save password in registry in HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\TPM\WMI\Admin\OwnerAuthFull

After TPM clear in BIOS







X





Manage the TPM security hardware

Restart your computer


You must restart your computer to apply necessary configuration changes to the TPM security hardware settings so that your TPM can be used. To do so:


Click the Restart button below.

Log on to Windows to continue the wizard automatically.



Create password







Password change completed

The password for the TPM security hardware on this computer has been successfully changed to the new password.



Close

Create TPM key file for VeraCrypt.

Owner password is required to create NV RAM in TPM

The key file is locked to PCRs selected to protect modification of objects selected by PCRs (BIOS, DcsProp, boot loaders).

```
TPM is configured but locked. Probably boot chain is modified!
Password:*
Pim:*
(0) TEST ALL (1) SHA-512 (2) Whirlpool (3) SHA-256 (4) RIPEMD-160 (5) Streebog
Hash:*
Authorizing...Success
Start 0 2
               2 len 1
Press 'c' to configure, others to skip 8
VeraCrupt 1.20-BETA2 configuration
b) Boot
r) Hard reset
n) New password
t) Configure TPM
[brnt]:t
TPM configured, locked
u) Update TPM secret
d) Delete TPM secret
p) Print PCRs
e) Exit
[udpe] :_
```

Press <F8> (or "TPM lck" button) to add TPM key file to password.

Press <F7> (or "PLT lck" button) to add BIOS serial and USB serial to password as key file

Important: Modification of BIOS or boot loader will block access to TPM! Before TPM/Platform lock - save rescue disk of system encrypted to restore.