## The Hairless MIDI to Serial Bridge

Pieter F

This is an installation guide for the Hairless MIDI to Serial Bridge on Ubuntu.

## Install the dependencies

The Hairless program is a 32-bit executable, so on most modern 64-bit Linux distributions, you'll have to explicitly install some 32-bit libraries to be able to run it:

\$ sudo apt install libasound2:i386 libsm6:i386 libxrender1:i386 libfontconfig1:i386 libasound2-plugins:i386

## Download and extract

Download Hairless from the website (direct link).

Extract the archive, and save it where you store your software, for example  $\sim\!\!/\!\operatorname{opt}$  .

The following commands download, extract, and move Hairless to ~/opt:

```
$ cd /tmp
$ wget https://github.com/downloads/projectgus/hairless-midiserial/hairless-midiserial-0.4-linux.tgz
$ tar xzf hairless-midiserial-0.4-linux.tgz
$ mkdir -p ~/opt
$ mv hairless-midiserial ~/opt
```

Now you can already run Hairless by running the following command in a terminal:

```
$ ~/opt/hairless-midiserial/hairless-midiserial
```

You can add Hairless to your PATH by creating a symbolic link in ~/.local/bin:

```
$ mkdir -p ~/.local/bin
$ ln -s ../../opt/hairless-midiserial/hairless-midiserial ~/.local/bin
```

You can now run it by just typing hairless-midiserial in a terminal.

## Tested on

• Ubuntu 19.10 - Hairless 0.4