```
NAME
top
```

kill - send signal to a process

SYNOPSIS top

#include <sys/types.h> #include <signal.h>

int kill(pid_t pid, int sig);

Feature Test Macro Requirements for glibc (see <u>feature test macros(7)</u>):

kill(): POSIX C SOURCE

DESCRIPTION top

The **kill**() system call can be used to send any signal to any process group or process.

If pid is positive, then signal sig is sent to the process with the ID specified by *pid*.

If pid equals 0, then sig is sent to every process in the process

group of the calling process. If pid equals -1, then sig is sent to every process for which the

calling process has permission to send signals, except for process 1

(init), but see below. If pid is less than -1, then sig is sent to every process in the process group whose ID is -pid.

If sig is 0, then no signal is sent, but existence and permission checks are still performed; this can be used to check for the existence of a process ID or process group ID that the caller is permitted to signal.

privileged (under Linux: have the CAP_KILL capability in the user namespace of the target process), or the real or effective user ID of the sending process must equal the real or saved set-user-ID of the target process. In the case of SIGCONT, it suffices when the sending and receiving processes belong to the same session. (Historically, the rules were different; see NOTES.)

For a process to have permission to send a signal, it must either be

On success (at least one signal was sent), zero is returned.

top

top

RETURN VALUE

error, -1 is returned, and <u>errno</u> is set appropriately.

EINVAL An invalid signal was specified.

ERRORS

EPERM The process does not have permission to send the signal to any

of the target processes. ESRCH The process or process group does not exist. Note that an

existing process might be a zombie, a process that has

terminated execution, but has not yet been <u>wait(2)</u>ed for. CONFORMING TO top

POSIX.1-2001, POSIX.1-2008, SVr4, 4.3BSD.

top

The only signals that can be sent to process ID 1, the init process,

NOTES

This is done to assure the system is not brought down accidentally. POSIX.1 requires that kill(-1, sig) send sig to all processes that the calling process may send signals to, except possibly for some

are those for which init has explicitly installed signal handlers.

implementation-defined system processes. Linux allows a process to signal itself, but on Linux the call kill(-1, sig) does not signal the calling process. POSIX.1 requires that if a process sends a signal to itself, and the sending thread does not have the signal blocked, and no other thread

has it unblocked or is waiting for it in sigwait(3), at least one unblocked signal must be delivered to the sending thread before the kill() returns. Linux notes Across different kernel versions, Linux has enforced different rules for the permissions required for an unprivileged process to send a

signal to another process. In kernels 1.0 to 1.2.2, a signal could be sent if the effective user ID of the sender matched effective user ID of the target, or the real user ID of the sender matched the real user ID of the target. From kernel 1.2.3 until 1.3.77, a signal could be sent if the effective user ID of the sender matched either the real or effective user ID of the target. The current rules, which conform to POSIX.1, were adopted in kernel 1.3.78. top

In 2.6 kernels up to and including 2.6.7, there was a bug that meant that when sending signals to a process group, **kill**() failed with the

BUGS

error EPERM if the caller did not have permission to send the signal to any (rather than all) of the members of the process group. Notwithstanding this error return, the signal was still delivered to all of the processes for which the caller had permission to signal. SEE ALSO top

kill(1), exit(2), signal(2), tkill(2), exit(3), killpg(3), sigqueue(3), capabilities(7), credentials(7), signal(7)

COLOPHON

top

This page is part of release 5.02 of the Linux man-pages project. description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.