

aptana® Jaxer® The world's first Ajax server

[Home](#) [Quick Start](#) [Guide](#) [Tutorials](#) [API](#) [Screenshots](#) [Forums](#) [Download](#)

Jaxer Guide

- [Introduction](#)
- [Setup](#)
- [Develop](#)
- [Debug](#)

Debug Settings

Change Jaxer Log Level

Command line

This change applies only to the current session and doesn't persist:

```
1. telljaxermanager [-p mgr_admin_port] set pref:Jaxer.Core.LogLevel TRACE
```

This will change Jaxer logging to its most verbose level. The default is INFO. You can change it back with

```
1. telljaxermanager [-p mgr_admin_port] set pref:Jaxer.Core.LogLevel INFO
```

Permanently change the level

Edit the configuration file (<JaxerInstallDir>/jaxer/defaults/pref/Jaxer_prefs.js)

```
1. // This option sets the log level for Jaxer core. Valid levels are:
2. // TRACE, DEBUG, INFO, WARN, ERROR, FATAL.
3. pref("Jaxer.Core.LogLevel", "INFO");
```

Making this change effective requires restarting JaxerManager.

Turn on protocol dumping

Command line

This change applies only to the current session and doesn't persist:

```
1. telljaxermanager [-p mgr_admin_port] set pref:Jaxer.dev.DumpProtocol true
```

This causes all network traffic to and from Jaxer be written to jaxer.log. Not surprisingly, it will slow the server down significantly. You can turn it off with

```
1. telljaxermanager [-p mgr_admin_port] set pref:Jaxer.dev.DumpProtocol false
```

Permanently change the level

Edit the configuration file (<JaxerInstallDir>/jaxer/defaults/pref/Jaxer_prefs.js)

```
1. pref("Jaxer.dev.DumpProtocol", true);
```

To turn it off

```
1. pref("Jaxer.dev.DumpProtocol", false);
```

Making this change effective requires restarting JaxerManager.