Spanning Tree Protocol (STP) Workbook

A Hands-On Guide to PVST+, RSTP, and MSTP

Mehdi JAFARI ZADEH

Date: February 4, 2025

Contents

1	Spanning Tree Protocol (STP)	5
2	PVST (Per-VLAN Spanning Tree)	11
3	PVST+ Lab Exercise: VLAN-Based Root Bridge Configuration	13

4 CONTENTS

Chapter 1

Spanning Tree Protocol (STP)

STP Introduction

Spanning Tree Protocol (STP) is essential for preventing broadcast storms and loops in switched networks with redundant paths. In this section, we'll cover the purpose of STP, its importance in maintaining a loop-free topology, and an overview of how it dynamically reconfigures the network when changes occur. This foundation sets the stage for understanding how STP supports network reliability and resilience.

Root Bridge

The Root Bridge is the central reference point in the STP topology. It is elected based on the lowest bridge ID, which is a combination of the bridge priority and MAC address. All other switches in the network compute the best path back to the Root Bridge. Understanding how the Root Bridge is selected is crucial because it directly influences the network's spanning tree structure and the flow of data through the network.

STP Root Port, Designated Port

Within each switch (except for the Root Bridge), the Root Port is the interface that offers the best path to the Root Bridge, based on the lowest path cost. On each network segment, the Designated Port is the switch port that has the best path to the Root Bridge and is responsible for forwarding traffic toward it. Together, these port roles determine the active topology of the network by ensuring there is only one active path between any two network devices, thereby preventing loops.

Network Topology Overview

In this exercise, you will work with the network topology as described below. The switches (SW1 to SW6) are connected as Figure 1.1.

The MAC addresses of the switches are as follows:


MAC SW1 < MAC SW2 < MAC SW3 < MAC SW4 < MAC SW6 < MAC SW6

This means SW1 has the lowest MAC address and SW6 has the highest.

Step-by-Step Tasks

1. Switch STP Mode to Traditional STP

Change the STP mode on all switches to traditional STP (IEEE 802.1D).



MAC SW1 < MAC SW2 < MAC SW3 < MAC SW4

Figure 1.1:

2. Disable Unused Interfaces

Turn off any extra or unused interfaces to prevent unnecessary loops.

3. Set Links to Point-to-Point Mode

Configure all links between switches as **Point-to-Point (P2P)** to optimize STP convergence.

4. Verify Bridge IDs

Check the **Bridge ID** for each switch to see how STP will select the Root Bridge.

5. Predict the Root Bridge

Based on the MAC addresses provided (SW1 < SW2 < SW3 < SW4 < SW5 < SW6), estimate which switch will become the Root Bridge.

• Question: Which switch is likely to be the Root Bridge and why?

6. Change the Root Bridge by Adjusting Priority

Modify the **priority** settings so that the switch identified in the diagram becomes the Root Bridge.

• Note: Lower priority values increase the chance of a switch becoming the Root Bridge.

7. Calculate Path Costs for Active Ports

For each non-root switch, **calculate the cost** of paths to the Root Bridge based on link speeds. Use standard STP cost values:

• Gigabit Ethernet (1 Gbps) = 4

• Fast Ethernet (100 Mbps) = 19

8. Estimate Root Ports

Identify the **Root Port** on each non-root switch. This is the port with the lowest path cost to the Root Bridge.

• Question: Which port will be the Root Port on SW2, SW3, SW4, SW5, and SW6?

9. How Many Root Bridges Are There in a Network?

• Question: In any given STP-enabled network, how many Root Bridges can exist?

10. How Many Root Ports Are There in a Network?

• Question: In any given STP-enabled network, how many Root Port can exist?

11. How Many Designated Ports (DP) Are in the Topology?

• Question: In any STP-enabled topology, how many Designated Ports (DP) will there be?

12. Estimate the Designated Ports on Each Switch

• Before using any commands, predict which ports will be Designated Ports on each switch in the topology.


13. Verify Designated Ports Using Commands

14. Are All Root Bridge Ports Designated Ports?

• Question: Based on your observations, can you conclude that all ports on the Root Bridge are Designated Ports?

15. Change the Port Cost of G0/2 on SW4

• Modify the path cost of interface G0/2 on SW4 to 15. This will influence STP's decision on which path to use.



MAC SW1 < MAC SW2 < MAC SW3 < MAC SW4

Figure 1.2:

16. Predict the New Root Port on SW4 After Link Removal

- If you remove the link connected to G0/1 on SW4 (Figure 1.2), which port will become the new Root Port? Explain your reasoning based on path costs and STP rules.
- Hint: Consider which remaining port on SW4 has the lowest cost path to the Root Bridge.

17. Identify Root Ports with SW1 as the Root Bridge

• In this topology, assuming SW1 is the Root Bridge, identify the Root Ports on the other switches (SW2, SW3, SW4, SW5, and SW6).

18. Change the Port ID to Influence Link Selection

- STP uses Port IDs as a tie-breaker when path costs are equal. By adjusting the Port Priority (which is part of the Port ID), you can influence which link STP selects as the active path.
- Task: Change the Port Priority of specific interfaces to modify STP's link selection.

Additional exercises

Draw the Active Topology for Each Scenario




Figure 1.3:




Figure 1.4:




Figure 1.5:

Chapter 2

PVST (Per-VLAN Spanning Tree)

What is PVST?

Per-VLAN Spanning Tree (PVST) is a version of the Spanning Tree Protocol (STP) that creates a separate spanning tree instance for each VLAN in the network. This allows for better load balancing and more efficient use of network resources, as different VLANs can have different root bridges and forwarding paths.

Key Features of PVST:

1. Separate Spanning Tree per VLAN:

Each VLAN runs its own independent instance of STP, meaning the topology can be optimized differently for each VLAN.

2. Improved Load Balancing:

By assigning different root bridges to different VLANs, PVST allows traffic to be distributed across multiple switches, reducing congestion and improving performance.

3. Root Bridge Election per VLANCompatibility with Cisco Devices:

VST is a Cisco proprietary protocol and is typically used in Cisco environments. It is based on the original IEEE 802.1D standard but with VLAN-specific enhancements.

4. Uses Common STP Concepts:

PVST uses the same roles and states as traditional STP:

- Root Bridge
- Root Port (RP)
- Designated Port (DP)
- Blocked Port

How PVST Works:

• Root Bridge Election per VLAN:

Each VLAN elects its own Root Bridge based on the lowest Bridge ID (priority + MAC address). This allows different switches to act as the Root Bridge for different VLANs.

• Port Roles and Path Selection:

For each VLAN, PVST determines the Root Ports and Designated Ports independently, which results in different forwarding paths for different VLANs.

Benefits of PVST:


- Flexibility: Allows network administrators to optimize traffic flow for each VLAN.
- Load Balancing: Distributes traffic across multiple links by having different root bridges for different VLANs.
- Faster Convergence: PVST+ (an enhanced version) offers faster convergence times compared to traditional STP.

Chapter 3

PVST+ Lab Exercise: VLAN-Based Root Bridge Configuration

Network Topology Overview

In this scenario, you will configure PVST+ (Per-VLAN Spanning Tree Plus), which allows separate spanning tree instances for each VLAN. The network consists of three switches (SW1, SW2, and SW3) and multiple VLANs with end devices connected to each switch.



 $Figure \ 3.1:$

• MAC Address Order:

 $\mathbf{MAC}\ \mathbf{SW1} < \mathbf{MAC}\ \mathbf{SW2} < \mathbf{MAC}\ \mathbf{SW3}$

(SW1 has the lowest MAC address.)

- VLANs and Devices:
 - **VLAN 10:** PC1, PC4, PC7
 - **VLAN 20:** PC2, PC5, PC8
 - **VLAN 30:** PC3, PC6, PC9

Step-by-Step Configuration Tasks

1. Set Inter-Switch Links to Trunk Mode

Configure the links between the switches (SW1, SW2, SW3) to operate in trunk mode to allow VLAN traffic to pass through.

2. Verify Current STP Status

Before making further changes, **check the current STP status** to see how the network has chosen the Root Bridge for each VLAN.

3. Enable VTP on All Switches

Configure VTP (VLAN Trunking Protocol) to manage VLANs centrally.

VTP Settings:

- Domain Name: network
- Version: 2
- Password: CCNP
- SW1 Configuration (VTP Master/Server):
- SW2 and SW3 Configuration (VTP Clients):

4. Create VLANs 10, 20, and 30 on SW1 (VTP Server)

Since SW1 is the VTP Server, create the VLANs here, and they will propagate to SW2 and SW3.

5. Verify STP Status After VLAN Creation

After setting up VTP and VLANs, check how **PVST** has adjusted the spanning tree roles.

PVST Root Bridge Configuration Per VLAN

1. Set Root Bridges for Each VLAN Using PVST+

Configure different Root Bridges for each VLAN to optimize traffic flow:

- VLAN 10 Root Bridge: Set SW1 as the Root Bridge.
- VLAN 20 Root Bridge: Set SW2 as the Root Bridge.
- VLAN 30 Root Bridge: Set SW3 as the Root Bridge.
- SW1 (Root for VLAN 10):
- SW2 (Root for VLAN 20):
- SW3 (Root for VLAN 30):

Note: A lower priority value increases the likelihood of a switch becoming the Root Bridge. The default is 32768.

2. Verify STP Status After Root Bridge Configuration

After configuring the Root Bridges for each VLAN, verify that the changes were applied correctly. Question:

- (a) Which switch is now the Root Bridge for each VLAN?
- (b) How did the Root Ports and Designated Ports change across the network?

3. Draw the active topology of each violin.

- SW1 (Root for VLAN 10):
- SW2 (Root for VLAN 20):
- SW3 (Root for VLAN 30):




Figure 3.2:

Configure PortFast for End Devices

1. Enable PortFast on All PC Ports

PortFast allows end devices (like PCs) to bypass STP's listening and learning states, enabling faster connections.

Task: Configure PortFast on interfaces connected to PCs (e.g., F0/3, F0/4, F0/5 on SW1).

2. Verify Connectivity Between PC2 and PC3

Task: Test the connection between PC2 (192.168.20.2) and PC3 (192.168.30.3) using the ping command.

3. Enable Debugging on SW3

Monitor STP behavior during topology changes.

Task: Turn on STP debugging on SW3.

4. Shut Down Interfaces to Trigger Topology Changes

Simulate link failures by shutting down specific interfaces:

Task: Shut down F0/1 on SW3 and F0/2 on SW1:

5. Observe and Estimate New Topology

After shutting down the interfaces:

Task: Check the **new port roles** and **STP state** using:

Question: Which ports have become Root Ports or Designated Ports? Identify if any ports are now Blocked.

6. Restore the Network to Its Original State

Re-enable the interfaces to bring the network back to its initial state.

Task: Turn on F0/1 on SW3 and F0/2 on SW1:

7. Reduce Network Diameter for Faster Convergence

The **network diameter** defines the maximum number of switches a BPDU can pass through. Reducing it speeds up convergence.

Task: Reduce the network diameter from the default 7 to 2.

8. Check Forward Delay and Max Age Timers

STP uses these timers to control how long switches stay in different states during convergence.

Task: Verify Forward Delay and Max Age settings:

9. Enable UplinkFast on SW2 for Faster Recovery

UplinkFast speeds up STP convergence when a primary link fails by immediately switching to a backup link.

Task: Enable UplinkFast on SW2:

10. Set Max-Update-Rate to 100 Packets per Second

Limit the number of update packets sent per second to prevent excessive flooding during topology changes.

Task: Set max-update-rate to 100 packets/sec:

11. Verify Uplink Status on SW2

Task: Check if **UplinkFast** is working correctly:

Discussion Questions

- 1. How did reducing the network diameter impact convergence speed?
- $2. \ \ After \ enabling \ Uplink Fast, \ how \ quickly \ did \ SW2 \ recover \ from \ link \ failures?$