

Process to ADD Nodes in BRMS Master Node (IASU1079).

This activity need to be done between 6.30 – 7.30 am and ensure no BRMS activity should not be performed by others.

Add all the list of nodes in IASU1079 by following procedure.

Example: List of Nodes: IASO1030, IASO1322, and IASO1331... e.t.c.

WRKPCYBRM *SYS and Take Option 4

Take option 1 – ADD and give the system name.

Now the status will go to INACTIVE.

Perform this below 2 commands in IASU1079 and the nodes which we are going to add in IASU1079.

CRTSAVF FILE (QGPL/SAVQUSRBRM)

SAVLIB LIB (QUSRBRM) DEV (*SAVF) SAVF (QGPL/SAVQUSRBRM)

Now perform this below steps in Nodes.

CPYMEDIBRM OPTION (*TOFILE) CPYMEDI (*NO)

INZBRM OPTION (*NETSYS) FROMSYS (IASU1079)

If you get an BRM1519 messages, Reply with Option I

CPYMEDIBRM OPTION (*FROMFILE) CPYMEDI (*NO)

Now check the node status in Master BRMS system IASU1079.It should be ACTIVE.