Mapping LWM2M model to CoMI YANG

draft-vanderstok-core-yang-LWM2M-00

Peter van der Stok
Jaime Jiménez (presenting)

(Work in Progress)

Purpose

- Standard organisations (BACnet, KNX, ZigBee, oBIX, OMA/IPSO) define hierarchical models that can be specified in XML and describe classes with attributes and operations that can be instantiated to objects.
    - OMA LWM2M and IPSO standardise numbered object types.
- CoMI at IETF (draft-vanderstok-core-comi-09) describes a network management interface based on CoAP and YANG.
- Goal: convert a LWM2M xml-based device specification to a YANG MODULE for CoMI consumption.

Conversion Rules

LWM2M →	**YANG**
optional /mandatory attribute	false / true statement
R, W attributes	Config parameter (False=R, True=W)
E attribute	YANG rpc
range attribute	range statement
units	units statement

Resources	Leafs on a YANG list
	`+--ro ID3301* [instance_number]`
	`+--ro 5700 uint16`

Object Instance	“instance” key attribute

IPSO Humidity Object

Object definition

Name	Object ID	Instances	Mandatory	Object URN
Humidity	0	Multiple	Mandatory	urn:oma:lwm2m:ipso:3304

Resource definitions

ID	Name	Operations	Instances	Mandatory	Type
5700	Sensor Value	R	Single	Mandatory	Float
5601	Min Measured Value	R	Single	Optional	Float
5602	Max Measured Value	R	Single	Optional	Float
5603	Min Range Value	R	Single	Optional	Float
5604	Max Range Value	R	Single	Optional	Float
5701	Sensor Units	R	Single	Optional	String
5605	Reset Min and Max	E	Single	Optional	Opaque

URI Conversion

LWM2M → **YANG**

URI:

http://example.com/type/instance/resource

coap+lwm2m://example.com/type/instance/resource

RESTCONF URI (example 3):

http://example.com/type/instance=0/resource

CoMI URI (example 3):

coap://example.com/type/resource**?keys=0**

if only one instance then

coap://example.com/type/resource

- Keys as query parameter for instance number.

Generated YANG modules

[ ]	list keys
rw	configuration data (read and write)
ro	state data (read only)
?	optional node
*****	list and leaf list
( )	choice
:	case nodes
...	subtrees not shown

1. module: **ietf-yang-humidityID**

```
      +--ro ID3301* [instance_number]
         +--ro instance_number    uint16
         +--ro ID5700             decimal64
         +--ro ID5701?            string
         +--ro ID5601?            decimal64
         +--ro ID5602?            decimal64
         +--ro ID5603?            decimal64
         +--ro ID5604?            decimal64
         +---x ID5605
```

2. module: **ietf-yang-humidityNM**

```
      +--ro IPSO-humidity* [instance_number]
         +--ro instance_number           uint16
         +--ro Sensor_Value              decimal64
         +--ro Units?                    string
         +--ro Min_Measured_Value?       decimal64
         +--ro Max_Measured_Value?       decimal64
         +--ro Min_Range_Value?          decimal64
         +--ro Max_Range_Value?          decimal64
         +---x Reset_Min_and_Max_measured_values
```

Generated YANG modules

[ ]	list keys
rw	configuration data (read and write)
ro	state data (read only)
?	optional node
*	list and leaf list
( )	choice
:	case nodes
...	subtrees not shown

3.
```
module: ietf-yang-humidityLF
     +--rw IPSO-humidity
        +--ro identifier    uint16
        +--ro resources* [instance_number]
           +--ro instance_number  uint16
           +--ro Sensor_Value
           |  +--ro identifier?   uint16
           |  +--ro content       decimal64
           +--ro Units
           |  +--ro identifier?   uint16
           |  +--ro content?      string
           +--ro Min_Measured_Value
           |  +--ro identifier?   uint16
           |  +--ro content?      decimal64
           +--ro Max_Measured_Value
           |  +--ro identifier?   uint16
           |  +--ro content?      decimal64
           +--ro Min_Range_Value
           |  +--ro identifier?   uint16
           |  +--ro content?      decimal64
           +--ro Max_Range_Value
           |  +--ro identifier?   uint16
           |  +--ro content?      decimal64
           +--ro Reset_Min_and_Max_measured_values
              +--ro identifier?   uint16
              +---x reset
```

Takeaways

- YANG is richer and more verbose than LWM2M.
- Multiple ways to express the same thing.
- IMO YANG still seems a bit overkill, CoMI might be able to use more purposely together with legacy devices.
- Both .XML and .YANG have a lot of “noise” in them.
- Key leafs are just one possible way to represent instances.
- Access Control mapping might not be ideal.
- Need to script automatic conversion.
- Where would a converter run? GWs, devices, server?

Links

- http://ipso-alliance.github.io/pub/
- http://technical.openmobilealliance.org/Technical/technical-information/release-program/current-releases/oma-lightweightm2m-v1-0
- http://jaimejim.github.io/drafts/draft-vanderstok-core-yang-lwm2m-00.txt
- jaimejim.github.io/drafts/3304.xml
- jaimejim.github.io/drafts/3304.yang