

HUBBLE FIELDS

Feature Overview & User Guide

工地考勤系统功能介绍与使用指南

Bilingual · English / 简体中文

Version 0.2 · Field Attendance App

Contents / 目录

1. Product Overview 产品简介
2. Roles & Permissions 角色与权限
3. Getting Started 快速开始
4. Daily Attendance 日常考勤操作
5. Onsite & History 现场人员与历史
6. Manpower 人力名册
7. Administration 管理功能
8. Settings 设置
9. Platform Console 平台控制台
10. Troubleshooting 常见问题

Note: Each section shows English first, then Chinese, so mixed teams can share one document.
说明：每一节先英文、后中文，便于现场中外团队共用同一份文档。

1. Product Overview / 1. 产品简介

Hubble Fields is a mobile/desktop web attendance app for construction sites. Supervisors check workers in and out with GPS geofence validation and a required site photo, with offline queuing when the network is weak.

Hubble Fields 是面向建筑工地的移动端/桌面端网页考勤系统。现场主管可为工人办理签到与签退，系统记录 GPS 地理围栏状态与现场照片，并支持弱网离线排队同步。

Platform operators can use the Hubble Fields Platform Console to manage customer companies, projects, and Project Admin accounts.

平台运营侧可使用 Hubble Fields Platform Console 管理客户公司、项目与项目管理员账号。

Key capabilities · 核心能力

- Worker check-in / check-out with GPS + photo
工人签到 / 签退（需 GPS 与现场照片）
- Live onsite roster and attendance history
在场名单与考勤历史
- Manpower directory (ID, company, trade, status)
人力名册管理
- Shift-hour reports and CSV export (admin)
报表与 CSV 导出（管理员）
- Manual punch create / edit for Project Admins
项目管理员手动补录 / 修改打卡时间
- Invite users and reset temporary passwords
用户邀请与密码重置
- Offline punch queue with automatic sync
离线同步
- English + Simplified Chinese UI
中英双语界面

2. Roles & Permissions / 2. 角色与权限

Menus and actions differ by role. Assign accounts according to job responsibility.

不同角色看到的菜单与可执行操作不同。请按岗位分配账号。

Role 角色	Check-in 签到	History 历史	Manpower 人力	Reports 报表	Users / Manual
Project Admin 项目管理员	✓	✓ (92 days)	Manage 读写	✓ CSV	Invite + Manual punch 邀请 + 手动补录
Supervisor 主管	✓	✓ (14 days)	Read 只读	—	—
Safety Officer 安全员	✓	✓ (14 days)	Read 只读	—	—
Attendance Admin 考勤管理员	✓	✓ (14 days)	Read 只读	—	—
Project Manager 项目经理	✓	✓ (14 days)	Read 只读	—	—
Viewer 只读访客	—	✓ (14 days)	Read 只读	—	—
Platform Admin 平台管理员	Same as project role 同项目角色	—	—	—	Console 控制台

• Project Admins can invite: Supervisor / Safety Officer / Attendance Admin / Project Manager / Viewer (not another Project Admin from the project app).

项目管理员可邀请上述角色（不能在项目应用内再邀请另一位 Project Admin）。

• Platform admins can open Platform Console (/platform or /console) to create customer companies and Project Admins.

平台管理员可进入 Platform Console（/platform 或 /console）创建客户公司与项目管理员。

3. Getting Started / 3. 快速开始

3.1 Open the sign-in page · 3.1 打开登录页

Open the sign-in URL in a phone or desktop browser, e.g. production <https://hubblefields.com/signin> or local <http://localhost:3000/signin>. On the same Wi-Fi you can also use the LAN IP.

在手机或电脑浏览器打开登录地址，例如生产环境：<https://hubblefields.com/signin>

；本地开发：<http://localhost:3000/signin>。同一 Wi-Fi 下也可用局域网 IP 访问。

3.2 Sign in · 3.2 登录

1. Enter company email and password, then tap Sign in →.

输入公司邮箱与密码，点击「Sign in →」。

2. On first login or temporary password, create a new password (10+ characters, including an uppercase letter and a number).

若为首次登录或临时密码，系统会要求设置新密码（至少 10 位，含大写字母与数字）。

3. Temporary passwords expire in 7 days if not changed.

临时密码如未更换，将在 7 天后失效。

3.3 Forgot password · 3.3 忘记密码

There is no self-service reset. Ask a Project Admin to Reset a temporary password under User access.

应用内无自助找回。请联系项目管理员在「User access」中重置临时密码。

4. Daily Attendance / 4. 日常考勤操作

Supervisors and other check-in roles use Overview to check workers in or out. Every field punch requires GPS location and a site photo.

主管及具备签到权限的角色在「Overview / 首页」办理签到与签退。每次现场打卡必须开启定位并拍摄现场照片。

4.1 Check In · 4.1 签到

1. Tap Check In.

点击「Check In」。

2. In WORKER ARRIVAL, search and select a worker (name / last four of ID / trade).

在「WORKER ARRIVAL」中搜索并选择工人（姓名 / 工号后四位 / 工种）。

3. Confirm Location shows Location verified · on site. If Outside site, move into the geofence (strict mode blocks off-site punches).

确认 Location：显示 Location verified · on site；若 Outside site，请移动至工地范围内（严格模式下离场将被拒绝）。

4. Optionally enter Remarks (max 300 characters).

可选填写 Remarks（最多 300 字）。

5. Capture a Site photo (Capture / Album), then Submit check in.

拍摄 Site photo：Capture / Album，确认后 Submit check in。

4.2 Check Out · 4.2 签退

Same flow as check-in via Check Out or Out on the onsite list. A worker must already be onsite to check out; a worker already checked in today cannot check in again.

流程与签到相同，入口为「Check Out」或在场名单中的「Out」。工人须当日已在场才能签退；已签到者不可重复签到。

4.3 Geofence & photo · 4.3 地理围栏与照片

- GPS is always required; allow location in the OS/browser and keep Settings → GPS Location on.
GPS 始终需要；请在系统设置与浏览器中允许定位，并在应用 Settings → GPS Location 保持开启。

- A photo is required; the client compresses images to ≤ 2MB JPEG.
照片为必填，客户端压缩至 ≤ 2MB JPEG。

- Only Active workers can be punched; Inactive workers cannot.
仅 Active 状态工人可被现场打卡；Inactive 不可选。

5. Onsite & History / 5. 现场人员与历史

5.1 Onsite list · 5.1 在场名单

Overview shows the ONSITE count and current workers. Use Out for a quick check-out. Desktop also shows Latest activity.

Overview 显示 ONSITE 人数与在场工人列表。可从列表快速签退（Out）。桌面端可查看 Latest activity。

5.2 Attendance History · 5.2 考勤历史

Open Attendance History for recent in/out records. Non-admins typically see up to ~14 days; admin reports can cover up to ~92 days.

导航「Attendance History / 历史」查看近期进出记录。非管理员默认最多约 14 天；管理员报表可查至约 92 天。

Project Admins also see + Manual punch on History, and Edit on each record row, to backfill or correct punch times.

项目管理员在历史页还可看到「+ Manual punch / 手动补录」，以及每条记录的「Edit /

修改」，用于补录或纠正打卡时间。

6. Manpower / 6. 人力名册

Manpower lists workers, company, trade, and status (Active / Inactive). All roles can search; only Project Admins can add or activate/deactivate.

「Manpower / 人力」列出工人、公司、工种与状态 (Active / Inactive)。所有角色可搜索查看；仅项目管理员可新增与启停。

Project Admin: add a worker · 项目管理员：新增工人

1. Tap + Add.
点击「+ Add」。
2. Enter Worker ID (last four digits), Full name, Company, Trade.
填写 Worker ID (后四位)、Full name、Company、Trade。
3. After save the worker is Active and can be checked in.
保存后工人状态为 Active，即可被签到。
4. Use Deactivate when no longer employed; Activate again if needed.
不再雇佣时使用 Deactivate；需要时可再 Activate。

7. Administration / 7. 管理功能

The following are visible only to Project Admins: User access, Reports, and Manual punch / Edit.

以下功能仅 Project Admin 可见：User access (用户权限)、Reports (报表)，以及手动补录 / 修改打卡时间。

7.1 User access · 7.1 用户权限

1. Open ADMINISTRATION → User access.
打开 ADMINISTRATION → User access。
2. Tap + Invite, create the account, choose a role, and share the temporary password privately.
点击「+ Invite」，创建管理账号并选择角色，私下告知临时密码。
3. Status may show Active / Temporary password / First login required.
账号状态可能为 Active / Temporary password / First login required。
4. If a user forgets the password, tap Reset for a new temporary password (not for other Project Admin rows).
用户忘记密码时，对其点击 Reset 生成新的临时密码 (不可重置其他 Project Admin)。

7.2 Reports & CSV · 7.2 报表与 CSV

1. Open Reports, set From / To dates, then Run report.
打开 Reports，选择 From / To 日期，点击 Run report。
2. Review TOTAL MOVEMENTS, CHECK INS, TOTAL HOURS, plus by-trade, shifts/hours, and movements.
查看 TOTAL MOVEMENTS、CHECK INS、TOTAL HOURS，以及按工种、班次与进出明细。
3. Tap CSV to export date/time, worker, ID last 4, company, trade, event, remarks, recorder, GPS, geofence, photo, source (Field/Manual), and shift hours.
点击 CSV 导出：含日期时间、工人、工号后四位、公司、工种、事件、备注、记录人、GPS、围栏结果、照片、来源 (Field/Manual) 与工时等。

7.3 Manual punch / edit punch time · 7.3 手动补录 / 修改打卡时间

When a worker fails to check in successfully (weak signal, GPS/camera issue, forgotten punch, etc.), a Project Admin can backfill or correct the record without GPS or photo.

当工人未打卡成功 (信号弱、定位/拍照异常、漏打卡等)，项目管理员可手动补录或修改记录，无需 GPS 与现场照片。

Add a manual punch · 新增手动补录

1. Open History (or Reports).

打开 History / 历史 (或 Reports / 报表)。

2. Tap + Manual punch.

点击「+ Manual punch / 手动补录」。

3. Select worker, action (Check In / Check Out), punch date & time, and enter a required reason.

选择工人、动作 (签到 / 签退)、打卡日期时间, 并填写必填原因。

4. Save. The record is marked Manual and shows the reason in remarks.

保存。记录会标记为 Manual, 原因写入备注。

Edit an existing punch · 修改已有打卡

1. On History or Reports, open a record row and tap Edit.

在历史或报表中打开记录行, 点击「Edit / 修改」。

2. Adjust punch time and/or action, and keep a clear reason for the audit trail.

调整打卡时间和/或动作, 并保留清晰原因以便审计。

3. Save changes. IN/OUT order for that calendar day is still validated.

保存更改。系统仍会校验该自然日内的签到/签退顺序。

- Only Project Admins can create or edit manual punches.
仅项目管理员可创建或修改手动打卡。
- Lookback is limited to about 92 days; future times are rejected.
可回溯约 92 天; 不允许设置未来时间。
- Supervisors continue to use normal field Check In / Out with GPS + photo.
主管仍使用常规现场签到/签退 (需 GPS + 照片)。

8. Settings / 8. 设置

Settings provides workspace links and preferences.

「Settings / 设置」提供工作区入口与系统偏好。

Item 项目	Description 说明
History / Manpower / All Projects	Workspace shortcuts 工作区快捷入口
Reports / User access	Admin-only when permitted 管理员功能 (按角色显示)
Platform Console	Platform admin only 仅平台管理员
Languages	English / 简体中文
GPS Location	Required for field punches 现场打卡必须开启
Offline Mode	On by default; queues punches 默认开启; 弱网时排队同步
Sign Out	End the 12-hour session 退出登录

Offline note: punches are queued locally (pending → uploading → synced / failed) and sync on app start, when online, and every 60 seconds. A banner may show Syncing N offline punch(es)...

离线说明: 打卡会写入本地队列 (pending → uploading → synced / failed), 应用启动、恢复联网及每 60 秒自动同步。界面可能显示「Syncing N offline punch(es)…」。

9. Platform Console / 9. 平台控制台

Platform admins open Settings → Platform Console, or go to /platform or /console.

平台管理员在 Settings → Platform Console，或直接访问 /platform、/console。

1. Choose company: select or + Add company.

Choose company: 选择或 + Add company 新建客户公司。

2. Maintain Projects under that company.

维护该公司下的 Projects (项目)。

3. Customer Admins: Create admin account for a customer Project Admin.

Customer Admins: Create admin account, 为客户创建 Project Admin。

4. Share the sign-in URL and temporary password with the customer admin; they then invite supervisors and add manpower.

将登录地址与临时密码交给客户管理员；其登录后邀请现场主管并录入人力。

10. Troubleshooting / 10. 常见问题

Issue 问题	Resolution 处理
No GPS / 无法定位	Enable OS/browser location; turn on GPS Location in Settings. 开启手机定位与浏览器权限；Settings → GPS Location 打开。
Outside site blocked	Move inside the geofence; non-strict mode may still record Off site. 移动至工地围栏内；若非严格模式仍可记录 Off site。
Cannot take photo	Allow camera/photos; a site photo is required for field punches. 允许相机/相册权限；现场打卡照片为必填。
Missed field punch	Ask a Project Admin to add a Manual punch on History. 请项目管理员在历史页使用手动补录。
Wrong punch time	Project Admin: tap Edit on the record and correct time + reason. 项目管理员在记录上点 Edit，改正时间并填写原因。
Offline not uploading	Keep Offline Mode on; wait for auto-sync when online. 保持 Offline Mode；联网后等待自动同步横幅消失。
Temporary password expired	Ask Project Admin to Reset; change password within 7 days. 联系项目管理员 Reset；须在 7 天内首次改密。
Signed out / session expired	Sessions last about 12 hours; sign in again. 会话约 12 小时，请重新登录。
Worker not found	Ensure the worker is Active and the ID/name is correct. 确认 Manpower 中为 Active，且工号/姓名正确。

For support, contact your project administrator or platform operator. This guide matches Hubble Fields attendance app v0.2 (includes manual punch).

如需技术支持，请联系项目管理人员或平台运营方。本文档对应 Hubble Fields 考勤应用 v0.2（含手动补录功能）。